Oracle® Exadata Exadata Database Service on Cloud@Customer Administrator's Guide





Oracle Exadata Exadata Database Service on Cloud@Customer Administrator's Guide,

F41226-44

Copyright © 2008, 2022, Oracle and/or its affiliates.

Primary Authors: Nirmal Kumar, James Spiller

Contributing Authors: Aneesh Khandelwal, Kasey Parker, Sridhar Murala

Contributors: Abhilash Gudasi, Akhila Prabhu, Alexander Prince Mathew, Ankit Mahale, Ankur Raina, Ankur Sinha, Ashutosh Chetal, Barb Lundhild, Behkam Aminzadeh, Bhargavi Amancharla, Bob Thome, Boming Zhang, Brad Nowrouzi, Bryce Cracco, Charan Chaudary Lekkalapudi, Cynthia Varela, David Jimenez Alvarez, Douglas Williams, Gorev Khanna, Guruprasad Hegde, Jai Krishnani, Jean-Francois Verrier, Jose Ricardo Ortiz Olivares, Karina Ledesma, Kishore Sridhar, Kris Bhanushali, Lakshmi Sneha Kandukuri, Lisa Grant, Luqman, Manini Chattopadhyay, Manish Mahawar, Manish Shah, Manu Sinha, Mark Bauer, Michael Fitch, Monika Gupta, Namratha Mandya Subramanya, Nayana Vishwa, Neil Hebert, Nishith Pandey, Nithin Kovoor, Omar Briseno Safa, Oscar Gallegos, Pablo Sainz Albanez, Peter Fusek, Peter Liu, Peter Sciarra, Pradeep Bhat, Pravin Jha, Raj Ojha, Ranganath Srirangapatna Ramachandra, Rhonda Day, Robert Greene, Rodrigo Gonzalez Alba, Rohan Anand, Rudregowda Mallegowda, Sanjay Narvekar, Santosh Uttam Bobade, Saravanan Sabapathy, Sarita Nori, Sheila Ray, Shravan Thatikonda, Smitha Gurunathakrishnan, Somnath Lahiri, Sonali Purdhani, Syam Vasa, Tammy Bednar, Terence Buencamino, Tushar Pandit, Vedavathi Eagala, Vedika Joshi, Vira Goorah, Vivek Nama, Vrishali Hajare, Xiao Pan, Youngju Cho

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1 Exadata Database Service on Cloud@Customer Overview

Oracle Exadata Database Service on Cloud@Customer Service Description	1-1
About Oracle Exadata Database Service on Cloud@Customer	1-2
Licensing Considerations for Oracle Exadata Database Service on Cloud@Customer	1-3
Per-Second Billing for OCPU Usage	1-3
Supported Database Edition and Versions	1-3
System and Shape Configuration Options	1-4
System Configuration Options for Oracle Exadata Database Service on Cloud@Customer	1-4
Oracle Exadata X9M-2 System Model Specifications	1-4
Oracle Exadata X8M-2 System Model Specifications	1-5
Oracle Exadata X8-2 System Model Specifications	1-6
Oracle Exadata X7-2 System Model Specifications	1-7
Exadata Cloud Management Interfaces	1-7
Introduction to Exadata Cloud Management Interfaces	1-7
OCI Control Plane Interfaces	1-8
Local VM Command-Line Interfaces	1-10

What's New in Oracle Exadata Database Service on Cloud@Customer Gen2

Concurrently Create or Terminate Oracle Databases in a VM Cluster	2-2
Support for Rack Serial Number as a System Tag	2-2
Support for DB Home Minor Version Selection (N-3)	2-3
VM Guest Exadata OS Image Major Version Update	2-3
Database Service Events	2-3
Control Plane Server (CPS) Offline Diagnostic Report	2-4
Enhanced Infrastructure Maintenance Controls	2-5
Manage Pluggable Databases on Exadata Cloud@Customer	2-6
Allow Customers to Choose Data Guard Type	2-6
Specify the Same SID for Primary and Standby Databases in a Data Guard Association	2-7
Specify db_unique_name and SID for Primary and Standby Databases in Data Guard	
Association	2-7



	VM Cluster Node Subsetting	2-7
	X9M-2 System Support	2-8
	Customize SCAN Listener Port	2-9
	Creating DG Association/Standby Database Using Existing Database Home	2-9
	Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster	2-10
	Updating Guest VM Operating System	2-10
	Upgrading Oracle Databases	2-10
	Download Network Validation Report	2-10
	Elastic Storage Expansion	2-11
	Oracle Database Software Images	2-12
	Exadata Cloud@Customer Infrastructure Patching Automation	2-12
	Customer Maintenance Contacts	2-13
	X8M-2 System Support	2-13
	Enable and Manage Data Guard Associations	2-14
	Oracle Exadata Cloud@Customer Deployment Assistant	2-14
	Oracle Grid Infrastructure and Oracle Database Patching	2-15
	Per-Second Billing for OCPU Usage	2-15
	Shared Database Home Resource Tags	2-16
	Create and Manage Multiple Virtual Machines per Exadata System (MultiVM)	2-16
	Scale OCPUs Without Cloud Connectivity	2-17
	Configure Oracle Database Character Set and National Character Set	2-17
	Specify a Time Zone While Provisioning Oracle Exadata Database Service on Cloud@Customer Infrastructure	2-18
	Shared Database Homes for Oracle Exadata Database Service on Cloud@Customer	2-18
	X7-2 System Support	2-19
3	Preparing for Exadata Database Service on Cloud@Customer	
	Oracle Cloud Infrastructure (OCI) Requirements for Oracle Exadata Database Service on Cloud@Customer	3-1
	Required IAM Policy for Exadata Database Service on Cloud@Customer	3-2
	Site Requirements for Oracle Exadata Database Service on Cloud@Customer	3-3
	Space Requirements for Oracle Exadata Database Service on Cloud@Customer	3-4
	Weight of Oracle Exadata Cloud X8 Racks	3-4
	Receiving, Unpacking, and Access for Oracle Exadata Database Service on Cloud@Customer Racks	3-4
	Flooring for Oracle Exadata Database Service on Cloud@Customer Racks	3-5
	Electrical Power for Oracle Exadata Database Service on Cloud@Customer Racks	3-5
	Temperature and Humidity Ranges for Oracle Exadata Database Service on Cloud@Customer	3-7
	Ventilation for Oracle Exadata Database Service on Cloud@Customer Racks	3-8
	Network Requirements for Oracle Exadata Database Service on Cloud@Customer	3-9



Network Requirements for Oracle Exadata Database Service on Cloud@Customer	3-9
Data Center Network Services for Exadata Database Service on Cloud@Customer	3-15
IP Addresses and Subnets for Exadata Database Service on Cloud@Customer	3-16
Uplinks for Exadata Database Service on Cloud@Customer	3-17
Network Cabling for Exadata Database Service on Cloud@Customer	3-18
Oracle Exadata Database Service on Cloud@Customer Gen2 Oracle Cloud Infrastructure FastConnect	3-18
Storage Configuration Requirements for Oracle Exadata Database Service on Cloud@Customer	3-20
About Storage Configuration for Oracle Exadata Database Service on Cloud@Customer	3-20
Allocation of Storage Space Options on Oracle Exadata Storage Servers	3-21
Allocation Proportions for DATA, RECO and SPARSE Disk Groups	3-21
Virtual Machine File System Structure for Exadata Cloud@Customer	3-22
Checklists for Exadata Database Service on Cloud@Customer Deployments	3-23
System Components Checklist for Exadata Database Service on Cloud@Customer	3-24
Data Center Room Checklist for Exadata Database Service on Cloud@Customer	3-24
Data Center Environment Checklist for Oracle Exadata Database Service on Cloud@Customer	3-24
Access Route Checklist for Oracle Exadata Database Service on Cloud@Customer	3-25
Facility Power Checklist for Oracle Exadata Database Service on Cloud@Customer	3-25
Safety Checklist for Oracle Exadata Database Service on Cloud@Customer	3-26
Logistics Checklist for Exadata Database Service on Cloud@Customer	3-26
Network Configuration Checklist for Oracle Exadata Database Service on Cloud@Customer	3-27
Reracking Checklist for Oracle Exadata Database Service on Cloud@Customer	3-28
Getting Started with Exadata Database Service on Cloud@Custom Deployment	
About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems	4-2
Oracle Exadata Cloud@Customer Deployment Assistant	4-2
Using Oracle Exadata Cloud@Customer Deployment Assistant	4-3
Accessing Oracle Exadata Cloud@Customer Deployment Assistant	4-3
Step 1: Pre-Installation	4-4
Step 2: Onsite Installation	4-4
Step 3: Post-Installation	4-5
Overview of Elastic Storage Expansion	4-5
Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure	4-8
Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure	4-8
Enabling or Disabling the Control Plane Server Diagnostic Offline Report	4-14



Viewing the Control Plane Server Diagnostic Offline Report	4-14
Using the Console to View Exadata Infrastructure Network Configuration Details	4-15
Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration	4-15
Using the Console to Download a File Containing Configuration Data	4-17
Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure	4-18
Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure	4-18
Configuring Oracle-Managed Infrastructure Maintenance	4-19
About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates	4-20
Overview of the Infrastructure Maintenance Process	4-20
Infrastructure Maintenance Contacts	4-22
Using the Console to Configure Oracle-Managed Infrastructure Updates	4-23
View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure	4-23
View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure	4-25
View the Maintenance History of Exadata Cloud@Customer Infrastructure	4-27
Monitor Infrastructure Maintenance Using Lifecycle State Information	4-28
Receive Notifications about Your Infrastructure Maintenance Updates	4-29
Creating First VM Cluster Network on Exadata Cloud@Customer	4-29
About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer	4-30
Using the Console to Create a VM Cluster Network	4-30
Using the Console to Edit a VM Cluster Network	4-33
Using the Console to Download a File Containing the VM Cluster Network Configuration Details	4-34
Using the Console to Validate a VM Cluster Network	4-35
Provisioning the First VM Cluster on an Exadata Cloud@Customer System	4-35
About Managing VM Clusters on Exadata Database Service on Cloud@Customer	4-36
Prerequisites for VM Clusters on Exadata Database Service on Cloud@Customer	4-36
Using the Console to Create a VM Cluster	4-36
Creating Database Backup Destinations for Exadata Cloud@Customer	4-41
About Managing Backup Destinations for Exadata Database Service on Cloud@Customer	4-41
Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer	4-42
Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer	4-43
Using the Console to Create a Backup Destination	4-43
Using the Console to Edit a Backup Destination	4-45
Using the Console to Move a Backup Destination to Another Compartment	4-46
Using the Console to Delete a Backup Destination	4-46



Creating First Database Home on an Exadata Database Service on Cloud@Customer System	4-4
About Creating Oracle Database Homes on an Exadata Database Service on Cloud@Customer System	4-47
Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer	4-48
Using the API to Create Oracle Database Home on Exadata Cloud@Customer	4-49
Creating First Database on an Exadata Database Service on Cloud@Customer System	4-50
Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer	4-50
Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer	4-5:
About Provisioning and Configuring Oracle Databases on Oracle Exadata Database Service on Cloud@Customer	4-5:
Using the Console to Create a Database	4-52
Connecting to an Exadata Database Service on Cloud@Customer System	4-5
Connecting to a Virtual Machine with SSH	4-5
Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System	4-5
Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY	4-58
Accessing a Database After You Connect to the Virtual Machine	4-59
Connecting from a Unix-Style System	4-6
Connecting to a Database with Oracle Net Services	4-6
Using Oracle Net Services to Connect to a Database	4-6
Prerequisites for Connecting to a Database with Oracle Net Services	4-62
Connecting to a Database Using SCAN	4-62
Connecting to a Database Using a Node Listener	4-64
How-to Guides	
Connect to the Exadata Database Service on Cloud@Customer Service	5-2
Connecting to a Virtual Machine with SSH	5-2
Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System	5-3
Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY	5-3
Connecting from a Unix-Style System	5-4
Accessing a Database After You Connect to the Virtual Machine	5-
Connecting to a Database with Oracle Net Services	5-
Using Oracle Net Services to Connect to a Database	5-0
Prerequisites for Connecting to a Database with Oracle Net Services	5-7
Connecting to a Database Using SCAN	5-
Connecting to a Database Using a Node Listener	5-9
Manage Exadata Database Service on Cloud@Customer Infrastructure	5-10



	About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems	5-11
	Overview of Elastic Storage Expansion	5-11
	Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure	5-14
	Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure	5-15
	Using the Console to View Exadata Infrastructure Network Configuration Details	5-20
	Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration	5-21
	Using the Console to Download a File Containing Configuration Data	5-23
	Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure	5-23
	Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure	5-24
	Using the Console to Scale Infrastructure Storage	5-25
	Using the Console to Download Scale Infrastructure Storage Configuration File	5-25
	Using the Console to Activate New Storage Servers	5-26
	Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption	5-26
	Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity	5-27
	Using the Console to Move Exadata Database Service on Cloud@Customer Infrastructure	5-28
	Using the Console to Delete Exadata Database Service on Cloud@Customer Infrastructure	5-28
	Using the Console to Manage Tags for Your Exadata Cloud@Customer Resources	5-29
	Managing Infrastructure Maintenance Contacts	5-29
	Using the API to Manage Exadata Cloud@Customer Infrastructure	5-32
Co	nfigure Oracle-Managed Infrastructure Maintenance	5-33
	About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates	5-33
	Overview of the Infrastructure Maintenance Process	5-34
	Infrastructure Maintenance Contacts	5-36
	Using the Console to Configure Oracle-Managed Infrastructure Updates	5-36
	View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure	5-37
	View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure	5-39
	View the Maintenance History of Exadata Cloud@Customer Infrastructure	5-41
	View and Edit Maintenance While Maintenance is In Progress or Waiting for Custom Action	5-42
	Monitor Infrastructure Maintenance Using Lifecycle State Information	5-44
	Receive Notifications about Your Infrastructure Maintenance Updates	5-44
	Using the API to Manage Exadata Cloud@Customer Infrastructure Maintenance Controls	5-45



Manage VM Cluster Networks	5-45
About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer	5-46
Using the Console to Create a VM Cluster Network	5-47
Using the Console to View SCAN Listener Port Configured	5-49
Using the Console to Edit a VM Cluster Network	5-50
Using the Console to Download a File Containing the VM Cluster Network Configuration Details	5-51
Using the Console to Validate a VM Cluster Network	5-52
Using the Console to Download Network Validation Report	5-52
Using the Console to Terminate a VM Cluster Network	5-54
Manage VM Clusters	5-54
About Managing VM Clusters on Exadata Database Service on Cloud@Customer	5-55
Overview of VM Cluster Node Subsetting	5-55
Introduction to Scale Up or Scale Down Operations	5-56
Scaling Up or Scaling Down the VM Cluster Resources	5-56
Calculating the Minimum Required Memory	5-57
Calculating the ASM Storage	5-58
Estimating How Much Local Storage You Can Provision to Your VMs	5-60
Scaling Local Storage Down	5-62
Using the Console to Manage VM Clusters on Exadata Cloud@Customer	5-62
Using the Console to Create a VM Cluster	5-63
Using the Console to Enable or Disable Diagnostics Notification	5-67
Using the Console to Add VMs to a Provisioned Cluster	5-68
Using the Console to View a List of DB Servers on an Exadata Infrastructure	5-69
Using the Console to Remove a VM from a VM Cluster	5-69
Using the Console to Update the License Type on a VM Cluster	5-70
Using the Console to Add SSH Keys After Creating a VM Cluster	5-70
Using the Console to Scale the Resources on a VM Cluster	5-71
Using the Console to Stop, Start, or Reboot a VM Cluster Virtual Machine	5-73
Using the Console to Check the Status of a VM Cluster Virtual Machine	5-73
Using the Console to Move a VM Cluster to Another Compartment	5-74
Using the Console to Terminate a VM Cluster	5-74
Using the API to Manage Exadata Cloud@Customer VM Clusters	5-74
Manage Oracle Database Software Images	5-76
Creation and Storage of Database Software Images	5-76
Using a Database Software Image with an Exadata Cloud@Customer System	5-77
Using the Console to Create a Database Software Image	5-78
Using the OPatch Isinventory Command to Verify the Patches Applied to an Oracle Home	5-79
Using the Console to Delete a Database Software Image	5-79
Using the Console to View the Patch Information of a Database Software Image	5-79
•	



Using the Console to Move Database Software Image to a Different Cor	mpartment 5-80
Using the API for Managing Oracle Database Software Images	5-80
Create Oracle Database Homes on an Exadata Database Service on Cloud	•
System	5-81
About Creating Oracle Database Homes on an Exadata Database Servi Cloud@Customer System	ice on 5-81
Using the Console to Create Oracle Database Home on Exadata Database Cloud@Customer	ase Service on 5-82
Using the API to Create Oracle Database Home on Exadata Cloud@Cu	stomer 5-83
Manage Oracle Database Homes on Exadata Database Service on Cloud@ Systems	Customer 5-84
About Managing Oracle Database Homes on Exadata Database Service Cloud@Customer Systems	e on 5-84
Manage Database Home Using the Console	5-84
	lome 5-85
	5-85
9	Service on
Cloud@Customer	5-86
Differences Between Managing Resources with dbaascli and the Databa	ase API 5-86
Manage Databases on Exadata Database Service on Cloud@Customer	5-87
Prerequisites and Limitations for Creating and Managing Oracle Databa Exadata Database Service on Cloud@Customer	ses on Oracle 5-88
Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer 5- About Provisioning and Configuring Oracle Databases on Oracle Exadata Database	vice on 5-88
About Provisioning and Configuring Oracle Databases on Oracle Exada Service on Cloud@Customer	ta Database 5-89
Using the Console to Manage Databases on Oracle Exadata Database Cloud@Customer	Service on 5-90
_	5-90
· ·	
Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer Using the API to Create Oracle Database Home on Exadata Cloud@Customer Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems About Managing Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems About Managing Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems About Managing Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems Manage Database Home Using the Console Using the Console to View Information About an Oracle Database Home Using the API to Manage Oracle Database Home on Exadata Database Service on Cloud@Customer Differences Between Managing Resources with dbaascli and the Database API Manage Databases on Exadata Database Service on Cloud@Customer Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer About Provisioning and Configuring Oracle Databases on Oracle Exadata Database Service on Cloud@Customer Using the Console to Manage Databases on Oracle Exadata Database Service on Cloud@Customer Using the Console to Manage Database Using the Console to Move a Database Using the Console to Terminate a Database Using the API to Manage Oracle Database Components Changing the Database Passwords To Change the SYS Password for an Exadata Database Service on	
	5-96
Changing the Database Passwords	5-97
	5-97
To Change Database Passwords in a Data Guard Environment	5-97
To Change the TDE Wallet Password for an Exadata Database Serv Cloud@Customer Database	
Manage Pluggable Databases on Exadata Database Service on Cloud@	
Pluggable Database Operations	5-98
Manage Database Backup and Recovery on Oracle Exadata Database Serv	
Cloud@Customer	5-108
Backup Destinations	5-109
About Managing Backup Destinations for Exadata Database Service Cloud@Customer	e on 5-109



	Prerequisites for Backup Destinations for Exadata Database Service on	
	Cloud@Customer	5-110
	Using the Console for Backup Destinations for Exadata Database Service on	F 444
	Cloud@Customer	5-111
	Using the API to Manage Exadata Cloud@Customer Backup Destinations	5-115
C	Oracle Database Backup Methods in Exadata Cloud	5-115
	Oracle Managed Backup	5-116
	User Configured Backup	5-129
C	Configuring and Customizing Backups with bkup_api	5-137
	Customizing Backup Settings by Using a Generated Configuration File	5-138
	Customizing Which System Files Are Backed Up	5-144
	Customizing Which Database Configuration Files Are Backed Up	5-145
C	Creating an On-Demand Backup by Using the bkup_api Utility	5-146
	Disabling Automatic Backups to Facilitate Manual Backup and Recovery Management	5-148
	Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups	5-150
	Alternative Backup Methods	5-151
	Recovering a Database Using Oracle Recovery Manager (RMAN)	5-152
Patch	n and Update an Exadata Database Service on Cloud@Customer System	5-153
F	Perform User Managed Maintenance Updates	5-153
	Patching and Updating an Exadata Database Service on Cloud@Customer System	5-153
	Patching and Updating VM Clusters and Database Homes	5-154
	Updating Guest VM Operating System	5-160
	Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster	5-163
	Upgrading Oracle Databases	5-165
F	Patching and Updating an Exadata Database Service on Cloud@Customer System	
	Manually	5-170
	Updating Software Manually	5-171
	Updating the Guest VM Operating System Manually	5-171
Use (Oracle Data Guard with Exadata Database Service on Cloud@Customer	5-181
Δ	About Using Oracle Data Guard with Exadata Database Service on Cloud@Customer	5-181
	Prerequisites for Using Oracle Data Guard with Exadata Database Service on	
C	Cloud@Customer	5-182
	Compute Nodes	5-182
	Password	5-182
V	Vorking with Data Guard	5-182
	Switchover	5-183
	Failover	5-183
	Reinstate	5-183
L	Jsing the Console to Manage Oracle Data Guard Associations	5-183
	Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System	5-184
	Using the Console To View and Edit Data Guard Associations	5-187



Using the Console To Perform a Database Switchover	5-187
Using the Console To Perform a Database Failover	5-188
Using the Console To Reinstate a Database	5-188
Using the Console To Terminate a Data Guard Association on an Exadata Database Service on Cloud@Customer System	5-189
Using the API to Manage Data Guard Associations on an Exadata Database Service on Cloud@Customer System	e 5-190
Migrate to Exadata Database Service on Cloud@Customer	5-190
Moving to Oracle Cloud Using Zero Downtime Migration	5-190
Overview of Exadata Cloud@Customer Gen1 to Out-of-Place Cloud Upgrade to Exadata Database Service on Cloud@Customer Gen2 Infrastructure	a 5-191
Scope for Exadata Cloud@Customer Gen1 to Gen2 Out-of-Place Cloud Upgrade	5-192
Hardware and Software Required for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure	5-193
Using Oracle Zero Downtime Migration (ZDM) to Migrate Oracle Databases	5-194
During Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure	5-198
Post Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure	5-199
Hardware and Software Required for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure Using Oracle Zero Downtime Migration (ZDM) to Migrate Oracle Databases During Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure Post Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure Best Practices for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer	
Gen2 Infrastructure	5-200
Gen2 Infrastructure Autonomous Database on Exadata Cloud@Customer	
Gen2 Infrastructure Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer	6-2
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection	6-2 6-2
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database	6-2 6-2 6-3
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name	6-2 6-2 6-3 6-5
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database	6-2 6-2 6-3
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup	6-2 6-3 6-5 6-6
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support	6-2 6-3 6-4 6-6 6-6
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database	6-2 6-3 6-5 6-6 6-6
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support	6-2 6-3 6-4 6-6 6-7 6-7 6-8
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK	6-2 6-2 6-3 6-4 6-7 6-7 6-8 V)
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK Integration	6-2 6-3 6-3 6-4 6-7 6-7 6-8 V)
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK Integration Infrastructure Patching Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled	6-2 6-3 6-4 6-6 6-7 6-7 6-8
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK Integration Infrastructure Patching Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled Autonomous Databases ADB-D on Exadata Cloud@Customer: Monitor Performance with Autonomous	6-2 6-3 6-3 6-4 6-7 6-7 6-8 V) 6-8
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK Integration Infrastructure Patching Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled Autonomous Databases ADB-D on Exadata Cloud@Customer: Monitor Performance with Autonomous Database Metrics	6-2 6-3 6-4 6-6 6-7 6-7 6-8 V) 6-8
Autonomous Database on Exadata Cloud@Customer What's New in ADB-D on Exadata Cloud@Customer Character Set Selection Enhanced Resource Tracking for Autonomous Database Longer Database Name Create a New Autonomous Database Instance from Backup Multiple Autonomous VM Cluster Support Automatic Failover with a Standby Autonomous Container Database X9M-2 System Support Fractional OCPU and GB Storage Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OK Integration Infrastructure Patching Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled Autonomous Databases ADB-D on Exadata Cloud@Customer: Monitor Performance with Autonomous Database Metrics ADB-D on Exadata Cloud@Customer: Autonomous Data Guard	6-2 6-2 6-3 6-4 6-6 6-7 6-8 V) 6-8 6-9 6-9



Per-Second Billing for Autonomous Database OCPU Usage	6-10
Oracle Autonomous Database on Oracle Exadata Database Service on	C 11
Cloud@Customer	6-11
Introduction to ADB-D on Exadata Cloud@Customer	6-11
Database System Architecture Overview	6-11
Resource Types	6-11
Deployment Order	6-12
User Roles	6-13
Available Exadata Infrastructure Hardware Shapes	6-13
Access Control Lists (ACLs) for ADB-D on Exadata Cloud@Customer	6-15
Managing Autonomous Exadata VM Clusters	6-16
About Autonomous Exadata VM Clusters	6-17
Create an Autonomous Exadata VM Cluster	6-17
View a List of Autonomous Exadata VM Clusters	6-19
View Details of an Autonomous Exadata VM Cluster	6-20
Schedule Oracle-Managed Infrastructure Updates	6-20
Set the Automatic Maintenance Schedule for Autonomous Exadata VM Cluster	6-20
View or Edit the Time of the Next Scheduled Maintenance for Autonomous Exadata VM Cluster	6-21
View the Maintenance History of Autonomous Exadata VM Cluster	6-22
Change the License Type on an Autonomous VM Cluster	6-22
Move an Autonomous Exadata VM Cluster to Another Compartment	6-23
Terminate an Autonomous Exadata VM Cluster	6-23
Using the API to Manage Autonomous Exadata VM Clusters	6-23
Managing Encryption Keys on External Devices	6-24
About Oracle Key Vault	6-24
Overview of Key Store	6-25
Required IAM Policy for Managing OKV on Oracle Exadata Database Service on Cloud@Customer	6-25
Tagging Resources	6-26
Moving Resources to a Different Compartment	6-26
Setting Up Your Exadata Cloud@Customer to Work With Oracle Key Vault	6-26
Step 1: Create a Vault in OCI Vault Service and Add a Secret to the Vault to Store OKV REST Administrator Password	6-27
Step 2: Create a Dynamic Group and a Policy Statement for Key Store to Access Secret in OCI Vault	6-27
Step 3: Create a Dynamic Group and a Policy Statement for Exadata Infrastructure to Key Store	6-28
Step 4: Create a Policy Statement for Database Service to Use Secret from OCI Vault Service	6-29
Step 5: Create Key Store	6-29
Managing Your Key Store	6-30
View Key Store Details	6-30
,	



Edit Key Store Details	6-31
Move a Key Store to Another Compartment	6-31
Delete a Key Store	6-31
View Key Store Associated Autonomous Container Database Details	6-32
Using the API to Manage Key Store	6-32
Managing Autonomous Container Databases	6-33
Create an Autonomous Container Database	6-33
View a List of Autonomous Container Databases	6-35
View the List of Autonomous Container Databases in an Autonomous Cluster	s Exadata VM 6-35
View the List of Autonomous Container Databases in a Compartmen	t 6-36
View Details of an Autonomous Container Database	6-36
Rotate CDB Encryption Key	6-36
Change the Backup Retention Policy of an Autonomous Container Datab	pase 6-37
Change the Maintenance Schedule of an Autonomous Container Databa	se 6-37
Restart an Autonomous Container Database	6-38
Move an Autonomous Container Database to Another Compartment	6-39
Terminate an Autonomous Container Database	6-39
Using the API to Manage Autonomous Container Databases	6-40
Managing Autonomous Databases	6-40
Create an Autonomous Database	6-41
Manage Access Control List of an Autonomous Database	6-44
View a List of Autonomous Databases	6-45
View Details of an Autonomous Database	6-45
Rotate ADB Encryption Key	6-45
Set the Password of an Autonomous Database's ADMIN User	6-46
Scale the CPU Core Count or Storage of an Autonomous Database	6-47
Enable or Disable Auto Scaling for an Autonomous Database	6-48
Move an Autonomous Database to Another Compartment	6-49
Stop or Start an Autonomous Database	6-49
Restart an Autonomous Database	6-50
Back Up an Autonomous Database Manually	6-50
Restore an Autonomous Database	6-51
Restore from a Backup	6-51
Restore to a Point in Time	6-52
Clone an Autonomous Database	6-52
Clone an Autonomous Database Backup	6-55
Clone a Standby Database	6-59
Clone a Standby Database Backup	6-62
Terminate an Autonomous Database	6-65
API to Manage Autonomous Databases	6-65



Monitor Performance with Autonomous Database Metrics	6-66
View Top Six Metrics for an Autonomous Database	6-67
View Aggregated Metrics for Autonomous Databases in a Compartment	6-67
Autonomous Database Metrics and Dimensions	6-68
Connecting to Autonomous Databases	6-68
Download the Wallet for an Autonomous Database	6-69
Get the APEX and SQL Developer Web URLs for an Autonomous Database	6-70
Patching ADB on Exadata Cloud@Customer Infrastructure	6-70
Overview of ADB on Exadata Cloud@Customer Infrastructure Patching	6-70
Specifying When Maintenance Can Occur	6-71
Specifying What Kind of Patches to Apply	6-72
Using Autonomous Data Guard with Autonomous Database on Exadata Cloud@Customer	6-72
Enabling Autonomous Data Guard on an Autonomous Container Database	6-72
Create an Autonomous Data Guard Enabled Autonomous Container Database	6-73
View Details of a Data Guard Enabled Primary or Standby Autonomous Container Database	6-76
Rotate CDB Encryption Key	6-77
Managing a Standby Autonomous Container Database	6-77
Perform a Failover to Standby Autonomous Container Database	6-79
Perform a Switchover to Standby or Primary Autonomous Container Database	6-79
Reinstate Data Guard Enabled Standby Autonomous Container Database	6-80
Terminate a Data Guard Enabled Primary Autonomous Container Database	6-80
Terminate a Data Guard Enabled Standby Autonomous Container Database	6-81
Operations Performed Using the APIs	6-81
Enabling Autonomous Data Guard on an Autonomous Database	6-82
View Autonomous Data Guard Enablement	6-83
Create an Autonomous Data Guard Enabled Autonomous Database	6-83
View Details of a Data Guard Enabled Primary or Standby Autonomous Database	6-85
Rotate ADB Encryption Key	6-86
Maintenance Scheduling and Patching Data Guard Enabled Autonomous Container Database	6-86
Configure Automatic Maintenance Schedule for a Data Guard Enabled Autonomous Container Database	6-86
View the Next Scheduled Maintenance Run of a Data Guard Enabled Autonomous Container Database	6-88
View the Maintenance History of a Data Guard Enabled Autonomous Container Database	6-88
Immediately Patch a Data Guard Enabled Autonomous Container Database	6-89
Reschedule or Skip scheduled Maintenance for Data Guard Enabled Autonomous Container Database	6-89
Using Performance Hub to Analyze Database Performance	6-90
Performance Hub Features	6-90
Time Range Selector	6-91



Time Zone Selector	6-92
ASH Analytics Tab	6-92
SQL Monitoring Tab	6-92
Blocking Sessions Tab	6-93
Using the Oracle Cloud Infrastructure Console	6-93
Navigate to Performance Hub in the Oracle Cloud Infrastructure Console Interface of an Autonomous Database	6-93
View the Average Active Sessions Data by a Selected Dimension	6-93
Filter Average Active sessions Data	6-94
View the SQL Monitoring Report	6-95
View the Blocking and Waiting Sessions	6-95
Reference Guides for Exadata Database Service on Cloud@Cust	omer
Using the dbaascli Utility with Exadata Database Service on Cloud@Customer	7-1
About Using the dbaascli Utility on Exadata Database Service on Cloud@Customer	7-2
Creating Oracle Database Using dbaascli	7-2
Listing Available Software Images and Versions for Database	7-3
Creating Oracle Database Home	7-4
Creating Oracle Database In the Specified Oracle Database Home	7-5
Changing the Database Passwords	7-8
To Change the SYS Password for an Exadata Database Service on Cloud@Customer Database	7-8
To Change Database Passwords in a Data Guard Environment	7-8
To Change the TDE Wallet Password for an Exadata Database Service on Cloud@Customer Database	7-9
Managing Exadata Database Service on Cloud@Customer Software Images Using the Dbaascli Utility	7-9
Listing Available Software Images and Versions for Database and Grid Infrastructure	7-9
To download a software image	7-11
Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli	7-12
Patching Databases using dbaascli	7-12
Patching Oracle Grid Infrastructure	7-14
Listing Available Software Images and Versions for Database and Grid Infrastructure	7-15
Performing a Precheck Before Patching Databases and Grid Infrastructure	7-17
Resuming or Rolling Back a Patching Operation	7-19
Updating Cloud Tooling Using dbaascli	7-21
Release Notes	7-22
Release 22.2.1.1.0 (220713)	7-22
Release 22.2.1.0.1 (220504)	7-23
Release 22.1.1.1.0 (220301)	7-24



R	elease 22.1.1.0.1 (220223)	7-24
R	elease 21.4.1.1.0	7-25
R	elease 21.3.1.2.0	7-26
R	elease 21.3.1.1.0	7-26
R	elease 21.3.1.0.1	7-26
R	elease 21.2.1.x.x	7-27
dbaas	scli Command Reference	7-28
dl	baascli admin updateStack	7-32
dl	baascli cpuscale get_status	7-36
dl	baascli cpuscale update	7-36
dl	baascli cswlib download	7-37
dl	baascli cswlib showImages	7-38
dl	baascli database backup	7-39
dl	baascli database bounce	7-41
dl	baascli database changepassword	7-42
dl	baascli database convertToPDB	7-42
dl	baascli database create	7-43
dl	baascli database delete	7-45
dl	baascli database getPDBs	7-46
dl	baascli database modifyParameters	7-49
dl	baascli database move	7-50
dl	baascli database recover	7-51
dl	baascli database runDatapatch	7-52
dl	baascli database start	7-53
dl	baascli database stop	7-53
dl	baascli database upgrade	7-54
dl	baascli dataguard prepareStandbyBlob	7-55
dl	baascli dataguard updateDGConfigAttributes	7-55
dl	baascli dbhome create	7-56
dl	baascli dbHome delete	7-56
dl	baascli dbhome getDatabases	7-57
dl	baascli dbHome getDetails	7-59
dl	baascli dbHome patch	7-60
dl	baascli diag collect	7-61
dl	baascli diag healthCheck	7-62
dl	baascli grid configureTCPS	7-63
dl	baascli grid patch	7-64
dl	baascli grid rotateTCPSCert	7-65
dl	baascli grid upgrade	7-66
dl	baascli job getStatus	7-67
dl	baascli patch db apply	7-68



dbaascli patch db prereq	7-69
dbaascli pdb backup	7-69
dbaascli pdb bounce	7-70
dbaascli pdb close	7-71
dbaascli pdb connectString	7-72
dbaascli pdb create	7-73
dbaascli pdb delete	7-74
dbaascli pdb getDetails	7-75
dbaascli pdb list	7-75
dbaascli pdb localClone	7-76
dbaascli pdb open	7-77
dbaascli pdb recover	7-78
dbaascli pdb relocate	7-79
dbaascli pdb remoteClone	7-80
dbaascli system getDBHomes	7-81
dbaascli tde addSecondaryHsmKey	7-83
dbaascli tde changePassword	7-84
dbaascli tde enableWalletRoot	7-84
dbaascli tde encryptTablespacesInPDB	7-85
dbaascli tde fileToHsm	7-86
dbaascli tde getHsmKeys	7-87
dbaascli tde getMkidForKeyVersionOCID	7-88
dbaascli tde getPrimaryHsmKey	7-88
dbaascli tde hsmToFile	7-89
dbaascli tde listKeys	7-90
dbaascli tde removeSecondaryHsmKey	7-91
dbaascli tde setKeyVersion	7-92
dbaascli tde setPrimaryHsmKey	7-93
dbaascli tde status	7-93
Monitoring and Managing Exadata Storage Servers with ExaCLI	7-94
About the ExaCLI Command	7-94
Exadata Storage Server Username and Password	7-95
ExaCLI Command	7-95
Connecting to a Storage Server with ExaCLI	7-101
Oracle Exadata Database Service on Cloud@Customer Events	7-102
About Event Types on Exadata Cloud@Customer	7-103
Exadata Infrastructure Event Types	7-103
VM Cluster Network Event Types	7-106
VM Cluster Event Types	7-107
Backup Destination Event Types	7-109
Database Node Event Types (Cloud@Customer)	7-110



Database Home Event Types (Cloud@Customer)	7-111
Database Event Types (Cloud@Customer)	7-112
Database and Grid Infrastructure Patching Event Types	7-113
Autonomous VM Cluster Event Types	7-116
Autonomous Container Database Event Types	7-120
Autonomous Database Event Types	7-121
Data Guard Event Types	7-122
Autonomous Data Guard Association Event Types	7-125
Key Store Event Types	7-129
Exadata Cloud@Customer Infrastructure Maintenance Event Types	7-130
Storage Expansion Event Types	7-143
Database Software Images Event Types	7-145
Database Upgrade Event Types	7-153
Pluggable Database Event Types	7-161
VM Node Subsetting Event Types	7-162
Database Service Events	7-166
Overview of Database Service Events	7-167
Receive Notifications about Database Service Events	7-169
Database Service Event Types	7-170
Temporarily Restrict Automatic Diagnostic Collections for Specific Events	7-180
Remediation	7-184
Policy Details for Exadata Database Service on Cloud@Customer	7-201
About Resource-Types	7-202
Resource-Types for Exadata Database Service on Cloud@Customer	7-202
Supported Variables	7-203
Details for Verb + Resource-Type Combinations	7-204
Database-Family Resource Types	7-205
exadata-infrastructures	7-205
vmcluster-networks	7-206
vmclusters	7-207
backup-destinations	7-208
db-nodes	7-209
db-homes	7-210
databases	7-211
backups	7-212
database-software-image	7-213
autonomous-vmclusters	7-214
autonomous-container-databases	7-214
autonomous-databases	7-215
key-stores	7-216
pluggable-databases (PDBs)	7-217



dbServers	7-218
Permissions Required for Each API Operation	7-218
Managing Exadata Resources with Oracle Enterprise Manager Cloud Control	7-225
Overview of Oracle Enterprise Manager Cloud Control	7-225
Features of Enterprise Manager Cloud Control	7-225
Security Guide for Exadata Database Service on Cloud@Customer Systems	7-226
Security Configurations and Default Enabled Features	7-226
Responsibilities	7-227
Guiding Principles Followed for Security Configuration Defaults	7-227
Security Features	7-228
Guest VM Default Fixed Users	7-230
Guest VM Default Security Settings	7-232
Guest VM Default Processes	7-233
Guest VM Network Security	7-233
Additional Procedures for Updating Security Posture	7-236
Customer Responsibilities	7-236
Enabling Additional Security Capabilities	7-237
Troubleshooting Exadata Database Service on Cloud@Customer Systems	7-241
Patching Failures on Exadata Database Service on Cloud@Customer Systems	7-241
Determining the Problem	7-242
Troubleshooting and Diagnosis	7-242
Obtaining Further Assistance	7-243
Collecting Cloud Tooling Logs	7-244
Collecting Oracle Diagnostics	7-244
VM Operating System Update Hangs During Database Connection Drain	7-244
Adding a VM to a VM Cluster Fails	7-246
CPU Offline Scaling Fails	7-246



Exadata Database Service on Cloud@Customer Overview

This topic is an overview of the Exadata Database Service on Cloud@Customer service.

- Oracle Exadata Database Service on Cloud@Customer Service Description
 Learn how you can leverage the combined capabilities of Oracle Exadata and Oracle
 Cloud Infrastructure with Oracle Exadata Database Service on Cloud@Customer
- Exadata Cloud Management Interfaces
 Exadata Database Service on Cloud@Customer provides a variety of management interfaces to fit your use case and automation needs.

Oracle Exadata Database Service on Cloud@Customer Service Description

Learn how you can leverage the combined capabilities of Oracle Exadata and Oracle Cloud Infrastructure with Oracle Exadata Database Service on Cloud@Customer



For information related to the ADB-D service on Exadata Cloud@Customer please refer to Autonomous Database on Exadata Cloud@Customer.

- About Oracle Exadata Database Service on Cloud@Customer
 Oracle Exadata Database Service on Cloud@Customer is one of the Database services
 offered on Oracle Cloud Infrastructure. Oracle offers both autonomous and co-managed
 Oracle Database cloud solutions. For more information, see Overview of the Database
 Service.
- Licensing Considerations for Oracle Exadata Database Service on Cloud@Customer Subscription to Exadata Database Service on Cloud@Customer can include all of the required Oracle Database software licenses, or you can choose to bring Oracle Database software licenses that you already own to Oracle Exadata Database Service on Cloud@Customer.
- Per-Second Billing for OCPU Usage
 Oracle Exadata Database Service on Cloud@Customer Gen2 uses for OCPUs.
- Supported Database Edition and Versions
 Exadata Database Service on Cloud@Customer databases require Enterprise Edition Extreme Performance subscriptions or you can bring your own Oracle Enterprise Edition software licenses.
- System and Shape Configuration Options Review the list of Exadata System Shapes

Related Topics

Autonomous Database on Exadata Cloud@Customer

About Oracle Exadata Database Service on Cloud@Customer

Oracle Exadata Database Service on Cloud@Customer is one of the Database services offered on Oracle Cloud Infrastructure. Oracle offers both autonomous and co-managed Oracle Database cloud solutions. For more information, see Overview of the Database Service.



For more information on technical architecture, see *Oracle Exadata Cloud@Customer (ExaC@C) Technical Architecture*.

With Oracle Exadata Database Service on Cloud@Customer, you can maintain absolute control over your data while leveraging the combined capabilities of Oracle Exadata and Oracle Cloud Infrastructure managed by Oracle.

Oracle Exadata Database Service on Cloud@Customer enables you to apply the combined power of Oracle Exadata and Oracle Cloud Infrastructure inside your own data center. You have full access to the features and capabilities of Oracle Database along with the intelligent performance and scalability of Oracle Exadata, but with Oracle owning and managing the Exadata infrastructure. You can use the Oracle Cloud Infrastructure console and APIs to manage Oracle Exadata Database Service on Cloud@Customer just as with any other cloud resource, while maintaining absolute sovereignty over your data.

Each Oracle Exadata Database Service on Cloud@Customer system configuration contains Oracle Exadata Database Servers and Oracle Exadata Storage Servers that are interconnected using a high-speed, low-latency RDMA fabric network, and intelligent Oracle Exadata software.

Oracle Exadata Database Service on Cloud@Customer uses virtual machine (VM) technology to separate the customer-managed and Oracle-managed components on each database server. You have root privilege for the Oracle Exadata database server VMs, so you can manage the Oracle Database, Oracle Grid Infrastructure, and Oracle Exadata system software. However, you do not have administrative access to the physical database server hardware, which Oracle administers.

Oracle Exadata Database Service on Cloud@Customer uses Oracle Exadata Storage Servers for database storage. The storage is allocated to disk groups managed by Oracle Automatic Storage Management (Oracle ASM). You have full administrative access to the Oracle ASM disk groups, but Oracle administers the Oracle Exadata Storage Server hardware and software.

In addition to the database server hardware and Oracle Exadata Storage Servers, Oracle also manages other Oracle Exadata Database Service on Cloud@Customer infrastructure components, including the network switches, power distribution units (PDUs), and integrated lights-out management (ILOM) interfaces.

On each Oracle Exadata Database Service on Cloud@Customer system, you can create one or more databases. Apart from the inherent storage and processing



capacity of your Oracle Exadata system, there is no set maximum for the number of databases that you can create.

Related Topics

- Overview of the Database Service
- Oracle Exadata Cloud@Customer (ExaC@C) Technical Architecture

Licensing Considerations for Oracle Exadata Database Service on Cloud@Customer

Subscription to Exadata Database Service on Cloud@Customer can include all of the required Oracle Database software licenses, or you can choose to bring Oracle Database software licenses that you already own to Oracle Exadata Database Service on Cloud@Customer.

If you choose to include Oracle Database software licenses in your Oracle Exadata Database Service on Cloud@Customer subscription, then the included licenses contain all of the features of Oracle Database Enterprise Edition, plus all of the database enterprise management packs, and all of the Enterprise Edition options, such as Oracle Database In-Memory and Oracle Real Application Clusters (Oracle RAC). Exadata Database Service on Cloud@Customer also comes with cloud-specific software tools that assist with administration tasks, such as backup, recovery, and patching.

Per-Second Billing for OCPU Usage

Oracle Exadata Database Service on Cloud@Customer Gen2 uses for OCPUs.

Per-second billing means that OCPU usage is billed by the second, with a minimum usage period of 1 minute.



Oracle doesn't stop billing when a VM or VM Cluster is stopped. To stop billing for a VM Cluster, lower the OCPU count to zero.

Supported Database Edition and Versions

Exadata Database Service on Cloud@Customer databases require Enterprise Edition - Extreme Performance subscriptions or you can bring your own Oracle Enterprise Edition software licenses.

Exadata Cloud@Customer supports the following database versions:

- Oracle Database 19c (19.0)
- Oracle Database 18c (18.0)
- Oracle Database 12c Release 2 (12.2)
- Oracle Database 12c Release 1 (12.1)
- Oracle Database 11g Release 2 (11.2) is supported for approved customers only.



For Oracle Database release and software support timelines, see *Release Schedule of Current Database Releases (Doc ID 742060.1)* in the My Oracle Support portal.

Related Topics

Release Schedule of Current Database Releases (Doc ID 742060.1)

System and Shape Configuration Options

Review the list of Exadata System Shapes

- System Configuration Options for Oracle Exadata Database Service on Cloud@Customer
 - To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.
- Oracle Exadata X9M-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.
- Oracle Exadata X8M-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.
- Oracle Exadata X8-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.
- Oracle Exadata X7-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.

System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

Exadata Cloud@Customer is offered in the following Exadata System Shapes:

- Base System: Contains two database servers and three Oracle Exadata Storage Servers. A Base System is an entry-level configuration. Compared to other configurations, a Base System contains Oracle Exadata Storage Servers with significantly less storage capacity, and database servers with significantly less memory and processing power.
- Quarter Rack: Contains two database servers and three Oracle Exadata Storage Servers.
- Half Rack: Contains four database servers and six Oracle Exadata Storage Servers
- Full Rack: Contains eight database servers and 12 Oracle Exadata Storage Servers.

Each Exadata System Shape is equipped with a fixed amount of memory, storage, and network resources. All Shapes are based on Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

Oracle Exadata X9M-2 System Model Specifications

Review the technical specifications of available Exadata System Shapes.



Table 1-1 Oracle Exadata X9M-2 System Model Specifications

Property	Base Rack	Quarter Rack	Half Rack	Full Rack
Number of Compute Nodes	2	2	4	8
Number of Exadata Storage Servers	3	3	6	12
Total Number of Usable Data Base Node OCPUs (assuming 2 cores per host)	48	124	248	496
Total Data Base Memory for Guest VMs	656 GB	2780 GB	5560 GB	11120 GB
Maximum /u02 Capacity (per single VM)*	892 GB	900 GB	900 GB	900 GB
Total Number of VM Clusters per System	4	8	16	16
Maximum number of VMs	4	8	8	8
Minimum CPUs per VM	2	2	2	2
Minimum Memory per VM	30 GB	30 GB	30 GB	30 GB
Minimum Local File System Storage per VM	60 GB	60 GB	60 GB	60 GB
Minimum Exadata Storage per VM	2 TB	2 TB	2 TB	2 TB
Total usable ASM Storage Capacity	73.8 TB	190.8 TB	381.6 TB	763.2 TB
Elastic Storage (quantity - 1 cell) Usable ASM Storage Capacity	24.6 TB	63.6 TB	63.6 TB	63.6 TB

Oracle Exadata X8M-2 System Model Specifications

Review the technical specifications of available Exadata System Shapes.

Table 1-2 Oracle Exadata X8M-2 System Model Specifications

Property	Base Rack	Quarter Rack	Half Rack	Full Rack
Number of Database Servers	2	2	4	8
Total Maximum Number of Enabled CPU Cores	48	100	200	400



Table 1-2 (Cont.) Oracle Exadata X8M-2 System Model Specifications

Property	Base Rack	Quarter Rack	Half Rack	Full Rack
Total RAM Capacity	656 GB	2780 GB	5560 GB	11120 GB
Persistent Memory	0	4.6 TB	9.2 TB	18.4 TB
Number of Exadata Storage Servers	3	3	6	12
Total Raw Flash Storage Capacity	38.4 TB	76.8 TB	153.6 TB	307.2 TB
Total Usable Storage Capacity**	73.8 TB	148.8 TB	297.6 TB	595.2 TB
Total Number of VM Clusters per System	4	8	16	16
Maximum Number of VMs	4	8	8	8

Usable capacity is measured using normal powers of 2 space terminology with 1 TB = 1024 * 1024 * 1024 * 1024 bytes. It is the actual space available to create a database after taking into account space needed for ASM high redundancy and recovering from a drive failure, but before database compression.

Oracle Exadata X8-2 System Model Specifications

Review the technical specifications of available Exadata System Shapes.

Table 1-3 Oracle Exadata X8-2 System Model Specifications

Property	Base System	Quarter Rack	Half Rack	Full Rack
Number of Database Servers	2	2	4	8
Total Maximum Number of Enabled CPU Cores	48	100	200	400
Total RAM Capacity	720 GB	1440 GB	2880 GB	5760 GB
Number of Exadata Storage Servers	3	3	6	12
Total Raw Flash Storage Capacity	38.4 TB	76.8 TB	153.6 TB	307.2 TB
Total Raw Disk Storage Capacity	252 TB	504 TB	1008 TB	2016 TB
Total Usable Storage Capacity	73.8 TB	148.8 TB	297.6 TB	595.2 TB
Total Number of VM Clusters per System	5	5	10	10



Table 1-3 (Cont.) Oracle Exadata X8-2 System Model Specifications

Property	Base System	Quarter Rack	Half Rack	Full Rack
Maximum Number of VMs	5	5	5	5

Oracle Exadata X7-2 System Model Specifications

Review the technical specifications of available Exadata System Shapes.

Table 1-4 Oracle Exadata X7-2 System Model Specifications

Property	Base System	Quarter Rack	Half Rack	Full Rack
Number of Database Servers	2	2	4	8
Total Maximum Number of Enabled CPU Cores	44	92	184	368
Total RAM Capacity	480 GB	1440 GB	2880 GB	5760 GB
Number of Exadata Storage Servers	3	3	6	12
Total Raw Flash Storage Capacity	19.2 TB	76.8 TB	153.6 TB	307.2 TB
Total Raw Disk Storage Capacity	144 TB	360 TB	720 TB	1440 TB
Total Usable Storage Capacity	42 TB	105.9 TB	211.8 TB	423.6 TB
Total Number of VM Clusters per System	6	6	12	12
Maximum Number of VMs	6	6	6	6

Exadata Cloud Management Interfaces

Exadata Database Service on Cloud@Customer provides a variety of management interfaces to fit your use case and automation needs.

- Introduction to Exadata Cloud Management Interfaces
 The Exadata Cloud resources on Oracle Cloud Infrastructure (OCI) are created and managed through a variety of interfaces provided to fit your different management use cases.
- OCI Control Plane Interfaces
- Local VM Command-Line Interfaces

Introduction to Exadata Cloud Management Interfaces

The Exadata Cloud resources on Oracle Cloud Infrastructure (OCI) are created and managed through a variety of interfaces provided to fit your different management use cases.

The various interfaces include:

- OCI Console interface and automation tools, see Using the Console
- Application Programming Interfaces (APIs)
- Command-Line Interfaces (CLIs)

The management interfaces are grouped into two primary categories:

- OCI Control Plane Interfaces
- Local Exadata Cloud VM CLIs



For more information and best practices on how these interfaces align for various Exadata Cloud database management use cases, refer to My Oracle Support note: Exadata Cloud API/CLI Alignment Matrix (Doc ID 2768569.1).

Related Topics

- Using the Console
- https://support.oracle.com/epmos/faces/DocContentDisplay?id=2768569.1

OCI Control Plane Interfaces

The OCI APIs are typical REST APIs that use HTTPS requests and responses. The OCI Console, an intuitive, graphical interface for creating and managing your Exadata Cloud and other OCI resources, is one of the interfaces to the OCI APIs. When looking to develop automation utilizing the OCI APIs, a number of additional interfaces including: kits, tools and plug-ins, are provided to facilitate development and simplify the management of OCI resources. A subset of these APIs apply to Exadata Cloud resources and its infrastructure. Each of these interfaces can be used to accomplish the same functionality, all calling the OCI APIs, and are provided to enable flexibility and choice depending on preference and use case.

- Command Line Interface (CLI): The OCI CLI is a small footprint tool that you can
 use on its own or with the Console to complete Exadata Cloud resource and other
 OCI tasks. The CLI provides the same core functionality as the Console, plus
 additional commands. Some of these, such as the ability to run scripts, extend the
 Console's functionality.
- Software Development Kits (SDK): OCI provides SDKs to enable the developing custom solutions for your Exadata Cloud and other OCI based services and applications.
- DevOps Tools and Plug-ins: These tools can simplify provisioning and managing infrastructure, enable automated processes and facilitate development. Tools include the OCI Terraform Provider used with Resource Manager and OCI Ansible Collection.
- Cloud Shell: Cloud Shell is a free-to-use, browser-based terminal, accessible
 from the OCI Console, that provides access to a Linux shell with pre-authenticated
 OCI CLI and other useful developer tools. You can use the shell to interact with
 Exadata Cloud and other OCI resources, follow labs and tutorials, and quickly run
 OCI CLI commands.



- Appendix and Reference: This general reference shows how to configure the SDKs and other developer tools to integrate with Oracle Cloud Infrastructure services.
- REST APIs: This complete reference provides details on the Oracle Cloud Infrastructure REST APIs, including descriptions, syntax, endpoints, errors, and signatures. Exadata Cloud at Customer specific OCI REST APIs can be found throughout the documentation in the *Using the API* sections:
 - Using the API to Manage Exadata Cloud@Customer Infrastructure
 - Using the API to Manage Exadata Cloud@Customer Backup Destinations
 - Using the API to Manage Exadata Cloud@Customer VM Clusters
 - Using the API to Create Oracle Database Home on Exadata Cloud@Customer
 - Using the API to Manage Oracle Database Home on Exadata Cloud@Customer
 - Using the API to Manage Oracle Database Components
 - Using the API to Manage Data Guard Associations on an Exadata Cloud@Customer System
 - Using the API to Manage Database Backup and Recovery
 - Using the API to Patch an Exadata Cloud@Customer System

Related Topics

- Command Line Interface (CLI)
- Software Development Kits
- DevOps Tools and Plug-ins
- Terraform Provider
- Resource Manager
- Ansible Collection
- Cloud Shell
- Appendix and Reference
- REST APIs
- Using the API to Manage Exadata Cloud@Customer Infrastructure
 Oracle Exadata Database Service on Cloud@Customer uses the same API as Oracle
 Cloud Infrastructure.
- Using the API to Manage Exadata Cloud@Customer Backup Destinations
 Review the list of API calls to manage your Exadata Database Service on
 Cloud@Customer backup destinations.
- Using the API to Manage Exadata Cloud@Customer VM Clusters
 Review the list of API calls to manage your Exadata Database Service on
 Cloud@Customer VM cluster networks and VM clusters.
- Using the API to Create Oracle Database Home on Exadata Cloud@Customer
 To create an Oracle Database home, review the list of API calls.
- Using the API to Manage Oracle Database Home on Exadata Database Service on Cloud@Customer
 - Review the list of API calls to manage Oracle Database home.



- Using the API to Manage Oracle Database Components
 Use various API features to help manage your databases on Oracle Exadata
 Database Service on Cloud@Customer.
- Using the API to Manage Data Guard Associations on an Exadata Database Service on Cloud@Customer System
 Learn how to use the API to manage Data Guard associations on an Exadata Database Service on Cloud@Customer system.
- Using the API to Manage Database Backup and Recovery
 Learn how to use the API to manage database backup and recovery with Oracle Exadata Database Service on Cloud@Customer.
- Using the API for Patching and Updating VM Cluster and Database Homes
 Use various API features to help manage patching an Oracle Exadata Database
 Service on Cloud@Customer system.

Local VM Command-Line Interfaces

In addition to the OCI REST-based APIs, CLI utilities located on the VM guests, provisioned as part of the VM clusters on the Exadata Cloud Infrastructure, are available to perform various lifecycle and administration operations.

The best practice is to use these utilities when a corresponding OCI API is not available or the Exadata Cloud@Customer is in a disconnected mode.

The utilities include:

- dbaascli: Use the dbaascli utility to perform various database lifecycle and administration operations on the Exadata Cloud Service such as
 - changing the password of a database user
 - starting a database
 - managing pluggable databases (PDBs)
 - scaling the CPU core count in disconnected mode
- bkup_api: Use the bkup_api utility to perform various backup and recovery operations on the Exadata Cloud Service such as creating an on-demand backup of a complete database or an individual pluggable database (PDB), or to customize backup settings used by the automatic backup configuration
- **ExaCLI:** Use the ExaCLI command-line utility to perform monitoring and management functions on Exadata storage servers in the Exadata Cloud.

These utilities are provided in addition to, and separate from, the OCI API-based interfaces listed above. To use the local VM command-line utilities, you must be connected to a virtual machine in an Exadata Cloud VM cluster and use the VM operating system user security, not the OCI user security, for execution. The utilities can be used to perform operations if the Exadata Cloud@Customer is disconnected from the OCI Control Plane. Most operations executed by these utilities sync their changes back to the OCI Control Plane using a process called DB Sync. However, there can be operations not synced with the Control Plane.

The cloud tooling software on the virtual machines, containing these CLI utilities, is automatically updated by Oracle on a regular basis. If needed, the tooling can be updated manually by following the instructions in *Updating Cloud Tooling Using dbaascli*.



Related Topics

- About Using the dbaascli Utility on Exadata Database Service on Cloud@Customer
 You can use the dbaascli utility to perform various database lifecycle and administration
 operations on Exadata Cloud@Customer such as creating an Oracle Database, patching
 an Oracle Database, managing pluggable databases (PDBs), scaling the CPU core count
 in disconnected mode, and more.
- Creating an On-Demand Backup by Using the bkup_api Utility
 You can use the bkup_api utility to create an on-demand backup of a complete
 database or an individual pluggable database (PDB):
- Customizing Backup Settings by Using a Generated Configuration File
 You can customize backup settings for a database deployment by generating a file
 containing the current customizable settings, editing the file, and then using the file to
 update the backup settings.
- Monitoring and Managing Exadata Storage Servers with ExaCLI
 Learn to use the ExaCLI command-line utility to perform monitoring and management
 functions on Exadata storage servers in the Exadata Cloud Service.
- Updating Cloud Tooling Using dbaascli
 To update the cloud tooling release for Oracle Exadata Database Service on Cloud@Customer, complete this procedure.



What's New in Oracle Exadata Database Service on Cloud@Customer Gen2

Oracle is constantly adding new capabilities to Oracle Exadata Database Service on Cloud@Customer. This section provides a brief overview of new features as they are released.



For information on new features for Autonomous Database on Oracle Exadata Cloud@Customer see What's New in ADB-D on Oracle Exadata Cloud@Customer

- Concurrently Create or Terminate Oracle Databases in a VM Cluster
- Support for Rack Serial Number as a System Tag
- Support for DB Home Minor Version Selection (N-3)
- VM Guest Exadata OS Image Major Version Update
- Database Service Events
- Control Plane Server (CPS) Offline Diagnostic Report
- Enhanced Infrastructure Maintenance Controls
- Manage Pluggable Databases on Exadata Cloud@Customer
- Allow Customers to Choose Data Guard Type
- Specify the Same SID for Primary and Standby Databases in a Data Guard Association
- Specify db_unique_name and SID for Primary and Standby Databases in Data Guard Association
- VM Cluster Node Subsetting
- X9M-2 System Support
- Customize SCAN Listener Port
- Creating DG Association/Standby Database Using Existing Database Home
- Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster
- Updating Guest VM Operating System
- Upgrading Oracle Databases
- Download Network Validation Report
- Elastic Storage Expansion
- Oracle Database Software Images
- Exadata Cloud@Customer Infrastructure Patching Automation



- Customer Maintenance Contacts
- X8M-2 System Support
- Enable and Manage Data Guard Associations
- Oracle Exadata Cloud@Customer Deployment Assistant
- Oracle Grid Infrastructure and Oracle Database Patching
- Per-Second Billing for OCPU Usage
- Shared Database Home Resource Tags
- Create and Manage Multiple Virtual Machines per Exadata System (MultiVM)
- Scale OCPUs Without Cloud Connectivity
- Configure Oracle Database Character Set and National Character Set
- Specify a Time Zone While Provisioning Oracle Exadata Database Service on Cloud@Customer Infrastructure
- Shared Database Homes for Oracle Exadata Database Service on Cloud@Customer
- X7-2 System Support

Concurrently Create or Terminate Oracle Databases in a VM Cluster

Services: Database

Release Date: July 22, 2022

With this enhancement, you can now concurrently create or terminate Oracle databases even if the VM cluster is in the **Updating** state.

- The number of databases that can be created on a cluster depends on the
 available memory on the VMs. For each database, by default, 12.6 GB (7.6 GB for
 SGA and 5 GB for PGA) is allocated if the VM has greater than 60 GB of memory.
 If the VM has less than or equal to 60 GB, then 6.3 GB (3.8 GB for SGA and 2.5
 GB for PGA) is allocated. Also, Grid Infrastructure and ASM consume some
 memory, approximately 2 to 4 GB.
- A database that is being created cannot be terminated. You can, however, terminate other databases in the VM Cluster.

Support for Rack Serial Number as a System Tag

Services: Database

Release Date: July 19, 2022

This enhancement is to display the Exadata cloud@Customer rack serial number in the OCI console under the **Infrastructure details** page in the **General Information** section. The serial number may be required when creating an SR or during a service call.



Support for DB Home Minor Version Selection (N-3)

Services: Database

Release Date: May 23, 2022

Provision a DB Home using a major version and RU version of your choice.

While provisioning, if you opt to use **Oracle Provided Database Software Images** as the image type, then you can use the **Display all available versions** switch to choose from all available PSUs and RUs. The most recent release for each major version is indicated with a **latest** label.

For the Oracle Database major version releases available in Oracle Cloud Infrastructure, images are provided for the current version plus the three most recent older versions (N through N - 3). For example, if an instance is using Oracle Database 19c, and the latest version of 19c offered is 19.8.0.0.0, images available for provisioning are for versions 19.8.0.0.0, 19.7.0.0, 19.6.0.0 and 19.5.0.0.

Related Topics

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer

To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.

VM Guest Exadata OS Image Major Version Update

Services: Database

Release Date: April 20, 2022

In addition to performing minor version updates to the Exadata VM Cluster images, you can update to a new major version if the currently installed version is 19.2 or higher. For example, if the Exadata Cloud@Customer VM cluster is on version 20, then you can update it to version 21.

Related Topics

Supported Software Versions and Update Restrictions
 Review the list of supported software versions and update restrictions.

Database Service Events

Services: Database

Release Date: April 12, 2022

Database Service Events feature implementation enables you to get notified about health issues with your Oracle Databases or other components on the Guest VM.



Related Topics

- Overview of Database Service Events
- Receive Notifications about Database Service Events
 Subscribe to the Database Service Events and get notified.
- Database Service Event Types
 Review the list of event types that the Database Service emits.
- Temporarily Restrict Automatic Diagnostic Collections for Specific Events
 Use the tfact1 blackout command to temporarily suppress automatic diagnostic
 collections.
- Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to Enable or Disable Diagnostics Notification
 You can enable or disable diagnostics collection for your Guest VMs after provisioning the VM cluster.

Control Plane Server (CPS) Offline Diagnostic Report

Services: Database

Release Date: March 01, 2022

Control Plane Server (CPS) offline diagnostic report assists you in troubleshooting connectivity issues between the CPS and OCI endpoints.

It is your responsibility to maintain and troubleshoot the network infrastructure of your data center. To connect to OCI Region, Exadata Cloud@Customer Gen2 depends on your infrastructure and reliability. Exadata Cloud@Customer's connectivity from OCI Region to Exadata Cloud@Customer's Control Plane Servers (CPS) may be impacted by any changes you make to your infrastructure. Nevertheless, Oracle does not have any control over your firewall or networking.

In the event that the connection between CPS and OCI is broken, the Control Plane Server (CPS) Offline Diagnostic Report provides information that may help you in diagnosing problems in your network infrastructure.

To view the report, do the following:

- Find the CPS IP addresses.
 For more information, see Using the Console to View Exadata Infrastructure Network Configuration Details.
- 2. From your local network, access the report over HTTP.
 To view the report in HTML format, use http://cpspublicIp>:18080/report

To view the report in JSON format, use http://<CPSPublicIP>:18080/report/json



Note:

- You cannot enable or disable Control Plane Server (CPS) Offline Diagnostic Report if the Exadata Infrastructure is in DISCONNECTED mode.
- Every hour, even if no issues are detected on the CPS, the system will still
 generate and save a diagnostic report in HTML and JSON formats. Whenever a
 connectivity issue arises between CPS and OCI endpoints, the system
 generates a report immediately.

For more information, see ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side (Doc ID 2745571.1).

Related Topics

- Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure
 - To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.
- Enabling or Disabling the Control Plane Server Diagnostic Offline Report To enable or disable CPS offline report, use this procedure.
- Using the Console to View Exadata Infrastructure Network Configuration Details
 To view network configuration details, follow these steps. Save this information for later
 use to troubleshoot if you face network issues.
- ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side (Doc ID 2745571.1)

Enhanced Infrastructure Maintenance Controls

Services: Database

Release Date: March 01, 2022

The Exadata Cloud@Customer Oracle-managed infrastructure maintenance now allows greater control and visibility including:

- Choice of rolling and non-rolling maintenance methods.
- Ability to perform custom actions before maintenance on each database server by having the automated maintenance wait before shutting down VMs until the maintenance has been resumed or the configured timeout has reached.
- Visibility into the database server update order.
- Granular tracking of the maintenance progress at a component level.

Related Topics

 Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.



 View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.

 Using the API to Manage Exadata Cloud@Customer Infrastructure Maintenance Controls

Oracle Exadata Cloud@Customer uses the same API as Oracle Cloud Infrastructure to manage infrastructure maintenance controls.

- Configure Oracle-Managed Infrastructure Maintenance
 Oracle performs the updates to all of the Oracle-managed infrastructure
 components on Exadata Cloud@Customer.
- Using the Console to Configure Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a
 maintenance window to determine the time your quarterly infrastructure
 maintenance will begin.
- Exadata Cloud@Customer Infrastructure Maintenance Event Types
 Review the list of event types that Exadata Cloud@Customer Infrastructure
 Maintenance emits.

Manage Pluggable Databases on Exadata Cloud@Customer

Services: Database

Release Date: February 16, 2022

Create and manage pluggable databases (PDBs) in Oracle Exadata Cloud@Customer systems using the Console and APIs.

Related Topics

 Manage Pluggable Databases on Exadata Database Service on Cloud@Customer Learn to manage pluggable databases on Exadata Cloud@Customer.

Allow Customers to Choose Data Guard Type

Services: Database

Release Date: February 16, 2022

Select a Data Guard type, Active Data Guard or Data Guard, based on the Oracle Database software license type you have deployed.

Related Topics

 Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System

Learn to enable Data Guard association between databases.



Using the Console To View and Edit Data Guard Associations
 You can switch between Data Guard types based on the Oracle Database software license type you have deployed.

Specify the Same SID for Primary and Standby Databases in a Data Guard Association

Services: Database

Release Date: February 16, 2022

The same SID prefix used for the primary database can now also be used for the standby database when creating a Data Guard Association.

Related Topics

 Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System

Learn to enable Data Guard association between databases.

Specify db_unique_name and SID for Primary and Standby Databases in Data Guard Association

Services: Database

Release Date: October 20, 2021

Oracle databases are identified by three important names: db_name, db_unique_name, and instance_name (SID). This new feature provides consistent database naming controls across primary and standby databases and allows entering the db_unique_name and the SID prefix on both primary and standby databases. This helps support different naming conventions to manage the Oracle Database fleet.

Related Topics

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System
 Learn to enable Data Guard association between databases.

VM Cluster Node Subsetting

Services: Database

Release Date: October 19, 2021



VM Cluster Node Subsetting feature is now available in all OCI commercial regions.



VM Cluster Node Subsetting enables you to allocate a subset of database servers to new and existing VM clusters to enable maximum flexibility in the allocation of compute (CPU, memory, local storage) resources.

Related Topics

Overview of VM Cluster Node Subsetting

VM Cluster Node Subsetting enables you to allocate a subset of database servers to new and existing VM clusters to enable maximum flexibility in the allocation of compute (CPU, memory, local storage) resources.

Using the Console to Create a VM Cluster

To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.

- Using the Console to Add VMs to a Provisioned Cluster
 To add virtual machines to a provisioned cluster, use this procedure.
- Using the Console to View a List of DB Servers on an Exadata Infrastructure
 To view a list of database server hosts on an Oracle Exadata Cloud@Customer
 system, use this procedure.
- Using the Console to Remove a VM from a VM Cluster
 To remove a virtual machine from a provisioned cluster, use this procedure.
- Permissions Required for Each API Operation
 Review the list of API operations for Exadata Database Service on Cloud@Customer resources in a logical order, grouped by resource type.
- dbServers

Review the list of permissions and API operations for dbServers resource-type.

- VM Node Subsetting Event Types
 Review the list of event types that VM Node Subsetting emits.
- Adding a VM to a VM Cluster Fails
- CPU Offline Scaling Fails

X9M-2 System Support

Services: Database

Release Date: September 28, 2021

Oracle Exadata Cloud@Customer comes in different infrastructure shapes to support workloads of different sizes. In this release, the capability of Oracle Exadata Cloud@Customer has been extended to support X9M-2 system.

For more information, see:

- System Configuration Options for Oracle Exadata Cloud@Customer
- Oracle Exadata X9M-2 System Model Specifications
- Estimating How Much Local Storage You Can Provision to Your VMs
- Overview of Elastic Storage Expansion



Related Topics

 System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

- Oracle Exadata X9M-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.
- Estimating How Much Local Storage You Can Provision to Your VMs
- Overview of Elastic Storage Expansion
 With elastic storage expansion, you can dynamically increase your storage capacity to
 meet your growing workload requirements.

Customize SCAN Listener Port

Services: Database

Release Date: August 27, 2021

You can now specify a SCAN listener port (TCP/IP) within the permissible range while creating a VM cluster network resource. For more information, see:

- Using the Console to Create a VM Cluster Network
- Using the Console to View SCAN Listener Port Configured

Related Topics

- Using the Console to Create a VM Cluster Network
 To create your VM cluster network with the Console, be prepared to provide values for
 the fields required for configuring the infrastructure.
- Using the Console to View SCAN Listener Port Configured
 You can only edit a VM cluster network that is not associated with a VM cluster.

Creating DG Association/Standby Database Using Existing Database Home

Services: Database

Release Date: August 08, 2021

Select an existing Database Home or create a new one for the standby while enabling Data Guard association. For more information, see *Using the Console to Enable Data Guard on an Exadata Cloud@Customer System*.

Related Topics

 Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System

Learn to enable Data Guard association between databases.



Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster

Services: Database

Release Date: July 20, 2021

Upgrade Oracle Grid Infrastructure (GI) on an Exadata Cloud@Customer VM cluster using the Oracle Cloud Infrastructure Console or APIs. For more information, see Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster.

Related Topics

 Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster Learn to upgrade Oracle Grid Infrastructure on an Exadata Cloud@Customer VM cluster using the Oracle Cloud Infrastructure Console or API.

Updating Guest VM Operating System

Services: Database

Release Date: July 20, 2021

Update the operating system image on Exadata Cloud@Customer VM cluster nodes in an automated manner from the OCI console and APIs. For more information, see *Updating Guest VM Operating System*.

Related Topics

Updating Guest VM Operating System
 Learn to update the operating system image on Exadata Cloud@Customer VM cluster nodes in an automated manner from the OCI console and APIs.

Upgrading Oracle Databases

Services: Database

Release Date: July 20, 2021

Upgrade Oracle Database 19c (Long Term Release) using the Console and the APIs. For more information, see *Upgrading Oracle Databases*.

Related Topics

Upgrading Oracle Databases
 Learn to upgrade Oracle Database 19c (Long Term Release) using the Console and the API.

Download Network Validation Report

Services: Database

Release Date: July 20, 2021



Validate and inspect the network validation failure report without active involvement from Oracle Cloud Ops in troubleshooting networking configuration issues. For more information, see *Using the Console to Download Network Validation Report*.

Related Topics

Using the Console to Download Network Validation Report
 Learn to validate and inspect the network validation failure report without active
 involvement from Oracle Cloud Ops in troubleshooting networking configuration issues.

Elastic Storage Expansion

Services: Database

Release Date: June 15, 2021

Expand the storage associated with your Exadata Cloud@Customer infrastructure and make them available for VM cluster allocation, both during and post infrastructure provisioning. For more information, see:

- Overview of Elastic Storage Expansion
- Using the Console to Scale Infrastructure Storage
- Using the Console to Download Scale Infrastructure Storage Configuration File
- Using the Console to Activate New Storage Servers
- Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption
- Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity
- Permissions Required for Each API Operation
- exadata-infrastructures
- Storage Expansion Event Types

Related Topics

- Overview of Elastic Storage Expansion
 With elastic storage expansion, you can dynamically increase your storage capacity to
 meet your growing workload requirements.
- Using the Console to Scale Infrastructure Storage
 To scale infrastructure storage, complete this procedure.
- Using the Console to Download Scale Infrastructure Storage Configuration File
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this
 procedure.
- Using the Console to Activate New Storage Servers
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.
- Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption
 - To make storage capacity from the new servers for VM clusters consumption, complete this procedure.



 Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity

To view the storage capacity from the new storage server use this procedure.

 Permissions Required for Each API Operation
 Review the list of API operations for Exadata Database Service on Cloud@Customer resources in a logical order, grouped by resource type.

exadata-infrastructures

Review the list of permissions and API operations for exadata-infrastructures resource-type.

• Storage Expansion Event Types
Review the list of event types that storage expansion emits.

Oracle Database Software Images

Services: Database

Release Date: April 08, 2021

Use Database Software Image resource type to create databases and Oracle Database Homes, and to patch databases. For more information, see:

- Oracle Database Software Images
- Using the Console to Create Oracle Database Home on Exadata Cloud@Customer
- Using the Console to Perform a Patch Operation on a Database Home

Related Topics

- Manage Oracle Database Software Images
 Learn about Database Software Image resource type and how you can use it to create Oracle Databases and Oracle Database Homes and to patch databases.
- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer

To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.

 Using the Console to Perform a Patch Operation on a Database Home Learn to apply patches on a Database Home.

Exadata Cloud@Customer Infrastructure Patching Automation

Services: Database

Release Date: December 08, 2020

You can now schedule a maintenance window for Oracle-managed Exadata Cloud@Customer infrastructure patching. For more information, see Using the Console to Configure Oracle-Managed Infrastructure Updates.



Customer Maintenance Contacts

Services: Database

Release Date: September 22, 2020

Release Notes: Exadata Cloud@Customer: Customer Maintenance Contacts

Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.

Add a primary maintenance contact and optionally add a maximum of nine secondary contacts. Both the primary and secondary contacts receive all notifications about hardware replacement, network issues, and software maintenance runs.

You can promote any secondary contacts as the primary anytime you want. When you promote a secondary contact to primary, the current primary contact will be demoted automatically to secondary.

For more information, see:

- Using the Console to Create Infrastructure
- Managing Infrastructure Maintenance Contacts

Related Topics

 Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.

Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.

X8M-2 System Support

Services: Database

Release Date: August 18, 2020

Release Notes: Exadata Cloud@Customer: X8M-2 System Support

Oracle Exadata Cloud@Customer comes in different infrastructure shapes to support workloads of different sizes. In this release, the capability of Oracle Exadata Cloud@Customer has been extended to support X8M-2 system.

For more information, see:

- System Configuration Options for Oracle Exadata Cloud@Customer
- Oracle Exadata Cloud@Customer X8M-2 System Specifications
- Network Requirements for Oracle Exadata Cloud@Customer



Related Topics

 System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

- Oracle Exadata X8M-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.
- Network Requirements for Oracle Exadata Database Service on Cloud@Customer
 To provide secure and reliable network connectivity for different application and
 management functions, Exadata Database Service on Cloud@Customer uses
 different networks.

Enable and Manage Data Guard Associations

Services: Database

Release Date: August 18, 2020

 Release Notes: Exadata Cloud@Customer: Enable and Manage Data Guard Associations

Oracle Data Guard ensures high availability, data protection, and disaster recovery for enterprise data.

Enable a Data Guard association between databases, change the role of a database in a Data Guard association using either a switchover or a failover operation, and reinstate a failed database.

For more information, see:

- Using Oracle Data Guard with Exadata Cloud@Customer
- Using the API To Manage Data Guard Associations on an Exadata Cloud@Customer System
- Permissions Required for Each API Operation
- Data Guard Event Types

Related Topics

- Use Oracle Data Guard with Exadata Database Service on Cloud@Customer
 Learn to configure and manage Data Guard associations in your VM cluster.
- Using the API to Manage Data Guard Associations on an Exadata Database Service on Cloud@Customer System
 - Learn how to use the API to manage Data Guard associations on an Exadata Database Service on Cloud@Customer system.
- Permissions Required for Each API Operation
 Review the list of API operations for Exadata Database Service on Cloud@Customer resources in a logical order, grouped by resource type.
- Data Guard Event Types
 Review the list of event types that Data Guard associations emit.

Oracle Exadata Cloud@Customer Deployment Assistant



Services: Database

Release Date: August 08, 2020

Release Notes: Exadata Cloud@Customer: Deployment Assistant

Oracle Exadata Cloud@Customer Deployment Assistant is an automated installation and configuration tool that enables you to set up your Oracle Exadata Cloud@Customer machine and create an Oracle Database instance with minimal effort.

For more information, see Oracle Exadata Cloud@Customer Deployment Assistant

Oracle Grid Infrastructure and Oracle Database Patching

Services: Database

Release Date: July 28, 2020

 Release Notes: Exadata Cloud@Customer: Oracle Grid Infrastructure and Oracle Database Patching

You can now view, pre-check, and apply Oracle Grid Infrastructure and Oracle Database patches by using the Oracle Cloud Infrastructure Console, API, or CLI. This functionality includes the ability to easily patch a database by moving it to a different Database Home. Similarly, you can easily roll back the version of the database by moving it back to its original Database Home.

For information and instructions, see:

- Patching and Updating an Exadata Cloud@Customer System
- Troubleshooting Exadata Cloud@Customer Systems
- Database and Grid Infrastructure Patching Event Types

Related Topics

- Patching and Updating an Exadata Database Service on Cloud@Customer System
 Learn how to perform patching operations on Exadata database virtual machines and
 Database Homes by using the Console, API, or the CLI.
- Troubleshooting Exadata Database Service on Cloud@Customer Systems
 These topics cover some common issues you might run into and how to address them.
- Database and Grid Infrastructure Patching Event Types
 Review the list of event types that Database and Grid Infrastructure Patching emit.

Per-Second Billing for OCPU Usage

Services: Database

Release Date: July 14, 2020

Release Notes: Exadata Cloud@Customer: Per-Second Billing for OCPU Usage

Oracle Exadata Database Service on Cloud@Customer Gen2 uses per-second billing for OCPUs. This means that OCPU usage is billed by the second, with a minimum usage period of 1 minute.



Shared Database Home Resource Tags

Services: Database

Release Date: June 23, 2020

 Release Notes: Exadata Cloud@Customer: Shared Database Home Resource Tags

Add, update, and remove tags applied to a shared Database Home resource.

For information and instructions, see:

- Using the Console to Create Oracle Database Home on Exadata Cloud@Customer
- Using the Console to Create a Database

Related Topics

 Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer

To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.

Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.

Create and Manage Multiple Virtual Machines per Exadata System (MultiVM)

Services: Database

Release Date: June 13, 2020

 Release Notes: Exadata Cloud@Customer: Create and Manage Multiple Virtual Machines per Exadata System (MultiVM)

Slice Exadata resources into multiple virtual machines. Define up to 8 multiple virtual machine (VM) clusters on an Oracle Exadata Database Service on Cloud@Customer, and specify how the overall system resources are allocated to them.

For information and instructions, see:

- Using the Console to Create a VM Cluster
- Using the Console to Scale the Resources on a VM Cluster
- VM Cluster Event Types

Related Topics

Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.



- Using the Console to Scale the Resources on a VM Cluster
 Starting in Exadata Database Service on Cloud@Customer Gen2, you can scale up or down multiple resources at the same time. You can also scale up or down resources one at a time.
- VM Cluster Event Types
 Review the list of event types that VM clusters emit.

Scale OCPUs Without Cloud Connectivity

Services: Database

Release Date: June 13, 2020

Release Notes: Exadata Cloud@Customer: Scale OCPUs Without Cloud Connectivity

Oracle Exadata Database Service on Cloud@Customer is considered to be in a "disconnected" mode when there is a loss of connectivity with the Database service control plane running on Oracle Cloud Infrastructure. Scale the CPU core count up or down for a virtual machine in a VM cluster in disconnected mode.

For information and instructions, see:

- About Using the dbaascli Utility on Exadata Cloud@Customer
- dbaascli cpuscale get_status
- dbaascli cpuscale update
- Exadata Infrastructure Event Types

Related Topics

- About Using the dbaascli Utility on Exadata Database Service on Cloud@Customer
 You can use the dbaascli utility to perform various database lifecycle and administration
 operations on Exadata Cloud@Customer such as creating an Oracle Database, patching
 an Oracle Database, managing pluggable databases (PDBs), scaling the CPU core count
 in disconnected mode, and more.
- dbaascli cpuscale get_status

To check the status of current or last scale request performed when network connectivity between the Control Plane Server and OCI region is disrupted, use the <code>dbaasclicupuscale get status command</code>.

dbaascli cpuscale update

To scale up or down the CPU core count for a virtual machine in a VM cluster when network connectivity between the Control Plane Server and OCI region is disrupted, use the dbaascli cpuscale update command.

Exadata Infrastructure Event Types
 Review the list of event types that Exadata Infrastructure instances emit.

Configure Oracle Database Character Set and National Character Set

Services: Database

Release Date: May 7, 2020

 Release Notes: Exadata Cloud@Customer: Configure Oracle Database Character Set and National Character Set

Before you create the database, decide the character set that you want to use.

After a database is created, changing its character set is usually very expensive in terms of time and resources. Such operations may require converting all character data by exporting the whole database and importing it back. Therefore, it is important that you carefully select the database character set at installation time.

For information and instructions, see *Using the Console to Create a Database*.

Related Topics

Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.

Specify a Time Zone While Provisioning Oracle Exadata Database Service on Cloud@Customer Infrastructure

Services: Database

Release Date: May 7, 2020

 Release Notes: Exadata Cloud@Customer: Specify a Time Zone While Provisioning Oracle Exadata Cloud@Customer Infrastructure

The default time zone for the Oracle Exadata Database Service on Cloud@Customer infrastructure is UTC. The time is displayed in the UTC format at the operating system and database level. You can choose a different Time Zone while provisioning your Oracle Exadata Database Service on Cloud@Customer infrastructure. However, Oracle recommends setting the database time zone to UTC (0:00), as no conversion of time zones will be required.

For information and instructions, see *Using the Console to Create Infrastructure*.

Related Topics

 Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.

Shared Database Homes for Oracle Exadata Database Service on Cloud@Customer

Services: Database

Release Date: March 31, 2020

Release Notes: Exadata Cloud@Customer: Shared Database Homes

Use a single Oracle Home for multiple databases. Besides saving space, sharing an Oracle Database Home with multiple databases provides the following benefits:



- One-off patches needed for multiple databases only need to be applied to fewer Oracle Homes, reducing patching overhead and administration.
- Space savings, for example, by having only a single Oracle Home per Oracle software version (though multiple are possible).
- Oracle Database patching through moving databases between homes instead of patching the DB Home.
- Fallback to move a database to a lower DB Home version without having to rollback a patch.
- Software installation of new Homes and new versions is not interrupting operation of database.
- Patching time of a database is reduced by not having to additionally lay down Oracle binaries.

Use the Oracle Cloud Infrastructure Console, API, or CLI to create and manage shared Oracle Database Homes for your databases on an Oracle Exadata Database Service on Cloud@Customer.

For information and instructions, see *Create Oracle Database Homes on an Exadata Cloud@Customer Systems*.

Related Topics

 Create Oracle Database Homes on an Exadata Database Service on Cloud@Customer System

Learn to create Oracle Database Homes on Exadata Database Service on Cloud@Customer.

X7-2 System Support

Services: Database

Release Date: March 19, 2020

Release Notes: Exadata Cloud@Customer: X7-2 System Support

Oracle Exadata Database Service on Cloud@Customer comes in different infrastructure shapes to support workloads of different sizes. In this release, the capability of Oracle Exadata Database Service on Cloud@Customer has been extended to support X7-2 system.

For more information, see *Oracle Exadata X7-2 System Model Specifications*.

Related Topics

Oracle Exadata X7-2 System Model Specifications
 Review the technical specifications of available Exadata System Shapes.



Preparing for Exadata Database Service on Cloud@Customer

Review OCI as well as the site, network and storage requirements to prepare and deploy Exadata Database Service on Cloud@Customer in your data center.

- Oracle Cloud Infrastructure (OCI) Requirements for Oracle Exadata Database Service on Cloud@Customer
 - Learn the basic concepts to get started using Oracle Cloud Infrastructure.
- Site Requirements for Oracle Exadata Database Service on Cloud@Customer Review the requirements for provisioning Oracle Exadata Database Service on Cloud@Customer at your site.
- Network Requirements for Oracle Exadata Database Service on Cloud@Customer Review the network requirements for provisioning Oracle Exadata Database Service on Cloud@Customer at your site.
- Storage Configuration Requirements for Oracle Exadata Database Service on Cloud@Customer
 - Review the storage requirements for the ASM disk groups and VM file systems to plan the best options for your enterprise needs.
- Checklists for Exadata Database Service on Cloud@Customer Deployments
 To determine your readiness for an Exadata Database Service on Cloud@Customer
 deployment, review the deployment checklists.

Oracle Cloud Infrastructure (OCI) Requirements for Oracle Exadata Database Service on Cloud@Customer

Learn the basic concepts to get started using Oracle Cloud Infrastructure.

Gen 2 Exadata Cloud@Customer is managed by the Oracle Cloud Infrastructure (OCI) control plane. The Exadata Database Service on Cloud@Customer resources are deployed in your OCI Tenancy.

Before you can provision Exadata Database Service on Cloud@Customer infrastructure, your Oracle Cloud Infrastructure tenancy must be enabled to use Oracle Exadata Database Service on Cloud@Customer. Review the information in this publication for further details.

The following tasks are common for all OCI deployments, refer to the links in the Related Topics to find the associated Oracle Cloud Infrastructure documentation.

- Getting Started with OCI.
 If you are new to OCI, learn the basic concepts to get started by following the OCI Getting Started Guide.
- Setting Up Your Tenancy.
 After Oracle creates your tenancy in OCI, an administrator at your company will need to perform some set up tasks and establish an organization plan for your cloud resources and users. The information in this topic will help you get started.

- Managing Regions
 - This topic describes the basics of managing your region subscriptions.
- Managing Compartments
 - This topic describes the basics of working with compartments.
- Managing Users
 - This topic describes the basics of working with users.
- Managing Groups
 - This topic describes the basics of working with groups.
- Required IAM Policy for Exadata Database Service on Cloud@Customer
 Review the identity access management (IAM) policy for provisioning Oracle
 Exadata Database Service on Cloud@Customer systems.

Related Topics

- OCI Getting Started Guide
- Setting Up Your Tenancy
- Managing Regions
- Managing Compartments
- Managing Users
- Managing Groups

Required IAM Policy for Exadata Database Service on Cloud@Customer

Review the identity access management (IAM) policy for provisioning Oracle Exadata Database Service on Cloud@Customer systems.

A **policy** is an IAM document that specifies who has what type of access to your resources. It is used in different ways:

- An individual statement written in the policy language
- A collection of statements in a single, named "policy" document, which has an Oracle Cloud ID (OCID) assigned to it
- The overall body of policies your organization uses to control access to resources

A **compartment** is a collection of related resources that can be accessed only by certain groups that have been given permission by an administrator in your organization.

To use Oracle Cloud Infrastructure, you must be given the required type of access in a policy written by an administrator, whether you're using the Console, or the REST API with a software development kit (SDK), a command-line interface (CLI), or some other tool. If you try to perform an action, and receive a message that you don't have permission, or are unauthorized, then confirm with your administrator the type of access you've been granted, and which compartment you should work in.

For administrators: The policy in "Let database admins manage DB systems" lets the specified group do everything with databases, and related database resources.



If you're new to policies, then see "Getting Started with Policies" and "Common Policies". If you want to dig deeper into writing policies for databases, then see "Details for the Database Service".

For more details on writing policies specific to Exadata Cloud@Customer resources see "Policy Details for Exadata Cloud@Customer".

Related Topics

- Let database admins manage DB systems
- Getting Started with Policies
- Common Policies

package.

- Details for the Database Service
- Policy Details for Exadata Database Service on Cloud@Customer Learn to write policies to control access to Exadata Database Service on Cloud@Customer resources.

Site Requirements for Oracle Exadata Database Service on Cloud@Customer

Review the requirements for provisioning Oracle Exadata Database Service on Cloud@Customer at your site.

- Space Requirements for Oracle Exadata Database Service on Cloud@Customer Review the space requirements for each Exadata Database Service on Cloud@Customer X8 rack.
- Weight of Oracle Exadata Cloud X8 Racks
 Review and prepare to manage the weight of each Exadata Database Service on
 Cloud@Customer X8 rack.
- Receiving, Unpacking, and Access for Oracle Exadata Database Service on Cloud@Customer Racks
 Review and prepare the receiving area that is large enough for the Exadata Rack
- Flooring for Oracle Exadata Database Service on Cloud@Customer Racks
 Ensure that the Exadata Database Service on Cloud@Customer system is installed on raised flooring that is capable of supporting the Exadata Rack.
- Electrical Power for Oracle Exadata Database Service on Cloud@Customer Racks
 Exadata Database Service on Cloud@Customer can operate effectively over a wide
 range of voltages and frequencies.
- Temperature and Humidity Ranges for Oracle Exadata Database Service on Cloud@Customer
 - Excessive internal temperatures can result in full or partial shutdown of Exadata Database Service on Cloud@Customer system components.
- Ventilation for Oracle Exadata Database Service on Cloud@Customer Racks
 Always provide adequate space in front and behind the rack for proper ventilation.



Space Requirements for Oracle Exadata Database Service on Cloud@Customer

Review the space requirements for each Exadata Database Service on Cloud@Customer X8 rack.

Table 3-1 Space Requirements for Oracle Exadata

Description	Millimeters (mm)	Inches (")
Height	2000 mm	78.74"
Width	600 mm	23.62"
Depth	1237 mm with doors attached, from handle to handle	48.7"

Weight of Oracle Exadata Cloud X8 Racks

Review and prepare to manage the weight of each Exadata Database Service on Cloud@Customer X8 rack.

Model (X8)	Kilograms (kg)	Pounds (lbs)	
Base System	435.9 kg	961.1 lbs	
Quarter Rack	449.0 kg	989.8 lbs	
Half Rack	591.5 kg	1304.1 lbs	
Full Rack	883.9 kg	1948.7 lbs	

Receiving, Unpacking, and Access for Oracle Exadata Database Service on Cloud@Customer Racks

Review and prepare the receiving area that is large enough for the Exadata Rack package.

Description	Millimeters (mm)	Inches (")	
Shipping Height	2159 mm	85 inches	
Shipping Width	1219 mm	48 inches	
Shipping Depth	1575 mm	62 inches	

If your loading dock meets the height and ramp requirements for a standard freight carrier truck, then you can use a pallet jack to unload the rack. If the loading dock does not meet the requirements, then you must provide a standard forklift, or other means to unload the rack. You can also request that the rack is shipped in a truck with a lift gate.

Use a conditioned space to remove the packaging material to reduce particles before entering the data center. Allow enough space for unpacking it from its shipping cartons.

Use the information in the following table to ensure that there is a clear pathway for moving the Exadata Database Service on Cloud@Customer rack. Also, the entire



access route to the installation site should be free of raised-pattern flooring that can cause vibration.

Access Route Item	With Shipping Pallet	Without Shipping Pallet
Minimum door height	2184 mm (86 inches)	2040 mm (80.32 inches)
Minimum door width	1270 (50 inches)	640 mm (25.19 inches)
Minimum elevator depth	1625.6 mm (64 inches)	1240 mm (48.82 inches)
Maximum incline	6 degrees	6 degrees
Minimum elevator, pallet jack, and floor loading capacity	1134 kg (2500 lbs)	1134 kg (2500 lbs)

Flooring for Oracle Exadata Database Service on Cloud@Customer Racks

Ensure that the Exadata Database Service on Cloud@Customer system is installed on raised flooring that is capable of supporting the Exadata Rack.

The site floor and the raised flooring must be able to support the total weight of the Exadata Database Service on Cloud@Customer rack that you have selected. Review specifications accordingly.

Electrical Power for Oracle Exadata Database Service on Cloud@Customer Racks

Exadata Database Service on Cloud@Customer can operate effectively over a wide range of voltages and frequencies.

Reliability of Power Sources

Each rack must have a reliable power source. Damage can occur if the voltage ranges are exceeded. Electrical disturbances such as the following can damage Exadata Database Service on Cloud@Customer:

- Fluctuations caused by brownouts
- Wide and rapid variations in input voltage levels or in input power frequency
- Electrical storms
- Faults in the distribution system, such as defective wiring

To protect Exadata Database Service on Cloud@Customer from such disturbances, you should have a dedicated power distribution system, power-conditioning equipment, and lightning arresters or power cables to protect from electrical storms.

Power Distribution Unit Specifications

Each rack has two pre-installed power distribution units (PDUs). The PDUs accept different power sources. You must choose the type of PDU that is correct for your data center and the Exadata Database Service on Cloud@Customer rack.

Model (X8)	Minimum PDU Rating (kVA)
Base System	15 kVA
Quarter Rack	15 kVA
Half Rack	15 kVA



Model (X8)	Minimum PDU Rating (kVA)
Full Rack	22 kVA

The following list outlines the available PDUs for Exadata Database Service on Cloud@Customer, depending on your region. Follow each of the links to access detailed specifications for each PDU type:

- Americas, Japan, and Taiwan
 - Low-Voltage 15 kVA Single-Phase
 - Low-Voltage 15 kVA Three-Phase
 - Low-Voltage 22 kVA Single-Phase
 - Low-Voltage 24 kVA Three-Phase
- Europe, the Middle East and Africa (EMEA), and Asia Pacific (APAC), except for Japan and Taiwan
 - High-Voltage 15 kVA Three-Phase
 - High-Voltage 22 kVA Single-Phase
 - High-Voltage 24 kVA Three-Phase

Facility Power Requirements

To prevent catastrophic failures, design the input power sources to ensure that adequate power is provided to the PDUs.

Use dedicated AC breaker panels for all power circuits that supply power to the PDU. When planning for power distribution requirements, balance the power load between available AC supply branch circuits. In the United States of America and Canada, ensure that the overall system AC input current load does not exceed 80 percent of the branch circuit AC current rating.



Electrical work and installations must comply with applicable local, state, or national electrical codes.

PDU power cords are 4 meters (13.12 feet) long, and 1–1.5 meters (3.3–4.9 feet) of the cord is routed within the rack cabinet. The installation site AC power receptacle must be within 2 meters (6.6 feet) of the rack.

Circuit Breaker Requirements

If computer equipment is subjected to repeated power interruptions and fluctuations, then it is susceptible to a higher rate of component failure.

You are responsible for supplying the circuit breakers. One circuit breaker is required for each power cord. In addition to circuit breakers, provide a stable power source, such as an uninterruptible power supply (UPS) to reduce the possibility of component failures.



Use dedicated AC breaker panels for all power circuits that supply power to the server. Servers require grounded electrical circuits.



Electrical work and installations must comply with applicable local, state, or national electrical codes.

Electrical Grounding Guidelines

The cabinets for Oracle Exadata Rack are shipped with grounding-type power cords.

- Always connect the cords to grounded power outlets.
- Check the grounding type, because different grounding methods can be used, depending on your location.
- Refer to documentation such as IEC documents for the correct grounding method.
- Ensure that the facility administrator or qualified electrical engineer verifies the grounding method for the building, and performs the grounding work.

Temperature and Humidity Ranges for Oracle Exadata Database Service on Cloud@Customer

Excessive internal temperatures can result in full or partial shutdown of Exadata Database Service on Cloud@Customer system components.

Temperature and Humidity Ranges



Studies have shown that temperature increases of 10 degrees Celsius (15 degrees Fahrenheit) above 20 degrees Celsius (70 degrees Fahrenheit) reduce long-term electronics reliability by 50 percent.

Condition	Operating Requirement	Non-operating Requirement	Optimal Requirement
Temperature	5–32 degrees Celsius (59–89.6 degrees Fahrenheit)	-40–70 degrees Celsius (-40–158 degrees Fahrenheit)	21–23 degrees Celsius (70–74 degrees Fahrenheit)
Relative Humidity	10–90 percent relative humidity, non-condensing	Up to 93 percent relative humidity	45–50 percent, non- condensing
Altitude	3048 meters (10000 feet) maximum	12,000 meters (40000 feet) maximum	Maximum ambient temperature is reduced by 1 degree Celsius for every 300 meters of altitude over 900 meters above sea level.



Temperature and Humidity Guidelines

To minimize the chance of downtime because of component failure, set conditions to the optimal temperature and humidity ranges. Maintaining an Exadata Database Service on Cloud@Customer system for extended periods at or near the operating limits can significantly increase the potential for hardware component failure.

The ambient temperature range of 21–23 degrees Celsius (70–74 degrees Fahrenheit) is optimal for server reliability and operator comfort. Most computer equipment can operate in a wide temperature range, but near 22 degrees Celsius (72 degrees Fahrenheit) is desirable because it is easier to maintain safe humidity levels. Operating in this temperature range provides a safety buffer in case the air conditioning system fails for some time.

The ambient relative humidity range of 45–50 percent is suitable for safe data processing operations. Most computer equipment can operate in a wide range (20–80 percent), but the range of 45–50 percent is recommended for the following reasons:

- The optimal range helps protect computer systems from corrosion problems associated with high humidity levels..
- The optimal range provides the greatest operating time buffer in case the air conditioning system fails for some time.
- The optimal range avoids failures or temporary malfunctions caused by interference from static discharges that can occur when relative humidity is too low. Electrostatic discharge (ESD) is easily generated, and hard to dissipate in areas of low relative humidity, such as below 35 percent. ESD becomes critical when humidity drops below 30 percent

Ventilation for Oracle Exadata Database Service on Cloud@Customer Racks

Always provide adequate space in front and behind the rack for proper ventilation.

Do not obstruct the front or rear of the rack with equipment or objects that might prevent air from flowing through the rack. Each Exadata Database Service on Cloud@Customer rack draws cool air in through the front of the rack, and discharges warm air out the rear of the rack. There is no air flow requirement for the left and right sides, because of front-to-back cooling.

Each Exadata Database Service on Cloud@Customer rack is designed to function while installed in a natural convection air flow. To ensure adequate air flow, allow a minimum clearance of 1219.2 mm (48 inches) at the front of the server, and 914 mm (36 inches) at the rear of the server for ventilation.

Use perforated tiles, approximately 400 CFM/tile, in front of the rack for cold air intake. The tiles can be arranged in any order in front of the rack, as long as cold air from the tiles can flow into the rack. Inadequate cold air flow could result in a higher inlet temperature in the servers because of exhaust air recirculation. The following is the recommended number of floor tiles:

- Four floor tiles for an Exadata Database Service on Cloud@Customer Full Rack.
- Three floor tiles for an Exadata Database Service on Cloud@Customer Half Rack.
- One floor tile for an Exadata Database Service on Cloud@Customer Quarter Rack or Base System.



Network Requirements for Oracle Exadata Database Service on Cloud@Customer

Review the network requirements for provisioning Oracle Exadata Database Service on Cloud@Customer at your site.

- Network Requirements for Oracle Exadata Database Service on Cloud@Customer
 To provide secure and reliable network connectivity for different application and
 management functions, Exadata Database Service on Cloud@Customer uses different
 networks.
- Data Center Network Services for Exadata Database Service on Cloud@Customer Before you deploy Exadata Database Service on Cloud@Customer, ensure that your data center network meets requirements.
- IP Addresses and Subnets for Exadata Database Service on Cloud@Customer
 You must allocate a range of IP addresses to the administration network, and another range of IP addresses to the InfiniBand network.
- Uplinks for Exadata Database Service on Cloud@Customer
 Ensure that your Exadata Database Service on Cloud@Customer system meets control plane server and database server uplink requirements.
- Network Cabling for Exadata Database Service on Cloud@Customer
 You can choose to use the supplied network equipment, or you can build your own SFP network.
- Oracle Exadata Database Service on Cloud@Customer Gen2 Oracle Cloud Infrastructure FastConnect
 Oracle Cloud Infrastructure FastConnect enables a private high bandwidth connection between your on-premises data center and Oracle Cloud Infrastructure Region.

Network Requirements for Oracle Exadata Database Service on Cloud@Customer

To provide secure and reliable network connectivity for different application and management functions, Exadata Database Service on Cloud@Customer uses different networks.

The following list outlines the minimum network requirements to install an Exadata Database Service on Cloud@Customer system:

- Exadata Cloud@Customer Service Network: These network will be set up to Oracle specifications and should not be modified by customer without Oracle agreement.
 - Control Plane Network
 - This virtual private network (VPN) connects the two control plane servers that are located in the Exadata Database Service on Cloud@Customer rack to Oracle Cloud Infrastructure. The VPN facilitates secure customer-initiated operations using the Oracle Cloud Infrastructure Console and APIs. It also facilitates secure monitoring and administration of the Oracle-managed infrastructure components in Exadata Database Service on Cloud@Customer.
 - * Control Plane Connectivity Considerations



In order for the control plane to function, the control plane server must be able to connect to certain Oracle Cloud Infrastructure (OCI) addresses. You must enable TCP port 443 outbound access to 5 endpoints in a specific OCI region as follows:

 Table 3-2
 Ports to Open for Control Plane Connectivity

Description / Purpose	Open Port	Location
Outgoing Tunnel Service for Cloud Automation delivery	443 outbound	Use this URL format, replacing oci_region with your region:
		https:// wss.exacc.oci_regi on.oci.oraclecloud .com
Secure Tunnel Service for remote Oracle operator access	443 outbound	Use these URL formats, replacing <i>oci_region</i> with your region:
		https:// mgmthel.exacc.oci_ region.oci.oraclec loud.com
		https:// mgmthe2.exacc.oci_ region.oci.oraclec loud.com
Object Storage Service to retrieve system updates	443 outbound	Use this URL format, replacing oci_region with your region:
		https:// objectstorage.oci_ region.oraclecloud .com
		https:// swiftobjectstorage .oci_region.oracle cloud.com



Table 3-2 (Cont.) Ports to Open for Control Plane Connectivity

Description / Purpose	Open Port	Location
Monitoring Service to record and process Infrastructure Monitoring Metrics (IMM)	443 outbound	Use this URL format, replacing oci_region with your region:
		https://telemetry-
		ingestion.oci_regi
		on.oraclecloud.com
Identity Service for name resolution of Oracle operators	443 outbound	Use this URL format, replacing oci_region with your region:
		https://
		identity.oci_regio
		<pre>n.oraclecloud.com</pre>
Outgoing Tunnel Coming	442 outbound	Llas this LIDI format
Outgoing Tunnel Service for Cloud Automation delivery	443 outbound	Use this URL format, replacing oci_region with your region:
		https://
		wsshe.adbd-
		exacc.oci_region.o
		ci.oraclecloud.com



Table 3-2 (Cont.) Ports to Open for Control Plane Connectivity

Description / Purpose	Open Port	Location
Logging Service	443 outbound	Use this URL format replacing ad with your availability domain and oci_region with your region:
		<pre>* https:// frontend.loggin g.adl.oci_regio n.oracleiaas.co m/</pre>
		<pre>* https:// frontend.loggin g.ad2.oci_regio n.oracleiaas.co m/</pre>
		* https:// frontend.loggin g.ad3.oci_regio n.oracleiaas.co m/
		* https:// controlplane.lo gging.adl.oci_r egion.oracleiaa s.com/
		* https:// controlplane.lo gging.ad2.oci_r egion.oracleiaa s.com/
		* https:// controlplane.lo gging.ad3.oci_r egion.oracleiaa s.com/
Resource Principal based authentication and Autonomous Database service delivery	d 443 outbound	Use this URL format, replacing oci_region with your region:
·		https:// database.region.or aclecloud.com



Note that the Control Plane Server must be able to establish TCP Port 443 outbound access only. While outbound connections on Port 443 must be allowed, TCP Port 443 inbound access is not required, and it may be desirable from a security standpoint to block inbound connections. (Functionally, bi-directional traffic is still possible over the connection once the secure outbound connection is established.)

The Control Plane Server requires customer DNS and NTP services to be functional. Minimum bandwidth requirements for the Control Plane Server internet connection to OCI are 50/10 mbs download/upload.

Some customers have security policies requiring the use of proxies for all internet connections to IT infrastructure. Customer HTTP proxy, for example, passive/corporate proxy supported for the Control Plane Server connection to OCI. Customer HTTPS, challenge proxy, and traffic inspection are not supported.

If you are using IP address filtering based firewall rules, due to the dynamic nature of cloud interfaces, you must allow traffic with all the relevant IP CIDR ranges associated with your OCI region as identified by https://docs.oracle.com/en-us/iaas/tools/public_ip_ranges.json.

Administration Network

This network connects Exadata Database Service on Cloud@Customer servers and switches to the two control plane servers that are located in the Exadata Database Service on Cloud@Customer rack. It facilitates customer-initiated operations using the Oracle Cloud Infrastructure Console and APIs. It also facilitates monitoring and administration of the Oracle-managed infrastructure components in Exadata Database Service on Cloud@Customer.

This network is fully contained within the Exadata Database Service on Cloud@Customer rack, and does not connect to your corporate network. However, the Exadata infrastructure is indirectly connected to your corporate network through the control plane servers. This connection is required to provide Domain Name System (DNS) and Network Time Protocol (NTP) services to the Exadata infrastructure. Therefore, the IP addresses that are allocated to the administration network must not exist elsewhere in your corporate network.

Each Oracle Database server and Exadata Storage Server has two network interfaces connected to the administration network. One provides management access to the server through one of the embedded Ethernet ports (NETO). The other provides access to the Integrated Lights-Out Management (ILOM) subsystem through a dedicated ILOM Ethernet port. Exadata Database Service on Cloud@Customer is delivered with the ILOM and NETO ports connected to the Ethernet switch in the rack. Cabling or configuration changes to these interfaces are not permitted.

InfiniBand or RDMA Over Converged Ethernet (ROCE) Network

This network connects the database servers, Exadata Storage Servers, and control plane servers using the InfiniBand or ROCE switches on the rack. Each server contains two InfiniBand network interfaces (IB0 and IB1) or ROCE interface (re0 and re1) that are connected to separate InfiniBand or ROCE switches in the rack. Primarily, Oracle Database uses this network for Oracle RAC cluster interconnect traffic, and for accessing data on Exadata Storage Servers.

This non-routable network is fully contained within the Exadata Cloud@Customer rack, and does not connect to your corporate network. However, because the control plane servers are connected to the InfiniBand or ROCE network and to your corporate network, the IP addresses that are allocated to the InfiniBand or ROCE network must not exist elsewhere in your corporate network.



• **Customer Network:** Customer-owned and managed networks required for the Exadata Cloud@Customer data plane to access related systems.

Client Network

This network connects the Exadata Cloud@Customer database servers to your existing client network and is used for client access to the virtual machines. Applications access databases on Exadata Database Service on Cloud@Customer through this network using Single Client Access Name (SCAN) and Oracle Real Application Clusters (Oracle RAC) Virtual IP (VIP) interfaces.

The client access network uses a pair of network interfaces on each database server, which are connected to the customer network.



When you enable Data Guard, replication of data happens only over the client network.

Backup Network

This network is similar to the client access network, as it connects the Exadata Database Service on Cloud@Customer Oracle Database servers to your existing network. It can be used for access to the virtual machines for various purposes, including backups and bulk data transfers.

Like the client network, the backup network uses a pair of network interfaces on each database server, which are connected to the customer network. Physically connecting the backup network to a customer network is required.

If the customer's on-premises storage (NFS or ZDLRA) is to be used exclusively as a backup destination for databases, then no external connectivity to OCI is required for the backup network.

Exadata Cloud@Customer also offers an Oracle-managed cloud object storage backup destination. If Oracle's Object Storage Service is to be leveraged as a backup destination for database backups, then ensure that the backup network can reach the Object Storage Service through external connection. You must enable TCP port 443 outbound access for the backup network as follows:



Table 3-3 Ports to Open for Backup Network

Description / Purpose	Open Port	Location
Object Storage Service for cloud-based database backups (Optional)	443 outbound	Use this URL format, replacing <i>oci_region</i> with your region:
		https:// objectstorage.oci_reg ion.oraclecloud.com
		https:// swiftobjectstorage.oc i_region.oraclecloud. com

Related Topics

- Object Storage Service API
- Monitoring API
- Identity and Access Management Service API

Data Center Network Services for Exadata Database Service on Cloud@Customer

Before you deploy Exadata Database Service on Cloud@Customer, ensure that your data center network meets requirements.

Domain Name System (DNS) Requirements

As part of the deployment process, you must decide on the host names and IP addresses to be used for various Exadata Database Service on Cloud@Customer network interfaces. Oracle requires that you register the host names and IP addresses for the Exadata Database Service on Cloud@Customer client and backup network interfaces in your corporate DNS. At least one reliable DNS server is required, which must be accessible to the control plane servers and to all of the servers on the client network. Up to three DNS servers can be registered in Exadata Database Service on Cloud@Customer to ensure coverage in case a server is unavailable.

Network Time Protocol (NTP) Services Requirements

Exadata Database Service on Cloud@Customer uses NTP to ensure that all system components are synchronized to the same time. At least one reliable NTP server is required, which must be accessible to the control plane servers and to all of the servers on the client network. Up to three NTP servers can be registered in Exadata Database Service on Cloud@Customer to ensure coverage in case a server is unavailable.



IP Addresses and Subnets for Exadata Database Service on Cloud@Customer

You must allocate a range of IP addresses to the administration network, and another range of IP addresses to the InfiniBand network.

InfiniBand Requirements for Oracle Cloud@Customer

No overlap is permitted between the address ranges for the administration network and the InfiniBand network, and all IP addresses should be unique within your corporate network. You must also allocate IP addresses from your corporate network to the control plane servers. These network configuration details are specified when you create the Exadata infrastructure.

When you create the Exadata infrastructure, the console pre-populates default values for the administration network CIDR block and the InifinBand network CIDR block. You can use the suggested CIDR blocks if there is no overlap with existing IP addresses in your corporate network.

Review IP address requirements for each of these networks. The table specifies the maximum and minimum CIDR block prefix length that are allowed for each network. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, you can choose a smaller CIDR block prefix length, within the allowable range, which reserves more IP addresses for the network.

Network Type	IP Address Requirements
Administration network	Maximum CIDR block prefix length:
	/23
	Minimum CIDR block prefix length:
	/16
InifinBand network	Maximum CIDR block prefix length:
	/22
	Minimum CIDR block prefix length:
	/19
Control plane network	2 IP addresses, 1 for each control plane server

Host Name and IP Address Requirements for Oracle Cloud@Customer

To connect to your corporate network, Exadata Database Service on Cloud@Customer requires several host names and IP addresses for network interfaces on the client network and the backup network. The precise number of IP



addresses depends on the Exadata system shape. These network configuration details, including host names and IP addresses, are specified when you create a VM cluster network. All IP addresses must be statically assigned IP addresses, not dynamically assigned (DHCP) addresses. The client network and the backup network require separate subnets.

The following table outlines the IP address requirements for the client and backup networks. The table specifies the maximum and recommended CIDR block prefix length for each network. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network.

Network Type	IP Address Requirements for Base System, Quarter Rack, or Half Rack	IP Address Requirements for Full Rack
Client network	Maximum CIDR block prefix length:	Maximum CIDR block prefix length:
	/28	/27
	Recommended CIDR block prefix length:	Recommended CIDR block prefix length:
	/27	/26
Backup network	Maximum CIDR block prefix length:	Maximum CIDR block prefix length:
	/29	/28
	Recommended CIDR block prefix length:	Recommended CIDR block prefix length:
	/28	/27

Uplinks for Exadata Database Service on Cloud@Customer

Ensure that your Exadata Database Service on Cloud@Customer system meets control plane server and database server uplink requirements.

Control Plane Servers

Four uplinks (2 per server) are required to connect the Control Plane Servers to your corporate network to support the outbound secure network connections to the OCI services required by the Exadata Cloud@Customer service.

Database Server Connections

Typically, four uplinks are required for each database server to connect to your corporate network. Using this configuration, two uplinks support the client network and the other two uplinks support the backup network.



On Quarter Rack, Half Rack, or Full Rack systems, you can choose to use 10 Gbps RJ45 copper, 10 Gbps SFP+ fiber, or 25Gbps SFP28 fiber network connections to your corporate network. However, you cannot mix copper and fiber networks on the same physical server. For example, you cannot use fiber for the client network and copper for the backup network.

On Base System configurations, the options are more limited because of the physical network interfaces that are available on each database server. On Base Systems, you can choose to use copper or fiber network connections only for the client network, while the backup network uses a fiber connection.

You can also use shared network interfaces on the Base System for the client network and the backup network, which reduces the uplink requirement to two uplinks for each database server. Using shared network interfaces also enables you to use copper network connections to support both the client and backup networks on Base System configurations. However, in general, Oracle recommends that you do not use shared network interfaces, because sharing networks compromises the bandwidth and availability of both networks. Shared network interfaces are not supported for Quarter, Half, and Full Rack configurations.

Network Cabling for Exadata Database Service on Cloud@Customer

You can choose to use the supplied network equipment, or you can build your own SFP network.

Supplied Network Equipment Option

Every Exadata Database Service on Cloud@Customer rack is shipped with all of the network equipment and cables that are required to interconnect all hardware in the Exadata Database Service on Cloud@Customer rack.

Small Form-Factory Pluggable Network Option

Oracle supplies small form-factor pluggable (SFP) network interfaces to enable connectivity to your corporate network. However, if you choose to configure an SFP network, then you are responsible to provide the required cabling to connect the Exadata Database Servers and Control Plane Servers to your corporate network.

Oracle Exadata Database Service on Cloud@Customer Gen2 Oracle Cloud Infrastructure FastConnect

Oracle Cloud Infrastructure FastConnect enables a private high bandwidth connection between your on-premises data center and Oracle Cloud Infrastructure Region.

For more information, see Oracle Cloud Infrastructure FastConnect.

Oracle Exadata Database Service on Cloud@Customer service supports the public peering connectivity model of FastConnect.






Figure 3-1 Oracle Exadata Database Service on Cloud@Customer FastConnect connectivity to OCI through public peering

As shown in the figure, the Oracle Exadata Database Service on Cloud@Customer Control Plane network egresses to FastConnect provider and to Oracle edge. Customers who may already have existing FastConnect connectivity can use it to connect Oracle Exadata Database Service on Cloud@Customer to the OCI region using public peering.

Configuring FastConnect for Oracle Exadata Database Service on Cloud@Customer

You can set up and configure Oracle Cloud Infrastructure FastConnect either before or after deploying Oracle Exadata Database Service on Cloud@Customer.

Oracle Exadata Database Service on Cloud@Customer rack egress network configuration for FastConnect

- As shown in the figure, it is important to set the Oracle Exadata Database Service on Cloud@Customer Control Plane Server network egress rules to forward traffic over FastConnect, and also have a route to an internet-facing customer DNS. This "Customer DNS" is used by Oracle Exadata Database Service on Cloud@Customer infrastructure to resolve OCI public endpoints.
- Corporate HTTP proxy between Oracle Exadata Database Service on Cloud@Customer Control Plane Servers and OCI region is not recommended with FastConnect as it is already a dedicated network. If a corporate proxy is highly desired, then the proxy needs to have additional routing to ensure that Oracle Exadata Database Service on Cloud@Customer network traffic is sent over FastConnect.



Related Topics

Oracle Cloud Infrastructure FastConnect

Storage Configuration Requirements for Oracle Exadata Database Service on Cloud@Customer

Review the storage requirements for the ASM disk groups and VM file systems to plan the best options for your enterprise needs.



If you are looking for information to plan the local VM storage available on your VM Clusters refer to Estimating How Much Local Storage You Can Provision to Your VMs

- About Storage Configuration for Oracle Exadata Database Service on Cloud@Customer
 - As part of configuring each Exadata Database Service on Cloud@Customer VM cluster, the storage space inside the Exadata Storage Servers is configured for use by Oracle Automatic Storage Management (ASM).
- Allocation of Storage Space Options on Oracle Exadata Storage Servers
 Select the storage option that best meets your planned use case on your Oracle
 Exadata Storage Servers.
- Allocation Proportions for DATA, RECO and SPARSE Disk Groups
 Determine the storage allocation between the DATA, RECO, and SPARSE disk groups for Oracle Exadata Storage Servers.
- Virtual Machine File System Structure for Exadata Cloud@Customer

About Storage Configuration for Oracle Exadata Database Service on Cloud@Customer

As part of configuring each Exadata Database Service on Cloud@Customer VM cluster, the storage space inside the Exadata Storage Servers is configured for use by Oracle Automatic Storage Management (ASM).

By default, the following ASM disk groups are created:

- The DATA disk group is primarily intended for the storage of Oracle Database data files. Also, a small amount of space is allocated from the DATA disk group to support the shared file systems that are used to store software binaries (and patches) and files associated with the cloud-specific tooling. You should not store your own data, including Oracle Database data files, backups, trace files, and so on, inside the system-related ACFS file systems.
- The RECO disk group is primarily used for storing the Fast Recovery Area (FRA),
 which can be used to provide a local store for files related to backup and recovery.
 By default, the FRA is used to store archived redo log files and the backup control
 file. If you configure your VM cluster with the option to allocate storage for local
 backups, then you can use the FRA as a database backup destination. Finally, if



you enable flashback features on a database, then the FRA is used to store the flashback logs.

In addition, you can choose to create the SPARSE disk group. The SPARSE disk group is required to support Exadata snapshot functionality. Exadata snapshots enable space-efficient clones of Oracle databases that can be created and destroyed very quickly and easily. Snapshot clones are often used for development, testing, or other purposes that require a transient database. For more information about Exadata snapshot functionality, see "Setting Up Oracle Exadata Storage Snapshots" in *Oracle Exadata System Software User's Guide*.

Related Topics

Setting Up Oracle Exadata Storage Snapshots

Allocation of Storage Space Options on Oracle Exadata Storage Servers

Select the storage option that best meets your planned use case on your Oracle Exadata Storage Servers.

As an input to the virtual machine (VM) cluster creation process, you must choose options that determine how storage space in the Oracle Exadata Storage Servers is allocated to the Oracle ASM disk groups. Your choices profoundly affect how storage space in the Exadata Storage Servers is allocated to the ASM disk groups. Consider which option best meets your needs:

- Allocate Storage for Exadata Snapshots
 - If you select this option, then the SPARSE disk group is created, and less space is allocated to the DATA and RECO disk groups. If you do not select this option, then the SPARSE disk group is not created, and you cannot use Exadata snapshot functionality.
- Allocate Storage for Local Backups

If you select this option, then more space is allocated to the RECO disk group to accommodate local backups to Oracle Exadata storage. If you do not select this option, then more space is allocated to the DATA disk group, but you cannot use local Oracle Exadata storage as a backup destination for any databases in the VM cluster.

Allocation Proportions for DATA, RECO and SPARSE Disk Groups

Determine the storage allocation between the DATA, RECO, and SPARSE disk groups for Oracle Exadata Storage Servers.

Exadata Storage Server Configuration Allocation With No Exadata Snapshot Storage or Local Backup

When you select Allocate Storage for Exadata Snapshots: No and Enable Backups on Local Exadata Storage: No, then storage allocation is as follows:

- DATA Disk Group: 80%
- RECO Disk Group: 20%
- SPARSE Disk Group 0% (The SPARSE disk group is not created.)



Exadata Storage Server Configuration Allocation With No Exadata Snapshot Storage and Local Backup Enabled

When you select Allocate Storage for Exadata Snapshots: No and Enable Backups on Local Exadata Storage: Yes, so that backups are enabled on local storage, then storage allocation is as follows:

- DATA Disk Group: 40%
- RECO Disk Group: 60%
- SPARSE Disk Group 0% (The SPARSE disk group is not created.)

Exadata Storage Server Configuration Allocation With Exadata Snapshot Storage and No Local Backup

When you select Allocate Storage for Exadata Snapshots: Yes and Enable Backups on Local Exadata Storage: No, so that storage is allocated for Exadata snapshots, then storage allocation is as follows:

- DATA Disk Group: 60%
- RECO Disk Group: 20%
- SPARSE Disk Group 20%

Exadata Storage Server Configuration Allocation With Both Exadata Snapshot Storage and Local Backup Enabled

When you select **Allocate Storage for Exadata Snapshots: Yes** and **Enable Backups on Local Exadata Storage: Yes**, so that storage is allocated for Exadata snapshots, and storage is allocated for local backups, then storage allocation is as follows:

- DATA Disk Group: 35%
- RECO Disk Group: 50%
- SPARSE Disk Group 15%

Virtual Machine File System Structure for Exadata Cloud@Customer

Exadata Cloud@Customer X8M systems use the following file system organization on the virtual machines. To plan for local storage allocation on the virtual machines please refer to Estimating How Much Local Storage You Can Provision to Your VMs.

Filesystem	Mounted On
devtmpfs	/dev
tmpfs	/dev/shm
tmpfs	/run
tmpfs	/sys/fs/cgroup
tmpfs	/run/user/0
/dev/mapper/VGExaDb-LVDbSys1	1
/dev/mapper/VGExaDb-LVDbOra1	/u01
/dev/mapper/VGExaDb-LVDbTmp	/tmp



Filesystem	Mounted On
/dev/mapper/VGExaDb-LVDbVar1	/var
/dev/mapper/VGExaDb-LVDbVarLog	/var/log
/dev/mapper/VGExaDb-LVDbHome	/home
/dev/mapper/VGExaDbDisk.u02_extra.img- LVDBDisk	/u02
/dev/mapper/VGExaDb-LVDbVarLogAudit	/var/log/audit
/dev/sda1	/boot
/dev/mapper/ VGExaDbDisk.grid19.0.0.0.200414.img- LVDBDisk	/u01/app/19.0.0.0/grid
/dev/asm/acfsvol01-142	/acfs01

Related Topics

Estimating How Much Local Storage You Can Provision to Your VMs

Checklists for Exadata Database Service on Cloud@Customer Deployments

To determine your readiness for an Exadata Database Service on Cloud@Customer deployment, review the deployment checklists.

- System Components Checklist for Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the system component considerations are addressed.
- Data Center Room Checklist for Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the data center room requirements are addressed.
- Data Center Environment Checklist for Oracle Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the data center environment requirements are addressed.
- Access Route Checklist for Oracle Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the access route requirements are addressed.
- Facility Power Checklist for Oracle Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the facility power requirements are addressed.
- Safety Checklist for Oracle Exadata Database Service on Cloud@Customer Use this checklist to ensure that safety requirements are addressed.
- Logistics Checklist for Exadata Database Service on Cloud@Customer
 Use this checklist to ensure that the logistics requirements are addressed.
- Network Configuration Checklist for Oracle Exadata Database Service on Cloud@Customer
 - Use this checklist to ensure that the network configuration requirements are addressed.
- Reracking Checklist for Oracle Exadata Database Service on Cloud@Customer Use this checklist to determine your readiness for reracking.



System Components Checklist for Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the system component considerations are addressed.

- How many racks do you plan to install?
- Will additional equipment be attached to or installed in the rack?
 If additional equipment is attached, then ensure that the additional equipment meets Oracle guidelines, and there is sufficient power and cooling.

Data Center Room Checklist for Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the data center room requirements are addressed.

Answer yes, no, not applicable, or add your comments. Or let the site survey team fill in the requested information.

- Has the rack location been allocated and is it vacant?
- Does the floor layout meet the equipment maintenance access requirements?
- Will the rack be positioned so that the exhaust air of one rack does not enter the air inlet of another rack?
- Have cabinet stabilization measures been considered?
- If the data center has a raised floor:
 - Does the raised floor satisfy the weight requirements for the rack?
 - Is permission required to remove floor tiles for cabling and servicing below the floor?
- Will the rack location require any non-standard cable lengths?
- Is the floor-to-ceiling height a minimum of 2914 mm (114.72 inches)?
- Is the depth of the raised floor a minimum of 46 cm (18 inches)?

Data Center Environment Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the data center environment requirements are addressed.

- Does the computer room air conditioning meet temperature and humidity requirements?
- Does the installation floor layout satisfy the ventilation requirements?
- If the room cooling is from a raised floor:
 - Are the perforated floor tiles each rated at 400 CFM or greater?



- Can additional perforated floor tiles be obtained if required for additional cooling?
- Does the data center air conditioning provide sufficient front-to-back airflow?
- Is airflow adequate to prevent hot spots?
- Can the data center continuously satisfy the environmental requirements?

Access Route Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the access route requirements are addressed.

Answer yes, no, not applicable, or add your comments. Or, let the site survey team fill in the requested information.

- Has the access route been checked for clearance of the rack, including the minimum width and height requirements for all doors on the route?
- Are there any stairs, ramps, or thresholds that are of concern?
 If yes, then provide details.
- Are all access route incline angles within the permitted range (under 6 degrees)?
- Are all the surfaces acceptable for rolling the new unpacked and packed equipment?
- If a pallet jack is to be used:
 - Can the pallet jack support the weight of the rack?
 - Are the pallet jack tines compatible with the shipping pallet?
- If there are stairs, is a loading elevator available for the equipment?
- If an elevator is to be used:
 - Does the elevator car meet the height, width, and depth requirements for carrying the rack?
 - Do the elevator doors meet the height and width requirements for moving the rack?
 - Does the elevator meet the weight requirements for transporting the rack?
- Can the complete access route support the weight of the rack?
- Is the access route onto the raised floor rated for dynamic loading of the rack?

Facility Power Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the facility power requirements are addressed.

- Have the operating voltage and electric current requirements been reviewed?
- What type of power supply will be used?
 - Single-phase or 3-phase.
 - Low-voltage or High-voltage.
- Are enough power outlets provided within 2 meters for each rack?



- Do the power outlets have appropriate socket receptacles for the planned Power Distribution Units (PDUs)?
- Will optional ground cables be attached to the rack?
- Are the electrical circuits suitable in terms of voltage and current-carrying capacities?
- Does the power frequency meet the equipment specifications?
- Are power outlets available for the new equipment at the designated location?
- Will system power be delivered from two separate grids?
- Is there a UPS to power the equipment?
- Are the minimum required power sources available to support the power load (kW or kVA) for the new hardware?

Safety Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to ensure that safety requirements are addressed.

Answer yes, no, not applicable, or add your comments. Or, let the site survey team fill in the requested information.

- Is there an emergency power shut off?
- Is there a fire protection system in the data center room?
- Is the computer room adequately equipped to extinguish a fire?
- Is antistatic flooring installed?
- Is the area below the raised floor free of obstacles and blockages?

Logistics Checklist for Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the logistics requirements are addressed.

- Is contact information for the data center personnel available?
- Is there security or access control for the data center?
- Are there any security background checks or security clearances required for Oracle personnel to access the data center?
 If yes, then provide the process for Oracle to follow.
- How many days in advance must background checks be completed?
- Are there any additional security access issues?
- Is computer room access available for installation personnel?
- Are laptops allowed in the data center?
- Are cell phones allowed in the data center?



- Are cameras allowed in the data center?
- Does the building have a delivery dock?
- Is there a delivery / unpacking / staging area?
- Is inside delivery planned (direct to the final rack location in the data center room)?
- If the delivery is not inside, then is the site prepared for uncrating?
- Is the delivery / unpacking / staging area protected from the elements?
- Does the building have adequate receiving space?
- Is the unpacking area air-conditioned to avoid thermal shock for various hardware components?
- Will sufficient moving personnel be available to transport the rack?
- Is union labor required for any part of the delivery or installation?
- Is the site prepared for uncrating and packaging removal?
 Package removal should take place outside the data center room.
- Is uncrating of cabinet and packaging removal required?
- Are there any restrictions on delivery truck length, width, or height?
- Is there storage space (cabinet) for the ride along spares?
 If not, does the customer allow cardboard boxes and other packing material in the computer room, since the spares are packed in cardboard boxes?
- Is there a time constraint on dock access?
 If yes, provide time constraints.
- Is a tail or side lift required on the delivery carrier to unload the equipment at the delivery dock?
- Will any special equipment be required to place the rack in the data center room? For example:
 - Stair walkers
 - Lifters
 - Ramps
 - Steel plates
 - Floor covers
- Does the delivery carrier require any special equipment, such as non-floor damaging rollers, transport dollies, pallet jacks, or fork lifts?

Network Configuration Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to ensure that the network configuration requirements are addressed.

- Are the required network cables laid from the network equipment to the location where the Oracle Exadata Rack will be installed?
- Are the network cables that will connect the Oracle Exadata Rack labeled?



 Will the 10 GbE or 25 GbE interfaces be used for the client and backup access networks? If so, did the customer install the appropriate cables to their switch?

Reracking Checklist for Oracle Exadata Database Service on Cloud@Customer

Use this checklist to determine your readiness for reracking.

Use this checklist to ensure that the reracking requirements are addressed.

Note:

- Reracking requires prior approval. The checklist below provides high level guidance on re-racking requirements. Oracle maintains a detailed internal checklist that must be approved prior to performing reracking.
- You must purchase the Oracle Reracking service.
- Oracle does not provide technical support for customer-supplied equipment.

Answer yes, no, not applicable, or add your comments. Or, let the site survey team to fill in the requested information.

- Have you purchased the Oracle Reracking Service?
- Is there a cart capable of carrying the weight of the servers to move the components and associated cabling from the supplied rack to the rack that you supply?
- Is the target rack empty?
- Attach pictures of the target rack (inside and outside).
- Does the target rack meet the following requirements?
 - Height: 42 RU
 - Width: 600 mm (23.62 inches)
 - Depth: 1112 mm (43.78 inches) without front and rear doors

If the rack is less than 42 RU tall, then the rack must be at least 30 RU tall, and you must provide compatible PDUs to install in the target rack.

- Is the distance between the front and rear mounting planes between the minimum of 610 mm and the maximum 915 mm (24–36 inches)?
- Is the clearance depth in the front of the front mounting plane (distance to the front cabinet door) at least 25.4 mm (1 inch)?
- Does the target rack meet the following minimum load capacity?
 - 19 kg (41.89 lb) per RU
 - 785 kg (1730.63 lb) total
- Is the rack a four-post rack (mounting at both front and rear)?



Note:

Two-post racks are not compatible.

- Does the target rack's horizontal opening and unit vertical pitch conform to ANSI/EIA 310-D-1992 or IEC 60297 standards?
- Does the target rack have RETMA rail support?

Note:

Oracle Exadata rack requires 19 inches (483 mm) for RETMA rail spacing width. The minimum rack width of 600 mm (23.63 inches) is recommended to accommodate the PDU and cable harnesses on the side. If the rack is less than 600 mm wide, then it must have additional depth to accommodate mounting behind the server cable management arms.

- Does the target rack support Oracle cable management arms?
- Does the target rack support installation of Oracle vented and solid filler panels?
- Can the target rack provide tie-downs along the left rear side of the rack (as viewed from the front of the rack) to support the InfiniBand cables?
- Can the target rack provide tie-downs for the Ethernet wiring harness?
- Is there sufficient space for the cable harnesses and the PDUs in the target rack?
- Can a label with the Oracle Exadata Rack serial number be printed and attached to the target rack?
- Does the target rack support installation of standard Oracle PDUs?
 If not, then complete the following checklist items:
 - Can you provide provide an equivalent pair of PDUs?
 - Can you provide provide two PDUs, each with a capacity of 10 kVA?
 - Can you provide provide at least 17 x IOA C13 plugs per PDU?
 - Can you provide a single PDU and its circuits to support the Oracle Exadata Rack power requirements in case one PDU fails?
 - Can you ensure that power loads are evenly distributed across all circuits of a single PDU?
 - Can you provide appropriate power drops for the PDUs?



4

Getting Started with Exadata Database Service on Cloud@Customer Deployment

After completing the preparation tasks in Preparing for Exadata Database Service on Cloud@Customer, get started with deploying your Exadata Database Service on Cloud@Customer system following these procedures.

- About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems
 To provision an Oracle Exadata Database Service on Cloud@Customer system, you
 must work with Oracle to set up and configure the system.
- Oracle Exadata Cloud@Customer Deployment Assistant
 Oracle Exadata Cloud@Customer Deployment Assistant is an automated installation and
 configuration tool that enables you to set up your Oracle Exadata Cloud@Customer
 machine and create an Oracle Database instance with minimal effort.
- Overview of Elastic Storage Expansion
 With elastic storage expansion, you can dynamically increase your storage capacity to
 meet your growing workload requirements.
- Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure
 Learn how to provision an Exadata Database Service on Cloud@Customer system.
- Configuring Oracle-Managed Infrastructure Maintenance
 Oracle performs the updates to all of the Oracle-managed infrastructure components on Exadata Cloud@Customer.
- Creating First VM Cluster Network on Exadata Cloud@Customer
 Follow the steps in the following sections to create your first VM Cluster Network.
- Provisioning the First VM Cluster on an Exadata Cloud@Customer System
 Learn how to create the first VM cluster on your Exadata Cloud@Customer system.
- Creating Database Backup Destinations for Exadata Cloud@Customer Exadata Cloud@Customer provides a backup facility, which you can configure individually on each database.
- Creating First Database Home on an Exadata Database Service on Cloud@Customer System
 - After provisioning a VM Cluster, create your first Oracle Database Home on Exadata Cloud@Customer.
- Creating First Database on an Exadata Database Service on Cloud@Customer System After provisioning an Oracle Database Home and any needed backup destinations, you are ready to create your first database on Exadata Cloud@Customer.
- Connecting to an Exadata Database Service on Cloud@Customer System
 After deploying your Exadata Cloud@Customer system with a VM cluster, Oracle
 Database Home, and Oracle Database, learn how to connect to your VM Cluster virtual
 machine using SSH and to connect to an Exadata Cloud@Customer database using
 Oracle Net Services (SQL*Net).

About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems

To provision an Oracle Exadata Database Service on Cloud@Customer system, you must work with Oracle to set up and configure the system.

Provisioning an Oracle Exadata Database Service on Cloud@Customer system is a collaborative process. The process is performed in the following sequence:

- You create the Oracle Exadata Database Service on Cloud@Customer infrastructure.
- You generate a file containing the infrastructure configuration details, and provide it to Oracle.
- The Oracle Exadata Database Service on Cloud@Customer system is physically installed in your data center.
- 4. Oracle uses the infrastructure configuration file to perform initial system configuration. At the end of this task, Oracle supplies you with an activation file.
- 5. You activate the Exadata Database Service on Cloud@Customer infrastructure by using the supplied activation file.

When the provisioning process is complete, the Oracle Exadata Database Service on Cloud@Customer system is ready for you to use. You can then create a virtual machine (VM) cluster, and later create some databases.



Caution:

Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, the APIs, or the command-line interface.

Oracle Exadata Cloud@Customer Deployment Assistant

Oracle Exadata Cloud@Customer Deployment Assistant is an automated installation and configuration tool that enables you to set up your Oracle Exadata Cloud@Customer machine and create an Oracle Database instance with minimal effort.

- Using Oracle Exadata Cloud@Customer Deployment Assistant
 Oracle Exadata Cloud@Customer Deployment Assistant gathers your
 configuration details and creates the Oracle Exadata Cloud@Customer
 infrastructure configuration file. The configuration file drives the automated
 installation and configuration processes for Oracle Exadata Cloud@Customer
 infrastructure.
- Accessing Oracle Exadata Cloud@Customer Deployment Assistant
 Follow these steps to run the Deployment Assistant.



Step 1: Pre-Installation

Create Exadata Cloud@Customer infrastructure, VM cluster network, and download the infrastructure configuration file before your engineered system arrives at your premises.

• Step 2: Onsite Installation

Ensure that you activate the Exadata Cloud@Customer infrastructure and validate the VM cluster network.

Step 3: Post-Installation

Create a VM cluster, install Oracle Database, and validate your installation before performing any administrative tasks.

Using Oracle Exadata Cloud@Customer Deployment Assistant

Oracle Exadata Cloud@Customer Deployment Assistant gathers your configuration details and creates the Oracle Exadata Cloud@Customer infrastructure configuration file. The configuration file drives the automated installation and configuration processes for Oracle Exadata Cloud@Customer infrastructure.

Before your engineered system arrives, do the following:

- Work with your network and database administrators to evaluate the current network settings, such as current IP address use and network configuration.
- Define the settings for the rack, such as network configuration and backup method.
- Download the Oracle Exadata Cloud@Customer infrastructure configuration file.

During deployment, if you find any discrepancies at any stage, then click **Close and complete later** to exit Oracle Exadata Cloud@Customer Deployment Assistant. You will lose all of your settings and you will have to start afresh the next time.

Accessing Oracle Exadata Cloud@Customer Deployment Assistant

Follow these steps to run the Deployment Assistant.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Click Exadata Infrastructure.
- 3. Click Deployment Assistant.
- 4. Choose a deployment type.
 - New Deployment: Creates an Exadata Cloud@Customer infrastructure and all the resources needed to create your first Oracle Database.

 Select a Compartment, and then click Continue.
 - **Existing Deployment**: Uses an existing Exadata Cloud@Customer infrastructure and guides you through completing the deployment.
 - a. Select a Compartment.
 - b. Select an Exadata Cloud@Customer infrastructure.
 - c. Select a VM Cluster Network or create one.
 - d. Click Continue.
- 5. If you have created an Exadata Cloud@Customer infrastructure and if it is in **Active** state, then do the following:
 - a. Go the Exadata Cloud@Customer infrastructure details page.



- b. Click Deployment Assistant.
- 6. If you have created an Exadata Cloud@Customer infrastructure and if it is in Requires Activation state, then do the following:
 - a. Go the Exadata Cloud@Customer infrastructure details page.
 - b. Click More Actions and then select Deployment Assistant.

Step 1: Pre-Installation

Create Exadata Cloud@Customer infrastructure, VM cluster network, and download the infrastructure configuration file before your engineered system arrives at your premises.

- 1. Create Oracle Exadata Database Service on Cloud@Customer infrastructure.
 - For more information and instructions, see Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure.
- Create VM cluster network.
 - For more information and instructions, see Using the Console to Create a VM Cluster Network.
- Download the Oracle Exadata Database Service on Cloud@Customer configuration file.
 - For more information and instructions, see Using the Console to Download a File Containing Configuration Data.

Step 2: Onsite Installation

Ensure that you activate the Exadata Cloud@Customer infrastructure and validate the VM cluster network.

- 1. Add Infrastructure Contacts.
 - Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.
 - You must add a primary contact to activate your infrastructure. Ensure that you provide the details of the contact that you used while registering the Customer Support Identifier (CSI) associated with this infrastructure, as a primary contact.
 - For more information and instructions, see Infrastructure Maintenance Contacts
- 2. Activate Oracle Exadata Database Service on Cloud@Customer infrastructure.
 - For more information and instructions, see Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure.
- 3. Validate the VM cluster network.
 - You can only validate a VM cluster network if its current state is **Requires Validation** and if the underlying Exadata infrastructure is activated.
 - For more information and instructions, see Using the Console to Validate a VM Cluster Network.



Step 3: Post-Installation

Create a VM cluster, install Oracle Database, and validate your installation before performing any administrative tasks.

Create VM cluster.

For more information and instructions, see Using the Console to Create a VM Cluster.

2. Create Oracle Database.

For more information and instructions, see Using the Console to Create a Database.

Overview of Elastic Storage Expansion

With elastic storage expansion, you can dynamically increase your storage capacity to meet your growing workload requirements.

Expand the storage capacity on-demand by scaling up the infrastructure with additional storage servers without being constrained by the standard supported shapes. You can allocate additional storage capacity available from the newly added storage servers to the already deployed VM Cluster without disrupting the current running workloads. Additional storage capacity from newly added storage servers is also available for provisioning new VM Clusters on the infrastructure.

With the elastic storage expansion capability, you can now:

- Provision new Exadata Infrastructure with custom storage capacity.
- Start with a smaller storage footprint for the Exadata Infrastructure at install time.
- Expand the storage capacity on existing deployed Exadata Infrastructure on-demand in an automated, elastic fashion.
- Allocate additional storage capacity available from newly added storage servers to already deployed VM clusters and/or use them for provisioning new VM clusters on the infrastructure.

Table 4-1 Key Additional Resources

Specification	Exadata Base System Storage Server X7-2	Exadata Storage Server X7-2
Additional Raw Flash Storage Capacity	6.4 TB	25.6 TB
Additional Raw Disk Storage Capacity	48 TB	120 TB
Additional Usable Storage Capacity	14 TB	35.3 TB

Table 4-2 Key Additional Resources

Specification	Exadata Base System Storage Server X8-2	Exadata Storage Server X8-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB



Table 4-2 (Cont.) Key Additional Resources

Specification	Exadata Base System Storage Server X8-2	Exadata Storage Server X8-2
Additional Raw Disk Storage Capacity	84 TB	168 TB
Additional Usable Storage Capacity	24.6 TB	49.6 TB

Table 4-3 Key Additional Resources

Specification	Exadata Base System Storage Server X8M-2	Exadata Storage Server X8M-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB
Additional Raw Disk Storage Capacity	84 TB	168 TB
Additional Usable Storage Capacity	24.6 TB	49.6 TB
Additional Persistent Memory	-	1.5 TB

Table 4-4 Key Additional Resources

Specification	Exadata Base System Storage Server X9M-2	Exadata Storage Server X9M-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB
Additional Raw Disk Storage Capacity	84 TB	216 TB
Additional Usable Storage Capacity	24.6 TB	63.6 TB
Additional Persistent Memory	-	1.5 TB

Elastic scaling of Exadata Storage Servers is subject to the following conditions:

- The Exadata Cloud@Customer system configuration must be based on Oracle Exadata X7 hardware, Oracle Exadata X8 hardware, Oracle Exadata X8M hardware, or Oracle Exadata X9M hardware.
- Each Exadata Cloud@Customer system configuration can have an absolute maximum of 12 Exadata Storage Servers.
- Exadata Infrastructure deployed with base configuration shape can only be expanded using base expansion SKU storage servers.
- Exadata Infrastructures deployed with X7 generation at install time can be scaled with X8 generation storage servers. X8 storage servers used to scale X7 infrastructure will only present the same total usable capacity as all other X7 storage servers that are already part of the infrastructure.



 Exadata Infrastructures deployed with X8M generation at install time can only be scaled with X8M or higher generation storage servers.

Exadata Infrastructures deployed with additional storage servers will be configured as an Elastic shape with the total number of storage servers and usable capacity clearly called out for the given infrastructure.

Before you can scale the number of Exadata storage servers, review the site and network requirements, and the checklists to prepare and deploy Exadata Cloud@Customer. Ensure that you have worked with sales and followed the procurement process. The following figure provides you an overview of the order and deployment process.

Responsibilities: Book Sign Ordering Subscription Customer Oracle Docs Order Oracle and Customer Discuss Gather Delivery and Prepare Data Configuration Site Visit Ship Hardware Deployment Center Information Requirements Activate Create Deliver Deploy Handover Configuration Service and and Validate Hardware to Customer Billing Bundle

Figure 4-1 Overview of Order and Deployment Process

Related Topics

- Using the Console to Scale Infrastructure Storage
 To scale infrastructure storage, complete this procedure.
- Using the Console to Download Scale Infrastructure Storage Configuration File
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this
 procedure.
- Using the Console to Activate New Storage Servers
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.
- Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption
 - To make storage capacity from the new servers for VM clusters consumption, complete this procedure.
- Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity
 - To view the storage capacity from the new storage server use this procedure.



Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure

Learn how to provision an Exadata Database Service on Cloud@Customer system.

- Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure
 - To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.
- Enabling or Disabling the Control Plane Server Diagnostic Offline Report To enable or disable CPS offline report, use this procedure.
- Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration
 - To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration, be prepared to provide values for the infrastructure configuration.
- Using the Console to Download a File Containing Configuration Data
 To download an Oracle Exadata Database Service on Cloud@Customer configuration file, complete this procedure.
- Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure
 - To activate Oracle Exadata Database Service on Cloud@Customer infrastructure, ensure that you meet the prerequisites, and complete this procedure.
- Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure
 - To find the status of your Oracle Exadata Database Service on Cloud@Customer infrastructure, use this procedure to check the Infrastructure Details page.

Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Under **Region**, select the region that you want to associate with the Oracle Exadata infrastructure.
 - The region that is associated with your Oracle Exadata infrastructure cannot be changed after the Oracle Exadata infrastructure is created. Therefore, ensure that you select the most appropriate region for your infrastructure. Consider the following factors:



- Consider any business policies or regulations that preclude the use of a particular region. For example, you can be required to maintain all operations within national boundaries.
- Consider the physical proximity of the region to your data center. Needless extra
 physical separation adds unnecessary latency to network communications between
 Oracle Cloud Infrastructure and your corporate data center.
- Click Exadata Infrastructure.
- 4. Click Create Exadata Infrastructure.
- **5.** In the Create Exadata Infrastructure page, provide the requested information:
 - Oracle Cloud Infrastructure region: The region that is associated with your Oracle Exadata infrastructure cannot be changed after the Oracle Exadata infrastructure is created. Therefore, check the displayed region to ensure that you are using the most appropriate region for your infrastructure.
 - See step 2 (earlier in this procedure) for further considerations. To switch regions now, use the **Region** menu at the top of the console.
 - **Choose a compartment:** From the list of available compartments, choose the compartment that you want to contain the Oracle Exadata infrastructure.
 - For more information, see *Understanding Compartments*.
 - **Provide the display name:** The display name is a user-friendly name that you can use to identify the Exadata infrastructure. The name doesn't need to be unique, because an Oracle Cloud Identifier (OCID) uniquely identifies the Oracle Exadata infrastructure.
 - Select the Exadata system model: From the list, choose the model of the Oracle Exadata hardware that is being used.
 - The Oracle Exadata system model and system shape combine to define the amount of CPU, memory, and storage resources that are available in the Exadata infrastructure. For more information, see *System Configuration*.
 - Select an Exadata system shape: Together with the Oracle Exadata system model, the Oracle Exadata system shape defines the amount of CPU, memory, and storage resources that are available in the Oracle Exadata infrastructure.
 - Base System: includes two compute nodes and three Oracle Exadata Storage Servers. A Base System is an entry-level configuration. Compared to other configurations, a Base System contains Oracle Exadata Storage Servers with significantly less storage capacity, and compute nodes with significantly less memory and processing power.
 - Quarter Rack: includes two compute nodes and three Oracle Exadata Storage Servers.
 - Half Rack: includes four compute nodes and six Oracle Exadata Storage Servers.
 - Full Rack: includes eight compute nodes and 12 Oracle Exadata Storage Servers.
 - Storage Configuration: You can add a minimum of 3 and extend up to a maximum
 of 12 storage servers. For each storage server you add, the storage capacity that will
 be added is displayed on the right.
 - Configure the cloud control plane server network



Each Oracle Exadata Database Service on Cloud@Customer system contains two control plane servers, which enable connectivity to Oracle Cloud Infrastructure. The control plane servers are connected to the control plane network, which is a subnet on your corporate network. The following settings define the network parameters:

- Control Plane Server 1 IP Address: Provide the IP address for the first control plane server. This IP address is for the network interface that connects the first control plane server to your corporate network using the control plane network.
- Control Plane Server 2 IP Address: Provide the IP address for the second control plane server. This IP address is for the network interface that connects the second control plane server to your corporate network using the control plane network.
- Netmask: Specify the IP netmask for the control plane network.
- Gateway: Specify the IP address of the control plane network gateway.
- HTTP Proxy: (Optional) You can choose to use this field to specify your corporate HTTP proxy. The expected format is as follows, where server is the server name, domain is the domain name, and port is the assigned port:

```
http://server.domain:port
```

For example:

```
http://proxy.example.com:80
```

For enhanced security, when possible, Oracle recommends that you use an HTTP proxy.

- Enable Control Plane Server Offline Report: Enabling the Control Plane Server (CPS) offline report helps in diagnosing connectivity issues between the CPS and OCI endpoints, should they arise.
 To view the report, do the following:
 - a. Find the CPS IP addresses.
 For more information, see Using the Console to View Exadata
 Infrastructure Network Configuration Details.
 - b. From your local network, access the report over HTTP. To view the report in HTML format, use http:// <CPSPublicIP>:18080/report

```
To view the report in JSON format, use http://
<CPSPublicIP>:18080/report/json
```

For more information, see ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side.

Configure the Oracle Exadata system networks

Each Oracle Exadata Database Service on Cloud@Customer system contains two system networks, which are not connected to your corporate network. The following settings define IP address allocations for these networks:



Administration Network CIDR Block: Specifies the IP address range for the
administration network using CIDR notation. The administration network provides
connectivity that enables Oracle to administer the Exadata system components,
such as the Exadata compute servers, storage servers, network switches, and
power distribution units. You can accept the suggested default, or specify a
custom value.

The maximum CIDR block prefix length is /23, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /16.

Ensure that the IP address range does not conflict with other hosts of your corporate network, and does not overlap with the InfiniBand network CIDR block.

InfiniBand Network CIDR Block: Specifies the IP address range for the Exadata
InfiniBand network using CIDR notation. The Exadata InfiniBand network provides
the high-speed low-latency interconnect used by Exadata software for internal
communications between various system components. You can accept the
suggested default, or specify a custom value.

The maximum CIDR block prefix length is /22, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /19.

Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the administration network CIDR block.

Configure DNS and NTP services

Each Exadata Database Service on Cloud@Customer system requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services to the Exadata infrastructure:

- DNS Servers: Provide the IP address of a DNS server that is accessible using the control plane network. You may specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible using the control plane network. You may specify up to three NTP servers.
- Time Zone: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.

Note:

If you want to set a time zone other than UTC or the browser-detected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

Provide maintenance details



Configure automatic maintenance Click Edit Maintenance Preferences.

Edit Maintenance Preferences dialog is displayed.

In the **Edit Maintenance Preferences** dialog, configure the following:

- * Choose a maintenance method:
 - * **Rolling:** By default, Exadata Infrastructure is updated in a rolling fashion, one server at a time with no downtime.
 - * **Non-rolling:** Update database and storage servers at the same time. The non-rolling maintenance method minimizes maintenance time but incurs full system downtime.
- * Enable custom action before performing maintenance on DB servers: Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers.
 - * Custom action timeout (in minutes): Timeout available to perform custom action before starting maintenance on the DB Servers.

Default: 30 minutes

Maximum: 120 minutes

* Maintenance schedule:

- * **No preference:** The system assigns a date and start time for infrastructure maintenance.
- * **Specify a schedule:** Choose your preferred month, week, weekday, start time, and lead time for infrastructure maintenance.
- * Lead Time: Specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message.

Click Save Changes.

If you switch from rolling to non-rolling maintenance method, then **Confirm Non-rolling Maintenance Method** dialog is displayed.

Enter the name of the infrastructure in the field provided to confirm the changes.

Click Save Changes.



Note:

After creating the infrastructure, you can find the maintenance method, maintenance schedule, DB Server version, and Storage Server version details under the **Maintenance** and **Version** sections on the **Infrastructure Details** page.

Provide maintenance contacts

Maintenance contacts are required for service request-based communications for hardware replacement and other maintenance events.

You can skip adding maintenance contacts while creating your infrastructure. However, you must add a primary contact prior to activating your infrastructure. Ensure that you provide the details of the contact that you used while registering the Customer Support Identifier (CSI) associated with this infrastructure, as a primary contact.

Optionally, you can add a maximum of nine secondary contacts. Both the primary and secondary contacts receive all notifications about hardware replacement, network issues, and software maintenance runs. Note that you can promote any secondary contacts as the primary anytime you want. When you promote a secondary contact to primary, the current primary contact will be demoted automatically to secondary.

Show Advanced Options

You have the option to configure advanced options.

Tags: (Optional) You can choose to apply tags. If you have permission to create a resource, then you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see *Resource Tags*. If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

6. Click Create Exadata Infrastructure.

If all of your inputs are valid, then the Infrastructure Details page appears. The page outlines the next steps in the provisioning process. Initially, after creation, the state of the Oracle Exadata infrastructure is **Requires-Activation**.

Related Topics

- Understanding Compartments
- System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

- ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side
- Resource Tags



Enabling or Disabling the Control Plane Server Diagnostic Offline Report

To enable or disable CPS offline report, use this procedure.

Note:

- You cannot enable or disable Control Plane Server diagnostic offline report if the Exadata Infrastructure is in DISCONNECTED mode.
- You can only generate CPS offline diagnostic report on the primary CPS.
- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Under Region, select the region that you want to associate with the Oracle Exadata infrastructure.
- Click Exadata Infrastructure.
- **4.** From the list of infrastructures, click the name of the infrastructure that you're interested in.
- On the Infrastructure Details page, find the Control Plane Server Offline Report details under the **Network** section.
- 6. Click the **Enable** or **Disable** link as needed.
 - If you click **Enable**, then the Enable Control Plane Server Offline Report window is displayed.
 - Review the information provided on the popup window, and then click **Enable**.
 - If you click **Disable**, then Disable Control Plane Server Offline Report window is displayed.
 - Review the information provided on the popup window, and then click **Disable**.

Viewing the Control Plane Server Diagnostic Offline Report

- Find the CPS IP addresses.
 For more information, see Using the Console to View Exadata Infrastructure Network Configuration Details.
- 2. From your local network, access the report over HTTP. To view the report in HTML format, use http://<CPSPublicIP>:18080/report To view the report in JSON format, use http://<CPSPublicIP>:18080/report/json

Related Topics

Using the Console to View Exadata Infrastructure Network Configuration Details
 To view network configuration details, follow these steps. Save this information for
 later use to troubleshoot if you face network issues.



Using the Console to View Exadata Infrastructure Network Configuration Details

To view network configuration details, follow these steps. Save this information for later use to troubleshoot if you face network issues.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- Under Region, select the region that you want to associate with the Oracle Exadata infrastructure.
- 3. Click Exadata Infrastructure.
- 4. From the list of infrastructures, click the name of the infrastructure that you're interested in. Note that the infrastructure must be in **Active** state.
- On the Infrastructure Details page, find the network configuration details under the Network section.

Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration, be prepared to provide values for the infrastructure configuration.

You can only edit Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration only if the current state of the Oracle Exadata infrastructure is **Requires Activation**. Also, ensure that you do not edit the Exadata infrastructure after you download the configuration file and provide it to Oracle.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Select Region and Compartment, and provide the region and the compartment where the Oracle Exadata infrastructure you want to edit is located.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Exadata infrastructure that you want to edit.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.

- Click Edit Infrastructure Networking.
- 6. Use the Edit Infrastructure Networking dialog to edit the Oracle Exadata infrastructure networking:
 - a. Configure the cloud control plane network

Each Oracle Exadata Database Service on Cloud@Customer system contains two Control Plane Servers, which enable connectivity to Oracle Cloud Infrastructure. The Control Plane Servers are connected to the control plane network, which is a subnet on your corporate network. The following settings define the network parameters:

Control Plane Server 1 IP Address: Provide the IP address for the first control
plane server. This IP address is for the network interface that connects the first
Control Plane Server to your corporate network using the control plane network.



- Control Plane Server 2 IP Address: Provide the IP address for the second control plane server. This IP address is for the network interface that connects the second Control Plane Server to your corporate network using the control plane network.
- **Netmask:** Specify the IP netmask for the control plane network.
- Gateway: Specify the IP address of the control plane network gateway.
- **HTTP Proxy:** Optionally, you can use this field to specify your corporate HTTP proxy to use for the HTTPS connection from the Control Plane Server to Oracle Cloud Infrastructure. The expected format is:

http://server.domain:port

For example:

http://proxy.example.com:80

For enhanced security, when possible, Oracle recommends that you use an HTTP proxy.

b. Configure the Exadata system networks

Each Oracle Exadata Database Service on Cloud@Customer system contains two system networks, which are not connected to your corporate network. The following settings define IP address allocations for these networks:

 Administration Network CIDR Block: Specifies the IP address range for the administration network using CIDR notation. The administration network provides connectivity that enables Oracle to administer the Exadata system components, such as the Exadata compute servers, storage servers, network switches, and power distribution units.

The maximum CIDR block prefix length is /23, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Oracle Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /16.

Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the InfiniBand network CIDR block.

 InfiniBand Network CIDR Block: Specifies the IP address range for the Exadata InfiniBand network using CIDR notation. The Exadata InfiniBand network provides the high-speed low-latency interconnect used by Exadata software for internal communications between various system components.

The maximum CIDR block prefix length is /22, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Oracle Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /19.



Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the administration network CIDR block.

c. Configure DNS and NTP services

Each Oracle Exadata Database Service on Cloud@Customer system requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services to the Exadata infrastructure:

- DNS Servers: Provide the IP address of a DNS server that is accessible using the control plane network. You can specify up to three DNS servers.
- **NTP Servers:** Provide the IP address of an NTP server that is accessible using the control plane network. You may specify up to three NTP servers.
- **Time zone:** The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.



If you want to set a time zone other than UTC or the browser-detected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

7. Click Save Changes.

Using the Console to Download a File Containing Configuration Data

To download an Oracle Exadata Database Service on Cloud@Customer configuration file, complete this procedure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.

5. Click Download Configuration.

Your browser downloads a file containing the infrastructure configuration details.

The generated configuration file includes all the relevant configuration details for the additional storage servers included as part of the create infrastructure flow.



When you provide the generated infrastructure configuration file to Oracle, ensure that it has not been altered in any way. Also, ensure that you do not edit the Oracle Exadata infrastructure after you download the configuration file and provide it to Oracle.

Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure

To activate Oracle Exadata Database Service on Cloud@Customer infrastructure, ensure that you meet the prerequisites, and complete this procedure.

- Ensure that you have added a primary contact. You cannot activate your infrastructure without adding a primary maintenance contact.
- Locate the activation file. This file is supplied to you by Oracle after installation and initial configuration of your Oracle Exadata Database Service on Cloud@Customer system.
- Ensure that the current state of your infrastructure is Requires Activation. You
 can only activate Oracle Exadata if its state is Requires Activation.
- Download the activation file.
- 2. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 3. Choose **Region** and **Compartment**, and select the region and compartment that contains the Oracle Exadata infrastructure that you want to activate.
- Click Exadata Infrastructure.
- 5. Click the name of the Oracle Exadata infrastructure that you want to activate.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 6. Click Activate.
 - The **Activate** button is only available if the Oracle Exadata infrastructure requires activation. You cannot activate Oracle Exadata infrastructure multiple times.
- 7. Use the Activate dialog to upload the activation file, and then click Activate Now.
 - The activation file includes all the relevant details for the additional storage servers included as part of the create infrastructure flow.
 - After activation, the state of the Oracle Exadata infrastructure changes to Active.

Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure

To find the status of your Oracle Exadata Database Service on Cloud@Customer infrastructure, use this procedure to check the Infrastructure Details page.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure that you are interested in.
- Click Exadata Infrastructure.



- 4. Click the name of the Oracle Exadata infrastructure that you are interested in.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- **5.** Check the icon on the Infrastructure Details page. The color of the icon and the text below it indicates the status of the Oracle Exadata infrastructure.
 - **Creating**: Yellow icon. The Oracle Exadata infrastructure definition is being created in the control plane.
 - Requires Activation: Yellow icon. The Oracle Exadata infrastructure is defined in the control plane, but it must be provisioned and activated before it can be used.
 - Active: Green icon. The Oracle Exadata infrastructure is successfully provisioned and activated.
 - Deleting: Gray icon. The Oracle Exadata infrastructure is being deleted by using the Console or API.
 - Deleted: Gray icon. The Oracle Exadata infrastructure is deleted, and is no longer available. This state is transitory. It is displayed for a short time, after which the Oracle Exadata infrastructure is no longer displayed.
 - Activation Failed: Red icon. An error condition currently prevents the activation of the Oracle Exadata infrastructure. Typically, this state is auto-correcting, and does not require user intervention.

Configuring Oracle-Managed Infrastructure Maintenance

Oracle performs the updates to all of the Oracle-managed infrastructure components on $Exadata\ Cloud@Customer$.

You may manage contacts who are notified regarding infrastructure maintenance, set a maintenance window to determine the time your quarterly infrastructure maintenance will begin, and also view scheduled maintenance runs and the maintenance history of your Exadata Cloud@Customer in the Oracle Cloud Infrastructure Console. For details regarding the infrastructure maintenance process and configuring the maintenance controls refer to the following:

- About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates
 Oracle performs patches and updates to all of the Oracle-managed system components
 on Exadata Cloud@Customer.
- Infrastructure Maintenance Contacts
 Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.
- Using the Console to Configure Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a
 maintenance window to determine the time your quarterly infrastructure maintenance will
 begin.
- Monitor Infrastructure Maintenance Using Lifecycle State Information
 The lifecycle state of your Exadata Infrastructure resource enables you to monitor when
 the maintenance of your infrastructure resource begins and ends.
- Receive Notifications about Your Infrastructure Maintenance Updates
 There are two ways to receive notifications. One is through email to infrastructure
 maintenance contacts and the other one is to subscribe to the maintenance events and
 get notified.



About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates

Oracle performs patches and updates to all of the Oracle-managed system components on Exadata Cloud@Customer.

Oracle patches and updates include the physical database server hosts, Exadata Storage Servers, Network Fabric Switches, management switch, power distribution units (PDUs), integrated lights-out management (ILOM) interfaces, and Control Plane Servers. This is referred to as Exadata Cloud@Customer infrastructure maintenance.

In all but rare exceptional circumstances, you receive advance communication about these updates to help you plan for them. If there are corresponding recommended updates for your VM cluster virtual machines (VMs), then Oracle provides notifications about them.

Wherever possible, scheduled updates are performed in a manner that preserves service availability throughout the update process. However, there can be some noticeable impact on performance and throughput while individual system components are unavailable during the update process.

For example, database server patching typically requires a reboot. In such cases, wherever possible, the database servers are restarted in a rolling manner, one at a time, to ensure that the service remains available throughout the process. However, each database server is unavailable for a short time while it restarts, and the overall service capacity diminishes accordingly. If your applications cannot tolerate the restarts, then take mitigating action as needed. For example, shut down an application while database server patching occurs.

Overview of the Infrastructure Maintenance Process
 By default, infrastructure maintenance updates the Exadata database server hosts in a rolling fashion, followed by updating the storage servers.

Overview of the Infrastructure Maintenance Process

By default, infrastructure maintenance updates the Exadata database server hosts in a rolling fashion, followed by updating the storage servers.

You can also choose non-rolling maintenance to update database and storage servers. The non-rolling maintenance method first updates your storage servers at the same time, then your database servers at the same time. Although non-rolling maintenance minimizes maintenance time, it incurs full system downtime while the storage servers and database servers are being updated.

Rolling infrastructure maintenance begins with the Exadata database server hosts. For the rolling maintenance method, database servers are updated one at a time. Each of the database server host's VMs is shut down, the host is updated, restarted, and then the VMs are started, while other database servers remain operational. This process continues until all servers are updated. After database server maintenance completes, storage server maintenance begins. For the rolling maintenance method, storage servers are updated one at a time and do not impact VM cluster VM's availability.

Note that while databases are expected to be available during the rolling maintenance process, the automated maintenance verifies Oracle Clusterware is running but does not verify that all database services and pluggable databases (PDBs) are available



after a server is brought back online. The availability of database services and PDBs after maintenance can depend on the application service definition. For example, a database service, configured with certain preferred and available nodes, may be relocated during the maintenance and wouldn't automatically be relocated back to its original node after the maintenance completes. Oracle recommends reviewing the documentation on *Achieving Continuous Availability for Your Applications* on Exadata Cloud Systems to reduce the potential for impact to your applications. By following the documentation's guidelines, the impact of infrastructure maintenance will be only minor service degradation as database servers are sequentially updated.

Oracle recommends that you follow the *Maximum Availability Architecture (MAA) best practices* and use Data Guard to ensure the highest availability for your critical applications. For databases with Data Guard enabled, Oracle recommends that you separate the maintenance windows for the infrastructure instances running the primary and standby databases. You may also perform a switchover prior to the maintenance operations for the infrastructure instance hosting the primary database. This allows you to avoid any impact on your primary database during infrastructure maintenance.

Prechecks are performed on the Exadata Cloud@Customer infrastructure components prior to the start of the maintenance window. The goal of the prechecks is to identify issues that may prevent the infrastructure maintenance from succeeding. The Exadata infrastructure and all components remain online during the prechecks. An initial precheck is run approximately two weeks prior to the maintenance start and another precheck is run approximately 24 hours prior to maintenance start. If the prechecks identify an issue that requires rescheduling the maintenance notification is sent to the maintenance contacts.

The time taken to update infrastructure components varies depending on the number of database servers and storage servers in the Exadata infrastructure, the maintenance method, and whether custom action has been enabled. The approximate times provided are estimates. Time for custom action, if configured, is not included in the estimates below. Database server maintenance time may vary depending on the time required to shutdown each VM before the update and then start each VM and associated resources after the update of each node before proceeding to the next node. The storage server maintenance time will vary depending on the time required for the ASM rebalance, which is not included in the estimates below.

Rolling:

- Each database server takes 90 minutes on average.
- Each storage server takes 60 minutes on average.
- Each InfiniBand or RoCE fabric switches take 30 minutes on average.
- The approximate total time for infrastructure maintenance is as follows:
 - * Base and Quarter Rack (2 Database Servers/3 Storage Servers): Approximately 7 hours
 - 2 Database Servers X 90 = 180 minutes
 - 3 Storage Servers X 60 = 180 minutes
 - 2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes
 - Half Rack (4 Database Servers/6 Storage Servers): Approximately 13 hours
 - 4 Database Servers X 90 = 360 minutes
 - 6 Storage Servers X 60 = 360 minutes
 - 2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes



Full Rack (8 Database Servers/12 Storage Servers): Approximately 26 hours

8 Database Servers X 90 = 720 minutes

12 Storage Servers X 60 = 720 minutes

2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes

Non-Rolling:

- All database servers take 180 minutes on average.
- All storage servers take 60 minutes on average.
- Storage Servers and Database servers are brought back online prior to starting fabric switch maintenance.
- Network fabric switches are still updated in a rolling method and take 30 minutes each on average.
- The approximate total time for infrastructure maintenance is 5 hours regardless of shape:
 - * All Database Servers = 180 minutes
 - * All Storage Servers = 60 minutes
 - * 2 InfiniBand or RoCE Fabric Switch = 60 minutes

Related Topics

- Achieving Continuous Availability For Your Applications
- Maximum Availability Architecture (MAA) Best Practices

Infrastructure Maintenance Contacts

Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.

Add a primary maintenance contact and optionally add a maximum of nine secondary contacts. Both the primary and secondary contacts receive all notifications about hardware replacement, network issues, and software maintenance runs.

You can promote any secondary contacts as the primary anytime you want. When you promote a secondary contact to primary, the current primary contact will be demoted automatically to secondary.

For more information, see: Using the Console to Create Infrastructure and Managing Infrastructure Maintenance Contacts.

Related Topics

 Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.

Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.



Using the Console to Configure Oracle-Managed Infrastructure Updates

Exadata Cloud Service updates are released on a quarterly basis. You can set a maintenance window to determine the time your quarterly infrastructure maintenance will begin.

You can also edit the maintenance method, enable custom action, view the scheduled maintenance runs and the maintenance history of your Exadata Cloud@Customer in the Oracle Cloud Infrastructure Console. For more information, see the following:

- View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure
- View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure
- View the Maintenance History of Exadata Cloud@Customer Infrastructure
- View and Edit Maintenance While Maintenance is In Progress or Waiting for Custom Action

In exceptional cases, Oracle might need to update your system apart from the regular quarterly updates to apply time-sensitive changes such as security updates. While you cannot opt-out of these infrastructure updates, Oracle alerts you in advance through the Cloud Notification Portal to help you plan for them.

- View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure
 - To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.
- View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure Learn how to view and edit the time of the next scheduled maintenance.
- View the Maintenance History of Exadata Cloud@Customer Infrastructure
 Learn how to view the maintenance history for an Exadata Cloud@Customer
 Infrastructure.

Related Topics

 View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.

View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



- 2. Select **Region** and **Compartment**, and provide the region and the compartment where the Oracle Exadata infrastructure you want to edit is located.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that you want to edit.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- Click Edit Maintenance Preferences.
 Edit Maintenance Preferences page is displayed.

Note:

Changes made to maintenance preferences apply only to future maintenance, not the maintenance that has already been scheduled. To modify scheduled maintenance, see *View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure*.

- **6.** On the Edit Maintenance Preferences page, configure the following:
 - Choose a maintenance method:
 - Rolling: By default, Exadata Infrastructure is updated in a rolling fashion, one server at a time with no downtime.
 - Non-rolling: Update database and storage servers at the same time. The non-rolling maintenance method minimizes maintenance time but incurs full system downtime.
 - Enable custom action before performing maintenance on DB servers:

 Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers. The maintenance run, while waiting for the custom action, may also be resumed prior to the timeout.
 - Custom action timeout (in minutes): Timeout available to perform custom action before starting maintenance on the DB Servers.

Default: 30 minutes

Maximum: 120 minutes

Maintenance schedule:

- No preference: The system assigns a date and start time for infrastructure maintenance.
- Specify a schedule: Choose your preferred month, week, weekday, start time, and lead time for infrastructure maintenance.
 - * Under Maintenance months, specify at least one month for each quarter during which Exadata infrastructure maintenance will take place. You can select more than one month per quarter. If you specify a long lead time for advanced notification (for example, 4 weeks), you may wish to specify 2 or 3 months per quarter during which



maintenance runs can occur. This will ensure that your maintenance updates are applied in a timely manner after accounting for your required lead time. Lead time is discussed in the following steps.

- * Optional. **Under Week of the month**, specify which week of the month, maintenance will take place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week. Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days. If you do not specify a week of the month, Oracle will run the maintenance update in a week to minimize disruption.
- * Optional. **Under Day of the week**, specify the day of the week on which the maintenance will occur. If you do not specify a day of the week, Oracle will run the maintenance update on a weekend day to minimize disruption.
- * Optional. **Under Start hour**, specify the hour during which the maintenance run will begin. If you do not specify a start hour, Oracle will pick the least disruptive time to run the maintenance update.
- * Under **Lead Time**, specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message. Your lead time ensures that a newly released maintenance update is scheduled to account for your required minimum period of advanced notification.

7. Click Save Changes.

If you switch from rolling to non-rolling maintenance method, then Confirm Non-rolling Maintenance Method dialog is displayed.

- a. Enter the name of the infrastructure in the field provided to confirm the changes.
- b. Click Save Changes.

View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure

Learn how to view and edit the time of the next scheduled maintenance.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
- Click Exadata Infrastructure.
- 4. In the list of Exadata Infrastructures, find the infrastructure you want to set the next scheduled maintenance window for and click its highlighted name.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.



An information block is displayed 6 hours before the start of a maintenance run, regardless of whether you've chosen rolling or non-rolling maintenance method. When the maintenance begins, it is automatically removed.

5. On the Infrastructure Details page, under **Maintenance**, click the view link in the **Next Maintenance** field.



The Exadata Infrastructure Maintenance page is displayed.

On the Exadata Infrastructure Maintenance page, scheduled maintenance details are listed.

Target DB Server Version and Target Storage Server Version: These fields display the Exadata software version to be applied by the scheduled maintenance. The version applied will be the most recent certified update for Exadata infrastructures in the cloud. If the next quarterly update is not yet certified when the maintenance is scheduled, then the versions may show "LATEST" until the new quarterly update becomes available. Once the update becomes available the new version will be displayed.

To find information on the Database Server Exadata software version or the Storage Server Exadata software version, see My Oracle Support note Exadata Database Machine and Exadata Storage Server Supported Versions (Doc ID 888828.1).

- 7. To change the next scheduled maintenance settings, click Edit Maintenance Run.
 On the Edit Maintenance page, do the following:
 - Select a maintenance method, Rolling or Non-rolling.



If you select the **Non-rolling** option, an information block appears stating that components will be updated simultaneously, resulting in full system downtime.

- Enable custom action before performing maintenance on DB servers: Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers. The maintenance run, while waiting for the custom action, may also be resumed prior to the timeout.
 - Custom action timeout (in minutes): Maximum timeout available to perform custom action before starting maintenance on the DB Servers.
 Default: 30 minutes

Maximum: 120 minutes

To reschedule the next maintenance run, enter a date and time in the Scheduled Start time field.

The following restrictions apply:

You can reschedule the infrastructure maintenance to a date no more than 180 days from the prior infrastructure maintenance. If a new maintenance release is announced prior to your rescheduled maintenance run, the newer release will be applied on your specified date. You can reschedule your maintenance to take place earlier than it is currently scheduled. You cannot reschedule the maintenance if the current time is within 2 hours of the scheduled maintenance start time.



- Oracle reserves certain dates each quarter for internal maintenance operations, and you cannot schedule your maintenance on these dates.
- Click Save Changes.
- 8. To view estimated maintenance time details for various components, click the **View** link is displayed in the **Total Estimated Maintenance Time** field.

The **View** link is displayed in the **Total Estimated Maintenance Time** field only if the Maintenance Method is **Rolling**.

The **Estimated Maintenance Time Details** page is displayed with details that include:

- Total Estimated Maintenance Time
- Database Servers Estimated Maintenance Time
- Storage Servers Estimated Maintenance Time
- Network Switches Estimated Maintenance Time
- Order in which components are updated. In rolling maintenance, components are updated in the sequence displayed
- To view the number of VMs that will be restarted as part of Database Server maintenance, click the Show details link.
 The VM Location dialog is displayed.
- b. In the VM Cluster Name field, you can find out what VM cluster a particular VM belongs to.
- c. Click Close.
- 9. Click Close to close the Estimated Maintenance Time Details page.

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=888828.1

View the Maintenance History of Exadata Cloud@Customer Infrastructure

Learn how to view the maintenance history for an Exadata Cloud@Customer Infrastructure.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
- 3. Click Exadata Infrastructure.
- **4.** In the list of Exadata Infrastructures, find the infrastructure you want to view the maintenance history and click its highlighted name.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. On the Infrastructure Details page, under **Maintenance**, click the **view** link in the **Next Maintenance** field.
 - The Exadata Infrastructure Maintenance page is displayed.
- 6. On the Exadata Infrastructure Maintenance page, click Maintenance History to see a list of past maintenance events including details on their completion state and the target database and storage server versions.



To find information on the Database Server Exadata software version or the Storage Server Exadata software version, see My Oracle Support note *Exadata Database Machine and Exadata Storage Server Supported Versions (Doc ID 888828.1).*

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=888828.1

Monitor Infrastructure Maintenance Using Lifecycle State Information

The lifecycle state of your Exadata Infrastructure resource enables you to monitor when the maintenance of your infrastructure resource begins and ends.

In the Oracle Cloud Infrastructure Console, you can see lifecycle state details messages on the **Exadata Infrastructure Details** page when a tooltip is displayed beside the **Status** field. You can also access these messages using the ListExadataInfrastructures API, and using tools based on the API, including *SDKs* and the *OCI CLI*.

During infrastructure maintenance operations, you can expect the following:

 If you specify a maintenance window, then patching begins at your specified start time. The infrastructure resource's lifecycle state changes from Available to Maintenance in Progress.



The prechecks are now done prior to the start of the maintenance.

- When Exadata database server maintenance starts, the infrastructure resource's lifecycle state is Maintenance in Progress, and the associated lifecycle state message is, The underlying infrastructure of this system (dbnodes) is being updated.
- When storage server maintenance starts, the infrastructure resource's lifecycle state is Maintenance in Progress, and the associated lifecycle state message is, The underlying infrastructure of this system (cell storage) is being updated and this will not impact Database availability.
- After storage server maintenance is complete, the networking switches are updated one at a time, in a rolling fashion.
- When maintenance is complete, the infrastructure resource's lifecycle state is
 Available, and the Console and API-based tools do not provide a lifecycle state message.

Related Topics

- ListExadataInfrastructures
- Software Development Kits and Command Line Interface
- Command Line Interface (CLI)



Receive Notifications about Your Infrastructure Maintenance Updates

There are two ways to receive notifications. One is through email to infrastructure maintenance contacts and the other one is to subscribe to the maintenance events and get notified.

Oracle schedules maintenance run of your infrastructure based on your scheduling preferences and sends email notifications to all your infrastructure maintenance contacts. You can login to the console and view details of the schedule maintenance run. Appropriate maintenance related events will be generated as Oracle prepares for your scheduled maintenance run, for example, precheck, patching started, patching end, and so on. For more information about all maintenance related events, see *Oracle Exadata Cloud@Customer Events*. In case, if there are any failures, then Oracle reschedules your maintenance run, generates related notification, and notifies your infrastructure maintenance contacts.

For more information about Oracle Cloud Infrastructure Events, see *Overview of Events*. To receive additional notifications other than the ones sent to infrastructure maintenance contacts, you can subscribe to infrastructure maintenance events and get notified using the Oracle Notification service, see *Notifications Overview*.

Related Topics

- Oracle Exadata Database Service on Cloud@Customer Events
 Exadata Cloud@Customer resources emit events, which are structured messages that indicate changes in resources.
- Overview of Events
- Notifications Overview
- Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.

Creating First VM Cluster Network on Exadata Cloud@Customer

Follow the steps in the following sections to create your first VM Cluster Network.

- About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer
 - The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.
- Using the Console to Create a VM Cluster Network
 To create your VM cluster network with the Console, be prepared to provide values for
 the fields required for configuring the infrastructure.
- Using the Console to Edit a VM Cluster Network
 You can only edit a VM cluster network that is not associated with a VM cluster.
- Using the Console to Download a File Containing the VM Cluster Network Configuration Details
 - To provide VM cluster network information to your network administrator, you can download and supply a file containing the network configuration.



Using the Console to Validate a VM Cluster Network
 You can only validate a VM cluster network if its current state is Requires
 Validation, and if the underlying Exadata infrastructure is activated.

About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer

The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.

Before you can create any databases on your Exadata Cloud@Customer infrastructure, you must create a VM cluster network, and you must associate it with a VM cluster.

The VM cluster network specifies network resources, such as IP addresses and host names, that reside in your corporate data center and are allocated to Exadata Cloud@Customer. The VM cluster network includes definitions for the Exadata client network and the Exadata backup network. The client network and backup network contain the network interfaces that you use to connect to the VM cluster virtual machines, and ultimately the databases that reside on those virtual machines.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Using the Console to Create a VM Cluster Network

To create your VM cluster network with the Console, be prepared to provide values for the fields required for configuring the infrastructure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure for which you want to create a VM cluster network.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure for which you want to create a VM cluster network.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

- 5. Click Create VM Cluster Network.
- 6. Provide the requested information in the Data Center Network Details page:
 - a. Provide the display name.

The display name is a user-friendly name that you can use to identify the VM cluster network. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the VM cluster network.



b. Provide client network details.

The client network is the primary channel for application connectivity to Exadata Database Service on Cloud@Customer resources. The following settings define the required network parameters:

• VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the client network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

 CIDR Block: Using CIDR notation, provide the IP address range for the client network.

The following table specifies the maximum and recommended CIDR block prefix lengths for each Exadata system shape. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network.

Exadata System Shape	Base System, Quarter Rack, or Half Rack	Full Rack
Maximum CIDR block prefix length	/28	/27
Recommended CIDR block prefix length	/27	/26

- Netmask: Specify the IP netmask for the client network.
- **Gateway:** Specify the IP address of the client network gateway.
- Hostname Prefix: Specify the prefix that is used to generate the hostnames in the client network.
- **Domain Name:** Specify the domain name for the client network.
- c. Provide backup network details.

The backup network is the secondary channel for connectivity to Exadata Database Service on Cloud@Customer resources. It is typically used to segregate application connections on the client network from other network traffic. The following settings define the required network parameters:

• VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the backup network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved, and cannot be entered.



 CIDR Block: Using CIDR notation, provide the IP address range for the backup network.

The following table specifies the maximum and recommended CIDR block prefix lengths for each Exadata system shape. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network.

Exadata System Shape	Base System, Quarter Rack, or Half Rack	Full Rack
Maximum CIDR block prefix length	/29	/28
Recommended CIDR block prefix length	/28	/27

- Netmask: Specify the IP netmask for the backup network.
- Gateway: Specify the IP address of the backup network gateway.
- **Hostname Prefix:** Specify the prefix that is used to generate the hostnames in the backup network.
- **Domain Name:** Specify the domain name for the backup network.
- d. Provide DNS and NTP server details.

The VM cluster network requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services:

- **DNS Servers:** Provide the IP address of a DNS server that is accessible using the client network. You may specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible using the client network. You may specify up to three NTP servers.
- e. Configure Advanced Options.

Network: (Optional) Assign a SCAN listener port (TCP/IP) in the range between 1024 and 8999. Default is 1521.

Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

7. Click Review Configuration.

The Review Configuration page displays detailed information about the VM cluster network, including the hostname and IP address allocations. These allocations are initially system-generated, and are based on your inputs to the Specify Parameters page.

- 8. (Optional) You can choose to adjust the system-generated network definitions on the Review Configuration page.
 - a. Click Edit IP Allocation.



- **b.** Use the **Edit** dialog to adjust the system-generated network definitions to meet your requirements.
- c. Click Save Changes.
- Click Create VM Cluster Network.

The VM Cluster Network Details page is now displayed. Initially after creation, the state of the VM cluster network is **Requires Validation**.

Related Topics

Resource Tags

Using the Console to Edit a VM Cluster Network

You can only edit a VM cluster network that is not associated with a VM cluster.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Exadata infrastructure that is associated with the VM cluster network that you want to edit.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

5. Click the name of the VM cluster network that you want to edit.

The VM Cluster Network Details page displays information about the selected VM cluster network.

- 6. Click Edit VM Cluster Network.
- 7. Use the **Edit** dialog to edit the VM cluster network attributes:
 - a. Client Network

The client network is the primary channel for application connectivity to Exadata Database Service on Cloud@Customer resources. You can edit the following client network settings:

• VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the client network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

- Netmask: Specify the IP netmask for the client network.
- Gateway: Specify the IP address of the client network gateway.
- **Hostname:** Specify the hostname for each address in the client network.
- **IP Address:** Specify the IP address for each address in the client network.



b. Backup Network

The backup network is the secondary channel for connectivity to Exadata Database Service on Cloud@Customer resources. It is typically used to segregate application connections on the client network from other network traffic. You can edit the following backup network settings:

 VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the backup network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

- Hostname: Specify the hostname for each address in the backup network.
- IP Address: Specify the IP address for each address in the backup network.

c. Configure DNS and NTP Servers

The VM cluster network requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. You can edit the following settings:

- **DNS Servers:** Provide the IP address of a DNS server that is accessible using the client network. You may specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible
 using the client network. You may specify up to three NTP servers.

8. Click Save Changes.

After editing, the state of the VM cluster network is **Requires Validation**.

Using the Console to Download a File Containing the VM Cluster Network Configuration Details

To provide VM cluster network information to your network administrator, you can download and supply a file containing the network configuration.

Use this procedure to download a configuration file that you can supply to your network administrator. The file contains the information needed to configure your corporate DNS and other network devices to work along with Exadata Database Service on Cloud@Customer.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Exadata infrastructure that is associated with the VM cluster network that you are interested in.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.

The Infrastructure Details page displays information about the selected Exadata infrastructure.



Click the name of the VM cluster network for which you want to download a file containing the VM cluster network configuration details.

The VM Cluster Network Details page displays information about the selected VM cluster network.

6. Click Download Network Configuration.

Your browser downloads a file containing the VM cluster network configuration details.

Using the Console to Validate a VM Cluster Network

You can only validate a VM cluster network if its current state is **Requires Validation**, and if the underlying Exadata infrastructure is activated.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure that is associated with the VM cluster network that you want to validate.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.
 - The Infrastructure Details page displays information about the selected Exadata infrastructure.
- 5. Click the name of the VM cluster network that you want to validate.
 - The VM Cluster Network Details page displays information about the selected VM cluster network.
- Click Validate VM Cluster Network.
 - Validation performs a series of automated checks on the VM cluster network. The Validate VM Cluster Network button is only available if the VM cluster network requires validation.
- 7. In the resulting dialog, click **Validate** to confirm the action.
 - After successful validation, the state of the VM cluster network changes to **Validated** and the VM cluster network is ready to use. If validation fails for any reason, examine the error message and resolve the issue before repeating validation.

Provisioning the First VM Cluster on an Exadata Cloud@Customer System

Learn how to create the first VM cluster on your Exadata Cloud@Customer system.

- About Managing VM Clusters on Exadata Database Service on Cloud@Customer
 The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.
- Prerequisites for VM Clusters on Exadata Database Service on Cloud@Customer
 To connect to the VM cluster virtual machine, you use an SSH public key.



Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.

About Managing VM Clusters on Exadata Database Service on Cloud@Customer

The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.

The VM cluster contains an installation of Oracle Clusterware, which supports databases in the cluster. In the VM cluster definition, you also specify the number of enabled CPU cores, which determines the amount of CPU resources that are available to your databases

Before you can create any databases on your Exadata Cloud@Customer infrastructure, you must create a VM cluster network, and you must associate it with a VM cluster.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Prerequisites for VM Clusters on Exadata Database Service on Cloud@Customer

To connect to the VM cluster virtual machine, you use an SSH public key.

The public key is in OpenSSH format, from the key pair that you plan to use for connecting to the VM cluster virtual machines through SSH. The following shows an example of a public key, which is abbreviated for readability.

ssh-rsa AAAAB3NzaC1yc2EAAAABJQAA....lo/gKMLVM2xzc1xJr/Hc26biw3TXWGEakrK10Q== rsa-key-20160304

Related Topics

Managing Key Pairs on Linux Instances

Using the Console to Create a VM Cluster

To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.

To create a VM cluster, ensure that you have:

- Active Exadata infrastructure is available to host the VM cluster.
- A validated VM cluster network is available for the VM cluster to use.



- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- Click VM Clusters.
- 4. Click Create VM Cluster.
- **5.** Provide the requested information on the Create VM Cluster page:
 - a. Choose a compartment: From the list of available compartments, choose the compartment that you want to contain the VM cluster.
 - b. **Provide the display name:** The display name is a user-friendly name that you can use to identify the VM cluster. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the VM cluster.
 - c. Select Exadata Database Service on Cloud@Customer Infrastructure: From the list, choose the Exadata infrastructure to host the VM cluster. You are not able to create a VM cluster without available and active Exadata infrastructure.
 - d. Select a VM Cluster Network: From the list, choose a VM cluster network definition to use for the VM cluster. You must have an available and validated VM cluster network before you can create a VM cluster.
 - **e. Choose the Oracle Grid Infrastructure version:** From the list, choose the Oracle Grid Infrastructure release that you want to install on the VM cluster.

The Oracle Grid Infrastructure release determines the Oracle Database releases that can be supported on the VM cluster. You cannot run an Oracle Database release that is later than the Oracle Grid Infrastructure software release.

f. Configure VM Cluster:

- Click Select DB Servers for VM placement to allocate VM resources.
- On the Select DB Servers dialog, select a minimum of two database servers for VM placement. Maximum resources available for allocation per VM are based on the number of database servers selected.

Note:

- DB Servers, which already have 8 VMs running on them are not available for selection.
- When calculating maximum local storage resources across selected DB Servers, the reserved local storage needed by the system to host a VM based on hardware generation is deducted from the DB Server with the least resources.
 For example, if the local storage available across selected DB servers is 823 GB for DB Server 3 and 813 GB for DB Server 4, then the minimum across selected servers is 813 GB and the maximum available for resource allocation is 813 GB 184 GB (reserved local storage for hosting VM on X8M DB servers) = 629 GB.

For more information, see Estimating How Much Local Storage You Can Provision to Your VMs.



- Click Save Changes.
- g. Specify the OCPU count per VM: Specify the OCPU count for each individual VM. The minimum value is 2 OCPUs per VM (for a live VM condition), unless you are specifying zero OCPUs (for a shutdown VM condition).

If you specify a value of zero, then the VM cluster virtual machines are all shut down at the end of the cluster creation process. In this case, you can later start the virtual machines by scaling the OCPU resources. See *Using the Console to Scale the Resources on a VM Cluster*.

The value for OCPU count for the whole VM Cluster will be calculated automatically based upon the per VM OCPU count you have specified and the number of physical Database Servers configured for the system. There is one VM created on each physical Database Server available.

OCPU: An Oracle Compute Unit (OCPU) provides CPU capacity equivalent of one physical core of an Intel Xeon processor with hyperthreading enabled. Each OCPU corresponds to two hardware execution threads, known as vCPUs.

See, Oracle Platform as a Service and Infrastructure as a Service – Public Cloud Service DescriptionsMetered & Non-Metered.

- h. Requested OCPU count for the VM Cluster: Displays the total number of CPU cores allocated to the VM cluster based on the value you specified in the Specify the OCPU count per VM field. This field is not editable.
- i. Specify the memory per VM (GB): Specify the memory for each individual VM. The value must be a multiple of 1 GB and is limited by the available memory on the Exadata infrastructure.
- j. Requested memory for the VM Cluster (GB): Displays the total amount of memory allocated to the VM cluster based on the value you specified in the Specify the memory per VM (GB) field. This field is not editable.
- k. Specify the local file system size per VM (GB): Specify the local file system size for each individual VM. The value must be a multiple of 1 GB and is limited by the available size of the file system on the X8-2 and X7-2 infrastructures.

Note that the minimum size of local system storage must be 60 GB. In addition to the 60 GB, each node of the VM must have at least 137 GB free for miscellaneous VM files. Each time when you create a new VM cluster, the space remaining out of the total available space is utilized for the new VM cluster.

For more information and instructions to specify the size for each individual VM, see *Introduction to Scale Up or Scale Down Operations*.

- I. Reserved local storage per VM (GB): Displays the local storage size reserved internally for root file systems, Oracle Grid Infrastructure Homes, and diagnostic logs. This field is not editable.
- m. Configure the Exadata Storage: The following settings define how the Exadata storage is configured for use with the VM cluster. These settings cannot be changed after creating the VM cluster.
 - Specify Usable Exadata Storage: Specify the size for each individual VM. The minimum recommended size is 2 TB.



- Allocate Storage for Exadata Snapshots: Check this option to create a sparse disk group, which is required to support Exadata snapshot functionality. Exadata snapshots enable space-efficient clones of Oracle databases that can be created and destroyed very quickly and easily.
- Allocate Storage for Local Backups: Check this option to configure the Exadata storage to enable local database backups. If you select this option, more space is allocated to the RECO disk group to accommodate the backups. If you do not select this option, you cannot use local Exadata storage as a backup destination for any databases in the VM cluster.

Table 4-5 Storage Allocation

Storage Allocation	DATA Disk Group	RECO Disk Group	SPARSE Disk Group
Exadata Snapshots: No	80%	20%	0% (The SPARSE disk group is not created.)
Enable Backups on Local Exadata Storage: No			
Exadata Snapshots: No	40%	60%	0% (The SPARSE disk group is not created.)
Enable Backups on Local Exadata Storage: Yes			
Allocate Storage for Exadata Snapshots: Yes	60%	20%	20%
Enable Backups on Local Exadata Storage: No			
Allocate Storage for Exadata Snapshots: Yes	35%	50%	15%
Enable Backups on Local Exadata Storage: Yes			

n. Add SSH Key: Specify the public key portion of an SSH key pair that you want to use to access the VM cluster virtual machines. You can upload a file containing the key, or paste the SSH key string.

To provide multiple keys, upload multiple key files or paste each key into a separate field. For pasted keys, ensure that each key is on a single, continuous line. The length of the combined keys cannot exceed 10,000 characters.

o. Choose a license type:

- Bring Your Own License (BYOL): Select this option if your organization already owns Oracle Database software licenses that you want to use on the VM cluster.
- **License Included:** Select this option to subscribe to Oracle Database software licenses as part of Exadata Database Service on Cloud@Customer.

p. Diagnostic Notification:

Select the **Enable** option. Enabling diagnostic notification will allow you and Oracle Support to identify, investigate, track, and resolve guest VM issues quickly and effectively. For more information, see *Overview of Database Service Events*.



q. Show Advanced Options:

 Time zone: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.

Note:

If you want to set a time zone other than UTC or the browserdetected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

Tags: Optionally, you can apply tags. If you have permission to create a
resource, you also have permission to apply free-form tags to that
resource. To apply a defined tag, you must have permission to use the tag
namespace. For more information about tagging, see *Resource Tags*. If
you are not sure if you should apply tags, skip this option (you can apply
tags later) or ask your administrator.

6. Click Create VM Cluster.

The VM Cluster Details page is now displayed. While the creation process is running, the state of the VM cluster is **Pending**. When the VM cluster creation process completes, the state of the VM cluster changes to **Available**.

Related Topics

- Oracle Exadata Database Service on Cloud@Customer Service Description
 Learn how you can leverage the combined capabilities of Oracle Exadata and
 Oracle Cloud Infrastructure with Oracle Exadata Database Service on
 Cloud@Customer
- Using the Console to Scale the Resources on a VM Cluster
 Starting in Exadata Database Service on Cloud@Customer Gen2, you can scale
 up or down multiple resources at the same time. You can also scale up or down
 resources one at a time.
- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can
 scale up or scale down your VM cluster resources.
- Estimating How Much Local Storage You Can Provision to Your VMs
- Resource Tags
- Oracle PaaS/laaS Cloud Service Description documents
- Oracle Platform as a Service and Infrastructure as a Service Public Cloud Service DescriptionsMetered & Non-Metered
- Getting Started with Events
- Overview of Database Service Events



Creating Database Backup Destinations for Exadata Cloud@Customer

Exadata Cloud@Customer provides a backup facility, which you can configure individually on each database.

To store database backups on a Recovery Appliance or on a network file storage (NFS) location that you manage, then you must first create a backup destination.

- About Managing Backup Destinations for Exadata Database Service on Cloud@Customer
 - For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.
- Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer
 - To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.
- Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer
 - Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.

Related Topics

- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer
 - Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

About Managing Backup Destinations for Exadata Database Service on Cloud@Customer

For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.

Exadata Database Service on Cloud@Customer provides a backup facility, which you can configure individually on each database.

See: Managing Databases on Exadata Cloud@Customer and Managing Database Backup and Recovery on Exadata Cloud@Customer.

If you want to store backups on a Recovery Appliance, or on a network file storage (NFS) location that you manage, then you must first create a backup destination. Each backup destination defines the properties that are required to connect to the Recovery Appliance or NFS location, and each backup destination must be accessible in your data center from the VM cluster nodes.

The Exadata Database Service on Cloud@Customer backup facility can also store backups on Oracle Cloud Infrastructure object storage, or on local Exadata storage on your Exadata Database Service on Cloud@Customer system. However, you do not need to create a backup destination for any of these other locations. Instead, applicable options for backup to cloud object storage or local Exadata storage are available directly when you create a database.



Note:

Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Related Topics

- Zero Data Loss Recovery Appliance
- Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems
 - Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.
- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer
 - Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer

To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.

- For a Zero Data Loss Recovery Appliance backup destination:
 - The appliance must be configured with a virtual private catalog (VPC) user, which is used for taking the backups.
 - The appliance must be configured with the unique database name of the database being backed up, and a mapping to the VPC user.
 - The appliance must be accessible from the Exadata Database Service on Cloud@Customer system using the Oracle Net Services connection string, which is provided by the Zero Data Loss Recovery Appliance administrator.
- For an NFS backup destination:
 - Exadata Database Service on Cloud@Customer non-autonomous databases:
 - * You must mount the NFS server location to a local mount point directory on each node in the VM cluster.
 - * The local mount point directory and the NFS server must be identical across all nodes in the cluster.
 - * You must ensure that the NFS mount is maintained continuously on all of the VM cluster nodes.
 - * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
 - Exadata Database Service on Cloud@Customer Autonomous Databases:



- * To ensure that the Autonomous VM cluster can access the NFS server over the Backup Network, enter valid Backup Network IP addresses while configuring VM Cluster Network.
- * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
- * If permissions are being controlled at the user level, then the uid:gid of the oracle user for the Autonomous VM cluster is 1001:1001.

Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer

Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.

- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Edit a Backup Destination
 To edit a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Move a Backup Destination to Another Compartment
 To move a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Delete a Backup Destination
 To delete a backup destination, be prepared to provide values for the backup destination configuration.

Using the Console to Create a Backup Destination

To create a backup destination, be prepared to provide values for the backup destination configuration.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- 3. Click Backup Destinations.
- 4. Click Create Backup Destination.
- 5. Provide the requested information in the **Create Backup Destination** page:
 - a. Choose a compartment.
 - From the list of available compartments, choose the compartment that you want to contain the backup destination.
 - **b.** Name your backup destination.
 - Specify a user-friendly name that you can use to identify the backup destination. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the backup destination.
 - Choose either a Zero Data Loss Recovery Appliance or a network file system (NFS) backup destination.



Note:

You can also set OCI Object Store as a backup destination. However, you cannot set it from this screen. You can configure OCI Object Store as a backup destination when creating a database. For more information, see *Backup Destination Type* in *Using the Console to Create a Database*.

Select Recovery Appliance or Network Storage (NFS).

- If you select Recovery Appliance, then you must also specify the following for Zero Data Loss Recovery Appliance:
 - Provide the Recovery Appliance connection string: Specify the
 Oracle Net Services connection string that connects to the appliance.
 This information is typically provided by the Zero Data Loss Recovery
 Appliance administrator.
 - Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Zero Data Loss Recovery Appliance. You can specify multiple VPC user names in case you want to use the appliance as a backup destination for multiple databases. This information is typically provided by the Zero Data Loss Recovery Appliance administrator.
- If you select Network Storage (NFS), then you must also specify the following:
 - Self-mount for non-autonomous databases:

Provide the local NFS mount point path: Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local directory path and the NFS server location must each be the same across all of the VM cluster nodes.

Auto-mount for Autonomous Databases:

Use this destination for Autonomous Databases:

- * **NFS server:** Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * **NFS export share:** Specify the directory path where the exported file system is mounted.
- d. Configure Advanced Options.
 - Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later), or ask your administrator.
- 6. Click Create Backup Destination.

The Backup Destination Details page displays the newly created backup destination.



Related Topics

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Resource Tags

Using the Console to Edit a Backup Destination

To edit a backup destination, be prepared to provide values for the backup destination configuration.

You can only edit a backup destination if it is not currently associated with database.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to edit.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to edit.

The Backup Destination Details page displays information about the selected backup destination.

- 5. Click Edit.
- 6. Use the **Edit Backup Destination** dialog to edit the backup destination attributes:



You cannot edit a Backup Destination if there is already a database attached to it

- If you are editing a Zero Data Loss Recovery Appliance backup destination:
 - Provide the Recovery Appliance connection string: Specify the Oracle Net Services connection string that connects to the Recovery Appliance. This information is typically provided by the Recovery Appliance administrator.
 - Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Recovery Appliance. You can specify multiple VPC user names in case you want to use the Recovery Appliance as a backup destination for multiple databases. This information is typically provided by the Recovery Appliance administrator.
- If you are editing an NFS backup destination:
 - Self-mount for non-autonomous databases:

Provide the local NFS mount point path: Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local directory path and the NFS server location must each be the same across all of the VM cluster nodes.

Auto-mount for Autonomous Databases:

Use this destination for Autonomous Databases:



- * NFS server: Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * NFS export share: Specify the directory path where the exported file system is mounted.
- 7. Click Save Changes.

Using the Console to Move a Backup Destination to Another Compartment

To move a backup destination, be prepared to provide values for the backup destination configuration.

You can change the compartment that contains your backup destination by moving it.

When you move a backup destination, the compartment change does not affect other associated resources. These other resources, such as the associated databases, remain in their current compartment.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to move.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to move.
 - The Backup Destination Details page displays information about the selected backup destination.
- 5. Click Move Resource.
- 6. In the resulting dialog, choose the new compartment for the backup destination and click **Move Resource**.

Using the Console to Delete a Backup Destination

To delete a backup destination, be prepared to provide values for the backup destination configuration.

Before you can delete a backup destination, you must ensure that it is not associated with any databases.

Deleting a backup destination:

- Does not remove any residual backups that are left in the backup destination
- Removes all references to the deleted backup destination from the Cloud Control Plane
- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the backup destination that you want to delete.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to delete.

The Backup Destination Details page displays information about the selected backup destination.



- 5. Click Delete.
- In the resulting dialog, enter the backup destination name and click **Delete Backup Destination** to confirm the action.

Creating First Database Home on an Exadata Database Service on Cloud@Customer System

After provisioning a VM Cluster, create your first Oracle Database Home on Exadata Cloud@Customer.

- About Creating Oracle Database Homes on an Exadata Database Service on Cloud@Customer System
 - You can add Oracle Database homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) to an existing VM cluster by using the Oracle Cloud Infrastructure Console, the API, or the CLI.
- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer
 - To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.
- Using the API to Create Oracle Database Home on Exadata Cloud@Customer
 To create an Oracle Database home, review the list of API calls.

About Creating Oracle Database Homes on an Exadata Database Service on Cloud@Customer System

You can add Oracle Database homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) to an existing VM cluster by using the Oracle Cloud Infrastructure Console, the API, or the CLI.

A Database Home is a directory location on the Exadata database virtual machines that contains Oracle Database software binary files.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

You can also add and remove Database homes, and perform other management tasks on a Database home by using the dbaascli utility.

Related Topics

 Using the dbaascli Utility with Exadata Database Service on Cloud@Customer Learn to use the dbaascli utility on Exadata Cloud@Customer.



Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer

To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.

 Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster on which you want to create the Database Home.
- 4. Under Resources, click Database Homes.
- Click Create Database Home.
- 6. In the Create Database Home dialog, enter the following:
 - **Database Home display name**: The display name for the Database Home.
 - Database image: Determines what Oracle Database version is used for the database. You can mix database versions on the Exadata VM Cluster, but not editions. By default, the latest Oracle-published database software image is selected.

Click **Change Database Image** to use an older Oracle-published image or a custom Database Software Image that you have created in advance, then select an **Image Type**.

Oracle Provided Database Software Images: These images contain generally available versions of Oracle Database software.

Custom Database Software Images: These images are created by your organization and contain customized configurations of software updates and patches. Use the Select a compartment and Select a Database version selectors to limit the list of custom Database Software Images to a specific compartment or Oracle Database software major release version.

After choosing a software image, click **Select** to return to the Create Database Home dialog.

Note:

For the Oracle Database major version releases available in Oracle Cloud Infrastructure, images are provided for the current version plus the three most recent older versions (N through N - 3). For example, if an instance is using Oracle Database 19c, and the latest version of 19c offered is 19.8.0.0.0, images available for provisioning are for versions 19.8.0.0.0, 19.7.0.0, 19.6.0.0 and 19.5.0.0.

A Database Software Image will not be available for Database Home creation if:



- The database version of Database Software Image is out of support. For example, Database Software Images created using 11.2.0.4 will not be available for Database Home provisioning after 31-Dec-2022.
- The Exadata model should support the PSU/RU version of the Database Software Image. For example, for the 19c release, the X8M-2 model supports RU version 19.4 and greater.
- Only Database Software Images created specifically in the context of Exadata Cloud@Customer service can be used while provisioning and patching Database Homes within the Exadata Cloud@Customer service.
- The Database Software Image is not in Available state, that is, Deleted or is being Updated.

Show Advanced Options

You have the option to configure advanced options.

Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, see "Resource Tags". If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

Note that after Home install, patch to the latest if the latest patch is available.

Click Create.

When the Database Home creation is complete, the status changes from Provisioning to Available.

Related Topics

Resource Tags

Using the API to Create Oracle Database Home on Exadata Cloud@Customer

To create an Oracle Database home, review the list of API calls.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

To create Database Homes in Exadata Database Service on Cloud@Customer, use the API operation CreateDbHome.

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- CreateDbHome
- Database Service API



Creating First Database on an Exadata Database Service on Cloud@Customer System

After provisioning an Oracle Database Home and any needed backup destinations, you are ready to create your first database on Exadata Cloud@Customer.

- Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer
 Review the prerequisites for creating and managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer.
- Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer
 Learn about the versions of Oracle Database that Oracle Exadata Database Service on Cloud@Customer supports.
- About Provisioning and Configuring Oracle Databases on Oracle Exadata
 Database Service on Cloud@Customer
 Learn about provisioning and configuring Oracle Database on Oracle Exadata
 Database Service on Cloud@Customer
- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.

Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer

Review the prerequisites for creating and managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer.

Before you can create and use an Oracle Database on Exadata Database Service on Cloud@Customer, you must:

- Provision Exadata Database Service on Cloud@Customer infrastructure
- Configure a VM cluster
- Create any required backup destinations

You can create one or more databases on each Oracle Exadata Database Service on Cloud@Customer system. Other than the storage and processing limits of your Oracle Exadata system, there is no maximum for the number of databases that you can create. By default, databases on Exadata Database Service on Cloud@Customer use Oracle Database Enterprise Edition - Extreme Performance. This edition provides all the features of Oracle Database Enterprise Edition, plus all of the database enterprise management packs, and all of the Enterprise Edition options, such as Oracle Database In-Memory, and Oracle Real Application Clusters (Oracle RAC). If you use your own Oracle Database licenses, then your ability to use various features is limited by your license holdings. TDE Encryption is required for all cloud databases. All new tablespaces will automatically be enabled for encryption.



Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer

Learn about the versions of Oracle Database that Oracle Exadata Database Service on Cloud@Customer supports.

Exadata Database Service on Cloud@Customer supports the following Oracle Database software releases:

- Oracle Database 19c (19.0)
- Oracle Database 18c (18.0) is supported for approved customers only.
- Oracle Database 12c Release 2 (12.2) is supported for approved customers only.
- Oracle Database 12c Release 1 (12.1). Creating or updating a 12.1.0.2 database with an RU later than July 2022 requires a valid Market Driven Support (MDS) contract.
- Oracle Database 11g Release 2 (11.2). Creating or updating an 11.2.0.4 database with PSU later than April 2021 requires a valid Market Driven Support (MDS) contract.

For Oracle Database release and software support timelines, see *Release Schedule of Current Database Releases (Doc ID 742060.1)* in the My Oracle Support portal.

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=742060.1

About Provisioning and Configuring Oracle Databases on Oracle Exadata Database Service on Cloud@Customer

Learn about provisioning and configuring Oracle Database on Oracle Exadata Database Service on Cloud@Customer

Each Oracle Database is configured as follows:

- When you provision a database, you can associate it with a backup destination, and enable automatic backups.
- When a database is provisioned an archivelog maintenance job is added to the crontab
 for the database.
 - If the database is not enabled for backups, then the archivelog job will maintain FRA space by deleting Archive Redo Logs older than 24 hours.
 - If the database is enabled for backups, then the archivelog job will backup archivelogs that have not been backed up. Once an archived log is backed up, it will be purged when older than 24 hours.
- Each database is configured with Oracle Real Application Clusters (Oracle RAC) database instances running on every node in the virtual machine (VM) cluster.
- Each database is created in an Oracle home, which uses a separate set of Oracle binaries in a separate Oracle home location.
- Each database is configured with default instance parameter settings. While the defaults
 are reasonable for many cases, you should review the instance parameter settings to
 ensure that they meet your specific application needs.



In particular, review the Oracle Database system global area (SGA) and program global area (PGA) instance parameter settings, especially if your VM cluster supports multiple databases. Also, ensure that the sum of all Oracle Database memory allocations never exceeds the available physical memory on each virtual machine.

- Each database using Oracle Database 12c Release 1 or a later release is configured as a container database (CDB). One pluggable database (PDB) is created inside the CDB. By default:
 - The first PDB is configured with a local PDB administration user account, named PDBADMIN.
 - The PDBADMIN user account is initially configured with the same administration password as the CDB SYS and SYSTEM users.
 - The PDBADMIN user account is initially configured with basic privileges
 assigned through two roles; CONNECT and PDB_DBA. However, for most practical
 administrative purposes you must assign extra privileges to the PDBADMIN user
 account, or to the PDB_DBA role.

You can use native Oracle Database facilities to create extra PDBs, and to manage all of your PDBs. The <code>dbaascli</code> utility also provides a range of convenient PDB management functions.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Using the Console to Create a Database

To create an Oracle Database with the console, use this procedure.

- Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.
 - VM Clusters is selected by default.
- Choose your Compartment.A list of VM Clusters is displayed for the chosen Compartment.
- Click the name of a VM cluster where you want to create the database.
 In the VM Cluster Details page, under Resources, Databases is selected by default.
- 4. Click Create Database. (or)
 - a. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
 VM Clusters is selected by default.
 - b. Choose your Compartment.A list of VM Clusters is displayed for the chosen Compartment.
 - c. Click the name of a VM cluster where you want to create the database.



In the VM Cluster Details page, under Resources, Databases is selected by default.

- d. Click Database Homes.
- e. Click the name of the Database Home where you want to create the database.
- f. Click Create Database.
- 5. Provide the requested information in the Create Database page:



You cannot modify the db_name, db_unique_name, and SID prefix after creating the database.

 Provide the database name: Specify a user-friendly name that you can use to identify the database. The database name must contain only the permitted characters.

Review the following guidelines when selecting a database name.

- maximum of 8 characters
- contain only alphanumeric characters
- begin with an alphabetic character
- cannot be part of first 8 characters of a db unique name on the VM cluster
- unique across all VM clusters on the same Exadata Infrastructure
- DO NOT use grid because grid is a reserved name
- DO NOT use ASM because ASM is a reserved name
- **Provide a unique name for the database**: Optionally, specify a unique name for the database. This attribute defines the value of the db_unique_name database parameter. The value is case insensitive.

The db_unique_name must contain only the permitted characters. Review the following guidelines when selecting a database name.

- maximum of 30 characters
- can contain alphanumeric and underscore () characters
- begin with an alphabetic character
- unique across the fleet/tenancy

If a unique name is not provided, then the db_unique_name defaults to the following format <db name> <3 char unique string> <region-name>.

If you plan to configure the database for backup to a Recovery Appliance backup destination, then the unique database name must match the name that is configured in the Recovery Appliance.

- Select a database version: From the list, choose the Oracle Database software release that you want to deploy.
- Database Home: Select an existing Database Home or create one as applicable.
 Note that this field is not available when you create a Database from the Database Home details page.



- Select an existing Database Home: If one or more Database Homes already exist for the database version you have selected, then this option is selected by default. And, you will be presented with a list of Database Homes. Select a Database Home from the list.
- Create a new Database Home: If no Database Homes exist for the database version you have selected, then this option is selected by default.
 - a. Enter Database Home display name.
 - b. Click Change Database Image to select your software version. Select a Database Software Image window is displayed.
 - c. Select an Image Type, Oracle Provided Database Software Images, or Custom Database Software Images.
 If you choose Oracle Provided Database Software Images, then you can use the Display all available version switch to choose from all available PSUs and RUs. The most recent release for each major version is indicated with a latest label.



For the Oracle Database major version releases available in Oracle Cloud Infrastructure, images are provided for the current version plus the three most recent older versions (N through N - 3). For example, if an instance is using Oracle Database 19c, and the latest version of 19c offered is 19.8.0.0.0, images available for provisioning are for versions 19.8.0.0.0, 19.7.0.0, 19.6.0.0 and 19.5.0.0.

 Provide the name of the first PDB: (Optional) Specify the name for the first PDB. A PDB is created with the database.

To avoid potential service name collisions when using Oracle Net Services to connect to the PDB, ensure that the PDB name is unique across the entire VM cluster. If you do not provide the name of the first PDB, then a system-generated name is used.

- **Provide the administration password**: Provide and confirm the Oracle Database administration password. This password is used for administration accounts and functions in the database, including:
 - The password for the Oracle Database SYS and SYSTEM users.
 - The Transparent Data Encryption (TDE) Keystore password.

For Oracle Database 12c Release 1 or later releases, the password for the PDB administration user in the first PDB (PDBADMIN) must be nine to 30 characters and contain at least two uppercase, two lowercase, two numeric, and two special characters. The special characters must be _, #, or -. In addition, the password must not contain the name of the tenancy or any reserved words, such as Oracle or Table, regardless of casing.

Use the administrator password for the TDE wallet: When this option
is checked, the password entered for the SYS user is also used for the
TDE wallet. To set the TDE wallet password manually, uncheck this option
and enter the TDE wallet password.



- Choose the database workload type: Select the workload type that best suits your application from one of the following options:
 - Transactional Processing: Select this option to configure the database for a transactional workload, with a bias toward high volumes of random data access.
 - Data Warehouse: Select this option to configure the database for decision support or data warehouse workload, with a bias toward large data scanning operations.
- **Backup Destination Type:** Select a backup destination for the database. From the list, choose an option:
 - None: Select to not define a backup configuration for the database.
 - Local: Select to store backups locally in the Oracle Exadata Storage Servers on your Oracle Exadata Cloud at Customer system.
 This option is available only if you enabled backups on local Oracle Exadata storage in the VM cluster that you want to host the database.
 - Object Storage: Select to store backups in an Oracle-managed object storage container on Oracle Cloud Infrastructure.
 To use this option, your Oracle Exadata Cloud@Customer system must have egress connectivity to Oracle Cloud Infrastructure Object Storage.
 - NFS: Select to store backups in one of your previously defined backup destinations that use Network File System (NFS) storage. For more information, refer to the information about backup destinations in this publication.

If you select this option, then you must also choose from the list of NFS **Backup Destinations**.

 Recovery Appliance: Select to store backups in one of your previously defined backup destinations that use Oracle Zero Data Loss Recovery Appliance. Refer to the information about backup destination options in this document.

If you select Oracle Zero Data Loss Recovery Appliance as your backup option, then you must also:

- * Choose from the list of appliance **Backup Destinations**.
- * Choose from the **VPC User** list, which contains the list of virtual private catalog (VPC) user names that are defined in the Oracle Zero Data Loss Recovery Appliance backup destination.
- * Provide the **Password** for the VPC user.

Note:

If you select a backup destination, then you cannot change a backup location after the database is created. However, if you select **None** now, then you can select a backup destination after the database is created.

 Enable automatic backups: Select this option to enable daily backups using the policy for automatic backups.

This option is only enabled when you select a **Backup Destination Type** other than **None**. You can change this setting after database creation.



- (Optional) Select Show Advanced Options. From this window, you can select the following options:
 - Provide the Oracle SID prefix:



Entering a SID prefix is only available for 12.1 databases and above.

Optionally, specify the Oracle SID prefix for the database. The instance number is automatically appended to the SID prefix to become the <code>instance_name</code> database parameter. If not provided, then the SID prefix defaults to the <code>db_name</code>.

Review the following guidelines when selecting a database name:

- * maximum of 12 characters
- contain only alphanumeric characters
- begin with an alphabetic character
- unique in the VM cluster
- Backup retention period: From the list, you can choose the length of time that you want automatic backups to be retained.

For backups to local Exadata storage, you can choose a retention period of 7 days or 14 days. The default retention period is 7 days.

For backups to Oracle Cloud Infrastructure Object Storage, or to an NFS backup destination, you can choose one of the following preset retention periods: 7 days, 14 days, 30 days, 45 days, or 60 days. The default retention period is 30 days.

This option does not apply to Oracle Zero Data Loss Recovery Appliance backup destinations. For backups to Oracle Zero Data Loss Recovery Appliance, the retention policy that is implemented in the appliance controls the retention period.

- Character set: The character set for the database. The default is AL32UTF8.
- National character set: The national character set for the database. The default is AL16UTF16.
- Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later), or ask your administrator.
- 6. Click Create Database.

Related Topics

Resource Tags



 Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer

Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

Connecting to an Exadata Database Service on Cloud@Customer System

After deploying your Exadata Cloud@Customer system with a VM cluster, Oracle Database Home, and Oracle Database, learn how to connect to your VM Cluster virtual machine using SSH and to connect to an Exadata Cloud@Customer database using Oracle Net Services (SQL*Net).

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- Connecting to a Database with Oracle Net Services
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system using Oracle Net Services.

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

Most Unix-style systems (including Linux, Oracle Solaris, and macOS) include an SSH client. For Microsoft Windows systems, you can download a free SSH client called PuTTY from the following site: "http://www.putty.org".

- Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System
 - To access a virtual machine in an Exadata Database Service on Cloud@Customer system using SSH, be prepared to provide the host name or IP address of the virtual machine.
- Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY Learn to access a virtual machine from a Microsoft Windows system using PuTTY.
- Accessing a Database After You Connect to the Virtual Machine
 After you connect to a virtual machine, you can use the following series of commands to identify a database and connect to it.
- Connecting from a Unix-Style System
 To access a virtual machine on an Oracle Cloud@Customer system from a Unix-style system using SSH, use this procedure.

Related Topics

http://www.putty.org/

Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System

To access a virtual machine in an Exadata Database Service on Cloud@Customer system using SSH, be prepared to provide the host name or IP address of the virtual machine.



 An SSH private key file that corresponds to a public key that is registered in the system.

When you create a VM cluster on your Exadata Database Service on Cloud@Customer system, you must specify the public key portion of one or more SSH key pairs. You can also register extra keys separately after you create the VM cluster.

Note:

The public keys are stored in the authorized_keys file at ~/.ssh/authorized_keys. Separate authorized_keys files are located under the home directories of the operating system users. By default, only the opc user account has an authorized_keys entry and is able to log in remotely. Do not remove or alter the automatically generated entry in authorized keys for the opc user.

• The host name or IP address for the virtual machine that you want to access. See, Using the Console to Check the Status of a VM Cluster Virtual Machine.

Related Topics

 Using the Console to Check the Status of a VM Cluster Virtual Machine Review the health status of a VM cluster virtual machine.

Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY

Learn to access a virtual machine from a Microsoft Windows system using PuTTY.

Before you begin

Before you use the PuTTY program to connect to a virtual machine, you need the following:

- The IP address of the virtual machine
- The SSH private key file that matches the public key associated with the deployment. This private key file must be in the PuTTY .ppk format. If the private key file was originally created on the Linux platform, you can use the PuTTYgen program to convert it to the .ppk format.

To connect to a virtual machine using the PuTTY program on Windows:

- Download and install PuTTY.
 - To download PuTTY, go to http://www.putty.org/ and click the **You can download PuTTY here** link.
- 2. Run the PuTTY program (putty.exe).
 - The PuTTY Configuration window is displayed, showing the **Session** panel.
- 3. In the **Host Name (or IP address)** field, enter the host name or IP address of the virtual machine that you want to access.
- 4. Confirm that the **Connection type** option is set to **SSH**.
- 5. In the **Category** tree, expand **Connection** if necessary and then click **Data**.



The **Data** panel is displayed.

- 6. In the Auto-login username field, enter the operating system user you want to connect as:
 - Connect as the user opc to perform operations that require root or oracle access to the virtual machine, such as backing up or patching; this user can use the sudo command to gain root or oracle access to the VM.
- 7. Confirm that the When username is not specified option is set to Prompt.
- 8. In the Category tree, expand SSH and then click Auth.

The **Auth** panel is displayed.

- 9. Click the Browse button next to the Private key file for authentication field. Then, in the Select private key file window, navigate to and open the private key file that matches the public key that is associated with the deployment.
- 10. In the Category tree, click Session.

The **Session** panel is displayed.

- In the Saved Sessions field, enter a name for the connection configuration. Then, click Save.
- 12. Click Open to open the connection.

The PuTTY Configuration window closes and the PuTTY terminal window displays.

If this is the first time you are connecting to the VM, the PuTTY Security Alert window is displayed, prompting you to confirm the public key. Click **Yes** to continue connecting.

Accessing a Database After You Connect to the Virtual Machine

After you connect to a virtual machine, you can use the following series of commands to identify a database and connect to it.

- 1. SSH in as the opc user.
- 2. sudo su oracle
- 3. Use the srvctl utility located under the Oracle Grid Infrastructure home directory to list the databases on the system. For example:

```
/u01/app/12.2.0.1/grid/bin/srvctl config database -v nc122 /u02/app/oracle/product/12.2.0/dbhome_6 12.2.0.1.0 s12c /u02/app/oracle/product/12.2.0/dbhome 2 12.2.0.1.0
```

4. Identify the database instances for the database that you want to access. For example:

```
/u01/app/12.2.0.1/grid/bin/srvctl status database -d s12c Instance s12c1 is running on node node01 Instance s12c2 is running on node node02
```



5. Configure the environment settings for the database that you want to access. For example:

```
. oraenv
ORACLE_SID = [oracle] ? s12c
The Oracle base has been set to /u02/app/oracle
export ORACLE SID=s12c1
```

6. You can use the svrctl command to display more detailed information about the database. For example:

```
srvctl config database -d s12c
Database unique name: s12c
Database name:
Oracle home: /u02/app/oracle/product/12.2.0/dbhome 2
Oracle user: oracle
Spfile: +DATAC4/s12c/spfiles12c.ora
Password file: +DATAC4/s12c/PASSWORD/passwd
Domain: example.com
Start options: open
Stop options: immediate
Database role: PRIMARY
Management policy: AUTOMATIC
Server pools:
Disk Groups: DATAC4
Mount point paths:
Services:
Type: RAC
Start concurrency:
Stop concurrency:
OSDBA group: dba
OSOPER group: racoper
Database instances: s12c1,s12c2
Configured nodes: node01, node02
CSS critical: no
CPU count: 0
Memory target: 0
Maximum memory: 0
Default network number for database services:
Database is administrator managed
```

7. You can access the database by using SQL*Plus. For example:

```
sqlplus / as sysdba

SQL*Plus: Release 12.2.0.1.0 Production ...

Copyright (c) 1982, 2016, Oracle. All rights reserved.

Connected to:
Oracle Database 12c EE Extreme Perf Release 12.2.0.1.0 - 64bit Production
```



Connecting from a Unix-Style System

To access a virtual machine on an Oracle Cloud@Customer system from a Unix-style system using SSH, use this procedure.

Enter the following SSH command to access the virtual machine:

```
ssh -i private-key user@node
```

In the preceding syntax:

- private-key is the full path and name of the file that contains the SSH private key that corresponds to a public key that is registered in the system.
- user is the operating system user that you want to use to connect:
 - * To perform operations as the Oracle Database software owner, connect as as opc and su oracle. The oracle user does not have root user access to the virtual machine.
 - * To perform operations that require root access to the virtual machine, such as patching, connect as opc. The opc user can use the sudo -s command to gain root access to the virtual machine.
- node is the host name or IP address for the virtual machine that you want to access.

Connecting to a Database with Oracle Net Services

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system using Oracle Net Services.

- Using Oracle Net Services to Connect to a Database
 Oracle Database Exadata Database Service on Cloud@Customer supports remote database access by using Oracle Net Services.
- Prerequisites for Connecting to a Database with Oracle Net Services
 Review the prerequisites to connect to an Oracle Database instance on Oracle Cloud@Customer using Oracle Net Services.
- Connecting to a Database Using SCAN
 To create an Oracle Net Services connection by using the SCAN listeners, you can choose between two approaches.
- Connecting to a Database Using a Node Listener
 To connect to an Oracle Database instance on Exadata Database Service on Cloud@Customer with a connect descriptor that bypasses the SCAN listeners, use this procedure to route your connection directly to a node listener.

Using Oracle Net Services to Connect to a Database

Oracle Database Exadata Database Service on Cloud@Customer supports remote database access by using Oracle Net Services.

Because Exadata Database Service on Cloud@Customer uses Oracle Grid Infrastructure, you can make Oracle Net Services connections by using **Single Client Access Name** (SCAN) connections. SCAN is a feature that provides a consistent mechanism for clients to access the Oracle Database instances running in a cluster.



By default, the SCAN is associated with three virtual IP addresses (VIPs). Each SCAN VIP is also associated with a SCAN listener that provides a connection endpoint for Oracle Database connections using Oracle Net Services. To maximize availability, Oracle Grid Infrastructure distributes the SCAN VIPs and SCAN listeners across the available cluster nodes. In addition, if there is a node shutdown or failure, then the SCAN VIPs and SCAN listeners are automatically migrated to a surviving node. By using SCAN connections, you enhance the ability of Oracle Database clients to have a reliable set of connection endpoints that can service all of the databases running in the cluster.

The SCAN listeners are in addition to the Oracle Net Listeners that run on every node in the cluster, which are also known as the node listeners. When an Oracle Net Services connection comes through a SCAN connection, the SCAN listener routes the connection to one of the node listeners, and plays no further part in the connection. A combination of factors, including listener availability, database instance placement, and workload distribution, determines which node listener receives each connection.



This documentation provides basic requirements for connecting to your Exadata Database Service on Cloud@Customer databases by using Oracle Net Services.

Prerequisites for Connecting to a Database with Oracle Net Services

Review the prerequisites to connect to an Oracle Database instance on Oracle Cloud@Customer using Oracle Net Services.

To connect to an Oracle Database on Exadata Database Service on Cloud@Customer with Oracle Net Services, you need the following:

- The IP addresses for your SCAN VIPs, or the hostname or IP address for a virtual machine that hosts the database that you want to access.
- The database identifier: Either the database system identifier (SID), or a service name.

Connecting to a Database Using SCAN

To create an Oracle Net Services connection by using the SCAN listeners, you can choose between two approaches.

- Connecting to a Database Using a Connect Descriptor that References All of the SCAN VIPs
 - You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using multiple SCAN listeners.
- Connecting to a Database Use a Connect Descriptor that References a Custom SCAN Name

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using a custom SCAN name.



Connecting to a Database Using a Connect Descriptor that References All of the SCAN VIPs

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using multiple SCAN listeners.

This approach requires you to supply all of the single client access name (SCAN) virtual IP (VIP) addresses, and enables Oracle Net Services to connect to an available SCAN listener.

• Use the following template to define a Net Services alias, which is typically used to provide a convenient name for the connect descriptor:

```
alias-name = (DESCRIPTION=
  (ADDRESS_LIST=
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-1) (PORT=1521))
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-2) (PORT=1521))
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-3) (PORT=1521)))
          (CONNECT_DATA=(sid-or-service-entry)))
```

Where:

alias-name is the name you use to identify the alias.

SCAN-VIP-[1-3] are the IP addresses for the SCAN VIPs.

sid-or-service-entry identifies the database SID or service name using one of the following formats:

- SID=sid-name. For example: SID=S12C1.
- SERVICE_NAME=service-name. For example: SERVICE NAME=PDB1.example.yourcloud.com.



By default, Oracle Net Services randomly selects one of the addresses in the address list to balance the load between the SCAN listeners.

Connecting to a Database Use a Connect Descriptor that References a Custom SCAN Name

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using a custom SCAN name.

Using this approach, you define a custom single client access name (SCAN) name in your domain name server (DNS), which resolves to the three SCAN virtual IP addresses (VIPs).

Use the following template to define a Net Services alias that references the custom SCAN name:

```
alias-name = (DESCRIPTION=
  (ADDRESS_LIST=(ADDRESS=(PROTOCOL=tcp) (HOST=scan-name) (PORT=1521)))
  (CONNECT_DATA=(sid-or-service-entry)))
```

Where:



alias-name is the name you use to identify the alias.

scan-name is the custom SCAN name.

sid-or-service-entry identifies the database SID or service name using one of the following formats:

• SID=sid-name. For example: SID=S12C1.

scan-name:1521/sid-or-service-entry

exalscan.example.com:1521/S12C1

 SERVICE_NAME=service-name. For example: SERVICE NAME=PDB1.example.yourcloud.com.

Alternatively, you can use the easy connect method to specify a connect descriptor with the following format:

```
For example:
```

Or

exalscan.example.com:1521/PDB1.example.yourcloud.com

Connecting to a Database Using a Node Listener

To connect to an Oracle Database instance on Exadata Database Service on Cloud@Customer with a connect descriptor that bypasses the SCAN listeners, use this procedure to route your connection directly to a node listener.

By using this method, you give up the high-availability and load-balancing provided by SCAN. However, this method may be desirable if you want to direct connections to a specific node or network interface. For example, you might want to ensure that connections from a program that performs bulk data loading use the backup network.

Using this approach, you direct your connection using the hostname or IP address of the node.

Example 4-1 Defining a Net Service Alias That Directly References the Node

```
alias-name = (DESCRIPTION=
  (CONNECT_TIMEOUT=timeout)
  (ADDRESS_LIST=(ADDRESS=(PROTOCOL=tcp) (HOST=node) (PORT=1521)))
  (CONNECT_DATA=(sid-or-service-entry)))
```

Where:

alias-name is the name you use to identify the alias.

timeout specifies a timeout period (in seconds), which enables you to terminate a connection attempt without having to wait for a TCP timeout. The (CONNECT TIMEOUT=timeout) parameter is optional.

node is the hostname or IP address for the virtual machine that you want to use.



sid-or-service-entry identifies the database SID or service name using one of the following formats:

- SID=sid-name. For example, SID=S12C1.
- SERVICE_NAME=service-name. For example, SERVICE NAME=PDB1.example.oraclecloudatcust.com.

Alternatively, you can use the easy connect method to specify a connect descriptor with the following format:

```
node:1521/sid-or-service-entry
```

For example:

```
exalnode01.example.com:1521/S12C1
```

Or

exalnode01.example.com:1521/PDB1.example.oraclecloudatcust.com



How-to Guides

A collection of tasks and procedures for managing Exadata Cloud

- Connect to the Exadata Database Service on Cloud@Customer Service
 Learn how to connect to an Exadata Cloud@Customer system using SSH, and how to
 connect to an Exadata Cloud@Customer database using Oracle Net Services (SQL*Net).
- Manage Exadata Database Service on Cloud@Customer Infrastructure
 Use the provided tools to manage the Infrastructure.
- Configure Oracle-Managed Infrastructure Maintenance
 Oracle performs the updates to all of the Oracle-managed infrastructure components on
 Exadata Cloud@Customer.
- Manage VM Cluster Networks
 Learn how to use the console to create, edit, download a configuration file, validate, and terminate your infrastructure network.
- Manage VM Clusters
 Learn how to manage your VM clusters on Exadata Database Service on Cloud@Customer.
- Manage Oracle Database Software Images
 Learn about Database Software Image resource type and how you can use it to create
 Oracle Databases and Oracle Database Homes and to patch databases.
- Create Oracle Database Homes on an Exadata Database Service on Cloud@Customer System
 Learn to create Oracle Database Homes on Exadata Database Service on Cloud@Customer.
- Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems
 - Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.
- Manage Databases on Exadata Database Service on Cloud@Customer
- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer
 - Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.
- Patch and Update an Exadata Database Service on Cloud@Customer System
 Learn to update and patch the Exadata Database Service on Cloud@Customer System
- Use Oracle Data Guard with Exadata Database Service on Cloud@Customer Learn to configure and manage Data Guard associations in your VM cluster.



Overview of Exadata Cloud@Customer Gen1 to Out-of-Place Cloud Upgrade to
Exadata Database Service on Cloud@Customer Gen2 Infrastructure
Gen1 is the first generation of Exadata Database Service on Cloud@Customer,
which is deployed in conjunction with Gen1 Oracle Cloud At Customer (OCC) as
Control Plane deployed in the customer data center. Exadata Database Service on
Cloud@Customer Gen2 is managed from Oracle Cloud Infrastructure (OCI)
Control Plane, which runs in OCI public cloud.

Connect to the Exadata Database Service on Cloud@Customer Service

Learn how to connect to an Exadata Cloud@Customer system using SSH, and how to connect to an Exadata Cloud@Customer database using Oracle Net Services (SQL*Net).

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- Connecting to a Database with Oracle Net Services
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system using Oracle Net Services.

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

Most Unix-style systems (including Linux, Oracle Solaris, and macOS) include an SSH client. For Microsoft Windows systems, you can download a free SSH client called PuTTY from the following site: "http://www.putty.org".

- Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System
 - To access a virtual machine in an Exadata Database Service on Cloud@Customer system using SSH, be prepared to provide the host name or IP address of the virtual machine.
- Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY
 Learn to access a virtual machine from a Microsoft Windows system using PuTTY.
- Connecting from a Unix-Style System
 To access a virtual machine on an Oracle Cloud@Customer system from a Unix-style system using SSH, use this procedure.
- Accessing a Database After You Connect to the Virtual Machine
 After you connect to a virtual machine, you can use the following series of
 commands to identify a database and connect to it.

Related Topics

http://www.putty.org/



Prerequisites for Connecting to an Exadata Database Service on Cloud@Customer System

To access a virtual machine in an Exadata Database Service on Cloud@Customer system using SSH, be prepared to provide the host name or IP address of the virtual machine.

An SSH private key file that corresponds to a public key that is registered in the system.
When you create a VM cluster on your Exadata Database Service on Cloud@Customer
system, you must specify the public key portion of one or more SSH key pairs. You can
also register extra keys separately after you create the VM cluster.

Note:

The public keys are stored in the authorized_keys file at ~/.ssh/authorized_keys. Separate authorized_keys files are located under the home directories of the operating system users. By default, only the operation user account has an authorized_keys entry and is able to log in remotely. Do not remove or alter the automatically generated entry in authorized keys for the operation.

• The host name or IP address for the virtual machine that you want to access. See, *Using the Console to Check the Status of a VM Cluster Virtual Machine*.

Related Topics

 Using the Console to Check the Status of a VM Cluster Virtual Machine Review the health status of a VM cluster virtual machine.

Connecting to a Virtual Machine from a Microsoft Windows System Using PuTTY

Learn to access a virtual machine from a Microsoft Windows system using PuTTY.

Before you begin

Before you use the PuTTY program to connect to a virtual machine, you need the following:

- The IP address of the virtual machine
- The SSH private key file that matches the public key associated with the deployment.
 This private key file must be in the PuTTY .ppk format. If the private key file was originally created on the Linux platform, you can use the PuTTYgen program to convert it to the .ppk format.

To connect to a virtual machine using the PuTTY program on Windows:

- Download and install PuTTY.
 - To download PuTTY, go to http://www.putty.org/ and click the **You can download PuTTY** here link.
- 2. Run the PuTTY program (putty.exe).
 - The PuTTY Configuration window is displayed, showing the **Session** panel.
- 3. In the **Host Name (or IP address)** field, enter the host name or IP address of the virtual machine that you want to access.
- Confirm that the Connection type option is set to SSH.



- In the Category tree, expand Connection if necessary and then click Data.
 The Data panel is displayed.
- 6. In the Auto-login username field, enter the operating system user you want to connect as:
 - Connect as the user opc to perform operations that require root or oracle access to the virtual machine, such as backing up or patching; this user can use the sudo command to gain root or oracle access to the VM.
- 7. Confirm that the **When username is not specified** option is set to **Prompt**.
- 8. In the Category tree, expand SSH and then click Auth.

The **Auth** panel is displayed.

- 9. Click the Browse button next to the Private key file for authentication field. Then, in the Select private key file window, navigate to and open the private key file that matches the public key that is associated with the deployment.
- 10. In the Category tree, click Session.

The **Session** panel is displayed.

- **11.** In the **Saved Sessions** field, enter a name for the connection configuration. Then, click **Save**.
- 12. Click Open to open the connection.

The PuTTY Configuration window closes and the PuTTY terminal window displays.

If this is the first time you are connecting to the VM, the PuTTY Security Alert window is displayed, prompting you to confirm the public key. Click **Yes** to continue connecting.

Connecting from a Unix-Style System

To access a virtual machine on an Oracle Cloud@Customer system from a Unix-style system using SSH, use this procedure.

Enter the following SSH command to access the virtual machine:

```
ssh -i private-key user@node
```

In the preceding syntax:

- private-key is the full path and name of the file that contains the SSH private key that corresponds to a public key that is registered in the system.
- user is the operating system user that you want to use to connect:
 - * To perform operations as the Oracle Database software owner, connect as as opc and su oracle. The oracle user does not have root user access to the virtual machine.
 - * To perform operations that require root access to the virtual machine, such as patching, connect as opc. The opc user can use the sudo -s command to gain root access to the virtual machine.
- node is the host name or IP address for the virtual machine that you want to access.



Accessing a Database After You Connect to the Virtual Machine

After you connect to a virtual machine, you can use the following series of commands to identify a database and connect to it.

- 1. SSH in as the opc user.
- 2. sudo su oracle
- 3. Use the srvctl utility located under the Oracle Grid Infrastructure home directory to list the databases on the system. For example:

```
/u01/app/12.2.0.1/grid/bin/srvctl config database -v nc122 /u02/app/oracle/product/12.2.0/dbhome_6 12.2.0.1.0 s12c /u02/app/oracle/product/12.2.0/dbhome 2 12.2.0.1.0
```

4. Identify the database instances for the database that you want to access. For example:

```
/u01/app/12.2.0.1/grid/bin/srvctl status database -d s12c Instance s12c1 is running on node node01 Instance s12c2 is running on node node02
```

5. Configure the environment settings for the database that you want to access. For example:

```
. oraenv
ORACLE_SID = [oracle] ? s12c
The Oracle base has been set to /u02/app/oracle
export ORACLE SID=s12c1
```

6. You can use the svrctl command to display more detailed information about the database. For example:

```
srvctl config database -d s12c
Database unique name: s12c
Database name:
Oracle home: /u02/app/oracle/product/12.2.0/dbhome 2
Oracle user: oracle
Spfile: +DATAC4/s12c/spfiles12c.ora
Password file: +DATAC4/s12c/PASSWORD/passwd
Domain: example.com
Start options: open
Stop options: immediate
Database role: PRIMARY
Management policy: AUTOMATIC
Server pools:
Disk Groups: DATAC4
Mount point paths:
Services:
Type: RAC
Start concurrency:
Stop concurrency:
```



```
OSDBA group: dba
OSOPER group: racoper
Database instances: s12c1,s12c2
Configured nodes: node01,node02
CSS critical: no
CPU count: 0
Memory target: 0
Maximum memory: 0
Default network number for database services:
Database is administrator managed
```

7. You can access the database by using SQL*Plus. For example:

```
sqlplus / as sysdba

SQL*Plus: Release 12.2.0.1.0 Production ...

Copyright (c) 1982, 2016, Oracle. All rights reserved.

Connected to:

Oracle Database 12c EE Extreme Perf Release 12.2.0.1.0 - 64bit Production
```

Connecting to a Database with Oracle Net Services

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system using Oracle Net Services.

- Using Oracle Net Services to Connect to a Database
 Oracle Database Exadata Database Service on Cloud@Customer supports remote database access by using Oracle Net Services.
- Prerequisites for Connecting to a Database with Oracle Net Services
 Review the prerequisites to connect to an Oracle Database instance on Oracle Cloud@Customer using Oracle Net Services.
- Connecting to a Database Using SCAN
 To create an Oracle Net Services connection by using the SCAN listeners, you can choose between two approaches.
- Connecting to a Database Using a Node Listener
 To connect to an Oracle Database instance on Exadata Database Service on Cloud@Customer with a connect descriptor that bypasses the SCAN listeners, use this procedure to route your connection directly to a node listener.

Using Oracle Net Services to Connect to a Database

Oracle Database Exadata Database Service on Cloud@Customer supports remote database access by using Oracle Net Services.

Because Exadata Database Service on Cloud@Customer uses Oracle Grid Infrastructure, you can make Oracle Net Services connections by using **Single Client Access Name** (SCAN) connections. SCAN is a feature that provides a consistent mechanism for clients to access the Oracle Database instances running in a cluster.



By default, the SCAN is associated with three virtual IP addresses (VIPs). Each SCAN VIP is also associated with a SCAN listener that provides a connection endpoint for Oracle Database connections using Oracle Net Services. To maximize availability, Oracle Grid Infrastructure distributes the SCAN VIPs and SCAN listeners across the available cluster nodes. In addition, if there is a node shutdown or failure, then the SCAN VIPs and SCAN listeners are automatically migrated to a surviving node. By using SCAN connections, you enhance the ability of Oracle Database clients to have a reliable set of connection endpoints that can service all of the databases running in the cluster.

The SCAN listeners are in addition to the Oracle Net Listeners that run on every node in the cluster, which are also known as the node listeners. When an Oracle Net Services connection comes through a SCAN connection, the SCAN listener routes the connection to one of the node listeners, and plays no further part in the connection. A combination of factors, including listener availability, database instance placement, and workload distribution, determines which node listener receives each connection.



This documentation provides basic requirements for connecting to your Exadata Database Service on Cloud@Customer databases by using Oracle Net Services.

Prerequisites for Connecting to a Database with Oracle Net Services

Review the prerequisites to connect to an Oracle Database instance on Oracle Cloud@Customer using Oracle Net Services.

To connect to an Oracle Database on Exadata Database Service on Cloud@Customer with Oracle Net Services, you need the following:

- The IP addresses for your SCAN VIPs, or the hostname or IP address for a virtual machine that hosts the database that you want to access.
- The database identifier: Either the database system identifier (SID), or a service name.

Connecting to a Database Using SCAN

To create an Oracle Net Services connection by using the SCAN listeners, you can choose between two approaches.

- Connecting to a Database Using a Connect Descriptor that References All of the SCAN VIPs
 - You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using multiple SCAN listeners.
- Connecting to a Database Use a Connect Descriptor that References a Custom SCAN Name

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using a custom SCAN name.



Connecting to a Database Using a Connect Descriptor that References All of the SCAN VIPs

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using multiple SCAN listeners.

This approach requires you to supply all of the single client access name (SCAN) virtual IP (VIP) addresses, and enables Oracle Net Services to connect to an available SCAN listener.

• Use the following template to define a Net Services alias, which is typically used to provide a convenient name for the connect descriptor:

```
alias-name = (DESCRIPTION=
  (ADDRESS_LIST=
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-1) (PORT=1521))
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-2) (PORT=1521))
          (ADDRESS=(PROTOCOL=tcp) (HOST=SCAN-VIP-3) (PORT=1521)))
          (CONNECT_DATA=(sid-or-service-entry)))
```

Where:

alias-name is the name you use to identify the alias.

SCAN-VIP-[1-3] are the IP addresses for the SCAN VIPs.

<code>sid-or-service-entry</code> identifies the database SID or service name using one of the following formats:

- SID=sid-name. For example: SID=S12C1.
- SERVICE_NAME=service-name. For example: SERVICE NAME=PDB1.example.yourcloud.com.



By default, Oracle Net Services randomly selects one of the addresses in the address list to balance the load between the SCAN listeners.

Connecting to a Database Use a Connect Descriptor that References a Custom SCAN Name

You can set up a connect descriptor for Oracle Exadata Database Service on Cloud@Customer System using a custom SCAN name.

Using this approach, you define a custom single client access name (SCAN) name in your domain name server (DNS), which resolves to the three SCAN virtual IP addresses (VIPs).



 Use the following template to define a Net Services alias that references the custom SCAN name:

```
alias-name = (DESCRIPTION=
  (ADDRESS_LIST=(ADDRESS=(PROTOCOL=tcp) (HOST=scan-name) (PORT=1521)))
  (CONNECT_DATA=(sid-or-service-entry)))
```

Where:

alias-name is the name you use to identify the alias.

scan-name is the custom SCAN name.

sid-or-service-entry identifies the database SID or service name using one of the following formats:

• SID=sid-name. For example: SID=S12C1.

scan-name:1521/sid-or-service-entry

 SERVICE_NAME=service-name. For example: SERVICE NAME=PDB1.example.yourcloud.com.

Alternatively, you can use the easy connect method to specify a connect descriptor with the following format:

```
For example:

exalscan.example.com:1521/S12C1

Or
```

exalscan.example.com:1521/PDB1.example.yourcloud.com

Connecting to a Database Using a Node Listener

To connect to an Oracle Database instance on Exadata Database Service on Cloud@Customer with a connect descriptor that bypasses the SCAN listeners, use this procedure to route your connection directly to a node listener.

By using this method, you give up the high-availability and load-balancing provided by SCAN. However, this method may be desirable if you want to direct connections to a specific node or network interface. For example, you might want to ensure that connections from a program that performs bulk data loading use the backup network.

Using this approach, you direct your connection using the hostname or IP address of the node.

Example 5-1 Defining a Net Service Alias That Directly References the Node

```
alias-name = (DESCRIPTION=
  (CONNECT_TIMEOUT=timeout)
  (ADDRESS_LIST=(ADDRESS=(PROTOCOL=tcp) (HOST=node) (PORT=1521)))
  (CONNECT_DATA=(sid-or-service-entry)))
```



Where:

alias-name is the name you use to identify the alias.

timeout specifies a timeout period (in seconds), which enables you to terminate a connection attempt without having to wait for a TCP timeout. The (CONNECT TIMEOUT=timeout) parameter is optional.

node is the hostname or IP address for the virtual machine that you want to use.

sid-or-service-entry identifies the database SID or service name using one of the following formats:

- SID=sid-name. For example, SID=S12C1.
- SERVICE_NAME=service-name. For example, SERVICE NAME=PDB1.example.oraclecloudatcust.com.

Alternatively, you can use the easy connect method to specify a connect descriptor with the following format:

```
node:1521/sid-or-service-entry
```

For example:

```
exalnode01.example.com:1521/S12C1
```

Or

exalnode01.example.com:1521/PDB1.example.oraclecloudatcust.com

Manage Exadata Database Service on Cloud@Customer Infrastructure

Use the provided tools to manage the Infrastructure.

- About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems
 - To provision an Oracle Exadata Database Service on Cloud@Customer system, you must work with Oracle to set up and configure the system.
- Overview of Elastic Storage Expansion
 With elastic storage expansion, you can dynamically increase your storage
 capacity to meet your growing workload requirements.
- Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure
 - Learn how to provision an Exadata Database Service on Cloud@Customer system.
- Using the API to Manage Exadata Cloud@Customer Infrastructure
 Oracle Exadata Database Service on Cloud@Customer uses the same API as
 Oracle Cloud Infrastructure.



About Provisioning Oracle Exadata Database Service on Cloud@Customer Systems

To provision an Oracle Exadata Database Service on Cloud@Customer system, you must work with Oracle to set up and configure the system.

Provisioning an Oracle Exadata Database Service on Cloud@Customer system is a collaborative process. The process is performed in the following sequence:

- You create the Oracle Exadata Database Service on Cloud@Customer infrastructure.
- You generate a file containing the infrastructure configuration details, and provide it to Oracle.
- The Oracle Exadata Database Service on Cloud@Customer system is physically installed in your data center.
- **4.** Oracle uses the infrastructure configuration file to perform initial system configuration. At the end of this task, Oracle supplies you with an activation file.
- You activate the Exadata Database Service on Cloud@Customer infrastructure by using the supplied activation file.

When the provisioning process is complete, the Oracle Exadata Database Service on Cloud@Customer system is ready for you to use. You can then create a virtual machine (VM) cluster, and later create some databases.



Caution:

Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, the APIs, or the command-line interface.

Overview of Elastic Storage Expansion

With elastic storage expansion, you can dynamically increase your storage capacity to meet your growing workload requirements.

Expand the storage capacity on-demand by scaling up the infrastructure with additional storage servers without being constrained by the standard supported shapes. You can allocate additional storage capacity available from the newly added storage servers to the already deployed VM Cluster without disrupting the current running workloads. Additional storage capacity from newly added storage servers is also available for provisioning new VM Clusters on the infrastructure.

With the elastic storage expansion capability, you can now:

- Provision new Exadata Infrastructure with custom storage capacity.
- Start with a smaller storage footprint for the Exadata Infrastructure at install time.
- Expand the storage capacity on existing deployed Exadata Infrastructure on-demand in an automated, elastic fashion.



 Allocate additional storage capacity available from newly added storage servers to already deployed VM clusters and/or use them for provisioning new VM clusters on the infrastructure.

Table 5-1 Key Additional Resources

Specification	Exadata Base System Storage Server X7-2	Exadata Storage Server X7-2
Additional Raw Flash Storage Capacity	6.4 TB	25.6 TB
Additional Raw Disk Storage Capacity	48 TB	120 TB
Additional Usable Storage Capacity	14 TB	35.3 TB

Table 5-2 Key Additional Resources

Specification	Exadata Base System Storage Server X8-2	Exadata Storage Server X8-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB
Additional Raw Disk Storage Capacity	84 TB	168 TB
Additional Usable Storage Capacity	24.6 TB	49.6 TB

Table 5-3 Key Additional Resources

Specification	Exadata Base System Storage Server X8M-2	Exadata Storage Server X8M-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB
Additional Raw Disk Storage Capacity	84 TB	168 TB
Additional Usable Storage Capacity	24.6 TB	49.6 TB
Additional Persistent Memory	-	1.5 TB

Table 5-4 Key Additional Resources

Specification	Exadata Base System Storage Server X9M-2	Exadata Storage Server X9M-2
Additional Raw Flash Storage Capacity	12.8 TB	25.6 TB
Additional Raw Disk Storage Capacity	84 TB	216 TB
Additional Usable Storage Capacity	24.6 TB	63.6 TB



Table 5-4 (Cont.) Key Additional Resources

Specification	Exadata Base System Storage Server X9M-2	Exadata Storage Server X9M-2
Additional Persistent Memory	-	1.5 TB


Elastic scaling of Exadata Storage Servers is subject to the following conditions:

- The Exadata Cloud@Customer system configuration must be based on Oracle Exadata X7 hardware, Oracle Exadata X8 hardware, Oracle Exadata X8M hardware, or Oracle Exadata X9M hardware.
- Each Exadata Cloud@Customer system configuration can have an absolute maximum of 12 Exadata Storage Servers.
- Exadata Infrastructure deployed with base configuration shape can only be expanded using base expansion SKU storage servers.
- Exadata Infrastructures deployed with X7 generation at install time can be scaled with X8 generation storage servers. X8 storage servers used to scale X7 infrastructure will only present the same total usable capacity as all other X7 storage servers that are already part of the infrastructure.
- Exadata Infrastructures deployed with X8M generation at install time can only be scaled with X8M or higher generation storage servers.

Exadata Infrastructures deployed with additional storage servers will be configured as an Elastic shape with the total number of storage servers and usable capacity clearly called out for the given infrastructure.

Before you can scale the number of Exadata storage servers, review the site and network requirements, and the checklists to prepare and deploy Exadata Cloud@Customer. Ensure that you have worked with sales and followed the procurement process. The following figure provides you an overview of the order and deployment process.

Figure 5-1 Overview of Order and Deployment Process





Related Topics

- Using the Console to Scale Infrastructure Storage
 To scale infrastructure storage, complete this procedure.
- Using the Console to Download Scale Infrastructure Storage Configuration File
 To download an Oracle Exadata Cloud@Customer scale configuration file,
 complete this procedure.
- Using the Console to Activate New Storage Servers
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.
- Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption
 - To make storage capacity from the new servers for VM clusters consumption, complete this procedure.
- Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity
 - To view the storage capacity from the new storage server use this procedure.

Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure

Learn how to provision an Exadata Database Service on Cloud@Customer system.

- Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure
 - To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to View Exadata Infrastructure Network Configuration Details
 To view network configuration details, follow these steps. Save this information for
 later use to troubleshoot if you face network issues.
- Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration
 - To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration, be prepared to provide values for the infrastructure configuration.
- Using the Console to Download a File Containing Configuration Data
 To download an Oracle Exadata Database Service on Cloud@Customer configuration file, complete this procedure.
- Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure
 - To activate Oracle Exadata Database Service on Cloud@Customer infrastructure, ensure that you meet the prerequisites, and complete this procedure.
- Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure
 - To find the status of your Oracle Exadata Database Service on Cloud@Customer infrastructure, use this procedure to check the Infrastructure Details page.
- Using the Console to Scale Infrastructure Storage
 To scale infrastructure storage, complete this procedure.



- Using the Console to Download Scale Infrastructure Storage Configuration File
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this
 procedure.
- Using the Console to Activate New Storage Servers
 To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.
- Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption

To make storage capacity from the new servers for VM clusters consumption, complete this procedure.

- Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity
 - To view the storage capacity from the new storage server use this procedure.
- Using the Console to Move Exadata Database Service on Cloud@Customer Infrastructure

To relocate Oracle Exadata Database Service on Cloud@Customer infrastructure to another compartment, use this procedure.

- Using the Console to Delete Exadata Database Service on Cloud@Customer Infrastructure
 - To delete Oracle Exadata Database Service on Cloud@Customer infrastructure, complete the prerequisites, and then complete this procedure.
- Using the Console to Manage Tags for Your Exadata Cloud@Customer Resources
- Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.

Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure

To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Under **Region**, select the region that you want to associate with the Oracle Exadata infrastructure.

The region that is associated with your Oracle Exadata infrastructure cannot be changed after the Oracle Exadata infrastructure is created. Therefore, ensure that you select the most appropriate region for your infrastructure. Consider the following factors:

- Consider any business policies or regulations that preclude the use of a particular region. For example, you can be required to maintain all operations within national boundaries.
- Consider the physical proximity of the region to your data center. Needless extra
 physical separation adds unnecessary latency to network communications between
 Oracle Cloud Infrastructure and your corporate data center.
- 3. Click Exadata Infrastructure.
- 4. Click Create Exadata Infrastructure.
- 5. In the Create Exadata Infrastructure page, provide the requested information:



- Oracle Cloud Infrastructure region: The region that is associated with your Oracle Exadata infrastructure cannot be changed after the Oracle Exadata infrastructure is created. Therefore, check the displayed region to ensure that you are using the most appropriate region for your infrastructure.
 - See step 2 (earlier in this procedure) for further considerations. To switch regions now, use the **Region** menu at the top of the console.
- **Choose a compartment:** From the list of available compartments, choose the compartment that you want to contain the Oracle Exadata infrastructure.
 - For more information, see *Understanding Compartments*.
- Provide the display name: The display name is a user-friendly name that you
 can use to identify the Exadata infrastructure. The name doesn't need to be
 unique, because an Oracle Cloud Identifier (OCID) uniquely identifies the
 Oracle Exadata infrastructure.
- **Select the Exadata system model:** From the list, choose the model of the Oracle Exadata hardware that is being used.
 - The Oracle Exadata system model and system shape combine to define the amount of CPU, memory, and storage resources that are available in the Exadata infrastructure. For more information, see *System Configuration*.
- Select an Exadata system shape: Together with the Oracle Exadata system
 model, the Oracle Exadata system shape defines the amount of CPU,
 memory, and storage resources that are available in the Oracle Exadata
 infrastructure.
 - Base System: includes two compute nodes and three Oracle Exadata Storage Servers. A Base System is an entry-level configuration.
 Compared to other configurations, a Base System contains Oracle Exadata Storage Servers with significantly less storage capacity, and compute nodes with significantly less memory and processing power.
 - Quarter Rack: includes two compute nodes and three Oracle Exadata Storage Servers.
 - Half Rack: includes four compute nodes and six Oracle Exadata Storage Servers.
 - Full Rack: includes eight compute nodes and 12 Oracle Exadata Storage Servers.
- Storage Configuration: You can add a minimum of 3 and extend up to a maximum of 12 storage servers. For each storage server you add, the storage capacity that will be added is displayed on the right.
- Configure the cloud control plane server network

Each Oracle Exadata Database Service on Cloud@Customer system contains two control plane servers, which enable connectivity to Oracle Cloud Infrastructure. The control plane servers are connected to the control plane network, which is a subnet on your corporate network. The following settings define the network parameters:

 Control Plane Server 1 IP Address: Provide the IP address for the first control plane server. This IP address is for the network interface that connects the first control plane server to your corporate network using the control plane network.



- Control Plane Server 2 IP Address: Provide the IP address for the second control plane server. This IP address is for the network interface that connects the second control plane server to your corporate network using the control plane network.
- Netmask: Specify the IP netmask for the control plane network.
- Gateway: Specify the IP address of the control plane network gateway.
- HTTP Proxy: (Optional) You can choose to use this field to specify your corporate HTTP proxy. The expected format is as follows, where server is the server name, domain is the domain name, and port is the assigned port:

http://server.domain:port

For example:

http://proxy.example.com:80

For enhanced security, when possible, Oracle recommends that you use an HTTP proxy.

 Enable Control Plane Server Offline Report: Enabling the Control Plane Server (CPS) offline report helps in diagnosing connectivity issues between the CPS and OCI endpoints, should they arise.
 To view the report, do the following:

- a. Find the CPS IP addresses.
 For more information, see Using the Console to View Exadata Infrastructure Network Configuration Details.
- b. From your local network, access the report over HTTP.
 To view the report in HTML format, use http://<CPSPublicIP>:18080/report

To view the report in JSON format, use http://<CPSPublicIP>:18080/report/json

For more information, see ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side.

Configure the Oracle Exadata system networks

Each Oracle Exadata Database Service on Cloud@Customer system contains two system networks, which are not connected to your corporate network. The following settings define IP address allocations for these networks:

Administration Network CIDR Block: Specifies the IP address range for the administration network using CIDR notation. The administration network provides connectivity that enables Oracle to administer the Exadata system components, such as the Exadata compute servers, storage servers, network switches, and power distribution units. You can accept the suggested default, or specify a custom value.

The maximum CIDR block prefix length is /23, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /16.



Manage Exadata Database Service on Cloud@Customer Infrastructure

Ensure that the IP address range does not conflict with other hosts of your corporate network, and does not overlap with the InfiniBand network CIDR block.

InfiniBand Network CIDR Block: Specifies the IP address range for the Exadata InfiniBand network using CIDR notation. The Exadata InfiniBand network provides the high-speed low-latency interconnect used by Exadata software for internal communications between various system components. You can accept the suggested default, or specify a custom value.

The maximum CIDR block prefix length is /22, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /19.

Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the administration network CIDR block.

Configure DNS and NTP services

Each Exadata Database Service on Cloud@Customer system requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services to the Exadata infrastructure:

- DNS Servers: Provide the IP address of a DNS server that is accessible using the control plane network. You may specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible using the control plane network. You may specify up to three NTP servers.
- Time Zone: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.

Note:

If you want to set a time zone other than UTC or the browserdetected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

Provide maintenance details

Configure automatic maintenance
 Click Edit Maintenance Preferences.

Edit Maintenance Preferences dialog is displayed.

In the **Edit Maintenance Preferences** dialog, configure the following:

* Choose a maintenance method:



- * **Rolling:** By default, Exadata Infrastructure is updated in a rolling fashion, one server at a time with no downtime.
- * **Non-rolling:** Update database and storage servers at the same time. The non-rolling maintenance method minimizes maintenance time but incurs full system downtime.
- * Enable custom action before performing maintenance on DB servers:
 Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers.
 - * Custom action timeout (in minutes): Timeout available to perform custom action before starting maintenance on the DB Servers.

Default: 30 minutes

Maximum: 120 minutes

* Maintenance schedule:

- * **No preference:** The system assigns a date and start time for infrastructure maintenance.
- * **Specify a schedule:** Choose your preferred month, week, weekday, start time, and lead time for infrastructure maintenance.
- * **Lead Time:** Specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message.

Click Save Changes.

If you switch from rolling to non-rolling maintenance method, then **Confirm Non-rolling Maintenance Method** dialog is displayed.

Enter the name of the infrastructure in the field provided to confirm the changes.

Click Save Changes.



After creating the infrastructure, you can find the maintenance method, maintenance schedule, DB Server version, and Storage Server version details under the **Maintenance** and **Version** sections on the **Infrastructure Details** page.

Provide maintenance contacts

Maintenance contacts are required for service request-based communications for hardware replacement and other maintenance events.

You can skip adding maintenance contacts while creating your infrastructure. However, you must add a primary contact prior to activating your infrastructure. Ensure that you provide the details of the contact that you used while registering the Customer Support Identifier (CSI) associated with this infrastructure, as a primary contact.



Optionally, you can add a maximum of nine secondary contacts. Both the primary and secondary contacts receive all notifications about hardware replacement, network issues, and software maintenance runs. Note that you can promote any secondary contacts as the primary anytime you want. When you promote a secondary contact to primary, the current primary contact will be demoted automatically to secondary.

Show Advanced Options

You have the option to configure advanced options.

Tags: (Optional) You can choose to apply tags. If you have permission to create a resource, then you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see *Resource Tags*. If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

6. Click Create Exadata Infrastructure.

If all of your inputs are valid, then the Infrastructure Details page appears. The page outlines the next steps in the provisioning process. Initially, after creation, the state of the Oracle Exadata infrastructure is **Requires-Activation**.

Related Topics

- Understanding Compartments
- System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.

- ExaCC gen2: Troubleshooting VPN/WSS connection from Customer Side
- Resource Tags

Using the Console to View Exadata Infrastructure Network Configuration Details

To view network configuration details, follow these steps. Save this information for later use to troubleshoot if you face network issues.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Under **Region**, select the region that you want to associate with the Oracle Exadata infrastructure.
- 3. Click Exadata Infrastructure.
- 4. From the list of infrastructures, click the name of the infrastructure that you're interested in. Note that the infrastructure must be in **Active** state.
- 5. On the **Infrastructure Details** page, find the network configuration details under the **Network** section.



Using the Console to Edit Oracle Exadata Database Service on Cloud@Customer Infrastructure Networking Configuration

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration, be prepared to provide values for the infrastructure configuration.

You can only edit Oracle Exadata Database Service on Cloud@Customer infrastructure networking configuration only if the current state of the Oracle Exadata infrastructure is **Requires Activation**. Also, ensure that you do not edit the Exadata infrastructure after you download the configuration file and provide it to Oracle.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and the compartment where the Oracle Exadata infrastructure you want to edit is located.
- Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that you want to edit.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.

- Click Edit Infrastructure Networking.
- 6. Use the Edit Infrastructure Networking dialog to edit the Oracle Exadata infrastructure networking:
 - a. Configure the cloud control plane network

Each Oracle Exadata Database Service on Cloud@Customer system contains two Control Plane Servers, which enable connectivity to Oracle Cloud Infrastructure. The Control Plane Servers are connected to the control plane network, which is a subnet on your corporate network. The following settings define the network parameters:

- Control Plane Server 1 IP Address: Provide the IP address for the first control
 plane server. This IP address is for the network interface that connects the first
 Control Plane Server to your corporate network using the control plane network.
- Control Plane Server 2 IP Address: Provide the IP address for the second control plane server. This IP address is for the network interface that connects the second Control Plane Server to your corporate network using the control plane network.
- Netmask: Specify the IP netmask for the control plane network.
- Gateway: Specify the IP address of the control plane network gateway.
- HTTP Proxy: Optionally, you can use this field to specify your corporate HTTP proxy to use for the HTTPS connection from the Control Plane Server to Oracle Cloud Infrastructure. The expected format is:

http://server.domain:port

For example:

http://proxy.example.com:80



Manage Exadata Database Service on Cloud@Customer Infrastructure

For enhanced security, when possible, Oracle recommends that you use an HTTP proxy.

b. Configure the Exadata system networks

Each Oracle Exadata Database Service on Cloud@Customer system contains two system networks, which are not connected to your corporate network. The following settings define IP address allocations for these networks:

Administration Network CIDR Block: Specifies the IP address range for the administration network using CIDR notation. The administration network provides connectivity that enables Oracle to administer the Exadata system components, such as the Exadata compute servers, storage servers, network switches, and power distribution units.

The maximum CIDR block prefix length is /23, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Oracle Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /16.

Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the InfiniBand network CIDR block.

 InfiniBand Network CIDR Block: Specifies the IP address range for the Exadata InfiniBand network using CIDR notation. The Exadata InfiniBand network provides the high-speed low-latency interconnect used by Exadata software for internal communications between various system components.

The maximum CIDR block prefix length is /22, which defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Oracle Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network. The minimum CIDR block prefix length is /19.

Ensure that the IP address range does not conflict with other hosts your corporate network, and does not overlap with the administration network CIDR block.

c. Configure DNS and NTP services

Each Oracle Exadata Database Service on Cloud@Customer system requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services to the Exadata infrastructure:

- **DNS Servers:** Provide the IP address of a DNS server that is accessible using the control plane network. You can specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible using the control plane network. You may specify up to three NTP servers.
- Time zone: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.



Note:

If you want to set a time zone other than UTC or the browser-detected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

7. Click Save Changes.

Using the Console to Download a File Containing Configuration Data

To download an Oracle Exadata Database Service on Cloud@Customer configuration file, complete this procedure.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.
- Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.

5. Click Download Configuration.

Your browser downloads a file containing the infrastructure configuration details.

The generated configuration file includes all the relevant configuration details for the additional storage servers included as part of the create infrastructure flow.

When you provide the generated infrastructure configuration file to Oracle, ensure that it has not been altered in any way. Also, ensure that you do not edit the Oracle Exadata infrastructure after you download the configuration file and provide it to Oracle.

Using the Console to Activate Exadata Database Service on Cloud@Customer Infrastructure

To activate Oracle Exadata Database Service on Cloud@Customer infrastructure, ensure that you meet the prerequisites, and complete this procedure.

- Ensure that you have added a primary contact. You cannot activate your infrastructure without adding a primary maintenance contact.
- Locate the activation file. This file is supplied to you by Oracle after installation and initial configuration of your Oracle Exadata Database Service on Cloud@Customer system.
- Ensure that the current state of your infrastructure is Requires Activation. You can only activate Oracle Exadata if its state is Requires Activation.
- 1. Download the activation file.



- 2. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 3. Choose **Region** and **Compartment**, and select the region and compartment that contains the Oracle Exadata infrastructure that you want to activate.
- Click Exadata Infrastructure.
- 5. Click the name of the Oracle Exadata infrastructure that you want to activate.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 6. Click Activate.
 - The **Activate** button is only available if the Oracle Exadata infrastructure requires activation. You cannot activate Oracle Exadata infrastructure multiple times.
- 7. Use the Activate dialog to upload the activation file, and then click **Activate Now**.
 - The activation file includes all the relevant details for the additional storage servers included as part of the create infrastructure flow.
 - After activation, the state of the Oracle Exadata infrastructure changes to **Active**.

Using the Console to Check the Status of Exadata Database Service on Cloud@Customer Infrastructure

To find the status of your Oracle Exadata Database Service on Cloud@Customer infrastructure, use this procedure to check the Infrastructure Details page.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure that you are interested in.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure that you are interested in. The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Check the icon on the Infrastructure Details page. The color of the icon and the text below it indicates the status of the Oracle Exadata infrastructure.
 - **Creating**: Yellow icon. The Oracle Exadata infrastructure definition is being created in the control plane.
 - Requires Activation: Yellow icon. The Oracle Exadata infrastructure is defined in the control plane, but it must be provisioned and activated before it can be used.
 - Active: Green icon. The Oracle Exadata infrastructure is successfully provisioned and activated.
 - **Deleting**: Gray icon. The Oracle Exadata infrastructure is being deleted by using the Console or API.
 - **Deleted**: Gray icon. The Oracle Exadata infrastructure is deleted, and is no longer available. This state is transitory. It is displayed for a short time, after which the Oracle Exadata infrastructure is no longer displayed.



 Activation Failed: Red icon. An error condition currently prevents the activation of the Oracle Exadata infrastructure. Typically, this state is auto-correcting, and does not require user intervention.

Using the Console to Scale Infrastructure Storage

To scale infrastructure storage, complete this procedure.

You can scale infrastructure storage when the current state of the Oracle Exadata infrastructure is **Active** or **Requires Activation**.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure that you are interested in.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Scale Infrastructure Storage.
- 6. Select the number of storage servers from the Additional storage servers field.
- 7. Click Scale Infrastructure.

Using the Console to Download Scale Infrastructure Storage Configuration File

To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure that you are interested in.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to download a file containing the infrastructure configuration details.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- Click Download New Configuration.
 Your browser downloads a file containing the infrastructure configuration details.

Note:

When you provide the generated infrastructure configuration file to Oracle, ensure that it has not been altered in any way. Also, ensure that you do not edit the Oracle Exadata infrastructure after you download the configuration file and provide it to Oracle.



Using the Console to Activate New Storage Servers

To download an Oracle Exadata Cloud@Customer scale configuration file, complete this procedure.

Upload the activation file once the field engineer finishes deploying the storage servers and shares the activation file with you.



Once the activation file is uploaded and the activate process is initiated, you cannot change the Scale Infrastructure request or cancel this whole operation. If there is an activation failure, then contact the field engineer to resolve the issue.

- Download the activation file.
- 2. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Oracle Exadata infrastructure that you are interested in.
- Click Exadata Infrastructure.
- Click the name of the Oracle Exadata infrastructure that you want to activate.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 6. Click Activate New Storage Server(s). The Activate button is only available if the Oracle Exadata infrastructure requires activation. You cannot activate Oracle Exadata infrastructure multiple times.
- Use the Activate New Server dialog to upload the activation file, and then click Activate Now.

After activation, the state of the Oracle Exadata infrastructure changes to Active.

Using the Console to Make Storage Capacity from New Server Available for VM Clusters Consumption

To make storage capacity from the new servers for VM clusters consumption, complete this procedure.

- Download the activation file.
- Open the navigation menu. Under Oracle Databases, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Oracle Exadata infrastructure that you are interested in.
- Click Exadata Infrastructure.
- Click the name of the Oracle Exadata infrastructure that you want to activate.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.



- 6. Click Add Storage Capacity.
- Review the advisory on the Add Storage Capacity dialog, and then click Add Storage Capacity.



While Add Storage Capacity operation is in progress,

- The system rebalances the storage to ensure that the capacity from the newly added storage servers is available for VM Cluster consumption. This rebalance will run with a ASM power limit of 4 independent of what you have set within your ASM configuration. If you would like the rebalance to complete faster, you can update the power limit after the rebalance process has begun. Monitor the ASM rebalance process to ensure it successfully completes (which will allow the add storage capacity workflow to complete).
- You cannot create or delete VM Clusters.
- Existing VM Clusters provisioned are in the Available life cycle state. However, they do not support scale up or down of resources allocated to the VM cluster, except for OCPU allocation. OCPU allocation changes are allowed even while Add Storage Capacity operation is in progress.

Using the Console to View Details of Exadata Cloud@Customer Infrastructure with Scaled Storage Capacity

To view the storage capacity from the new storage server use this procedure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Oracle Exadata infrastructure that you are interested in.
- 3. Click Exadata Infrastructure.

 After changing the storage capacity, Shape will change to either Elastic or Elastic Base.



When you perform scale VM Cluster Exadata storage operation, newly added Exadata storage capacity is also available for consumption. Similarly, when you create a VM cluster, the Console displays the newly added Exadata storage capacity (shared Exadata storage) as available storage.

Related Topics

- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can scale up or scale down your VM cluster resources.
- Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.



Using the Console to Move Exadata Database Service on Cloud@Customer Infrastructure

To relocate Oracle Exadata Database Service on Cloud@Customer infrastructure to another compartment, use this procedure.

You can change the compartment that contains your Exadata Database Service on Cloud@Customer infrastructure by moving it.

When you move Exadata infrastructure, the compartment change is also applied to the associated VM cluster networks. However, the compartment change does not affect any other associated resources, such as the VM clusters, which remain in their current compartment.

To move Oracle Exadata Database Service on Cloud@Customer infrastructure:

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and compartment that contains the Oracle Exadata infrastructure that you want to move.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Exadata infrastructure that you want to move.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Move Resource.
- **6.** In the resulting dialog, choose the new compartment for the Oracle Exadata infrastructure, and click **Move Resource**.

Using the Console to Delete Exadata Database Service on Cloud@Customer Infrastructure

To delete Oracle Exadata Database Service on Cloud@Customer infrastructure, complete the prerequisites, and then complete this procedure.

Deleting Exadata Database Service on Cloud@Customer infrastructure removes it from the Cloud Control Plane.

If you are deleting Oracle Exadata infrastructure before activation, then if required, you can create replacement Oracle Exadata infrastructure without any input from Oracle.

If you are deleting active Oracle Exadata infrastructure, then to create replacement Oracle Exadata infrastructure, you must repeat the full provisioning process, including the tasks that Oracle performs.

Before you can delete active Exadata infrastructure, you must:

- Terminate all of the resources that it contains, including the databases, VM cluster, and VM cluster network.
- Lodge a service request (SR) with Oracle indicating your intention to delete the Oracle Exadata infrastructure. In response to the SR, Oracle flags the Oracle Exadata infrastructure as ready for deletion.



After Oracle has flagged the Oracle Exadata infrastructure, delete the Exadata infrastructure by using the following process:

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and compartment that contains the Oracle Exadata infrastructure that you want to delete.
- 3. Click Exadata Infrastructure.
- Click the name of the Oracle Exadata infrastructure that you want to delete.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.

- Click Delete.
- 6. In the resulting dialog, enter the Oracle Exadata infrastructure name and click **Delete Exadata Infrastructure** to confirm the action.

Using the Console to Manage Tags for Your Exadata Cloud@Customer Resources

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose your Compartment.
- 3. Find the Exadata Infrastructure, VM Cluster Network, VM Cluster, Backup Destination, Database Home, or Database resource you're interested in, and click the name.
- 4. Click the **Tags** tab to view or edit the existing tags. Or, click **More Actions** and then **Apply Tags** to add new ones.

Related Topics

Resource Tags

Managing Infrastructure Maintenance Contacts

Learn to manage your Exadata infrastructure maintenance contacts.

- View Primary Maintenance Contact
 You must associate primary contact with the Customer Support Identifier (CSI).
- Add Secondary Contacts
 You can add up to nine secondary contacts.
- Edit Maintenance Contacts
 Edit maintenance contacts to update details.
- Promote a Secondary Contact to Primary
 You can promote a secondary contact to primary. The current primary is automatically
 demoted to secondary.
- Remove a Secondary Contact
 You can remove a secondary contact anytime you want to.



View Primary Maintenance Contact

You must associate primary contact with the Customer Support Identifier (CSI).

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Select Region and Compartment, and provide the region and compartment that contains the Oracle Exadata infrastructure for which you want to view contact details.
- 3. Click Exadata Infrastructure.
- Click the name of the Oracle Exadata infrastructure for which you want to view contact details.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Find the CSI and the primary contact under Maintenance. The operations team sets the infrastructure maintenance Service Level Objective (SLO) to Degraded:
 - If the primary contact CSI verification has failed.
 - If the primary contact is missing.
 - If the primary contact is verified and unresponsive.

Also, a warning message is displayed on the Console as follows:

"Ensure that the primary contact associated with your Customer Support Identifier (CSI) is available for Oracle support to coordinate maintenance-related activities.

The infrastructure maintenance Service Level Objective (SLO) is set to degraded status without proper primary contact."

Add a primary contact before you activate the infrastructure.

Add Secondary Contacts

You can add up to nine secondary contacts.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Select Region and Compartment, and provide the region and compartment that contains the Oracle Exadata infrastructure for which you want to add secondary contacts.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to add secondary contacts.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Manage Contacts.
- 6. In the Manage Exadata Infrastructure Contacts window, click Add Contact.
- 7. In the Add Contacts window, add contact details.
- Click Add Contacts.



Edit Maintenance Contacts

Edit maintenance contacts to update details.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Select Region and Compartment, and provide the region and compartment that contains the Oracle Exadata infrastructure for which you want to edit maintenance contact details.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to edit maintenance contact details.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Manage Contacts.
- 6. In the Manage Exadata Infrastructure Contacts window, click the actions button, and then select **Edit Contact**.
- 7. In the Edit Contacts window, edit the details.
- 8. Click Save.

Promote a Secondary Contact to Primary

You can promote a secondary contact to primary. The current primary is automatically demoted to secondary.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and compartment that contains the Oracle Exadata infrastructure for which you want to promote a secondary contact to primary.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to promote a secondary contact to primary.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Manage Contacts.
- **6.** In the Manage Exadata Infrastructure Contacts window, click the actions button, and then select **Make Primary**.
- 7. In the Promote to Primary Contact dialog, click **Promote**.

Remove a Secondary Contact

You can remove a secondary contact anytime you want to.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



- Select Region and Compartment, and provide the region and compartment that contains the Oracle Exadata infrastructure for which you want to remove a secondary contact.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Oracle Exadata infrastructure for which you want to remove a secondary contact.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. Click Manage Contacts.
- **6.** In the Manage Exadata Infrastructure Contacts window, click the actions button, and then select **Remove**.
- 7. In the Remove Infrastructure Contact dialog, click **Remove**.

Using the API to Manage Exadata Cloud@Customer Infrastructure

Oracle Exadata Database Service on Cloud@Customer uses the same API as Oracle Cloud Infrastructure.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Exadata Database Service on Cloud@Customer infrastructure:

- ActivateExadataInfrastructure
- CreateExadataInfrastructure
- DeleteExadataInfrastructure
- DownloadExadataInfrastructureConfigFile
- GenerateRecommendedVmClusterNetwork
- GetExadataInfrastructure
- ListExadataInfrastructure
- UpdateExadataInfrastructure
- AddStorageCapacityExadataInfrastructure

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- ActivateExadataInfrastructure
- CreateExadataInfrastructure
- DeleteExadataInfrastructure
- DownloadExadataInfrastructureConfigFile
- GenerateRecommendedVmClusterNetwork



- GetExadataInfrastructure
- ListExadataInfrastructure
- UpdateExadataInfrastructure
- AddStorageCapacityExadataInfrastructure

Configure Oracle-Managed Infrastructure Maintenance

Oracle performs the updates to all of the Oracle-managed infrastructure components on Exadata Cloud@Customer.

You may manage contacts who are notified regarding infrastructure maintenance, set a maintenance window to determine the time your quarterly infrastructure maintenance will begin, and also view scheduled maintenance runs and the maintenance history of your Exadata Cloud@Customer in the Oracle Cloud Infrastructure Console. For details regarding the infrastructure maintenance process and configuring the maintenance controls refer to the following:

- About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates
 Oracle performs patches and updates to all of the Oracle-managed system components
 on Exadata Cloud@Customer.
- Infrastructure Maintenance Contacts
 Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.
- Using the Console to Configure Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a
 maintenance window to determine the time your quarterly infrastructure maintenance will
 begin.
- Monitor Infrastructure Maintenance Using Lifecycle State Information
 The lifecycle state of your Exadata Infrastructure resource enables you to monitor when
 the maintenance of your infrastructure resource begins and ends.
- Receive Notifications about Your Infrastructure Maintenance Updates
 There are two ways to receive notifications. One is through email to infrastructure
 maintenance contacts and the other one is to subscribe to the maintenance events and
 get notified.
- Using the API to Manage Exadata Cloud@Customer Infrastructure Maintenance Controls
 Oracle Exadata Cloud@Customer uses the same API as Oracle Cloud Infrastructure to
 manage infrastructure maintenance controls.

About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates

Oracle performs patches and updates to all of the Oracle-managed system components on Exadata Cloud@Customer.

Oracle patches and updates include the physical database server hosts, Exadata Storage Servers, Network Fabric Switches, management switch, power distribution units (PDUs), integrated lights-out management (ILOM) interfaces, and Control Plane Servers. This is referred to as Exadata Cloud@Customer infrastructure maintenance.



In all but rare exceptional circumstances, you receive advance communication about these updates to help you plan for them. If there are corresponding recommended updates for your VM cluster virtual machines (VMs), then Oracle provides notifications about them.

Wherever possible, scheduled updates are performed in a manner that preserves service availability throughout the update process. However, there can be some noticeable impact on performance and throughput while individual system components are unavailable during the update process.

For example, database server patching typically requires a reboot. In such cases, wherever possible, the database servers are restarted in a rolling manner, one at a time, to ensure that the service remains available throughout the process. However, each database server is unavailable for a short time while it restarts, and the overall service capacity diminishes accordingly. If your applications cannot tolerate the restarts, then take mitigating action as needed. For example, shut down an application while database server patching occurs.

Overview of the Infrastructure Maintenance Process
 By default, infrastructure maintenance updates the Exadata database server hosts in a rolling fashion, followed by updating the storage servers.

Overview of the Infrastructure Maintenance Process

By default, infrastructure maintenance updates the Exadata database server hosts in a rolling fashion, followed by updating the storage servers.

You can also choose non-rolling maintenance to update database and storage servers. The non-rolling maintenance method first updates your storage servers at the same time, then your database servers at the same time. Although non-rolling maintenance minimizes maintenance time, it incurs full system downtime while the storage servers and database servers are being updated.

Rolling infrastructure maintenance begins with the Exadata database server hosts. For the rolling maintenance method, database servers are updated one at a time. Each of the database server host's VMs is shut down, the host is updated, restarted, and then the VMs are started, while other database servers remain operational. This process continues until all servers are updated. After database server maintenance completes, storage server maintenance begins. For the rolling maintenance method, storage servers are updated one at a time and do not impact VM cluster VM's availability.

Note that while databases are expected to be available during the rolling maintenance process, the automated maintenance verifies Oracle Clusterware is running but does not verify that all database services and pluggable databases (PDBs) are available after a server is brought back online. The availability of database services and PDBs after maintenance can depend on the application service definition. For example, a database service, configured with certain preferred and available nodes, may be relocated during the maintenance and wouldn't automatically be relocated back to its original node after the maintenance completes. Oracle recommends reviewing the documentation on *Achieving Continuous Availability for Your Applications* on Exadata Cloud Systems to reduce the potential for impact to your applications. By following the documentation's guidelines, the impact of infrastructure maintenance will be only minor service degradation as database servers are sequentially updated.

Oracle recommends that you follow the *Maximum Availability Architecture (MAA) best practices* and use Data Guard to ensure the highest availability for your critical applications. For databases with Data Guard enabled, Oracle recommends that you



separate the maintenance windows for the infrastructure instances running the primary and standby databases. You may also perform a switchover prior to the maintenance operations for the infrastructure instance hosting the primary database. This allows you to avoid any impact on your primary database during infrastructure maintenance.

Prechecks are performed on the Exadata Cloud@Customer infrastructure components prior to the start of the maintenance window. The goal of the prechecks is to identify issues that may prevent the infrastructure maintenance from succeeding. The Exadata infrastructure and all components remain online during the prechecks. An initial precheck is run approximately two weeks prior to the maintenance start and another precheck is run approximately 24 hours prior to maintenance start. If the prechecks identify an issue that requires rescheduling the maintenance notification is sent to the maintenance contacts.

The time taken to update infrastructure components varies depending on the number of database servers and storage servers in the Exadata infrastructure, the maintenance method, and whether custom action has been enabled. The approximate times provided are estimates. Time for custom action, if configured, is not included in the estimates below. Database server maintenance time may vary depending on the time required to shutdown each VM before the update and then start each VM and associated resources after the update of each node before proceeding to the next node. The storage server maintenance time will vary depending on the time required for the ASM rebalance, which is not included in the estimates below.

Rolling:

- Each database server takes 90 minutes on average.
- Each storage server takes 60 minutes on average.
- Each InfiniBand or RoCE fabric switches take 30 minutes on average.
- The approximate total time for infrastructure maintenance is as follows:
 - * Base and Quarter Rack (2 Database Servers/3 Storage Servers):
 Approximately 7 hours
 - 2 Database Servers X 90 = 180 minutes
 - 3 Storage Servers X 60 = 180 minutes
 - 2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes
 - * Half Rack (4 Database Servers/6 Storage Servers): Approximately 13 hours
 - 4 Database Servers X 90 = 360 minutes
 - 6 Storage Servers X 60 = 360 minutes
 - 2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes
 - * Full Rack (8 Database Servers/12 Storage Servers): Approximately 26 hours
 - 8 Database Servers X 90 = 720 minutes
 - 12 Storage Servers X 60 = 720 minutes
 - 2 InfiniBand or RoCE Fabric Switch X 30 = 60 minutes

Non-Rolling:

- All database servers take 180 minutes on average.
- All storage servers take 60 minutes on average.
- Storage Servers and Database servers are brought back online prior to starting fabric switch maintenance.



- Network fabric switches are still updated in a rolling method and take 30 minutes each on average.
- The approximate total time for infrastructure maintenance is 5 hours regardless of shape:
 - * All Database Servers = 180 minutes
 - * All Storage Servers = 60 minutes
 - * 2 InfiniBand or RoCE Fabric Switch = 60 minutes

Related Topics

- Achieving Continuous Availability For Your Applications
- Maximum Availability Architecture (MAA) Best Practices

Infrastructure Maintenance Contacts

Maintenance contacts are required for service request based communications for hardware replacement and other maintenance events.

Add a primary maintenance contact and optionally add a maximum of nine secondary contacts. Both the primary and secondary contacts receive all notifications about hardware replacement, network issues, and software maintenance runs.

You can promote any secondary contacts as the primary anytime you want. When you promote a secondary contact to primary, the current primary contact will be demoted automatically to secondary.

For more information, see: Using the Console to Create Infrastructure and Managing Infrastructure Maintenance Contacts.

Related Topics

- Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure
 - To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.
- Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.

Using the Console to Configure Oracle-Managed Infrastructure Updates

Exadata Cloud Service updates are released on a quarterly basis. You can set a maintenance window to determine the time your quarterly infrastructure maintenance will begin.

You can also edit the maintenance method, enable custom action, view the scheduled maintenance runs and the maintenance history of your Exadata Cloud@Customer in the Oracle Cloud Infrastructure Console. For more information, see the following:

 View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure



- View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure
- View the Maintenance History of Exadata Cloud@Customer Infrastructure
- View and Edit Maintenance While Maintenance is In Progress or Waiting for Custom Action

In exceptional cases, Oracle might need to update your system apart from the regular quarterly updates to apply time-sensitive changes such as security updates. While you cannot opt-out of these infrastructure updates, Oracle alerts you in advance through the Cloud Notification Portal to help you plan for them.

- View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure
 - To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.
- View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure Learn how to view and edit the time of the next scheduled maintenance.
- View the Maintenance History of Exadata Cloud@Customer Infrastructure
 Learn how to view the maintenance history for an Exadata Cloud@Customer
 Infrastructure.
- View and Edit Maintenance While Maintenance is In Progress or Waiting for Custom Action

While maintenance is in progress, you can enable or disable custom action and change the custom action timeout. While maintenance is waiting for custom action, you can resume the maintenance prior to the timeout or extend the timeout.

Related Topics

 View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.

View or Edit Infrastructure Maintenance Preferences for Exadata Cloud@Customer Infrastructure

To edit your Oracle Exadata Database Service on Cloud@Customer infrastructure maintenance preferences, be prepared to provide values for the infrastructure configuration. The changes you make will only apply to future maintenance runs, not those already scheduled.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and the compartment where the Oracle Exadata infrastructure you want to edit is located.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that you want to edit.
 The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.



Click Edit Maintenance Preferences.
 Edit Maintenance Preferences page is displayed.

Note:

Changes made to maintenance preferences apply only to future maintenance, not the maintenance that has already been scheduled. To modify scheduled maintenance, see *View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure*.

- **6.** On the Edit Maintenance Preferences page, configure the following:
 - Choose a maintenance method:
 - Rolling: By default, Exadata Infrastructure is updated in a rolling fashion, one server at a time with no downtime.
 - Non-rolling: Update database and storage servers at the same time. The non-rolling maintenance method minimizes maintenance time but incurs full system downtime.
 - Enable custom action before performing maintenance on DB servers: Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers. The maintenance run, while waiting for the custom action, may also be resumed prior to the timeout.
 - Custom action timeout (in minutes): Timeout available to perform custom action before starting maintenance on the DB Servers.

Default: 30 minutes

Maximum: 120 minutes

Maintenance schedule:

- No preference: The system assigns a date and start time for infrastructure maintenance.
- Specify a schedule: Choose your preferred month, week, weekday, start time, and lead time for infrastructure maintenance.
 - * Under Maintenance months, specify at least one month for each quarter during which Exadata infrastructure maintenance will take place. You can select more than one month per quarter. If you specify a long lead time for advanced notification (for example, 4 weeks), you may wish to specify 2 or 3 months per quarter during which maintenance runs can occur. This will ensure that your maintenance updates are applied in a timely manner after accounting for your required lead time. Lead time is discussed in the following steps.
 - * Optional. **Under Week of the month**, specify which week of the month, maintenance will take place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week.



Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days. If you do not specify a week of the month, Oracle will run the maintenance update in a week to minimize disruption.

- * Optional. **Under Day of the week**, specify the day of the week on which the maintenance will occur. If you do not specify a day of the week, Oracle will run the maintenance update on a weekend day to minimize disruption.
- * Optional. **Under Start hour**, specify the hour during which the maintenance run will begin. If you do not specify a start hour, Oracle will pick the least disruptive time to run the maintenance update.
- * Under **Lead Time**, specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message. Your lead time ensures that a newly released maintenance update is scheduled to account for your required minimum period of advanced notification.
- Click Save Changes.

If you switch from rolling to non-rolling maintenance method, then Confirm Non-rolling Maintenance Method dialog is displayed.

- a. Enter the name of the infrastructure in the field provided to confirm the changes.
- b. Click Save Changes.

View or Edit a Scheduled Maintenance for Exadata Cloud@Customer Infrastructure

Learn how to view and edit the time of the next scheduled maintenance.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
- 3. Click Exadata Infrastructure.
- 4. In the list of Exadata Infrastructures, find the infrastructure you want to set the next scheduled maintenance window for and click its highlighted name.

The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.



An information block is displayed 6 hours before the start of a maintenance run, regardless of whether you've chosen rolling or non-rolling maintenance method. When the maintenance begins, it is automatically removed.

5. On the Infrastructure Details page, under **Maintenance**, click the view link in the **Next Maintenance** field.

The Exadata Infrastructure Maintenance page is displayed.

On the Exadata Infrastructure Maintenance page, scheduled maintenance details are listed.

Target DB Server Version and Target Storage Server Version: These fields display the Exadata software version to be applied by the scheduled maintenance. The version applied will be the most recent certified update for Exadata infrastructures in the cloud. If the next quarterly update is not yet certified when the maintenance is scheduled, then the



versions may show "LATEST" until the new quarterly update becomes available. Once the update becomes available the new version will be displayed.

To find information on the Database Server Exadata software version or the Storage Server Exadata software version, see My Oracle Support note Exadata Database Machine and Exadata Storage Server Supported Versions (Doc ID 888828.1).

7. To change the next scheduled maintenance settings, click Edit Maintenance Run.
On the Edit Maintenance page, do the following:

Select a maintenance method, Rolling or Non-rolling.



If you select the **Non-rolling** option, an information block appears stating that components will be updated simultaneously, resulting in full system downtime.

- Enable custom action before performing maintenance on DB servers:

 Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting maintenance across all DB servers. The maintenance run, while waiting for the custom action, may also be resumed prior to the timeout.
 - Custom action timeout (in minutes): Maximum timeout available to perform custom action before starting maintenance on the DB Servers.
 Default: 30 minutes

Maximum: 120 minutes

 To reschedule the next maintenance run, enter a date and time in the Scheduled Start time field.

The following restrictions apply:

- You can reschedule the infrastructure maintenance to a date no more than 180 days from the prior infrastructure maintenance. If a new maintenance release is announced prior to your rescheduled maintenance run, the newer release will be applied on your specified date. You can reschedule your maintenance to take place earlier than it is currently scheduled. You cannot reschedule the maintenance if the current time is within 2 hours of the scheduled maintenance start time.
- Oracle reserves certain dates each quarter for internal maintenance operations, and you cannot schedule your maintenance on these dates.
- Click Save Changes.
- 8. To view estimated maintenance time details for various components, click the **View** link is displayed in the **Total Estimated Maintenance Time** field.

The **View** link is displayed in the **Total Estimated Maintenance Time** field only if the Maintenance Method is **Rolling**.



The **Estimated Maintenance Time Details** page is displayed with details that include:

- Total Estimated Maintenance Time
- Database Servers Estimated Maintenance Time
- Storage Servers Estimated Maintenance Time
- Network Switches Estimated Maintenance Time
- Order in which components are updated. In rolling maintenance, components are updated in the sequence displayed
- To view the number of VMs that will be restarted as part of Database Server maintenance, click the Show details link.
 The VM Location dialog is displayed.
- b. In the VM Cluster Name field, you can find out what VM cluster a particular VM belongs to.
- c. Click Close.
- 9. Click Close to close the Estimated Maintenance Time Details page.

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=888828.1

View the Maintenance History of Exadata Cloud@Customer Infrastructure

Learn how to view the maintenance history for an Exadata Cloud@Customer Infrastructure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
- 3. Click Exadata Infrastructure.
- **4.** In the list of Exadata Infrastructures, find the infrastructure you want to view the maintenance history and click its highlighted name.
 - The Infrastructure Details page displays information about the selected Oracle Exadata infrastructure.
- 5. On the Infrastructure Details page, under **Maintenance**, click the **view** link in the **Next Maintenance** field.
 - The **Exadata Infrastructure Maintenance** page is displayed.
- 6. On the Exadata Infrastructure Maintenance page, click Maintenance History to see a list of past maintenance events including details on their completion state and the target database and storage server versions.
 - To find information on the Database Server Exadata software version or the Storage Server Exadata software version, see My Oracle Support note *Exadata Database Machine and Exadata Storage Server Supported Versions (Doc ID 888828.1).*

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=888828.1



View and Edit Maintenance While Maintenance is In Progress or Waiting for Custom Action

While maintenance is in progress, you can enable or disable custom action and change the custom action timeout. While maintenance is waiting for custom action, you can resume the maintenance prior to the timeout or extend the timeout.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Select **Region** and **Compartment**, and provide the region and the compartment where the Oracle Exadata infrastructure you want to edit is located.
- 3. Click Exadata Infrastructure.
- 4. Click the name of the Exadata infrastructure that you want to edit.

The **Infrastructure Details** page displays information about the selected Oracle Exadata infrastructure.



Maintenance In Progress status is displayed in the Next Maintenance field

View and Edit Maintenance While Maintenance is In Progress

- 1. Click the View link in the Next Maintenance field.
 - The **Exadata Infrastructure Maintenance** page is displayed.
- 2. Click Edit Maintenance Run.

Edit Maintenance page is displayed.



You can only make edits to the custom action configuration, not the maintenance method or scheduled start time. Enabling or disabling the custom action or modifying the custom action timeout while maintenance is in progress will apply to all database servers that have yet to be updated.

- 3. On the **Edit Maintenance** page, do the following:
 - Enable custom action before performing maintenance on DB servers:
 Enable custom action only if you want to perform additional actions outside of Oracle's purview. For maintenance configured with a rolling software update, enabling this option will force the maintenance run to wait for a custom action with a configured timeout before starting maintenance on each DB server. For maintenance configured with non-rolling software updates, the maintenance run will wait for a custom action with a configured timeout before starting



maintenance across all DB servers. The maintenance run, while waiting for the custom action, may also be resumed prior to the timeout.

 Custom action timeout (in minutes): Timeout available to perform custom action before starting maintenance on the DB Servers.
 Default: 30 minutes

Maximum: 120 minutes

4. Click Save Changes.

If you have configured the rolling maintenance method, then the **View** link is displayed in the **Total Estimated Maintenance Time** field.

Click View.

Estimated Maintenance Time Details page is displayed with details that include:

- Total Estimated Maintenance Time
- Database Servers Estimated Maintenance Time
- Storage Servers Estimated Maintenance Time
- Network Switches Estimated Maintenance Time
- Order in which components are updated. In rolling maintenance, components are updated in the sequence displayed.
- b. Click Close.

View and Edit Maintenance While Maintenance is Waiting for Custom Action

1. Click the View link in the Next Maintenance field.

Exadata Infrastructure Maintenance page is displayed.



- Editing a maintenance run is not available while waiting for custom action.
- While maintenance is waiting for custom action, an information block is displayed. The information block is removed after the maintenance resumes.
- 2. On the information block, do the following:
 - **a.** Click **Resume Maintenance Now** to resume the maintenance, proceeding to the next database server.
 - Resume Maintenance dialog is displayed. Click **Resume Maintenance Now**.
 - b. Click Extend Custom Action Timeout.

You can extend timeout multiple times within the maximum allowable time of 2 hours. If you try extending beyond the maximum limit, then the system displays the Cannot Extend Custom Action Timeout dialog indicating that the custom action timeout has already been extended to the maximum allowable 2 hours and you cannot extend it further.



Monitor Infrastructure Maintenance Using Lifecycle State Information

The lifecycle state of your Exadata Infrastructure resource enables you to monitor when the maintenance of your infrastructure resource begins and ends.

In the Oracle Cloud Infrastructure Console, you can see lifecycle state details messages on the **Exadata Infrastructure Details** page when a tooltip is displayed beside the **Status** field. You can also access these messages using the ListExadataInfrastructures API, and using tools based on the API, including SDKs and the OCI CLI.

During infrastructure maintenance operations, you can expect the following:

 If you specify a maintenance window, then patching begins at your specified start time. The infrastructure resource's lifecycle state changes from Available to Maintenance in Progress.



The prechecks are now done prior to the start of the maintenance.

- When Exadata database server maintenance starts, the infrastructure resource's lifecycle state is Maintenance in Progress, and the associated lifecycle state message is, The underlying infrastructure of this system (dbnodes) is being updated.
- When storage server maintenance starts, the infrastructure resource's lifecycle state is Maintenance in Progress, and the associated lifecycle state message is, The underlying infrastructure of this system (cell storage) is being updated and this will not impact Database availability.
- After storage server maintenance is complete, the networking switches are updated one at a time, in a rolling fashion.
- When maintenance is complete, the infrastructure resource's lifecycle state is
 Available, and the Console and API-based tools do not provide a lifecycle state message.

Related Topics

- ListExadataInfrastructures
- Software Development Kits and Command Line Interface
- Command Line Interface (CLI)

Receive Notifications about Your Infrastructure Maintenance Updates

There are two ways to receive notifications. One is through email to infrastructure maintenance contacts and the other one is to subscribe to the maintenance events and get notified.

Oracle schedules maintenance run of your infrastructure based on your scheduling preferences and sends email notifications to all your infrastructure maintenance contacts. You can login to the console and view details of the schedule maintenance run. Appropriate maintenance related events will be generated as Oracle prepares for your scheduled maintenance run, for example, precheck, patching started, patching



end, and so on. For more information about all maintenance related events, see *Oracle Exadata Cloud@Customer Events*. In case, if there are any failures, then Oracle reschedules your maintenance run, generates related notification, and notifies your infrastructure maintenance contacts.

For more information about Oracle Cloud Infrastructure Events, see *Overview of Events*. To receive additional notifications other than the ones sent to infrastructure maintenance contacts, you can subscribe to infrastructure maintenance events and get notified using the Oracle Notification service, see *Notifications Overview*.

Related Topics

- Oracle Exadata Database Service on Cloud@Customer Events
 Exadata Cloud@Customer resources emit events, which are structured messages that indicate changes in resources.
- Overview of Events
- Notifications Overview
- Managing Infrastructure Maintenance Contacts
 Learn to manage your Exadata infrastructure maintenance contacts.

Using the API to Manage Exadata Cloud@Customer Infrastructure Maintenance Controls

Oracle Exadata Cloud@Customer uses the same API as Oracle Cloud Infrastructure to manage infrastructure maintenance controls.

For information about using the API and signing requests, see REST APIs and Security Credentials. For information about SDKs, see Software Development Kits and Command Line Interface.

Use these API operations to manage infrastructure maintenance controls:

- CreateExadataInfrastructure
- GetExadataInfrastructure
- ListExadataInfrastructures
- UpdateExadataInfrastructure
- UpdateMaintenanceRun
- GetMaintenanceRun
- ListMaintenanceRuns

Manage VM Cluster Networks

Learn how to use the console to create, edit, download a configuration file, validate, and terminate your infrastructure network.

 About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer

The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.



- Using the Console to Create a VM Cluster Network
 To create your VM cluster network with the Console, be prepared to provide values
 for the fields required for configuring the infrastructure.
- Using the Console to View SCAN Listener Port Configured
 You can only edit a VM cluster network that is not associated with a VM cluster.
- Using the Console to Edit a VM Cluster Network
 You can only edit a VM cluster network that is not associated with a VM cluster.
- Using the Console to Download a File Containing the VM Cluster Network Configuration Details
 To provide VM cluster network information to your network administrator, you can
- Using the Console to Validate a VM Cluster Network
 You can only validate a VM cluster network if its current state is Requires
 Validation, and if the underlying Exadata infrastructure is activated.

download and supply a file containing the network configuration.

- Using the Console to Download Network Validation Report
 Learn to validate and inspect the network validation failure report without active
 involvement from Oracle Cloud Ops in troubleshooting networking configuration
 issues.
- Using the Console to Terminate a VM Cluster Network
 Before you can terminate a VM cluster network, you must first terminate the
 associated VM cluster, if one exists, and all the databases it contains.

About Managing VM Cluster Networks on Exadata Database Service on Cloud@Customer

The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.

Before you can create any databases on your Exadata Cloud@Customer infrastructure, you must create a VM cluster network, and you must associate it with a VM cluster.

The VM cluster network specifies network resources, such as IP addresses and host names, that reside in your corporate data center and are allocated to Exadata Cloud@Customer. The VM cluster network includes definitions for the Exadata client network and the Exadata backup network. The client network and backup network contain the network interfaces that you use to connect to the VM cluster virtual machines, and ultimately the databases that reside on those virtual machines.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.



Using the Console to Create a VM Cluster Network

To create your VM cluster network with the Console, be prepared to provide values for the fields required for configuring the infrastructure.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Exadata infrastructure for which you want to create a VM cluster network.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure for which you want to create a VM cluster network.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

- Click Create VM Cluster Network.
- 6. Provide the requested information in the Data Center Network Details page:
 - a. Provide the display name.

The display name is a user-friendly name that you can use to identify the VM cluster network. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the VM cluster network.

b. Provide client network details.

The client network is the primary channel for application connectivity to Exadata Database Service on Cloud@Customer resources. The following settings define the required network parameters:

 VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the client network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

 CIDR Block: Using CIDR notation, provide the IP address range for the client network.

The following table specifies the maximum and recommended CIDR block prefix lengths for each Exadata system shape. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network.

Exadata System Shape	Base System, Quarter Rack, or Half Rack	Full Rack
Maximum CIDR block prefix length	/28	/27



Exadata System Shape	Base System, Quarter Rack, or Half Rack	Full Rack
Recommended CIDR block prefix length	/27	/26

- Netmask: Specify the IP netmask for the client network.
- Gateway: Specify the IP address of the client network gateway.
- Hostname Prefix: Specify the prefix that is used to generate the hostnames in the client network.
- Domain Name: Specify the domain name for the client network.
- c. Provide backup network details.

The backup network is the secondary channel for connectivity to Exadata Database Service on Cloud@Customer resources. It is typically used to segregate application connections on the client network from other network traffic. The following settings define the required network parameters:

• VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the backup network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved, and cannot be entered.

• **CIDR Block:** Using CIDR notation, provide the IP address range for the backup network.

The following table specifies the maximum and recommended CIDR block prefix lengths for each Exadata system shape. The maximum CIDR block prefix length defines the smallest block of IP addresses that are required for the network. To allow for possible future expansion within Exadata Database Service on Cloud@Customer, a smaller CIDR block prefix length is recommended, which reserves more IP addresses for the network.

Exadata System Shape	Base System, Quarter Rack, or Half Rack	Full Rack
Maximum CIDR block prefix length	/29	/28
Recommended CIDR block prefix length	/28	/27

- Netmask: Specify the IP netmask for the backup network.
- Gateway: Specify the IP address of the backup network gateway.
- Hostname Prefix: Specify the prefix that is used to generate the hostnames in the backup network.
- **Domain Name:** Specify the domain name for the backup network.
- d. Provide DNS and NTP server details.



The VM cluster network requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. The following settings specify the servers that provide these services:

- DNS Servers: Provide the IP address of a DNS server that is accessible using the client network. You may specify up to three DNS servers.
- **NTP Servers:** Provide the IP address of an NTP server that is accessible using the client network. You may specify up to three NTP servers.
- e. Configure Advanced Options.

Network: (Optional) Assign a SCAN listener port (TCP/IP) in the range between 1024 and 8999. Default is 1521.

Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

7. Click Review Configuration.

The Review Configuration page displays detailed information about the VM cluster network, including the hostname and IP address allocations. These allocations are initially system-generated, and are based on your inputs to the Specify Parameters page.

- **8.** (Optional) You can choose to adjust the system-generated network definitions on the Review Configuration page.
 - a. Click Edit IP Allocation.
 - b. Use the Edit dialog to adjust the system-generated network definitions to meet your requirements.
 - c. Click Save Changes.
- 9. Click Create VM Cluster Network.

The VM Cluster Network Details page is now displayed. Initially after creation, the state of the VM cluster network is **Requires Validation**.

Related Topics

Resource Tags

Using the Console to View SCAN Listener Port Configured

You can only edit a VM cluster network that is not associated with a VM cluster.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Exadata infrastructure that is associated with the VM cluster network that you want to edit.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure for which you want to view VM cluster network details.

The Infrastructure Details page displays information about the selected Exadata infrastructure.



5. Under VM Cluster Networks, click the name of the VM Cluster Network for which you want to view details.

VM Cluster Network Details page displays SCAN Listener Port under VM Cluster Network Information.

Using the Console to Edit a VM Cluster Network

You can only edit a VM cluster network that is not associated with a VM cluster.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure that is associated with the VM cluster network that you want to edit.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

5. Click the name of the VM cluster network that you want to edit.

The VM Cluster Network Details page displays information about the selected VM cluster network.

- Click Edit VM Cluster Network.
- 7. Use the **Edit** dialog to edit the VM cluster network attributes:

a. Client Network

The client network is the primary channel for application connectivity to Exadata Database Service on Cloud@Customer resources. You can edit the following client network settings:

 VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the client network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

- Netmask: Specify the IP netmask for the client network.
- Gateway: Specify the IP address of the client network gateway.
- Hostname: Specify the hostname for each address in the client network.
- **IP Address:** Specify the IP address for each address in the client network.

b. Backup Network

The backup network is the secondary channel for connectivity to Exadata Database Service on Cloud@Customer resources. It is typically used to segregate application connections on the client network from other network traffic. You can edit the following backup network settings:



• VLAN ID: Provide a virtual LAN identifier (VLAN ID) for the backup network between 1 and 4094, inclusive. To specify no VLAN tagging, enter "1". (This is equivalent to a "NULL" VLAN ID tag value.)



The values "0" and "4095" are reserved and cannot be entered.

- **Hostname:** Specify the hostname for each address in the backup network.
- IP Address: Specify the IP address for each address in the backup network.

c. Configure DNS and NTP Servers

The VM cluster network requires access to Domain Names System (DNS) and Network Time Protocol (NTP) services. You can edit the following settings:

- DNS Servers: Provide the IP address of a DNS server that is accessible using the client network. You may specify up to three DNS servers.
- NTP Servers: Provide the IP address of an NTP server that is accessible using the client network. You may specify up to three NTP servers.

8. Click Save Changes.

After editing, the state of the VM cluster network is **Requires Validation**.

Using the Console to Download a File Containing the VM Cluster Network Configuration Details

To provide VM cluster network information to your network administrator, you can download and supply a file containing the network configuration.

Use this procedure to download a configuration file that you can supply to your network administrator. The file contains the information needed to configure your corporate DNS and other network devices to work along with Exadata Database Service on Cloud@Customer.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure that is associated with the VM cluster network that you are interested in.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

5. Click the name of the VM cluster network for which you want to download a file containing the VM cluster network configuration details.

The VM Cluster Network Details page displays information about the selected VM cluster network.

6. Click Download Network Configuration.

Your browser downloads a file containing the VM cluster network configuration details.



Using the Console to Validate a VM Cluster Network

You can only validate a VM cluster network if its current state is **Requires Validation**, and if the underlying Exadata infrastructure is activated.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure that is associated with the VM cluster network that you want to validate.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.
 - The Infrastructure Details page displays information about the selected Exadata infrastructure.
- 5. Click the name of the VM cluster network that you want to validate.
 - The VM Cluster Network Details page displays information about the selected VM cluster network.
- Click Validate VM Cluster Network.
 - Validation performs a series of automated checks on the VM cluster network. The Validate VM Cluster Network button is only available if the VM cluster network requires validation.
- 7. In the resulting dialog, click **Validate** to confirm the action.
 - After successful validation, the state of the VM cluster network changes to **Validated** and the VM cluster network is ready to use. If validation fails for any reason, examine the error message and resolve the issue before repeating validation.

Using the Console to Download Network Validation Report

Learn to validate and inspect the network validation failure report without active involvement from Oracle Cloud Ops in troubleshooting networking configuration issues.

You can download the network validation report only when the VM Cluster Network State life cycle state is Validation Failed.

You cannot download the network validation report for the following VM Cluster Network State life cycle states:

- Validated (Successful validation run does not generate a results file)
- Requires Validation
- Updating
- Allocated
- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the Exadata infrastructure that is associated with the VM cluster network that you want to validate.



3. Click Exadata Infrastructure.

Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.

The Infrastructure Details page displays information about the selected Exadata infrastructure.

5. Click the name of the VM cluster network for which you want to download a file containing the VM cluster network configuration details.

The VM Cluster Network Details page displays information about the selected VM cluster network.

6. Click Download Report.

Example 5-2 Validation Report

```
{
   "Physical Links":[
      "Issue detected with Physical Links. Please check the cables connected
to ExaCC, or contact Oracle Support."
   ],
   "VLAN":
      "Gateway <G1> is not accessible from source <ipaddr > with vlan id
<vlanId>. Please ensure vlan Id, IP address and Gateway are correct",
      "Gateway <G2> is not accessible from source <ipaddr > with vlan id
<vlanId>. Please ensure vlan Id, IP address and Gateway are correct"
   "Gateway":[
      "Gateway <G1> is not accessible from source <ipaddr > with vlan id
<vlanId>. Please ensure vlan Id, IP address and Gateway are correct",
      "Gateway <G2> is not accessible from source <ipaddr > with vlan id
<vlanId>. Please ensure vlan Id, IP address and Gateway are correct"
   ],
   "DNS":[
      "Missing reverse DNS entry(ies) <hostname> for <IP addr> in the DNS
server <dnsIP>. Please update the DNS Server with appropriate entry(ies).",
      "Missing DNS entry(ies) <IP> for <hostname> in the DNS server <dnsIP>.
Please update the DNS Server with appropriate entry(ies).",
      "Wrong reverse DNS entry(ies) <hostname> found for <IP addr> in the
DNS server <dnsIP>. Please update the DNS Server with appropriate
entry(ies).",
      "Wrong DNS entry(ies) <IP addr> found for <hostname> in the DNS server
<dnsIP>. Please update the DNS Server with appropriate entry(ies)."
   ],
   "NTP":[
      "NTP <ntpIP> is not accessible from source <domU ipaddr> with vlan id
<vlanId> using gateway <gatewayIP>. Please ensure NTP, VlanId, IP address,
Gateway are correct."
   ],
   "IP Availability":[
      "IP <IP1> is already in use. Please ensure this IP is available.",
     "IP <IP2> is already in use. Please ensure this IP is available.",
      "IP <IP3> is already in use. Please ensure this IP is available."
   1
}
```



Using the Console to Terminate a VM Cluster Network

Before you can terminate a VM cluster network, you must first terminate the associated VM cluster, if one exists, and all the databases it contains.

Terminating a VM cluster network removes it from the Cloud Control Plane.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the Exadata infrastructure that is associated with the VM cluster network that you want to terminate.
- 3. Click Exadata Infrastructure.
- Click the name of the Exadata infrastructure that is associated with the VM cluster network that you are interested in.
 - The Infrastructure Details page displays information about the selected Exadata infrastructure.
- 5. Click the name of the VM cluster network that you want to terminate.
 - The VM Cluster Network Details page displays information about the selected VM cluster network.
- 6. Click Terminate.
- In the resulting dialog, enter the name of the VM cluster network, and click Terminate VM Cluster Network to confirm the action.

Manage VM Clusters

Learn how to manage your VM clusters on Exadata Database Service on Cloud@Customer.

- About Managing VM Clusters on Exadata Database Service on Cloud@Customer
 The VM cluster provides a link between your Exadata Database Service on
 Cloud@Customer infrastructure and Oracle Databases you deploy.
- Overview of VM Cluster Node Subsetting
 VM Cluster Node Subsetting enables you to allocate a subset of database servers
 to new and existing VM clusters to enable maximum flexibility in the allocation of
 compute (CPU, memory, local storage) resources.
- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can
 scale up or scale down your VM cluster resources.
- Using the Console to Manage VM Clusters on Exadata Cloud@Customer
 Learn how to use the console to create, edit, and manage your VM Clusters on Oracle Exadata Cloud@Customer.
- Using the API to Manage Exadata Cloud@Customer VM Clusters
 Review the list of API calls to manage your Exadata Database Service on
 Cloud@Customer VM cluster networks and VM clusters.

Related Topics

Application Checklist for Continuous Service for MAA Solutions



About Managing VM Clusters on Exadata Database Service on Cloud@Customer

The VM cluster provides a link between your Exadata Database Service on Cloud@Customer infrastructure and Oracle Databases you deploy.

The VM cluster contains an installation of Oracle Clusterware, which supports databases in the cluster. In the VM cluster definition, you also specify the number of enabled CPU cores, which determines the amount of CPU resources that are available to your databases

Before you can create any databases on your Exadata Cloud@Customer infrastructure, you must create a VM cluster network, and you must associate it with a VM cluster.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Overview of VM Cluster Node Subsetting

VM Cluster Node Subsetting enables you to allocate a subset of database servers to new and existing VM clusters to enable maximum flexibility in the allocation of compute (CPU, memory, local storage) resources.

With VM Cluster Node Subsetting, you can:

- Create a smaller VM cluster to host databases that have low resource and scalability requirements or to host a smaller number of databases that require isolation from the rest of the workload.
- Expand or shrink an existing VM cluster by adding and removing nodes to ensure optimal utilization of available resources.

Consider reviewing the points below that will assist you in subsetting VM cluster nodes.

- VM Cluster Node Subsetting capability is available for new and existing VM clusters in Gen2 Exadata Cloud@Customer service.
- All VMs across a VM cluster will have the same resource allocation per VM irrespective
 of whether the VM was created during cluster provisioning or added later by extending an
 existing VM cluster.
- Any VM cluster should have a minimum of 2 VMs even with the node subsetting capability. We currently do not support clusters with a single VM.
- Each VM cluster network is pre-provisioned with IP addresses for every DB Server in the
 infrastructure. One cluster network can only be used by a single VM cluster and is
 validated to ensure the IP addresses do not overlap with other cluster networks. Adding
 or removing VMs to the cluster does not impact the pre-provisioned IP addresses
 assigned to each DB server in the associated cluster network.
- You can host a maximum of 8 VMs on X8M and above generation of DB Servers. X7 and X8 generations can only support a maximum of 6 and 5 VMs per DB Server, respectively.



- Exadata Infrastructures with X8M and above generation of DB Servers can support a maximum of 16 VM clusters across all DB Servers. X7 and X8 generation Exadata Infrastructure DB Servers can only support a maximum of 12 and 10 VM clusters, respectively.
 - Maximum number of clusters across the infrastructure depends on the resources available per DB server and is subject to the per DB Server maximum VM limit.

Related Topics

- Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to Add VMs to a Provisioned Cluster
 To add virtual machines to a provisioned cluster, use this procedure.
- Using the Console to View a List of DB Servers on an Exadata Infrastructure
 To view a list of database server hosts on an Oracle Exadata Cloud@Customer
 system, use this procedure.
- Using the Console to Remove a VM from a VM Cluster
 To remove a virtual machine from a provisioned cluster, use this procedure.

Introduction to Scale Up or Scale Down Operations

With the Multiple VMs per Exadata system (MultiVM) feature release, you can scale up or scale down your VM cluster resources.

- Scaling Up or Scaling Down the VM Cluster Resources
 You can scale up or scale down the memory, local disk size (/u02), ASM Storage,
 and CPUs.
- Calculating the Minimum Required Memory
- Calculating the ASM Storage
- Estimating How Much Local Storage You Can Provision to Your VMs
- Scaling Local Storage Down

Scaling Up or Scaling Down the VM Cluster Resources

You can scale up or scale down the memory, local disk size (/u02), ASM Storage, and CPUs.



Oracle doesn't stop billing when a VM or VM Cluster is stopped. To stop billing for a VM Cluster, lower the OCPU count to zero.

Scaling up or down of these resources requires thorough auditing of existing usage and capacity management by the customer DB administrator. Review the existing usage to avoid failures during or after a scale down operation. While scaling up, consider how much of these resources are left for the next VM cluster you are planning to create. Exadata Cloud@Customer Cloud tooling calculates the current usage of memory, local disk, and ASM storage in the VM cluster, adds headroom to it,



and arrives at a "minimum" value below which you cannot scale down, and expects that you specify the value below this minimum value.

Note:

- When creating or scaling a VM Cluster, setting the number of OCPUs to zero will shut down the VM Cluster and eliminate any billing for that VM Cluster, but the hypervisor will still reserve the minimum 2 OCPUs for each VM. These reserved OCPUs cannot be allocated to any other VMs, even though the VM to which they are allocated is shut down. The Control Plane does not account for reserved OCPUs when showing maximum available OCPU, so you should account for these reserved OCPU when performing any subsequent scaling operations to ensure the operation can acquire enough OCPUs to successfully complete the operation.
- For memory and /u02 scale up or scale down operations, if the difference between the current value and the new value is less than 2%, then no change will be made to that VM. This is because memory change involves rebooting the VM, and /u02 change involves bringing down the Oracle Grid Infrastructure stack and un-mounting /u02. Productions customers will not resize for such a small increase or decrease, and hence such requests are a no-op.
- You can scale the VM Cluster resources even if any of the DB servers in the VM Cluster are down:
 - If a DB server is down and scaling is performed, the VMs on that server will
 not be automatically scaled to the new OCPUs when the DB server and the
 VMs come back online. It's your responsibility to ensure that all the VMs in
 the cluster have the same OCPU values.
 - Even if the DB server is down, billing does not stop for the VM Cluster that has the VMs on that DB server.

Calculating the Minimum Required Memory

Cloud tooling provides <code>dbaasapi</code> to identify the minimum required memory. As <code>root</code> user, you have to run <code>dbaasapi</code> and pass a JSON file with sample content as follows. The only parameter that you need to update in the <code>input.json</code> is <code>new_mem_size</code>, which is the new memory to which you want the VM cluster to be re-sized.

```
cat input.json
{
"object": "db",
"action": "get",
"operation": "precheck_memory_resize",
"params": {
"dbname": "grid",
"new_mem_size": "30 gb",
"infofile": "/tmp/result.json"
},
"outputfile": "/tmp/info.out",
"FLAGS": ""
}
```



```
dbaasapi -i input.json

cat /tmp/result.json
{
"is_new_mem_sz_allowed" : 0,
"min_req_mem" : 167
}
```

The result indicates that 30 GB is not sufficient and the minimum required memory is 167 GB, and that is the maximum you can reshape down to. On a safer side, you must choose a value greater than 167 GB, as there could be fluctuations of that order between this calculation and the next reshape attempt.

Calculating the ASM Storage

Use the following formula to calculate the minimum required ASM storage:

- For each disk group, for example, DATA, RECO, note the total size and free size by running the asmcmd lsdg command on any Guest VM of the VM cluster.
- Calculate the used size as (Total size Free size) / 3 for each disk group. The /3 is used because the disk groups are triple mirrored.
- DATA:RECO ratio is:

80:20 if **Local Backups** option was NOT selected in the user interface.

40:60 if **Local Backups** option was selected in the user interface.

 Ensure that the new total size as given in the user interface passes the following conditions:

```
Used size for DATA * 1.15 <= (New Total size * DATA % ) 
 Used size for RECO * 1.15 <= (New Total size * RECO % )
```

Example 5-3 Calculating the ASM Storage

- 1. Run the asmcmd lsdg command in the Guest VM:
 - Without SPARSE:

```
/u01/app/19.0.0.0/grid/bin/asmcmd lsdg
ASMCMD>
State Type Rebal Sector Logical Sector Block AU
                                                  Total MB
Free MB Req mir free MB Usable file MB Offline disks
Voting files Name
MOUNTED HIGH N
                    512
                                      4096 4194304 12591936
                            512
10426224 1399104
                           3009040
                     Y
                           DATAC5/
MOUNTED HIGH N
                    512
                           512
                                      4096 4194304 3135456
3036336 348384
                           895984
                            RECOC5/
                      Ν
ASMCMD>
```



With SPARSE:

```
/u01/app/19.0.0.0/grid/bin/asmcmd lsdg
ASMCMD>
State Type Rebal Sector Logical Sector Block AU
                                                     Total MB
                          Usable file MB Offline disks
Free MB Req mir free MB
Voting files Name
MOUNTED HIGH N
                    512
                            512
                                      4096 4194304 12591936
10426224 1399104
                          3009040
                      Y
                            DATAC5/
                                       4096 4194304
MOUNTED HIGH N
                    512
                            512
                                                     3135456
3036336 348384
                          895984
                            RECOC5/
                      N
MOUNTED HIGH N
                    512
                            512
                                      4096 4194304
                                                     31354560
31354500 3483840
                          8959840
                      N
                            SPRC5/
ASMCMD>
```

Note:

The listed values of all attributes for SPARSE diskgroup (SPRC5) present the virtual size. In Exadata DB Systems and Exadata Cloud@Customer, we use the ratio of 1:10 for physicalSize:virtualSize. Hence, for all purposes of our calculation we must use 1/10th of the values displayed above in case of SPARSE for those attributes.

- 2. Used size for a disk group = (Total MB Free MB) /3
 - Without SPARSE:
 Used size for DATAC5 = (12591936 10426224) / 3 = 704.98 GB
 Used size for RECO5 = (3135456 3036336) / 3 = 32.26 GB
 - With SPARSE:
 Used size for DATAC5 = (12591936 10426224) / 3 ~= 704.98 GB
 Used size for RECO5 = (3135456 3036336) /3 ~= 32.26 GB
 Used size for SPC5 = (1/10 * (31354560 31354500)) / 3 ~= 0 GB
- 3. Storage distribution among diskgroups
 - Without SPARSE:
 DATA:RECO ratio is 80:20 in this example.
 - With SPARSE:
 DATA RECO: SPARSE ratio is 60:20:20 in this example.
- 4. New requested size should pass the following conditions:
 - Without SPARSE: (For example, 5 TB in user interface.)
 5 TB = 5120 GB; 5120 *.8 = 4096 GB; 5120 *.2 = 1024 GB
 For DATA: (704.98 * 1.15) <= 4096 GB
 For RECO: (32.36 * 1.15) <= 1024 GB
 - With SPARSE: (For example, 8 TB in the user interface.)
 8 TB = 8192 GB; 8192 *.6 = 4915 GB; 8192 *.2 = 1638 GB; 8192 *.2 = 1638 GB



For DATA: (704.98 * 1.15) <= 4915 GB For RECO: (32.36 * 1.15) <= 1638 GB

For SPR: (0 * 1.15) <= 1638 GB

Above resize will go through. If above conditions are not met by the new size, then resize will fail the precheck.

Estimating How Much Local Storage You Can Provision to Your VMs

X8-2 and X7-2 Systems

You specify how much space is provisioned from local storage to each VM. This space is mounted at location /u02, and is used primarily for Oracle Database homes. The amount of local storage available will vary with the number of virtual machines running on each physical node, as each VM requires a fixed amount of storage for the root file systems, GI homes, and diagnostic log space. Refer to the tables below to see the maximum amount of space available to provision to local storage (/u02) across all VMs.

- Total space available for VM images (X7 All Systems): 1237 GB
- Total space available for VM images (X8 All Systems): 1037 GB
- Fixed storage per VM: 137 GB

Table 5-5 Space allocated to VMs

#VMs	Fixed Storage All VMs (GB)	X8-2 Space for ALL /u02 (GB)	X7-2 Space for ALL /u02 (GB)
1	137	900	1100
2	274	763	963
3	411	626	826
4	548	489	689
5	685	352	552
6	822	N/A	415

For an X8-2, to get the max space available for the nth VM, take the number in the table above and subtract anything previously allocated for /u02 to the other VMs. So if you allocated 60 GB to VM1, 70 GB to VM2, 80 GB to VM3, 60 GB to VM4 (total 270 GB) in an X8-2, the maximum available for VM 5 would be 352 - 270 = 82 GB.

In ExaC@C Gen 2, we require a minimum of 60 GB per /u02, so with that minimum size there is a maximum of 5 VMs in X8-2 and 6 VMs in X7-2.

X8M-2 Systems

The maximum number of VMs for an X8M-2 will be 8, regardless of whether there is local disk space or other resources available.

For an X8M-2 system, the fixed consumption per VM is 160 GB.

Total space available to all VMs on an ExaC@C X8M databases node is 2500 GB. Although there is 2500 GB per database node, with a single VM, you can allocate a



maximum of 900 GB local storage. Similarly, for the second VM, there is 1800 GB local storage available given the max limit of 900 GB per VM. With the third VM, the amount of space available is 2500 - (160 Gb * 3) = 2020 GB. And so on for 4 and more VMs.

- Total space available for VM images (X8M Base System): 1237 GB
- Total space available for VM images (X8M Qtr/Half/Full Racks): 2500 GB
- Fixed storage per VM: 160 GB

Table 5-6 Space allocated to VMs

#VMs	Fixed Storage All VMs (GB)	X8M-2 Base System Space for All /u02 (GB)	X8M-2 Quarter/Half/ Full Rack Space for All /u02 (GB)
1	160	900	900*
2	320	740	1800*
3	480	580	2020
4	640	420	1860
5	800	N/A	1700
6	960	N/A	1540
7	1120	N/A	1380
8	1280	N/A	1220

*Space is limited by 900 GB max per VM

For an X8M-2, to get the max space available for the nth VM, take the number in the table above and subtract anything previously allocated for /u02 to the other VMs. So, for a quarter and larger rack, if you allocated 60 GB to VM1, 70 GB to VM2, 80 GB to VM3, 60 GB to VM4 (total 270 GB) in an X8M-2, the maximum available for VM 5 would be 1700 - 270 = 1430 GB. However, the per VM maximum is 900 GB, so that would take precedent and limits VM5 to 900 GB.

X9M-2 Systems

- Total Available for VM Images (Base System): 1077 GB
- Total Available for VM Images (Qtr/Half/Full Racks): 2243 GB
- Fixed overhead per VM: 184 GB

Table 5-7 Space allocated to VMs

#VMs	Fixed Storage All VMs (GB)	X9M-2 Base System Space All /u02 (GB)	X9M-2 Qtr/Half/Full Racks All /u02 (GB)
1	184	892	900*
2	368	708	1800*
3	552	524	1691
4	736	340	1507
5	920	N/A	1323
6	1104	N/A	1139



Table 5-7 (Cont.) Space allocated to VMs

#VMs	Fixed Storage All VMs (GB)	X9M-2 Base System Space All /u02 (GB)	X9M-2 Qtr/Half/Full Racks All /u02 (GB)
7	1288	N/A	955
8	1472	N/A	771

^{*}Space is limited by 900 GB max per VM

Scaling Local Storage Down

Scale Down Local Space Operation Guidelines

Scale down operation expects you to input local space value that you want each node to scale down to.

- Resource Limit Based On Recommended Minimums
 Scale down operation must meet 60 GB recommended minimum size requirement for local storage.
- Resource Limit Based On Current Utilization
 The scale down operation must leave 15% buffer on top of highest local space utilization across all nodes in the cluster.

The lowest local space per node allowed is higher of the above two limits.

Run ${\tt df}$ -kh command on each node to find out the node with the highest local storage.

You can also use the utility like cssh to issue the same command from all hosts in a cluster by typing it just once.

Lowest value of local storage each node can be scaled down to would be = 1.15x (highest value of local space used among all nodes).

Using the Console to Manage VM Clusters on Exadata Cloud@Customer

Learn how to use the console to create, edit, and manage your VM Clusters on Oracle Exadata Cloud@Customer.

- Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to Enable or Disable Diagnostics Notification
 You can enable or disable diagnostics collection for your Guest VMs after provisioning the VM cluster.
- Using the Console to Add VMs to a Provisioned Cluster
 To add virtual machines to a provisioned cluster, use this procedure.



- Using the Console to View a List of DB Servers on an Exadata Infrastructure
 To view a list of database server hosts on an Oracle Exadata Cloud@Customer system,
 use this procedure.
- Using the Console to Remove a VM from a VM Cluster
 To remove a virtual machine from a provisioned cluster, use this procedure.
- Using the Console to Update the License Type on a VM Cluster
 To modify licensing, be prepared to provide values for the fields required for modifying the licensing information.
- Using the Console to Add SSH Keys After Creating a VM Cluster
- Using the Console to Scale the Resources on a VM Cluster
 Starting in Exadata Database Service on Cloud@Customer Gen2, you can scale up or down multiple resources at the same time. You can also scale up or down resources one at a time.
- Using the Console to Stop, Start, or Reboot a VM Cluster Virtual Machine Use the console to stop, start, or reboot a virtual machine.
- Using the Console to Check the Status of a VM Cluster Virtual Machine Review the health status of a VM cluster virtual machine.
- Using the Console to Move a VM Cluster to Another Compartment
 To change the compartment that contains your VM cluster on Exadata Database Service on Cloud@Customer, use this procedure.
- Using the Console to Terminate a VM Cluster
 Before you can terminate a VM cluster, you must first terminate the databases that it contains.

Using the Console to Create a VM Cluster

To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.

To create a VM cluster, ensure that you have:

- Active Exadata infrastructure is available to host the VM cluster.
- A validated VM cluster network is available for the VM cluster to use.
- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- 3. Click VM Clusters.
- 4. Click Create VM Cluster.
- **5.** Provide the requested information on the Create VM Cluster page:
 - **a.** Choose a compartment: From the list of available compartments, choose the compartment that you want to contain the VM cluster.
 - b. Provide the display name: The display name is a user-friendly name that you can use to identify the VM cluster. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the VM cluster.
 - c. Select Exadata Database Service on Cloud@Customer Infrastructure: From the list, choose the Exadata infrastructure to host the VM cluster. You are not able to create a VM cluster without available and active Exadata infrastructure.



- d. Select a VM Cluster Network: From the list, choose a VM cluster network definition to use for the VM cluster. You must have an available and validated VM cluster network before you can create a VM cluster.
- **e.** Choose the Oracle Grid Infrastructure version: From the list, choose the Oracle Grid Infrastructure release that you want to install on the VM cluster.

The Oracle Grid Infrastructure release determines the Oracle Database releases that can be supported on the VM cluster. You cannot run an Oracle Database release that is later than the Oracle Grid Infrastructure software release.

f. Configure VM Cluster:

- Click **Select DB Servers** for VM placement to allocate VM resources.
- On the Select DB Servers dialog, select a minimum of two database servers for VM placement. Maximum resources available for allocation per VM are based on the number of database servers selected.

Note:

- DB Servers, which already have 8 VMs running on them are not available for selection.
- When calculating maximum local storage resources across selected DB Servers, the reserved local storage needed by the system to host a VM based on hardware generation is deducted from the DB Server with the least resources. For example, if the local storage available across selected DB servers is 823 GB for DB Server 3 and 813 GB for DB Server 4, then the minimum across selected servers is 813 GB and the maximum available for resource allocation is 813 GB 184 GB (reserved local storage for hosting VM on X8M DB servers) = 629 GB.

For more information, see *Estimating How Much Local Storage You Can Provision to Your VMs*.

- Click Save Changes.
- g. Specify the OCPU count per VM: Specify the OCPU count for each individual VM. The minimum value is 2 OCPUs per VM (for a live VM condition), unless you are specifying zero OCPUs (for a shutdown VM condition).

If you specify a value of zero, then the VM cluster virtual machines are all shut down at the end of the cluster creation process. In this case, you can later start the virtual machines by scaling the OCPU resources. See *Using the Console to Scale the Resources on a VM Cluster*.

The value for OCPU count for the whole VM Cluster will be calculated automatically based upon the per VM OCPU count you have specified and the number of physical Database Servers configured for the system. There is one VM created on each physical Database Server available.

OCPU: An Oracle Compute Unit (OCPU) provides CPU capacity equivalent of one physical core of an Intel Xeon processor with hyperthreading enabled.



Each OCPU corresponds to two hardware execution threads, known as vCPUs.

See, Oracle Platform as a Service and Infrastructure as a Service – Public Cloud Service DescriptionsMetered & Non-Metered.

- h. Requested OCPU count for the VM Cluster: Displays the total number of CPU cores allocated to the VM cluster based on the value you specified in the Specify the OCPU count per VM field. This field is not editable.
- i. Specify the memory per VM (GB): Specify the memory for each individual VM. The value must be a multiple of 1 GB and is limited by the available memory on the Exadata infrastructure.
- j. Requested memory for the VM Cluster (GB): Displays the total amount of memory allocated to the VM cluster based on the value you specified in the Specify the memory per VM (GB) field. This field is not editable.
- k. Specify the local file system size per VM (GB): Specify the local file system size for each individual VM. The value must be a multiple of 1 GB and is limited by the available size of the file system on the X8-2 and X7-2 infrastructures.

Note that the minimum size of local system storage must be 60 GB. In addition to the 60 GB, each node of the VM must have at least 137 GB free for miscellaneous VM files. Each time when you create a new VM cluster, the space remaining out of the total available space is utilized for the new VM cluster.

For more information and instructions to specify the size for each individual VM, see *Introduction to Scale Up or Scale Down Operations*.

- Reserved local storage per VM (GB): Displays the local storage size reserved internally for root file systems, Oracle Grid Infrastructure Homes, and diagnostic logs. This field is not editable.
- m. Configure the Exadata Storage: The following settings define how the Exadata storage is configured for use with the VM cluster. These settings cannot be changed after creating the VM cluster.
 - **Specify Usable Exadata Storage:** Specify the size for each individual VM. The minimum recommended size is 2 TB.
 - Allocate Storage for Exadata Snapshots: Check this option to create a sparse disk group, which is required to support Exadata snapshot functionality. Exadata snapshots enable space-efficient clones of Oracle databases that can be created and destroyed very quickly and easily.
 - Allocate Storage for Local Backups: Check this option to configure the Exadata storage to enable local database backups. If you select this option, more space is allocated to the RECO disk group to accommodate the backups. If you do not select this option, you cannot use local Exadata storage as a backup destination for any databases in the VM cluster.

Table 5-8 Storage Allocation

Storage Allocation	DATA Disk Group	RECO Disk Group	SPARSE Disk Group
Exadata Snapshots:	80%	20%	0% (The SPARSE disk group is not created.)
Enable Backups on Local Exadata Storage: No			



Table 5-8 (Cont.) Storage Allocation

Storage Allocation	DATA Disk Group	RECO Disk Group	SPARSE Disk Group
Exadata Snapshots: No	40%	60%	0% (The SPARSE disk group is not created.)
Enable Backups on Local Exadata Storage: Yes			,
Allocate Storage for Exadata Snapshots: Yes	60%	20%	20%
Enable Backups on Local Exadata Storage: No			
Allocate Storage for Exadata Snapshots: Yes	35%	50%	15%
Enable Backups on Local Exadata Storage: Yes			

n. Add SSH Key: Specify the public key portion of an SSH key pair that you want to use to access the VM cluster virtual machines. You can upload a file containing the key, or paste the SSH key string.

To provide multiple keys, upload multiple key files or paste each key into a separate field. For pasted keys, ensure that each key is on a single, continuous line. The length of the combined keys cannot exceed 10,000 characters.

o. Choose a license type:

- Bring Your Own License (BYOL): Select this option if your organization already owns Oracle Database software licenses that you want to use on the VM cluster.
- License Included: Select this option to subscribe to Oracle Database software licenses as part of Exadata Database Service on Cloud@Customer.

p. Diagnostic Notification:

Select the **Enable** option. Enabling diagnostic notification will allow you and Oracle Support to identify, investigate, track, and resolve guest VM issues quickly and effectively. For more information, see *Overview of Database Service Events*.

q. Show Advanced Options:

 Time zone: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.



Note:

If you want to set a time zone other than UTC or the browser-detected time zone, then select the **Select another time zone** option, select a **Region** or **country**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

Tags: Optionally, you can apply tags. If you have permission to create a
resource, you also have permission to apply free-form tags to that resource. To
apply a defined tag, you must have permission to use the tag namespace. For
more information about tagging, see Resource Tags. If you are not sure if you
should apply tags, skip this option (you can apply tags later) or ask your
administrator.

6. Click Create VM Cluster.

The VM Cluster Details page is now displayed. While the creation process is running, the state of the VM cluster is **Pending**. When the VM cluster creation process completes, the state of the VM cluster changes to **Available**.

Related Topics

- Oracle Exadata Database Service on Cloud@Customer Service Description
 Learn how you can leverage the combined capabilities of Oracle Exadata and Oracle
 Cloud Infrastructure with Oracle Exadata Database Service on Cloud@Customer
- Using the Console to Scale the Resources on a VM Cluster
 Starting in Exadata Database Service on Cloud@Customer Gen2, you can scale up or
 down multiple resources at the same time. You can also scale up or down resources one
 at a time.
- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can scale up or
 scale down your VM cluster resources.
- Estimating How Much Local Storage You Can Provision to Your VMs
- Resource Tags
- Oracle PaaS/laaS Cloud Service Description documents
- Oracle Platform as a Service and Infrastructure as a Service Public Cloud Service DescriptionsMetered & Non-Metered
- Getting Started with Events
- Overview of Database Service Events

Using the Console to Enable or Disable Diagnostics Notification

You can enable or disable diagnostics collection for your Guest VMs after provisioning the VM cluster.

Enabling diagnostics collection at the VM cluster level applies the configuration to all the resources such as DB home, Database, and so on under the VM cluster.

- 1. Open the navigation menu. Under **Database**, click **Exadata Cloud at Customer**.
- 2. Choose the **Region** that contains your Exadata infrastructure.



- 3. Click VM Clusters.
- Click the name of the VM cluster you want to enable or disable diagnostic data collection.
- On the VM Cluster Details page, under General Information, enable or disable Diagnostic Notification.

Related Topics

Overview of Database Service Events

Using the Console to Add VMs to a Provisioned Cluster

To add virtual machines to a provisioned cluster, use this procedure.

Consider reviewing the points below that will assist you in adding VMs to a provisioned cluster.

- The same Guest OS Image version running on the existing provisioned VMs in the cluster is used to provision new VMs added to extend the VM cluster. However, any customizations made to the Guest OS Image on the existing VMs must be manually applied to the newly added VM.
- For VM clusters running a Guest OS Image version older than a year, you must update the Guest OS Image version before adding a VM to extend the cluster.
- Adding a VM to a cluster will not automatically extend any database which is part
 of a Data Guard configuration (either primary or standby) to the newly provisioned
 VM.
- For databases not part of a Data Guard configuration, only databases that are running on all VMs in the existing cluster will be added to the newly provisioned VM. Any database running on a subset of VMs will not extend automatically to run on the newly added VM.

When you attempt to add a VM to a VM cluster, you might encounter the error [FATAL] [INS-32156] Installer has detected that there are non-readable files in oracle home. To resolve the issue, follow the steps outlined in Adding a VM to a VM Cluster Fails before you try adding a cluster node.

 Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. Click the name of a VM cluster where you want to add virtual machines.
- 4. In the VM Cluster Details page, under **Resources**, click **Virtual Machines**, and then click **Add Virtual Machines**.
- On the Add Virtual Machines dialog, select additional DB servers on which to add the VM.
 - You cannot unselect existing DB Servers. The maximum resources available per VM get updated based on the newly added DB servers.
- 6. To view a list of DB Servers that have more than 2 VM Custers, click **Show More**.



Clicking the link opens an overlay panel to list all the VM Clusters running on a particular DB Server.

Related Topics

Adding a VM to a VM Cluster Fails

Using the Console to View a List of DB Servers on an Exadata Infrastructure

To view a list of database server hosts on an Oracle Exadata Cloud@Customer system, use this procedure.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer.
- 2. Under Infrastructure, click Exadata Infrastructure.
- 3. In the list of Exadata Infrastructures, click the display name of the infrastructure you wish to view details.
- 4. Under Resources, click DB Servers.
- In the list of DB Servers, click the name of the DB Server that you wish to view details.DB Server lists VMs from each cluster hosted on them along with resources allocated to them.

Using the Console to Remove a VM from a VM Cluster

To remove a virtual machine from a provisioned cluster, use this procedure.



Terminating a VM from a cluster requires the removal of any database which is part of a Data Guard configuration (either primary or standby) from the VM to proceed with the terminate flow. For more information on manual steps, see My Oracle Support note 2811352.1.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer.
- Choose the Region and Compartment that contains the VM cluster for which you want to scale the CPU resources.
- 3. Click VM Clusters.
- 4. Click the name of the VM cluster for which you want to remove a virtual machine.
- 5. Under Resources, click Virtual Machines.
- 6. In the list of virtual machines, click the **Actions** icon (three dots) for a virtual machine, and then click **Terminate**.
- On the Terminate Virtual Machine dialog, enter the name of the virtual machine, and then click Terminate.

VM removed from the cluster. VM Cluster Details page displays the updated resource allocation details under VM Cluster Resource Allocation.

Related Topics

https://support.oracle.com/rs?type=doc&id=2811352.1



Using the Console to Update the License Type on a VM Cluster

To modify licensing, be prepared to provide values for the fields required for modifying the licensing information.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the VM cluster for which you want to update the license type.
- 3. Click VM Clusters.
- Click the name of the VM cluster for which you want to update the license type.
 The VM Cluster Details page displays information about the selected VM cluster.
- 5. Click Update License Type.
- 6. In the dialog box, choose one of the following license types and then click **Save Changes**.
 - Bring Your Own License (BYOL): Select this option if your organization already owns Oracle Database software licenses that you want to use on the VM cluster.
 - License Included: Select this option to subscribe to Oracle Database software licenses as part of Exadata Database Service on Cloud@Customer.

Updating the license type does not change the functionality or interrupt the operation of the VM cluster.

Using the Console to Add SSH Keys After Creating a VM Cluster

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- 3. Click VM Clusters.
- 4. Click the name of the VM cluster that you want to add SSH key(s).
- In the VM Cluster Details page, click Add SSH Keys.
- 6. In the ADD SSH Keys dialog, choose any one of the methods:
 - Generate SSH key pair: Select this option if you want the Control Plane to generate public/private key pairs for you.
 Click Save Private Key and Save Public Key to download and save SSH Key pair.
 - Upload SSH key files: Select this option to upload the file that contains SSH Key pair.
 - Paste SSH keys: Select this option to paste the SSH key string.
 To provide multiple keys, click Another SSH Key. For pasted keys, ensure that each key is on a single, continuous line. The length of the combined keys cannot exceed 10,000 characters.
- 7. Click Save Changes.



Related Topics

Managing Key Pairs on Linux Instances

Using the Console to Scale the Resources on a VM Cluster

Starting in Exadata Database Service on Cloud@Customer Gen2, you can scale up or down multiple resources at the same time. You can also scale up or down resources one at a time.

Scale down resources under the following circumstances:

- Use Case 1: If you have allocated all of the resources to one VM cluster, and if you want
 to create multiple VM clusters, then there wouldn't be any resources available to allocate
 to the new clusters. Therefore, scale down the resources as needed to then create
 additional VM clusters.
- Use Case 2: If you want to allocate different resources based on the workload, then
 scale down or scale up accordingly. For example, you may want to run nightly batch jobs
 for reporting/ETL and scale down the VM once the job is over.

You can scale down the following resources in any combinations:

- OCPU
- Memory
- Local storage
- Exadata storage

Each scale down operation can take approximately 15 minutes to complete. If you run multiple scale down operations, then all the operations are performed in a series. For example, if you scale down memory and local storage from the Console, then scaling down happens one after the other. Scaling down local storage and memory takes more time than the time taken to scale down OCPU and Exadata storage.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the VM cluster for which you want to scale the CPU resources.
- 3. Click VM Clusters.
- 4. Click the name of the VM cluster for which you want to scale the CPU resources.

The VM Cluster Details page displays information about the selected VM cluster.

- Click Scale Up/Down.
- 6. In the dialog box, adjust any or all of the following:
 - OCPU Count:

The OCPU Count value must be a multiple of the number of virtual machines so that every virtual machine has the same number of CPU cores enabled.

If you set the OCPU Count to zero, then the VM cluster virtual machines are all shut down. If you change from a zero setting, then the VM cluster virtual machines are all started. Otherwise, modifying the number of enabled CPU cores is an online operation, and virtual machines are not rebooted because of this operation. See also *System Configuration*.



Note:

If you have explicitly set the CPU_COUNT database initialization parameter, that setting is not affected by modifying the number of CPU cores that are allocated to the VM cluster. Therefore, if you have enabled the Oracle Database instance caging feature, the database instance does not use extra CPU cores until you alter the CPU_COUNT setting. If CPU_COUNT is set to 0 (the default setting), then Oracle Database continuously monitors the number of CPUs reported by the operating system and uses the current count.

Memory:

Specify the memory for each individual VM. The value must be a multiple of 1 GB and is limited by the available memory on the Exadata infrastructure.

When you scale up or down the memory, the associated virtual machines are rebooted in a rolling manner one virtual machine at a time to minimize the impact on the VM cluster.

Local file system size:

Specify the size for each individual VM. The value must be a multiple of 1 GB and is limited by the available size of the file system on the Exadata infrastructure.

When you scale up or down the local file system size, the associated virtual machines are rebooted in a rolling manner one virtual machine at a time to minimize the impact on the VM cluster.

Reserved local storage per VM (GB): Displays the size reserved internally for root file systems, Oracle Grid Infrastructure Homes, and diagnostic logs.

Usable Exadata storage size:

Specify the total amount of Exadata storage that is allocated to the VM cluster. This storage is allocated evenly from all of the Exadata Storage Servers. The minimum recommended size is 2 TB.

You may reduce the Exadata storage allocation for a VM cluster. However, you must ensure that the new amount covers the existing contents, and you should also allow for anticipated data growth.



When you downsize, the new size must be at least 15% more than the currently used size.

Modifying the Exadata storage allocated to the VM cluster is an online operation. Virtual machines are not rebooted because of this operation.

7. Click Save Changes.

Related Topics

 System Configuration Options for Oracle Exadata Database Service on Cloud@Customer

To meet the needs of your enterprise, you can select from one of the four Oracle Exadata X9M-2, X8M-2, X8-2, or X7-2 System Models.



Using the Console to Stop, Start, or Reboot a VM Cluster Virtual Machine

Use the console to stop, start, or reboot a virtual machine.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that is associated with the VM cluster that contains the virtual machine that you want to stop, start, or reboot.
- Click VM Clusters.
- 4. Click the name of the VM cluster that contains the virtual machine that you want to stop, start, or reboot.

The VM Cluster Details page displays information about the selected VM cluster.

5. In the Resources list, click Virtual Machines.

The list of virtual machines is displayed.

- 6. In the list of nodes, click the **Actions** icon (three dots) for a node, and then click one of the following actions:
 - a. Start: Restarts a stopped node. After the node is restarted, the Stop action is enabled.
 - b. Stop: Shuts down the node. After the node is stopped, the Start action is enabled.
 - c. Reboot: Shuts down the node, and then restarts it.

Using the Console to Check the Status of a VM Cluster Virtual Machine

Review the health status of a VM cluster virtual machine.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that is associated with the VM cluster that contains the virtual machine that you are interested in.
- Click VM Clusters.
- 4. Click the name of the VM cluster that contains the virtual machine that you are interested in.

The VM Cluster Details page displays information about the selected VM cluster.

5. In the Resources list, click Virtual Machines.

The list of virtual machines displays. For each virtual machine in the VM cluster, the name, state, and client IP address are displayed.

6. In the node list, find the virtual machine that you are interested in and check its state.

The color of the icon and the associated text it indicates its status.

- Available: Green icon. The node is operational.
- Starting: Yellow icon. The node is starting because of a start or reboot action in the Console or API.
- Stopping: Yellow icon. The node is stopping because of a stop or reboot action in the Console or API.



- Stopped: Yellow icon. The node is stopped.
- Failed: Red icon. An error condition prevents the continued operation of the virtual machine.

Using the Console to Move a VM Cluster to Another Compartment

To change the compartment that contains your VM cluster on Exadata Database Service on Cloud@Customer, use this procedure.

When you move a VM cluster, the compartment change is also applied to the virtual machines and databases that are associated with the VM cluster. However, the compartment change does not affect any other associated resources, such as the Exadata infrastructure, which remains in its current compartment.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the VM cluster that you want to move.
- Click VM Clusters.
- Click the name of the VM cluster that you want to move.
 The VM Cluster Details page displays information about the selected VM cluster.
- Click Move Resource.
- In the resulting dialog, choose the new compartment for the VM cluster, and click Move Resource.

Using the Console to Terminate a VM Cluster

Before you can terminate a VM cluster, you must first terminate the databases that it contains.

Terminating a VM cluster removes it from the Cloud Control Plane. In the process, the virtual machines and their contents are destroyed.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the VM cluster that you want to terminate.
- Click VM Clusters.
- 4. Click the name of the VM cluster that you want to terminate.

The VM Cluster Details page displays information about the selected VM cluster.

- 5. Click Terminate.
- In the resulting dialog, enter the name of the VM cluster, and click Terminate VM Cluster to confirm the action.

Using the API to Manage Exadata Cloud@Customer VM Clusters

Review the list of API calls to manage your Exadata Database Service on Cloud@Customer VM cluster networks and VM clusters.



For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Exadata Database Service on Cloud@Customer VM cluster networks and VM clusters:

VM cluster networks:

- GenerateRecommendedVmClusterNetwork
- CreateVmClusterNetwork
- DeleteVmClusterNetwork
- GetVmClusterNetwork
- ListVmClusterNetworks
- UpdateVmClusterNetwork
- ValidateVmClusterNetwork

VM clusters:

- CreateVmCluster
- DeleteVmCluster
- GetVmCluster
- ListVmClusters
- UpdateVmCluster

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- GenerateRecommendedVmClusterNetwork
- CreateVmClusterNetwork
- DeleteVmClusterNetwork
- GetVmClusterNetwork
- ListVmClusterNetworks
- UpdateVmClusterNetwork
- ValidateVmClusterNetwork
- CreateVmCluster
- DeleteVmCluster
- GetVmCluster
- ListVmClusters
- UpdateVmCluster
- Database Service API



Manage Oracle Database Software Images

Learn about Database Software Image resource type and how you can use it to create Oracle Databases and Oracle Database Homes and to patch databases.

Database Software Images enable you to create a customized Oracle Database software configuration that includes your chosen updates (PSU, RU or RUR), and optionally, a list of one-off (or interim) patches or an Oracle Home inventory file. This reduces the time required to provision and configure your databases, and makes it easy for your organization to create an approved "gold image" for developers and database administrators.

- Creation and Storage of Database Software Images
 Database software images are resources within your tenancy that you create prior to provisioning or patching an Exadata Cloud@Customer instance, a Database Home, or a database.
- Using a Database Software Image with an Exadata Cloud@Customer System Create, save, and reuse an Oracle Database Software Image.
- Using the Console to Create a Database Software Image
 To create an Oracle Database Software Image with the console, use this procedure.
- Using the OPatch Isinventory Command to Verify the Patches Applied to an Oracle Home
 - OPatch utility enables you to apply the interim patches to Oracle Database software. You can find opatch utility in the <code>\$ORACLE HOME/Opatch</code> directory.
- Using the Console to Delete a Database Software Image
- Using the Console to View the Patch Information of a Database Software Image
 To view the Oracle Database version, update information (PSU/BP/RU level), and
 included one-off (interim) patches of a database software image, use the following
 instructions:
- Using the Console to Move Database Software Image to a Different Compartment Follow these steps to move a Database Software Image to a different compartment of your choice:
- Using the API for Managing Oracle Database Software Images
 Review the list of API calls to manage Oracle Database Software Image.

Related Topics

- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer
 - To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.
- Using the Console to Perform a Patch Operation on a Database Home Learn to apply patches on a Database Home.

Creation and Storage of Database Software Images

Database software images are resources within your tenancy that you create prior to provisioning or patching an Exadata Cloud@Customer instance, a Database Home, or a database.



There is no limit on the number of database software images you can create in your tenancy, and you can create your images with any Oracle Database software version and update supported in Oracle Cloud Infrastructure.

Database software images are automatically stored in Oracle-managed Object Storage and can be viewed and managed in the Oracle Cloud Infrastructure Console. Note that database software images incur Object Storage usage costs. Database software image are regional-level resources and can be accessed from any **availability domain** within their region.

For information on creating an image, see *Using the Console to Create a Database Software Image*.

Related Topics

- About Regions and Availability Domains
- Using the Console to Create a Database Software Image
 To create an Oracle Database Software Image with the console, use this procedure.

Using a Database Software Image with an Exadata Cloud@Customer System

Create, save, and reuse an Oracle Database Software Image.

Creating an Oracle Database Software Image enables you to:

- Create custom Database Home images based on Database Software Images, RU/RUR, and one-off patches.
- Save a custom image automatically to Object Storage as a resource.
- Use a Database Software Image to create Database Homes.
- Patch the Database Home created using the Database Software Image.
- Clone Database Software Image to another service in the Data Guard creation process.

Provisioning: After you create a database software image, you can use it to create an Oracle Database Home in an Exadata Cloud@Customer system. For more information, see *Using the Console to Create Oracle Database Home on Exadata Cloud@Customer*.

Patching: To patch a database in an Exadata Cloud@Customer system using a custom database software image, create the Database Home using the image, and then move the database to that Database Home. For more information, see *Patching an Exadata Cloud at Customer System*.

Setting up Data Guard: When creating an Oracle Data Guard association, the custom Database Software Image associated with the primary database will be used to create a Database Home for the new standby. If the Database Software Image used by the primary database is no longer available, then enable Data Guard operation will not proceed. For more information, see *Using Oracle Data Guard with Exadata Cloud@Customer*.



The Database Software Images are created and managed by the customer and they are available for use until explicitly deleted.



Related Topics

- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer
 - To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.
- Patching and Updating an Exadata Database Service on Cloud@Customer System
 - Learn how to perform patching operations on Exadata database virtual machines and Database Homes by using the Console, API, or the CLI.
- Use Oracle Data Guard with Exadata Database Service on Cloud@Customer
 Learn to configure and manage Data Guard associations in your VM cluster.

Using the Console to Create a Database Software Image

To create an Oracle Database Software Image with the console, use this procedure.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Under Resources, click Database Software Images.
- 3. Click Create Database Software Image.
- In the **Display name** field, provide a display name for your image. Avoid entering confidential information.
- 5. Choose your Compartment.
- Choose the **Database version** for your image.
- Choose the patch set update, proactive bundle patch, or release update. For information on Oracle Database patching models, see Release Update Introduction and FAQ (Doc ID 2285040.1).
- 8. Optionally, you can enter a comma-delimited list of one-off (interim) patch numbers.
- 9. Optionally, you can upload an Oracle Home inventory file from an existing Oracle Database. For more information, see *Using the OPatch Isinventory Command to Verify the Patches Applied to an Oracle Home*.
- 10. Click Show Advanced Options to add tags to your database software image. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator.
- 11. Click Create Database Software Image.

Related Topics

- Release Update Introduction and FAQ (Doc ID 2285040.1)
- Using the OPatch Isinventory Command to Verify the Patches Applied to an Oracle Home
 - OPatch utility enables you to apply the interim patches to Oracle Database software. You can find opatch utility in the \$ORACLE HOME/Opatch directory.
- Resource Tags



Using the OPatch Isinventory Command to Verify the Patches Applied to an Oracle Home

OPatch utility enables you to apply the interim patches to Oracle Database software. You can find opatch utility in the <code>\$ORACLE HOME/Opatch</code> directory.

1. Run the opatch lsinventory command to get the list of interim patches applied.

```
$ORACLE_HOME/OPatch/opatch lsinventory
Oracle Interim Patch Installer version 12.2.0.1.21
Copyright (c) 2021, Oracle Corporation. All rights reserved.

Oracle Home: /u02/app/oracle/product/19.0.0.0/dbhome_2
Central Inventory: /u01/app/oraInventory
from: /u02/app/oracle/product/19.0.0.0/dbhome_2/oraInst.loc
OPatch version: 12.2.0.1.21
OUI version: 12.2.0.7.0
Log file location: /u02/app/oracle/product/19.0.0.0/dbhome_2/cfgtoollogs/opatch/opatch2021-01-21_09-22-45AM_1.log

Lsinventory Output file location: /u02/app/oracle/product/19.0.0.0/
dbhome_2/cfgtoollogs/opatch/lsinv/lsinventory2021-01-21_09-22-45AM.txt
```

2. Use the lsinventory output file to extract the additional One Off Patches applied to a specific Oracle Home.

Using the Console to Delete a Database Software Image

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Under Resources, click Database Software Images.
- 3. In the list of database software images, find the image you want to delete and click the action icon (three dots) at the end of the row.
- Click Delete.
- Enter the Database Software Image name to confirm the deletion and click Delete Database Software Image.

Using the Console to View the Patch Information of a Database Software Image

To view the Oracle Database version, update information (PSU/BP/RU level), and included one-off (interim) patches of a database software image, use the following instructions:

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Under Resources, click Database Software Images.
- In the list of database software images, find the image you want to view and click on the display name of the image.



- **4.** On the Database Software Image Details page for your selected image, details about the image are displayed:
 - The Oracle Database version is displayed in the **General Information** section. For example: 19.0.0.0
 - The PSU/BP/RU field of the Patch Information section displays the update level for the image. For example: 19.5.0.0
 - The One-Off Patches field displays the number of one-off patches included in the image if any. The count includes all patches specified when creating the image (excluding patches listed in lsinventory). To view the included patches (if any are included), click the Copy All link and paste the list of included patches into a text editor. The copied list of patch numbers is comma-delimited and can be used to create additional Database Software Images.

Using the Console to Move Database Software Image to a Different Compartment

Follow these steps to move a Database Software Image to a different compartment of your choice:

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Under Resources, click Database Software Images.
- 3. In the list of database software images, find the image you want to delete and click the action icon (three dots) at the end of the row.
- 4. Click Move Resource.
- 5. Choose a new compartment in the **Move Resource to a Different Compartment** dialog.
- 6. Click Move Resource.

Using the API for Managing Oracle Database Software Images

Review the list of API calls to manage Oracle Database Software Image.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Database Software Images:

- CreateDatabaseSoftwareImage
- ListDatabaseSoftwareImages
- GetDatabaseSoftwareImage
- DeleteDatabaseSoftwareImage
- ChangeDatabaseSoftwareImageCompartment

For the complete list of APIs, see "Database Service API".

Related Topics

REST APIs



- Security Credentials
- Software Development Kits and Command Line Interface
- CreateDatabaseSoftwareImage
- ListDatabaseSoftwareImages
- GetDatabaseSoftwareImage
- DeleteDatabaseSoftwareImage
- ChangeDatabaseSoftwareImageCompartment
- Database Service API

Create Oracle Database Homes on an Exadata Database Service on Cloud@Customer System

Learn to create Oracle Database Homes on Exadata Database Service on Cloud@Customer.

- About Creating Oracle Database Homes on an Exadata Database Service on Cloud@Customer System
 - You can add Oracle Database homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) to an existing VM cluster by using the Oracle Cloud Infrastructure Console, the API, or the CLI.
- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer
 - To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.
- Using the API to Create Oracle Database Home on Exadata Cloud@Customer
 To create an Oracle Database home, review the list of API calls.

About Creating Oracle Database Homes on an Exadata Database Service on Cloud@Customer System

You can add Oracle Database homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) to an existing VM cluster by using the Oracle Cloud Infrastructure Console, the API, or the CLI.

A Database Home is a directory location on the Exadata database virtual machines that contains Oracle Database software binary files.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

You can also add and remove Database homes, and perform other management tasks on a Database home by using the dbaascli utility.



Related Topics

 Using the dbaascli Utility with Exadata Database Service on Cloud@Customer Learn to use the dbaascli utility on Exadata Cloud@Customer.

Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer

To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.

 Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer .

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster on which you want to create the Database Home.
- Under Resources, click Database Homes.
- 5. Click Create Database Home.
- 6. In the Create Database Home dialog, enter the following:
 - **Database Home display name**: The display name for the Database Home.
 - Database image: Determines what Oracle Database version is used for the database. You can mix database versions on the Exadata VM Cluster, but not editions. By default, the latest Oracle-published database software image is selected.

Click **Change Database Image** to use an older Oracle-published image or a custom Database Software Image that you have created in advance, then select an **Image Type**.

Oracle Provided Database Software Images: These images contain generally available versions of Oracle Database software.

Custom Database Software Images: These images are created by your organization and contain customized configurations of software updates and patches. Use the **Select a compartment** and **Select a Database version** selectors to limit the list of custom Database Software Images to a specific compartment or Oracle Database software major release version.

After choosing a software image, click **Select** to return to the Create Database Home dialog.



For the Oracle Database major version releases available in Oracle Cloud Infrastructure, images are provided for the current version plus the three most recent older versions (N through N - 3). For example, if an instance is using Oracle Database 19c, and the latest version of 19c offered is 19.8.0.0.0, images available for provisioning are for versions 19.8.0.0.0, 19.7.0.0, 19.6.0.0 and 19.5.0.0.



A Database Software Image will not be available for Database Home creation if:

- The database version of Database Software Image is out of support. For example, Database Software Images created using 11.2.0.4 will not be available for Database Home provisioning after 31-Dec-2022.
- The Exadata model should support the PSU/RU version of the Database Software Image. For example, for the 19c release, the X8M-2 model supports RU version 19.4 and greater.
- Only Database Software Images created specifically in the context of Exadata Cloud@Customer service can be used while provisioning and patching Database Homes within the Exadata Cloud@Customer service.
- The Database Software Image is not in Available state, that is, Deleted or is being Updated.

Show Advanced Options

You have the option to configure advanced options.

Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, see "Resource Tags". If you are not sure if you should apply tags, then skip this option (you can apply tags later) or ask your administrator.

Note that after Home install, patch to the latest if the latest patch is available.

7. Click Create.

When the Database Home creation is complete, the status changes from Provisioning to Available.

Related Topics

Resource Tags

Using the API to Create Oracle Database Home on Exadata Cloud@Customer

To create an Oracle Database home, review the list of API calls.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

To create Database Homes in Exadata Database Service on Cloud@Customer, use the API operation CreateDbHome.

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- CreateDbHome



Database Service API

Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems

Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.

 About Managing Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems

You can delete or view information about Oracle Database Homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) by using the Oracle Cloud Infrastructure Console, the API, or the CLI.

- Manage Database Home Using the Console
 Use the OCI console to manage the various operations needed on a Database
 Home.
- Using the API to Manage Oracle Database Home on Exadata Database Service on Cloud@Customer
 Review the list of API calls to manage Oracle Database home.
- Differences Between Managing Resources with dbaascli and the Database API Learn how Oracle Cloud@Customer automatically synchronizes dbaascli utility parameters and Database Service API properties of Oracle Database instance and Oracle Database Home.

About Managing Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems

You can delete or view information about Oracle Database Homes (referred to as **Database Homes** in Oracle Cloud Infrastructure) by using the Oracle Cloud Infrastructure Console, the API, or the CLI.

To find out how to delete or view information about Database Homes manually, See "Using the dbaascli Utility on Exadata Database Service on Cloud@Customer."



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Related Topics

 Using the dbaascli Utility with Exadata Database Service on Cloud@Customer Learn to use the dbaascli utility on Exadata Cloud@Customer.

Manage Database Home Using the Console

Use the OCI console to manage the various operations needed on a Database Home.



- Using the Console to View Information About an Oracle Database Home
 To view the configuration details of an Oracle Database home, use this procedure.
- Using the Console to Delete an Oracle Database Home
 To delete an Oracle Database home with the Console, use this procedure.

Using the Console to View Information About an Oracle Database Home

To view the configuration details of an Oracle Database home, use this procedure.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Click **Compartment**, and select your compartment.

A list of VM Clusters is displayed for the compartment you selected.

- 3. In the list of VM clusters, click the VM cluster that contains the Database Home in which you are interested.
- 4. Under Resources, click Database Homes.
- 5. In the list of Database Homes, find the Database Home you want to view, and then click the Database Home name to display details about it.

Using the Console to Delete an Oracle Database Home

To delete an Oracle Database home with the Console, use this procedure.

You cannot delete an Oracle Database home that contains databases. Before you can delete an Oracle Database home, you must first terminate the databases to empty the Database Home. You can terminate a database by using the Console.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Select Compartment, and choose the Compartment that you want to view.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster that contains the Database Home that you want to delete.
- 4. Under Resources, click Database Homes.
- 5. In the list of Database Homes, find the Database Home that you want to delete, and click thie Database Home name to display details about it.
- 6. On the Database Home Details page, click **Delete**.

Related Topics

Using the Console to Terminate a Database
 You can terminate a database and thereby remove the terminated database from the
 Cloud Control Plane.



Using the API to Manage Oracle Database Home on Exadata Database Service on Cloud@Customer

Review the list of API calls to manage Oracle Database home.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Database Homes:

- ListDbHomes
- GetDbHome
- DeleteDbHome

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- ListDbHomes
- GetDbHome
- DeleteDbHome
- Database Service API

Differences Between Managing Resources with dbaascli and the Database API

Learn how Oracle Cloud@Customer automatically synchronizes <code>dbaascli</code> utility parameters and Database Service API properties of Oracle Database instance and Oracle Database Home.

You can manage resources using host tooling such as <code>dbaascli</code> or <code>dbaasapi</code>, or tools based on the Database service API (including the Oracle Cloud Infrastructure Console, SDKs, and the API itself). For the management operations discussed in this topic, if you perform them using <code>dbaascli</code> or <code>dbaasapi</code>, then the updates are not visible in tools based on the Database Service API until the next synchronization operation, which happens every 10 minutes.

The following table lists operations that you perform using dbaascli or dbaasapi, and maps these operations to the related Database Service API parameters:

Operation	Host Tooling Parameters (dbaascli / dbaasapi)	Database Service API Parameters
Creating Database Home	name, DatabaseVersion, dbHomeLocation, createTime	displayName, dbVersion, dbHomeLocation, timeCreated



Operation	Host Tooling Parameters (dbaascli / dbaasapi)	Database Service API Parameters
Updating Database Home	DatabaseVersion, dbHomeLocation	dbVersion, dbHomeLocation
Creating Database	dbName, dbUniqueName, pdbName, characterSet, NlsCharacterSet, dbClass, createTime	dbName, dbUniqueName, pdbName, characterSet, ncharacterSet, dbType, timeCreated
Updating Database	dbHomeId, dbUniqueName, dbClass	dbHomeId, dbUniqueName, dbType

If you terminate a Database Home using the dbaascli or dbaasapi, the status of the Database Home is displayed as Terminated in the Database Service REST API based tools. If you terminate a database, the status of the database is displayed as Failed.

Manage Databases on Exadata Database Service on Cloud@Customer

- Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer
 - Review the prerequisites for creating and managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer.
- Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer
 - Learn about the versions of Oracle Database that Oracle Exadata Database Service on Cloud@Customer supports.
- About Provisioning and Configuring Oracle Databases on Oracle Exadata Database Service on Cloud@Customer
 - Learn about provisioning and configuring Oracle Database on Oracle Exadata Database Service on Cloud@Customer
- Using the Console to Manage Databases on Oracle Exadata Database Service on Cloud@Customer
 - To create or terminate a database, complete procedures using the Oracle Exadata console.
- Using the API to Manage Oracle Database Components
 Use various API features to help manage your databases on Oracle Exadata Database Service on Cloud@Customer.
- Changing the Database Passwords
 To change the SYS password, or to change the TDE wallet password, use this procedure.
- Manage Pluggable Databases on Exadata Database Service on Cloud@Customer Learn to manage pluggable databases on Exadata Cloud@Customer.



Prerequisites and Limitations for Creating and Managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer

Review the prerequisites for creating and managing Oracle Databases on Oracle Exadata Database Service on Cloud@Customer.

Before you can create and use an Oracle Database on Exadata Database Service on Cloud@Customer, you must:

- Provision Exadata Database Service on Cloud@Customer infrastructure
- Configure a VM cluster
- Create any required backup destinations

You can create one or more databases on each Oracle Exadata Database Service on Cloud@Customer system. Other than the storage and processing limits of your Oracle Exadata system, there is no maximum for the number of databases that you can create. By default, databases on Exadata Database Service on Cloud@Customer use Oracle Database Enterprise Edition - Extreme Performance. This edition provides all the features of Oracle Database Enterprise Edition, plus all of the database enterprise management packs, and all of the Enterprise Edition options, such as Oracle Database In-Memory, and Oracle Real Application Clusters (Oracle RAC). If you use your own Oracle Database licenses, then your ability to use various features is limited by your license holdings. TDE Encryption is required for all cloud databases. All new tablespaces will automatically be enabled for encryption.

Oracle Database Releases Supported by Oracle Exadata Database Service on Cloud@Customer

Learn about the versions of Oracle Database that Oracle Exadata Database Service on Cloud@Customer supports.

Exadata Database Service on Cloud@Customer supports the following Oracle Database software releases:

- Oracle Database 19c (19.0)
- Oracle Database 18c (18.0) is supported for approved customers only.
- Oracle Database 12c Release 2 (12.2) is supported for approved customers only.
- Oracle Database 12c Release 1 (12.1). Creating or updating a 12.1.0.2 database with an RU later than July 2022 requires a valid Market Driven Support (MDS) contract.
- Oracle Database 11g Release 2 (11.2). Creating or updating an 11.2.0.4 database with PSU later than April 2021 requires a valid Market Driven Support (MDS) contract.

For Oracle Database release and software support timelines, see *Release Schedule of Current Database Releases (Doc ID 742060.1)* in the My Oracle Support portal.

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=742060.1



About Provisioning and Configuring Oracle Databases on Oracle Exadata Database Service on Cloud@Customer

Learn about provisioning and configuring Oracle Database on Oracle Exadata Database Service on Cloud@Customer

Each Oracle Database is configured as follows:

- When you provision a database, you can associate it with a backup destination, and enable automatic backups.
- When a database is provisioned an archivelog maintenance job is added to the crontab
 for the database.
 - If the database is not enabled for backups, then the archivelog job will maintain FRA space by deleting Archive Redo Logs older than 24 hours.
 - If the database is enabled for backups, then the archivelog job will backup archivelogs that have not been backed up. Once an archived log is backed up, it will be purged when older than 24 hours.
- Each database is configured with Oracle Real Application Clusters (Oracle RAC) database instances running on every node in the virtual machine (VM) cluster.
- Each database is created in an Oracle home, which uses a separate set of Oracle binaries in a separate Oracle home location.
- Each database is configured with default instance parameter settings. While the defaults are reasonable for many cases, you should review the instance parameter settings to ensure that they meet your specific application needs.
 In particular, review the Oracle Database system global area (SGA) and program global area (PGA) instance parameter settings, especially if your VM cluster supports multiple databases. Also, ensure that the sum of all Oracle Database memory allocations never exceeds the available physical memory on each virtual machine.
- Each database using Oracle Database 12c Release 1 or a later release is configured as a container database (CDB). One pluggable database (PDB) is created inside the CDB. By default:
 - The first PDB is configured with a local PDB administration user account, named PDBADMIN.
 - The PDBADMIN user account is initially configured with the same administration password as the CDB SYS and SYSTEM users.
 - The PDBADMIN user account is initially configured with basic privileges assigned through two roles; CONNECT and PDB_DBA. However, for most practical administrative purposes you must assign extra privileges to the PDBADMIN user account, or to the PDB_DBA role.

You can use native Oracle Database facilities to create extra PDBs, and to manage all of your PDBs. The dbaascli utility also provides a range of convenient PDB management functions.



Note:

Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Using the Console to Manage Databases on Oracle Exadata Database Service on Cloud@Customer

To create or terminate a database, complete procedures using the Oracle Exadata console.

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Using the Console to Move a Database to Another Database Home Learn to move a database to another Database Home.
- Using the Console to Terminate a Database
 You can terminate a database and thereby remove the terminated database from the Cloud Control Plane.

Using the Console to Create a Database

To create an Oracle Database with the console, use this procedure.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- Click the name of a VM cluster where you want to create the database. In the VM Cluster Details page, under Resources, Databases is selected by default.
- 4. Click Create Database.

(or)

a. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.

VM Clusters is selected by default.

- **b.** Choose your **Compartment**.
 - A list of VM Clusters is displayed for the chosen Compartment.
- c. Click the name of a VM cluster where you want to create the database. In the VM Cluster Details page, under **Resources**, **Databases** is selected by default.
- d. Click Database Homes.
- e. Click the name of the Database Home where you want to create the database.
- f. Click Create Database.
- **5.** Provide the requested information in the Create Database page:



Note:

You cannot modify the db_name, db_unique_name, and SID prefix after creating the database.

 Provide the database name: Specify a user-friendly name that you can use to identify the database. The database name must contain only the permitted characters.

Review the following guidelines when selecting a database name.

- maximum of 8 characters
- contain only alphanumeric characters
- begin with an alphabetic character
- cannot be part of first 8 characters of a db unique name on the VM cluster
- unique across all VM clusters on the same Exadata Infrastructure
- DO NOT use grid because grid is a reserved name
- DO NOT use ASM because ASM is a reserved name
- **Provide a unique name for the database**: Optionally, specify a unique name for the database. This attribute defines the value of the db_unique_name database parameter. The value is case insensitive.

The db_unique_name must contain only the permitted characters. Review the following guidelines when selecting a database name.

- maximum of 30 characters
- can contain alphanumeric and underscore (_) characters
- begin with an alphabetic character
- unique across the fleet/tenancy

If a unique name is not provided, then the db_unique_name defaults to the following format <db name> <3 char unique string> <region-name>.

If you plan to configure the database for backup to a Recovery Appliance backup destination, then the unique database name must match the name that is configured in the Recovery Appliance.

- **Select a database version**: From the list, choose the Oracle Database software release that you want to deploy.
- Database Home: Select an existing Database Home or create one as applicable.
 Note that this field is not available when you create a Database from the Database Home details page.
 - Select an existing Database Home: If one or more Database Homes already exist for the database version you have selected, then this option is selected by default. And, you will be presented with a list of Database Homes. Select a Database Home from the list.
 - Create a new Database Home: If no Database Homes exist for the database version you have selected, then this option is selected by default.
 - a. Enter Database Home display name.



- b. Click Change Database Image to select your software version. Select a Database Software Image window is displayed.
- c. Select an Image Type, Oracle Provided Database Software Images, or Custom Database Software Images. If you choose Oracle Provided Database Software Images, then you can use the Display all available version switch to choose from all available PSUs and RUs. The most recent release for each major version is indicated with a latest label.

Note:

For the Oracle Database major version releases available in Oracle Cloud Infrastructure, images are provided for the current version plus the three most recent older versions (N through N - 3). For example, if an instance is using Oracle Database 19c, and the latest version of 19c offered is 19.8.0.0.0, images available for provisioning are for versions 19.8.0.0.0, 19.7.0.0, 19.6.0.0 and 19.5.0.0.

 Provide the name of the first PDB: (Optional) Specify the name for the first PDB. A PDB is created with the database.

To avoid potential service name collisions when using Oracle Net Services to connect to the PDB, ensure that the PDB name is unique across the entire VM cluster. If you do not provide the name of the first PDB, then a system-generated name is used.

- **Provide the administration password**: Provide and confirm the Oracle Database administration password. This password is used for administration accounts and functions in the database, including:
 - The password for the Oracle Database SYS and SYSTEM users.
 - The Transparent Data Encryption (TDE) Keystore password.

For Oracle Database 12c Release 1 or later releases, the password for the PDB administration user in the first PDB (PDBADMIN) must be nine to 30 characters and contain at least two uppercase, two lowercase, two numeric, and two special characters. The special characters must be _, #, or -. In addition, the password must not contain the name of the tenancy or any reserved words, such as Oracle or Table, regardless of casing.

- Use the administrator password for the TDE wallet: When this option
 is checked, the password entered for the SYS user is also used for the
 TDE wallet. To set the TDE wallet password manually, uncheck this option
 and enter the TDE wallet password.
- Choose the database workload type: Select the workload type that best suits your application from one of the following options:
 - Transactional Processing: Select this option to configure the database for a transactional workload, with a bias toward high volumes of random data access.
 - Data Warehouse: Select this option to configure the database for decision support or data warehouse workload, with a bias toward large data scanning operations.



- Backup Destination Type: Select a backup destination for the database. From the list, choose an option:
 - None: Select to not define a backup configuration for the database.
 - Local: Select to store backups locally in the Oracle Exadata Storage Servers on your Oracle Exadata Cloud at Customer system.
 This option is available only if you enabled backups on local Oracle Exadata storage in the VM cluster that you want to host the database.
 - Object Storage: Select to store backups in an Oracle-managed object storage container on Oracle Cloud Infrastructure.
 To use this option, your Oracle Exadata Cloud@Customer system must have
 - egress connectivity to Oracle Cloud Infrastructure Object Storage.
 - NFS: Select to store backups in one of your previously defined backup destinations that use Network File System (NFS) storage. For more information, refer to the information about backup destinations in this publication.

If you select this option, then you must also choose from the list of NFS **Backup Destinations**.

 Recovery Appliance: Select to store backups in one of your previously defined backup destinations that use Oracle Zero Data Loss Recovery Appliance. Refer to the information about backup destination options in this document.

If you select Oracle Zero Data Loss Recovery Appliance as your backup option, then you must also:

- * Choose from the list of appliance **Backup Destinations**.
- * Choose from the **VPC User** list, which contains the list of virtual private catalog (VPC) user names that are defined in the Oracle Zero Data Loss Recovery Appliance backup destination.
- * Provide the **Password** for the VPC user.

Note:

If you select a backup destination, then you cannot change a backup location after the database is created. However, if you select **None** now, then you can select a backup destination after the database is created.

 Enable automatic backups: Select this option to enable daily backups using the policy for automatic backups.

This option is only enabled when you select a **Backup Destination Type** other than **None**. You can change this setting after database creation.

- (Optional) Select **Show Advanced Options**. From this window, you can select the following options:
 - Provide the Oracle SID prefix:



Entering a SID prefix is only available for 12.1 databases and above.



Optionally, specify the Oracle SID prefix for the database. The instance number is automatically appended to the SID prefix to become the <code>instance_name</code> database parameter. If not provided, then the SID prefix defaults to the <code>db name</code>.

Review the following guidelines when selecting a database name:

- maximum of 12 characters
- contain only alphanumeric characters
- begin with an alphabetic character
- * unique in the VM cluster
- Backup retention period: From the list, you can choose the length of time that you want automatic backups to be retained.

For backups to local Exadata storage, you can choose a retention period of 7 days or 14 days. The default retention period is 7 days.

For backups to Oracle Cloud Infrastructure Object Storage, or to an NFS backup destination, you can choose one of the following preset retention periods: 7 days, 14 days, 30 days, 45 days, or 60 days. The default retention period is 30 days.

This option does not apply to Oracle Zero Data Loss Recovery Appliance backup destinations. For backups to Oracle Zero Data Loss Recovery Appliance, the retention policy that is implemented in the appliance controls the retention period.

- Character set: The character set for the database. The default is AL32UTF8.
- National character set: The national character set for the database. The default is AL16UTF16.
- Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later), or ask your administrator.
- 6. Click Create Database.

Related Topics

- Resource Tags
- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer

Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

Using the Console to Move a Database to Another Database Home

Learn to move a database to another Database Home.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



VM Clusters is selected by default.

- Choose your Compartment that contains the VM cluster that hosts the database that you want to move.
- 3. Click the name of the VM cluster that contains the database that you want to move.
- 4. In the Resources list of the VM Cluster Details page, click **Databases**.
- 5. Click the name of the database that you want to move.

The Database Details page displays information about the selected database.

- 6. Click Move Database.
- 7. In the resulting dialog, select the target Database Home.



Oracle recommends using Database Homes, which are running the latest (N) to 3 versions from the latest (N-3) RU versions when updating the software version of the database by moving them to a target DB Home. Only DB Homes provisioned with database versions, which meet this best practice criterion are available as target homes to move your database.

8. Click Move Database.

The database will be stopped in the current home and then restarted in the destination home. While the database is being moved, the Database Home status displays as **Moving Database**. When the operation completes, Database Home is updated with the current home. If the operation is unsuccessful, the status of the database displays as **Failed**, and the Database Home field provides information about the reason for the failure.

Using the Console to Terminate a Database

You can terminate a database and thereby remove the terminated database from the Cloud Control Plane.

Terminating a database removes it from the Cloud Control Plane. In the process, all of the associated data files and backups are destroyed.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

- Choose your Compartment that contains the VM cluster that hosts the database that you want to terminate.
- 3. Click the name of the VM cluster that contains the database that you want to terminate.
- 4. In the Resources list of the VM Cluster Details page, click **Databases**.
- 5. Click the name of the database that you want to terminate.

The Database Details page displays information about the selected database.

- 6. Click Terminate.
- 7. In the resulting dialog, enter the name of the database, and then click **Terminate Database** to confirm the action.



Using the API to Manage Oracle Database Components

Use various API features to help manage your databases on Oracle Exadata Database Service on Cloud@Customer.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use the following API operations to manage various database components.

Database homes:

- CreateDbHome
- DeleteDbHome
- GetDbHome
- ListDbHomes

Databases:

- CreateDatabase
- GetDatabase
- ListDatabases
- UpdateDatabase
- UpdateDatabaseDetails

Nodes:

- GetDbNode
- List DbNodes

Use UpdateDatabase to move a database to a different Database Home, thereby updating the database to the same version as the target Database Home.

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- CreateDbHome
- DeleteDbHome
- GetDbHome
- ListDbHomes
- CreateDatabase
- GetDatabase
- ListDatabases
- UpdateDatabase



- UpdateDatabaseDetails
- GetDbNode
- List DbNodes
- Database Service API

Changing the Database Passwords

To change the SYS password, or to change the TDE wallet password, use this procedure.

The password that you specify in the **Database Admin Password** field when you create a new Exadata Database Service on Cloud@Customer instance or database is set as the password for the SYS, SYSTEM, TDE wallet, and PDB administrator credentials. Use the following procedures if you need to change passwords for an existing database.



if you are enabling Data Guard for a database, then the SYS password and the TDE wallet password of the primary and standby databases must all be the same.

Note:

Using the <code>dbaascli</code> to change the SYS password will ensure the backup/restore automation can parallelize channels across all nodes in the cluster.

To Change the SYS Password for an Exadata Database Service on Cloud@Customer Database

- 1. Log onto the Exadata Database Service on Cloud@Customer virtual machine as opc.
- 2. Run the following command:

sudo dbaascli database changepassword --dbname database name --user SYS

To Change Database Passwords in a Data Guard Environment

1. Run the following command on the primary database:

```
dbaascli database changePassword -dbName <dbname> --user SYS -- prepareStandbyBlob true --blobLocation <location to create the blob file>
```

- Copy the blob file created to all the standby databases and update the file ownership to oracle user.
- 3. Run the following command on all the standby databases:

dbaascli database changePassword -dbName <dbname> --user SYS --standbyBlobFromPrimary <location of copies the blob file>



To Change the TDE Wallet Password for an Exadata Database Service on Cloud@Customer Database

- Log onto the Exadata Database Service on Cloud@Customer virtual machine as opc.
- 2. Run the following command:

sudo dbaascli tde changepassword --dbname database name

Manage Pluggable Databases on Exadata Database Service on Cloud@Customer

Learn to manage pluggable databases on Exadata Cloud@Customer.

Pluggable Database Operations
 You can create and manage pluggable databases (PDBs) in Oracle Exadata
 Cloud@Customer systems using the Console and APIs.

Pluggable Database Operations

You can create and manage pluggable databases (PDBs) in Oracle Exadata Cloud@Customer systems using the Console and APIs.

In this documentation, "database" refers to a container database, also called a CDB. For more information on these resource types, see *Multitenant Architecture in the Oracle Database documentation*.

Oracle 19c or later databases created in a virtual machine include an initial PDB that you can access from the CDB's **Database Details** page in the Console. Using the Console or APIs, you can start, stop, clone, and delete the PDB. You can also create additional PDBs in the container database. You can monitor all PDB operations performed using the Console or APIs using the *work request* generated by the operation.

- Limitations for Pluggable Database Management Review the list of limitations in managing PDBs.
- Create a Pluggable Database
 You can create a PDB from the OCI Console, or with the pluggable database APIs.
- Manage a Pluggable Database
 To start, stop, clone, and delete a PDB, use these procedures.

Related Topics

- Multitenant Architecture
- Work Requests

Limitations for Pluggable Database Management

Review the list of limitations in managing PDBs.



- Oracle recommends using the Console or API-based tools (including the OCI CLI, SDKs, and Terraform) to create and manage PDBs. However, there would be periodic sync of the PDBs created through DBAASCLI and SQL*Plus.
- PDB management using the OCI Console and API is available only for Oracle Database versions 19c and later.
- PDBs are backed up at the CDB level, and each backup includes all the PDBs in the
 database. OCI Control Plane does not support the creation of backups for individual
 PDBs. However, bkup_api supports PDB backup operations. For more information, see
 Configuring and Customizing Backups with bkup_api.
 Examples:
 - List backups:

```
/var/opt/oracle/bkup api/bkup api list --dbname psarch
```

Create initial PDB backup manually:

```
/var/opt/oracle/bkup_api/bkup_api bkup_start --level1 --dbname psarch --pdb NEWPDBA
```

- Restore operations are performed at the CDB level. OCI Control Plane does not support restoring individual PDBs. However, bkup_api supports PDB restore operations.
 Examples:
 - Recover a PDB with least or no data loss possible:

```
/var/opt/oracle/bkup_api/bkup_api recover_start --latest --dbname psarch --pdb NEWPDBA
```

Recover a PDB back to a point in time:

```
/var/opt/oracle/bkup_api/bkup_api recover_start -t '17-AUG2021 21:15:00' --dbname psarch --pdb NEWPDBA
```

Recover until SCN:

```
/var/opt/oracle/bkup_api/bkup_api recover_start -scn 138935800 -pdb=NEWPDBA -uuid=fec6579e077211ec8b0a00102ee75632 -bname=psarch
```

Related Topics

• Configuring and Customizing Backups with bkup_api
In addition to the console-based automated backup option, there is a command line
backup utility, bkup_api, which can allow for further customization. If configuring backups
using bkup_api instead of the console, then do not enable backups for your database in
the console.

Create a Pluggable Database

You can create a PDB from the OCI Console, or with the pluggable database APIs.

Using the Console to Create a Pluggable Database
 To create a pluggable database with the console, use this procedure.



Using the API to Create a Pluggable Database
 Use various API features to help create your pluggable databases on Oracle Exadata Cloud@Customer.

Using the Console to Create a Pluggable Database

To create a pluggable database with the console, use this procedure.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

- Choose your Compartment.A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of cloud VM clusters, click the name of the cluster in which you want to create the PDB, and then click its name to display the database details page.
- 4. In the lower-left corner of the database details page, click **Pluggable Databases**. A list of existing PDBs in this database is displayed.
- Click Create Pluggable Database.
 The Create Pluggable Database dialog box is displayed.
- 6. In the Create Pluggable Database dialog box, enter the following:
 - Provide the name of the PDB Enter a name for the PDB. The name must begin with an alphabetic character and can contain a maximum of 30 alphanumeric characters.
 - Unlock my PDB Admin Account:
 - To enter the administrator's password, check this check box.
 - * PDB Admin Password: Enter PDB admin password. The password must contain:
 - a minimum of 9 and a maximum of 30 characters
 - * at least two uppercase characters
 - at least two lowercase characters
 - * at least two special characters. The valid special characters are underscore (_), a pound or hash sign (#), and dash (-). You can use two of the same characters or any combination of two of the same characters.
 - * at least two numeric characters (0 9)
 - * **Confirm PDB Admin Password:** Enter the same PDB Admin password in the confirmation field.
 - To skip entering the administrator's password, uncheck this check box. If you uncheck this check box, then the PDB is created but you cannot use it. To use the PDB, you must reset the administrator password.

Note:

When you create a new PDB, a local user in the PDB is created as the administrator and granted the PDB_DBA role locally to the administrator.



To reset the password:

 Connect to the container where your PDB exists using the SQL*Plus CONNECT statement.

```
SQL> show con_name;
CON_NAME
-----CDB$ROOT
```

For more information, see *Administering a CDB* and *Administering PDBs* in the *Oracle® Multitenant Administrator's Guide*.

b. Find the administrator name of your PDB:

```
SQL> select grantee from cdb_role_privs where con_id = (select
con_id from cdb_pdbs where pdb_name = '<PDB_NAME>') and
granted_role = 'PDB_DBA';
```

c. Switch into your PDB:

d. Reset the PDB administrator password:

```
SQL> alter user <PDB_Admin> identified by <PASSWORD>;
User altered.
```

- TDE Wallet password: Enter a wallet password for the CDB. This password has the same rules as the PDB Admin Password.
- Advanced Options:
 - Tags: Optionally, you can apply tags. If you have permission to create a resource, you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator.
- 7. Click Create Pluggable Database.

The system starts the creation process and opens the Work Request page for the new PDB. The Work request page shows the status of the creation process of the new PDB.

By default, the Work Request details page shows the log messages created by the system. Click **Error Messages** or **Associated Resources** to see any error messages or associated resources for the creation process, in the Resources area on the left side of the page.





The numbers at the right side of the **Log Messages**, **Error Messages**, and **Associated Resources** links indicate how many of each item exists.

Related Topics

- Administering a CDB
- Administering PDBs

Using the API to Create a Pluggable Database

Use various API features to help create your pluggable databases on Oracle Exadata Cloud@Customer.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use this API operation to create pluggable databases on Exadata Cloud@Customer systems.

CreatePluggableDatabase

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- CreatePluggableDatabase
- Database Service API

Manage a Pluggable Database

To start, stop, clone, and delete a PDB, use these procedures.

- Using the Console to Start a Pluggable Database
 The PDB must be available and stopped to use this procedure.
- Using the Console to Stop a Pluggable Database
 The PDB must be available and running (started) to use this procedure.
- Using the Console to Delete a Pluggable Database
 The PDB must be available and stopped to use this procedure.
- Using the Console to Get Connection Strings for a Pluggable Database
 Learn how to get connection strings for the administrative service of a PDB. Oracle
 recommends connecting applications to an application service using the strings
 created for the application service.
- Using the API to Manage Pluggable Databases
 Use various API features to help manage your pluggable databases on Oracle Exadata Cloud@Customer.



Using the Console to Clone a PDB

You can create clones of your PDBs within the same database (CDB). This operation is known as local cloning. You can also clone a PDB to a different CDB. This operation is known as remote cloning.

Using the API to Clone a Pluggable Database

Clone a pluggable database (PDB) in the same database (CDB) as the source PDB or to a different database from the source PDB.

Using the Console to Start a Pluggable Database

The PDB must be available and stopped to use this procedure.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the name of the VM cluster that contains the PDB you want to start, and then click its name to display the details page.
- 4. Under **Databases**, find the database containing the PDB you want to start.
- 5. Click the name of the database to view the Database Details page.
- Click Pluggable Databases in the Resources section of the page.
 A list of existing PDBs in this database is displayed.
- 7. Click the name of the PDB that you want to start. The pluggable details page is displayed.
- 8. Click Start.

The Start PDB dialog box is displayed.

9. Click **Start PDB** to confirm the start operation.

Using the Console to Stop a Pluggable Database

The PDB must be available and running (started) to use this procedure.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

2. Choose your **Compartment**.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the name of the VM cluster that contains the PDB you want to stop, and then click its name to display the details page.
- 4. Under **Databases**, find the database containing the PDB you want to stop.
- 5. Click the name of the database to view the Database Details page.
- **6.** Click **Pluggable Databases** in the **Resources** section of the page.

A list of existing PDBs in this database is displayed.

- 7. Click the name of the PDB that you want to stop. The pluggable details page is displayed.
- 8. Click Stop.

The Stop PDB dialog box is displayed.



9. Click **Stop PDB** to confirm the stop operation.

Using the Console to Delete a Pluggable Database

The PDB must be available and stopped to use this procedure.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the name of the VM cluster that contains the PDB you want to delete, and then click its name to display the details page.
- 4. Under **Databases**, find the database containing the PDB you want to delete.
- 5. Click the name of the database to view the Database Details page.
- **6.** Click **Pluggable Databases** in the **Resources** section of the page. A list of existing PDBs in this database is displayed.
- 7. Click the name of the PDB that you want to delete. The pluggable details page is displayed.
- 8. Click More Actions, and then choose **Delete**. The Delete PDB dialog box is displayed.
- 9. Click **Delete PDB** to confirm the delete operation.

Using the Console to Get Connection Strings for a Pluggable Database

Learn how to get connection strings for the administrative service of a PDB. Oracle recommends connecting applications to an application service using the strings created for the application service.

 Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- In the list of VM clusters, click the name of the VM cluster that contains the PDB you want to get connections strings for, and then click its name to display the details page.
- 4. Under **Databases**, find the database containing the PDB you want to get connection strings.
- 5. Click the name of the database to view the Database Details page.
- **6.** Click **Pluggable Databases** in the **Resources** section of the page. A list of existing PDBs in this database is displayed.
- 7. Click the name of the PDB that you want to get connection strings. The pluggable details page is displayed.
- 8. Click PDB Connection.
- 9. In the Pluggable Database Connection dialog, use the **Show** and **Copy** links to display and copy connection strings, as needed.



10. Click Close to exit the dialog.

Using the API to Manage Pluggable Databases

Use various API features to help manage your pluggable databases on Oracle Exadata Cloud@Customer.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use these APIs to manage pluggable databases on Exadata Cloud@Customer systems.

- ListPluggableDatabases
- GetPluggableDatabase
- StartPluggableDatabase
- StopPluggableDatabase
- CreatePluggableDatabase
- DeletePluggableDatabase
- LocalclonePluggableDatabase
- RemoteclonePluggabledatabase

For the complete list of APIs for the Database service, see Database Service API.

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- ListPluggableDatabases
- GetPluggableDatabase
- StartPluggableDatabase
- StopPluggableDatabase
- CreatePluggableDatabase
- DeletePluggableDatabase
- LocalclonePluggableDatabase
- RemoteclonePluggabledatabase
- Database Service API

Using the Console to Clone a PDB

You can create clones of your PDBs within the same database (CDB). This operation is known as local cloning. You can also clone a PDB to a different CDB. This operation is known as remote cloning.

Restrictions for Remote Cloning



You can create a remote clone across Exadata System Shapes, VM clusters, compartments, and networks. However, you cannot create a remote clone across database versions and services.

To create a remote clone, the source, and destination databases:

- Must have identical Oracle Database software version
- Must have identical Oracle Database software edition
- Can be in different compartments
- Can be in different VM clusters
- · Can be in different networks

You can also create a remote clone using the RemoteclonePluggabledatabase API, and with API-based tools including the OCI CLI, SDKs, and Terraform.



You must have the TDE wallet password of the PDB's parent CDB to clone the PDB.

1. Open the navigation menu Under Oracle Database, and click Exadata Cloud@Customer.

VM Clusters is selected by default.

- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of VM clusters, click the name of the VM cluster that contains the PDB you want to clone, and then click its name to display the details page.
- 4. Under **Databases**, find the database containing the PDB you want to clone.
- Click Pluggable Databases in the Resources section of the page. A list of existing PDBs in this database is displayed.
- **6.** Click the name of the PDB that you want to clone. The pluggable details page is displayed.
- Click Clone.
- 8. In the Clone PDB dialog box, enter the following:
 - VM Cluster: Use the menu to select the source VM cluster.
 - Destination database: Use the menu to select an existing database where the PDB is created. This database can be the same database as the source PDB is in or a different CDB.
 - Source Database Admin password: Enter the database admin password.
 This field is disabled if the source PDB and cloned PDB are in the same CDB.
 - **New PDB name for the clone:** The name must begin with an alphabetic character and can contain up to 30 characters.
 - Database TDE wallet password: Enter the TDE wallet password for the parent CDB of the source PDB.
 - Unlock my PDB Admin Account:



- To enter the administrator's password, check this check box.
 - * PDB Admin Password: Enter PDB admin password. The password must contain:
 - a minimum of 9 and a maximum of 30 characters
 - * at least two uppercase characters
 - at least two lowercase characters
 - * at least two special characters. The valid special characters are underscore (_), a pound or hash sign (#), and dash (-). You can use two of the same characters or any combination of two of the same characters.
 - * at least two numeric characters (0 9)
 - * Confirm PDB Admin Password: Enter the same PDB Admin password in the confirmation field.
- To skip entering the administrator's password, uncheck this check box. If you uncheck this check box, then the PDB is created but you cannot use it. To use the PDB, you must reset the administrator password.



When you create a new PDB, a local user in the PDB is created as the administrator and granted the PDB $\ \ DBA$ role locally to the administrator.

To reset the password:

 Connect to the container where your PDB exists using the SQL*Plus CONNECT statement.

```
SQL> show con_name;
CON_NAME
----CDB$ROOT
```

For more information, see *Administering a CDB* and *Administering PDBs* in the *Oracle® Multitenant Administrator's Guide*.

b. Find the administrator name of your PDB:

```
SQL> select grantee from cdb_role_privs where con_id = (select
con_id from cdb_pdbs where pdb_name = '<PDB_NAME>') and
granted_role = 'PDB_DBA';
```

c. Switch into your PDB:

```
SQL> alter session set container=<PDB_NAME>;
Session altered.

SQL> show con_name;
CON_NAME
```



<PDB NAME>

d. Reset the PDB administrator password:

SQL> alter user <PDB_Admin> identified by <PASSWORD>; User altered.

9. Click Clone PDB.

Using the API to Clone a Pluggable Database

Clone a pluggable database (PDB) in the same database (CDB) as the source PDB or to a different database from the source PDB.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use these APIs to manage pluggable databases on Exadata Cloud@Customer systems.

- LocalclonePluggableDatabase
- RemoteclonePluggabledatabase

For the complete list of APIs for the Database service, see Database Service API.

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- LocalclonePluggableDatabase
- RemoteclonePluggabledatabase
- Database Service API

Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer

Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

- Backup Destinations
- Oracle Database Backup Methods in Exadata Cloud
 Oracle Exadata Cloud@Customer offers two approaches to configure and take
 backups as a recommended solution: Oracle Managed Backup and User
 Configured Backup.
- Configuring and Customizing Backups with bkup_api
 In addition to the console-based automated backup option, there is a command line backup utility, bkup_api, which can allow for further customization. If



configuring backups using $bkup_api$ instead of the console, then do not enable backups for your database in the console.

- Creating an On-Demand Backup by Using the bkup_api Utility
 You can use the bkup_api utility to create an on-demand backup of a complete
 database or an individual pluggable database (PDB):
- Disabling Automatic Backups to Facilitate Manual Backup and Recovery Management
- Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups
- Alternative Backup Methods
 Learn about alternative backup methods that are available in addition to the OCI Console.

Backup Destinations

- About Managing Backup Destinations for Exadata Database Service on Cloud@Customer
 - For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.
- Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer
 - To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.
- Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer
 - Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.
- Using the API to Manage Exadata Cloud@Customer Backup Destinations
 Review the list of API calls to manage your Exadata Database Service on
 Cloud@Customer backup destinations.

About Managing Backup Destinations for Exadata Database Service on Cloud@Customer

For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.

Exadata Database Service on Cloud@Customer provides a backup facility, which you can configure individually on each database.

See: Managing Databases on Exadata Cloud@Customer and Managing Database Backup and Recovery on Exadata Cloud@Customer.

If you want to store backups on a Recovery Appliance, or on a network file storage (NFS) location that you manage, then you must first create a backup destination. Each backup destination defines the properties that are required to connect to the Recovery Appliance or NFS location, and each backup destination must be accessible in your data center from the VM cluster nodes.

The Exadata Database Service on Cloud@Customer backup facility can also store backups on Oracle Cloud Infrastructure object storage, or on local Exadata storage on your Exadata



Database Service on Cloud@Customer system. However, you do not need to create a backup destination for any of these other locations. Instead, applicable options for backup to cloud object storage or local Exadata storage are available directly when you create a database.

Note:

Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Related Topics

- Zero Data Loss Recovery Appliance
- Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems

Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.

- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer

Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer

To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.

- For a Zero Data Loss Recovery Appliance backup destination:
 - The appliance must be configured with a virtual private catalog (VPC) user, which is used for taking the backups.
 - The appliance must be configured with the unique database name of the database being backed up, and a mapping to the VPC user.
 - The appliance must be accessible from the Exadata Database Service on Cloud@Customer system using the Oracle Net Services connection string, which is provided by the Zero Data Loss Recovery Appliance administrator.
- For an NFS backup destination:
 - Exadata Database Service on Cloud@Customer non-autonomous databases:
 - * You must mount the NFS server location to a local mount point directory on each node in the VM cluster.
 - The local mount point directory and the NFS server must be identical across all nodes in the cluster.



- * You must ensure that the NFS mount is maintained continuously on all of the VM cluster nodes.
- * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
- Exadata Database Service on Cloud@Customer Autonomous Databases:
 - * To ensure that the Autonomous VM cluster can access the NFS server over the Backup Network, enter valid Backup Network IP addresses while configuring VM Cluster Network.
 - * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
 - * If permissions are being controlled at the user level, then the uid:gid of the oracle user for the Autonomous VM cluster is 1001:1001.

Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer

Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.

- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Edit a Backup Destination
 To edit a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Move a Backup Destination to Another Compartment
 To move a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Delete a Backup Destination
 To delete a backup destination, be prepared to provide values for the backup destination configuration.

Using the Console to Create a Backup Destination

To create a backup destination, be prepared to provide values for the backup destination configuration.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- 3. Click Backup Destinations.
- 4. Click Create Backup Destination.
- 5. Provide the requested information in the Create Backup Destination page:
 - a. Choose a compartment.
 - From the list of available compartments, choose the compartment that you want to contain the backup destination.
 - b. Name your backup destination.



Specify a user-friendly name that you can use to identify the backup destination. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the backup destination.

 Choose either a Zero Data Loss Recovery Appliance or a network file system (NFS) backup destination.

Note:

You can also set OCI Object Store as a backup destination. However, you cannot set it from this screen. You can configure OCI Object Store as a backup destination when creating a database. For more information, see *Backup Destination Type* in *Using the Console to Create a Database*.

Select Recovery Appliance or Network Storage (NFS).

- If you select Recovery Appliance, then you must also specify the following for Zero Data Loss Recovery Appliance:
 - Provide the Recovery Appliance connection string: Specify the
 Oracle Net Services connection string that connects to the appliance.
 This information is typically provided by the Zero Data Loss Recovery
 Appliance administrator.
 - Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Zero Data Loss Recovery Appliance. You can specify multiple VPC user names in case you want to use the appliance as a backup destination for multiple databases. This information is typically provided by the Zero Data Loss Recovery Appliance administrator.
- If you select Network Storage (NFS), then you must also specify the following:
 - Self-mount for non-autonomous databases:

Provide the local NFS mount point path: Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local directory path and the NFS server location must each be the same across all of the VM cluster nodes.

Auto-mount for Autonomous Databases:

Use this destination for Autonomous Databases:

- * **NFS server:** Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * **NFS export share:** Specify the directory path where the exported file system is mounted.
- d. Configure Advanced Options.
 - Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply



tags, then skip this option (you can apply tags later), or ask your administrator.

6. Click Create Backup Destination.

The Backup Destination Details page displays the newly created backup destination.

Related Topics

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Resource Tags

Using the Console to Edit a Backup Destination

To edit a backup destination, be prepared to provide values for the backup destination configuration.

You can only edit a backup destination if it is not currently associated with database.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to edit.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to edit.

The Backup Destination Details page displays information about the selected backup destination.

- Click Edit.
- 6. Use the Edit Backup Destination dialog to edit the backup destination attributes:



You cannot edit a Backup Destination if there is already a database attached to it.

- If you are editing a Zero Data Loss Recovery Appliance backup destination:
 - Provide the Recovery Appliance connection string: Specify the Oracle Net Services connection string that connects to the Recovery Appliance. This information is typically provided by the Recovery Appliance administrator.
 - Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Recovery Appliance. You can specify multiple VPC user names in case you want to use the Recovery Appliance as a backup destination for multiple databases. This information is typically provided by the Recovery Appliance administrator.
- If you are editing an NFS backup destination:
 - Self-mount for non-autonomous databases:

Provide the local NFS mount point path: Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local



directory path and the NFS server location must each be the same across all of the VM cluster nodes.

Auto-mount for Autonomous Databases:

Use this destination for Autonomous Databases:

- * **NFS server:** Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * NFS export share: Specify the directory path where the exported file system is mounted.

7. Click Save Changes.

Using the Console to Move a Backup Destination to Another Compartment

To move a backup destination, be prepared to provide values for the backup destination configuration.

You can change the compartment that contains your backup destination by moving it.

When you move a backup destination, the compartment change does not affect other associated resources. These other resources, such as the associated databases, remain in their current compartment.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the backup destination that you want to move.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to move.
 - The Backup Destination Details page displays information about the selected backup destination.
- 5. Click Move Resource.
- In the resulting dialog, choose the new compartment for the backup destination and click Move Resource.

Using the Console to Delete a Backup Destination

To delete a backup destination, be prepared to provide values for the backup destination configuration.

Before you can delete a backup destination, you must ensure that it is not associated with any databases.

Deleting a backup destination:

- Does not remove any residual backups that are left in the backup destination
- Removes all references to the deleted backup destination from the Cloud Control Plane
- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the backup destination that you want to delete.



- Click Backup Destinations.
- 4. Click the name of the backup destination that you want to delete.

The Backup Destination Details page displays information about the selected backup destination.

- Click Delete.
- In the resulting dialog, enter the backup destination name and click **Delete Backup Destination** to confirm the action.

Using the API to Manage Exadata Cloud@Customer Backup Destinations

Review the list of API calls to manage your Exadata Database Service on Cloud@Customer backup destinations.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Exadata Database Service on Cloud@Customer backup destinations:

- CreateBackupDestination
- DeleteBackupDestination
- GetBackupDestination
- ListBackupDestination
- UpdateBackupDestination
- ChangeBackupDestinationCompartment

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- · Software Development Kits and Command Line Interface
- CreateBackupDestination
- DeleteBackupDestination
- GetBackupDestination
- ListBackupDestination
- UpdateBackupDestination
- ChangeBackupDestinationCompartment
- Database Service API

Oracle Database Backup Methods in Exadata Cloud

Oracle Exadata Cloud@Customer offers two approaches to configure and take backups as a recommended solution: Oracle Managed Backup and User Configured Backup.



Oracle Managed Backup

Database backups are managed entirely by the Oracle Exadata Cloud@Customer service based on a one-time configuration.

User Configured Backup

It is the user's responsibility to configure and execute backup operations using dbaascli according to their preferences.

Oracle Managed Backup

Database backups are managed entirely by the Oracle Exadata Cloud@Customer service based on a one-time configuration.

Once configured, you need not perform any maintenance such as backup scheduling and deletion of the backups. Oracle manages the backups through well-defined workflows. Certain backup configuration parameters are not fully integrated with the Oracle Managed Backup workflow. If you want to set any of those parameters for the backups, then you can use <code>dbaascli database backup -configure</code> to set them. For more information, see *Configuring Database for Backup*.

- Backup Destinations
- Automatic Backup and Recovery

Related Topics

Configuring Database for Backup

Once the backup destination is set up and available, you can use the dbaascli utility to configure the database with backup destination and associated configuration parameters, for example, Backup Retention Recovery Window, Backup Scheduling, Archivelog Scheduling, and so on.

Backup Destinations

 About Managing Backup Destinations for Exadata Database Service on Cloud@Customer

For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.

 Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer

To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.

 Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer

Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.

Using the API to Manage Exadata Cloud@Customer Backup Destinations
Review the list of API calls to manage your Exadata Database Service on
Cloud@Customer backup destinations.



About Managing Backup Destinations for Exadata Database Service on Cloud@Customer

For backups, you can either use the Exadata Database Service on Cloud@Customer backup facility, or you can configure a backup location on a location you manage.

Exadata Database Service on Cloud@Customer provides a backup facility, which you can configure individually on each database.

See: Managing Databases on Exadata Cloud@Customer and Managing Database Backup and Recovery on Exadata Cloud@Customer.

If you want to store backups on a Recovery Appliance, or on a network file storage (NFS) location that you manage, then you must first create a backup destination. Each backup destination defines the properties that are required to connect to the Recovery Appliance or NFS location, and each backup destination must be accessible in your data center from the VM cluster nodes.

The Exadata Database Service on Cloud@Customer backup facility can also store backups on Oracle Cloud Infrastructure object storage, or on local Exadata storage on your Exadata Database Service on Cloud@Customer system. However, you do not need to create a backup destination for any of these other locations. Instead, applicable options for backup to cloud object storage or local Exadata storage are available directly when you create a database.



Avoid entering confidential information when assigning descriptions, tags, or friendly names to your cloud resources through the Oracle Cloud Infrastructure Console, API, or CLI.

Related Topics

- Zero Data Loss Recovery Appliance
- Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems

Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.

- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer

Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.

Prerequisites for Backup Destinations for Exadata Database Service on Cloud@Customer

To configure backup destinations on a Zero Data Loss Recovery Appliance location, or an NFS backup location, review the prerequisites.

For a Zero Data Loss Recovery Appliance backup destination:



- The appliance must be configured with a virtual private catalog (VPC) user, which is used for taking the backups.
- The appliance must be configured with the unique database name of the database being backed up, and a mapping to the VPC user.
- The appliance must be accessible from the Exadata Database Service on Cloud@Customer system using the Oracle Net Services connection string, which is provided by the Zero Data Loss Recovery Appliance administrator.
- For an NFS backup destination:
 - Exadata Database Service on Cloud@Customer non-autonomous databases:
 - * You must mount the NFS server location to a local mount point directory on each node in the VM cluster.
 - * The local mount point directory and the NFS server must be identical across all nodes in the cluster.
 - * You must ensure that the NFS mount is maintained continuously on all of the VM cluster nodes.
 - * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
 - Exadata Database Service on Cloud@Customer Autonomous Databases:
 - To ensure that the Autonomous VM cluster can access the NFS server over the Backup Network, enter valid Backup Network IP addresses while configuring VM Cluster Network.
 - * The NFS-mounted file system must be readable and writable by the oracle operating system user on all of the VM cluster nodes.
 - * If permissions are being controlled at the user level, then the uid:gid of the oracle user for the Autonomous VM cluster is 1001:1001.

Using the Console for Backup Destinations for Exadata Database Service on Cloud@Customer

Learn how to use the console to create, edit, move, and terminate a backup destination for your infrastructure for Oracle Exadata Database Service on Cloud@Customer.

- Using the Console to Create a Backup Destination
 To create a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Edit a Backup Destination
 To edit a backup destination, be prepared to provide values for the backup destination configuration.
- Using the Console to Move a Backup Destination to Another Compartment
 To move a backup destination, be prepared to provide values for the backup
 destination configuration.
- Using the Console to Delete a Backup Destination
 To delete a backup destination, be prepared to provide values for the backup destination configuration.

Using the Console to Create a Backup Destination



To create a backup destination, be prepared to provide values for the backup destination configuration.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** that contains your Exadata infrastructure.
- 3. Click Backup Destinations.
- 4. Click Create Backup Destination.
- 5. Provide the requested information in the **Create Backup Destination** page:
 - a. Choose a compartment.
 - From the list of available compartments, choose the compartment that you want to contain the backup destination.
 - b. Name your backup destination.
 - Specify a user-friendly name that you can use to identify the backup destination. The name doesn't need to be unique because an Oracle Cloud Identifier (OCID) uniquely identifies the backup destination.
 - c. Choose either a Zero Data Loss Recovery Appliance or a network file system (NFS) backup destination.



You can also set OCI Object Store as a backup destination. However, you cannot set it from this screen. You can configure OCI Object Store as a backup destination when creating a database. For more information, see *Backup Destination Type* in *Using the Console to Create a Database*.

Select Recovery Appliance or Network Storage (NFS).

- If you select Recovery Appliance, then you must also specify the following for Zero Data Loss Recovery Appliance:
 - Provide the Recovery Appliance connection string: Specify the Oracle Net Services connection string that connects to the appliance. This information is typically provided by the Zero Data Loss Recovery Appliance administrator.
 - Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Zero Data Loss Recovery Appliance. You can specify multiple VPC user names in case you want to use the appliance as a backup destination for multiple databases. This information is typically provided by the Zero Data Loss Recovery Appliance administrator.
- If you select Network Storage (NFS), then you must also specify the following:
 - Self-mount for non-autonomous databases:
 - **Provide the local NFS mount point path:** Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local directory path and the NFS server location must each be the same across all of the VM cluster nodes.
 - Auto-mount for Autonomous Databases:



Use this destination for Autonomous Databases:

- * **NFS server:** Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * **NFS export share:** Specify the directory path where the exported file system is mounted.
- d. Configure Advanced Options.
 - Tags: (Optional) You can choose to apply tags. If you have permissions to create a resource, then you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, refer to information about resource tags. If you are not sure if you should apply tags, then skip this option (you can apply tags later), or ask your administrator.
- 6. Click Create Backup Destination.

The Backup Destination Details page displays the newly created backup destination.

Related Topics

- Using the Console to Create a Database
 To create an Oracle Database with the console, use this procedure.
- Resource Tags

Using the Console to Edit a Backup Destination

To edit a backup destination, be prepared to provide values for the backup destination configuration.

You can only edit a backup destination if it is not currently associated with database.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to edit.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to edit.

The Backup Destination Details page displays information about the selected backup destination.

- 5. Click Edit.
- 6. Use the Edit Backup Destination dialog to edit the backup destination attributes:



You cannot edit a Backup Destination if there is already a database attached to it.

• If you are editing a Zero Data Loss Recovery Appliance backup destination:



- Provide the Recovery Appliance connection string: Specify the Oracle Net Services connection string that connects to the Recovery Appliance. This information is typically provided by the Recovery Appliance administrator.
- Provide the Virtual Private Catalog (VPC) Users: Provide a VPC user name for connecting to the Recovery Appliance. You can specify multiple VPC user names in case you want to use the Recovery Appliance as a backup destination for multiple databases. This information is typically provided by the Recovery Appliance administrator.
- If you are editing an NFS backup destination:
 - Self-mount for non-autonomous databases:

Provide the local NFS mount point path: Specify the local directory path on each VM cluster node where the NFS server location is mounted. The local directory path and the NFS server location must each be the same across all of the VM cluster nodes.

Auto-mount for Autonomous Databases:

Use this destination for Autonomous Databases:

- * **NFS server:** Specify the IP address of the NFS server. Optionally, you can specify up to four IP addresses.
- * **NFS export share:** Specify the directory path where the exported file system is mounted.
- 7. Click Save Changes.

Using the Console to Move a Backup Destination to Another Compartment

To move a backup destination, be prepared to provide values for the backup destination configuration.

You can change the compartment that contains your backup destination by moving it.

When you move a backup destination, the compartment change does not affect other associated resources. These other resources, such as the associated databases, remain in their current compartment.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to move.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to move.

The Backup Destination Details page displays information about the selected backup destination.

- Click Move Resource.
- In the resulting dialog, choose the new compartment for the backup destination and click Move Resource.

Using the Console to Delete a Backup Destination

To delete a backup destination, be prepared to provide values for the backup destination configuration.

Before you can delete a backup destination, you must ensure that it is not associated with any databases.



Deleting a backup destination:

- Does not remove any residual backups that are left in the backup destination
- Removes all references to the deleted backup destination from the Cloud Control Plane
- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the backup destination that you want to delete.
- 3. Click Backup Destinations.
- 4. Click the name of the backup destination that you want to delete.

The Backup Destination Details page displays information about the selected backup destination.

- 5. Click Delete.
- 6. In the resulting dialog, enter the backup destination name and click **Delete Backup Destination** to confirm the action.

Using the API to Manage Exadata Cloud@Customer Backup Destinations

Review the list of API calls to manage your Exadata Database Service on Cloud@Customer backup destinations.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage Exadata Database Service on Cloud@Customer backup destinations:

- CreateBackupDestination
- DeleteBackupDestination
- GetBackupDestination
- ListBackupDestination
- UpdateBackupDestination
- ChangeBackupDestinationCompartment

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- CreateBackupDestination
- DeleteBackupDestination
- GetBackupDestination
- ListBackupDestination



- UpdateBackupDestination
- ChangeBackupDestinationCompartment
- Database Service API

Automatic Backup and Recovery

- About Managing Database Backup for Oracle Exadata Database Service on Cloud@Customer
 - Learn how configure backup when creating the database on Oracle Exadata Database Service on Cloud@Customer.
- Using the Console to Configure and Manage Backup and Recovery
 Learn how to use the console to view a list of available backups, edit backup settings, and restore a database for Oracle Exadata Database Service on Cloud@Customer.
- Using the API to Manage Database Backup and Recovery
 Learn how to use the API to manage database backup and recovery with Oracle Exadata
 Database Service on Cloud@Customer.

About Managing Database Backup for Oracle Exadata Database Service on Cloud@Customer

Learn how configure backup when creating the database on Oracle Exadata Database Service on Cloud@Customer.

Oracle Exadata Database Service on Cloud@Customer provides automatic database backup facilities that use Oracle Recovery Manager (RMAN). When you create a database on Oracle Exadata Database Service on Cloud@Customer, you can specify a backup destination and enable automatic backups. For more information, refer to the information in this publication about managing backup destinations for Oracle Exadata Database Service on Cloud@Customer.

After database creation, you can also:

- View a list of available backups.
- Enable or disable automatic backups.
- Edit backup settings.
- Restore a database.

You can perform these operations by using either the Console, or the API.

Automatic database backups are configured as follows:

- Automatic backups are scheduled daily. The automatic backup process can run at any time within the daily backup window, which is between midnight and 6:00 AM in the time zone of the virtual machine (VM) cluster that hosts the database.
- Automatic backups use a combination of full (RMAN level 0) and incremental (RMAN level 1) database backups:
 - For backups to a Zero Data Loss Recovery Appliance, after an initial full backup is performed, Zero Data Loss Recovery Appliance creates and validates virtual full backups from each daily incremental backup.
 - For backups to NFS, or OSS, the default interval between level 0 backups is seven days. The default level 0 day is Sunday.



For backups to Local Exadata Storage:
 The retention period option for Local Exadata Storage is 7 or 14 days.
 Regardless of the retention window selected for backups to Local Exadata Storage, incremental level 1 backups are always performed after the initial level 0 image copy is taken. Also, the incremental level 1 backups are merged into the level 0 image copy backup when they become older than the retention period.

For example: A 14 day for Local retention window includes one "merged" level 0, 14 incremental level 1's plus archivelogs for the 14 days.

- The retention period defines the period for which automatic backups are maintained:
 - For backups to Zero Data Loss Recovery Appliance, the retention policy that is implemented in the appliance controls the retention period.
 - For backups to local Exadata storage, you can choose a retention period of 7 days, or 14 days. The default retention period is 7 days.
 - For backups to Oracle Cloud Infrastructure Object Storage, or to an NFS backup destination, you can choose one of the following preset retention periods: 7 days, 14 days, 30 days, 45 days, or 60 days. The default retention period is 30 days.
- By default, Oracle Database runs in ARCHIVELOG mode, and archived redo log files are backed up every 30 minutes. .
- Regardless of the backup destination, backups of user data are encrypted by default.

While a backup is in progress, Oracle recommends that you avoid performing actions that could interfere with availability, such as restarting virtual machines, or applying patches. If an automatic backup operation fails, then the backup is deferred until the next day's backup window.

When required, you can restore Oracle Database to:

- The latest available restore point.
- A specific point in time by providing a time stamp.
- An Oracle Database System Change Number (SCN).

Note:

The backup and recovery facilities described in this topic cater only for database backup and recovery, which includes Oracle Database data files, log files, control files, and the server parameter (SP) file. You are responsible for backing up other files on your virtual machines. In particular, Oracle strongly recommends that you back up the Transparent Data Encryption (TDE) keystore (wallet). Without the TDE keystore, the Oracle Database backups are effectively useless, because you cannot read the data contained in the backup.



Note:

If TAG based recovery fails with error ORA-01152, then use Recovery Manager (RMAN) directly to complete the recovery.

If the server parameter file (SPFILE) recovery fails for local configuration using dbaascli, then use Recovery Manager (RMAN) directly to complete the recovery.

Using the Console to Configure and Manage Backup and Recovery

Learn how to use the console to view a list of available backups, edit backup settings, and restore a database for Oracle Exadata Database Service on Cloud@Customer.

- Viewing a List of Available Backups with the Console
 To view a list of available backups with Oracle Exadata Database Service on Cloud@Customer, complete this procedure.
- Editing Backup Settings with the Console
 To edit backup destinations, change backup schedules and other backup administration, you can use with the Oracle Exadata Database Service on Cloud@Customer console.
- Restoring a Database with the Console
 To restore a database to a point in time, to a system change number (SCN), or to the
 latest backup, use the Exadata Database Service on Cloud@Customer Console.

Viewing a List of Available Backups with the Console

To view a list of available backups with Oracle Exadata Database Service on Cloud@Customer, complete this procedure.

Note:

Only the managed backups are synced to the Console. If you configure backups directly in the backend, then they are not synced to the Console. This is an expected behavior and Oracle has no plans to change this behavior.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the VM cluster that hosts the database in which you are interested.
- Click VM Clusters.
- 4. Click the name of the VM cluster that hosts the database in which you are interested.
- 5. In the **Resources** list of the VM Cluster Details page, click **Databases**.
- 6. Click the name of the database in which you are interested.

The Database Details page displays information about the selected database, which includes a list of the available backups.

Editing Backup Settings with the Console



To edit backup destinations, change backup schedules and other backup administration, you can use with the Oracle Exadata Database Service on Cloud@Customer console.

Use this procedure to change the available backup settings:

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose the Region and Compartment that contains the VM cluster that hosts the database for which you want to edit backup settings.
- Click VM Clusters.
- Click the name of the VM cluster that hosts the database for which you want to edit backup settings.
- In the Resources list of the VM Cluster Details page, click Databases.
- Click the name of the database for which you want to edit backup settings.The Database Details page displays information about the selected database.
- 7. Click Edit Backup Settings.
- 8. Your current backup configuration determines the changes that you can make in the **Backup Settings** dialog, as follows:
 - If automatic backups are not configured (Backup Destination Type is set to None), then you can use the following settings to define the backup configuration for the database:
 - Backup Destination Type: From the list, choose an option.
 - * None Select if you do not define a backup configuration for the database.
 - * Local Select to store backups locally in the Exadata Storage Servers on your Exadata Database Service on Cloud@Customer system.
 - This option is available only if you enabled backups on local Exadata storage in the VM cluster that you want to host the database.
 - Object Storage Select to store backups in an object storage container managed by Oracle on Oracle Cloud Infrastructure.
 - To use this option, your Exadata Database Service on Cloud@Customer system must have egress connectivity to Oracle Cloud Infrastructure Object Storage.
 - * NFS Select to store backups in one of your previously defined backup destinations that uses Network File System (NFS) storage. See "Managing Backup Destinations for Exadata Database Service on Cloud@Customer".
 - If you select this option, then you must also choose from the list of NFS **Backup Destinations**.
 - Recovery Appliance Select to store backups in one of your previously defined backup destinations that uses Oracle Zero Data Loss Recovery Appliance. See Managing Backup Destinations for Exadata Database Service on Cloud@Customer.
 - If you select this option, then you must also provide the following information:



- * Choose Backup Destinations from the list of Recovery Appliance.
- * Choose from the **VPC User** list, which contains the list of virtual private catalog (VPC) user names that are defined in the **Recovery Appliance** backup destination.
- * Provide the **Password** for the VPC user.



If you select a backup destination (other than **None**), then you cannot change it later.

For more information on customizing Real Time Redo Transport (RTRT) behavior, see *Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups*

 Enable automatic backups: Select this option to enable daily backups using the policy for automatic backups.

This option is only enabled when you select a **Backup Destination Type** other than **None**. You can change this setting later.

 Backup retention period: Select this option to choose one of the options for the length of time that automatic backups are retained.

For backups to local Exadata storage, you can choose a retention period of 7 days, or 14 days. The default retention period is 7 days.

For backups to Oracle Cloud Infrastructure Object Storage or to an NFS backup destination, you can choose one of the following preset retention periods: 7 days, 14 days, 30 days, 45 days, or 60 days. The default retention period is 30 days.

This option does not apply to Recovery Appliance backup destinations. For backups to Oracle Zero Data Loss Recovery Appliance, the retention policy that is implemented in the appliance controls the retention period.

- If automatic backups were previously configured, then you can make the following changes:
 - For Oracle Zero Data Loss Recovery Appliance backup destinations, you can
 update the **Password** for the virtual private catalog (VPC) user that is used to
 access the appliance.
 - For backup destinations that do not use Oracle Zero Data Loss Recovery
 Appliance, you can update the Backup retention period for automatic backups:
 - * For backups to local Exadata storage, you can choose a retention period of 7 days or 14 days. The default retention period is 7 days.
 - * For backups to Oracle Cloud Infrastructure Object Storage, or to an NFS backup destination, you can choose one of the following preset retention periods: 7 days, 14 days, 30 days, 45 days, or 60 days. The default retention period is 30 days.
 - For backups to Oracle Zero Data Loss Recovery Appliance, the retention policy that is implemented in the appliance controls the retention period.



- You can set the option to Enable automatic backups. Select this option to enable automatic database backups. Deselect this option to suspend automatic database backups.
- 9. Click Save Changes.

Related Topics

- Backup Destinations
- Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups

Restoring a Database with the Console

To restore a database to a point in time, to a system change number (SCN), or to the latest backup, use the Exadata Database Service on Cloud@Customer Console.

Use the following procedure to restore a database:

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose the **Region** and **Compartment** that contains the VM cluster that hosts the database that you want to restore.
- 3. Click VM Clusters.
- 4. Click the name of the VM cluster that hosts the database that you want to restore.
- 5. In the **Resources** list of the VM Cluster Details page, click **Databases**.
- Click the name of the database that you want to restore.The Database Details page displays information about the selected database.
- 7. Click Restore Database.
- 8. In the resulting dialog box, select one of the following options, and click **Restore**Database:
 - **Restore to latest**: The database is restored and recovered with zero, or least possible, data loss.
 - Restore to a timestamp: The database is restored and recovered to the specified timestamp.
 - Restore to SCN: The database is restored and recovered to the specified
 Oracle Database System Change Number (SCN). The specified SCN must be
 valid otherwise the operation fails.



Backup fails after a point in time restore to a timestamp or SCN on NFS storage. Wait for 10 minutes or so before proceeding with the backup.

Using the API to Manage Database Backup and Recovery

Learn how to use the API to manage database backup and recovery with Oracle Exadata Database Service on Cloud@Customer.



For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage database backup and recovery:

- GetBackup
- ListBackups
- RestoreDatabase
- UpdateDatabase To enable and disable automatic backups.

For the complete list of APIs, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- GetBackup
- ListBackups
- RestoreDatabase
- UpdateDatabase
- Database Service API

User Configured Backup

It is the user's responsibility to configure and execute backup operations using <code>dbaascli</code> according to their preferences.

Backups using dbaascli are not recognized as Oracle managed backups. Use the dbaascli database backup, dbaascli pdb backup, dbaascli database recover, and dbaascli pdb recover commands to configure and perform various backup and recover operations.

- How to Backup Using dbaascli for User Configured Backup
- How to Recover a Database

How to Backup Using dbaascli for User Configured Backup

User configured backups involve the following 4 steps:

- Set up network and security rules to allow database hosts to store backup to the desired storage destination. For Exadata Cloud Service, refer to Network Setup for Exadata Cloud Service Instances.
- 2. Set up Backup Destination
- 3. Configure database with a Backup Destination
- 4. Backup database



Setting up Backup Destination

Depending on the Oracle Database Cloud Service, Oracle Exadata Cloud@Customer, or Oracle Exadata Cloud Service, you can choose one of the following backup destinations for storing backups.

Configuring Database for Backup

Once the backup destination is set up and available, you can use the dbaascli utility to configure the database with backup destination and associated configuration parameters, for example, Backup Retention Recovery Window, Backup Scheduling, Archivelog Scheduling, and so on.

- Backing Up a Container Database (CDB)
- Backing Up a Pluggable Database (PDB)
- Fetching Backup Job Status

Related Topics

Network Setup for Exadata Cloud Service Instances

Setting up Backup Destination

Depending on the Oracle Database Cloud Service, Oracle Exadata Cloud@Customer, or Oracle Exadata Cloud Service, you can choose one of the following backup destinations for storing backups.

- Oracle Cloud Infrastructure Object Storage: Applies to Exadata Cloud@Customer and Exadata Cloud Service.
- Zero Data Loss Recovery Appliance (ZDLRA): Applies to Exadata Cloud@Customer.
- Network File System (NFS): Applies to Exadata Cloud@Customer.
- Fast Recovery Area (FRA): Applies to Exadata Cloud@Customer.

Related Topics

Backup Destinations

Configuring Database for Backup

Once the backup destination is set up and available, you can use the dbaascli utility to configure the database with backup destination and associated configuration parameters, for example, Backup Retention Recovery Window, Backup Scheduling, Archivelog Scheduling, and so on.

The configuration parameters are specified through an input configuration file having a list of **parameter=value** pairs. The template for this input file can be generated using <code>--getConfig</code> option, which can be modified according to desired destination settings and other preferences and then used as input to <code>--configure</code> option.

dbaascli database backup --getConfig --dbName < value> --configFile < value>

Returns the Backup configuration of the database in a file specified by the user. If the backup is never configured, it returns the default template where the user can fill the configuration parameters with their values and use it as input to --configure command option.



Using dbaascli database backup --configure, you can set the backup configuration information for a database in the following cases:

- 1. User Managed Backup: Set complete backup configuration based on the destination.
- 2. **Oracle Managed Backup:** Set additional configuration parameters if a parameter is compatible with Oracle Managed Backup.

Note that using <code>dbaascli database backup --configure</code> to set incompatible parameters with Oracle Managed Backups can lead to backup/recovery issues. Currently, Oracle does not validate whether a parameter is compatible or not. Until Oracle implements validation, it is your responsibility to verify compatibility.

dbaascli database backup --configure --dbName <value> --configFile <value>

This asynchronous command generates a universally unique identifier (UUID), which you can use to track the status.

dbaascli database backup status --uuid <value> --dbname <value>

To retrieve the current configuration for the validation, run:

dbaascli database --dbaname --getConfig

Note:

When using Oracle Managed Backups, you may want to change some of the backup configuration settings based on your application requirements. You can use dbaascli to modify these parameters if they are tagged with Compatible with console automatic backup.

Configuration Parameters for Backup

Table 5-9 General Configuration Parameters (valid for all backup destinations except Local Storage (FRA))

Parameter	Description	Compatible with Oracle Managed Backup
bkup_rman_compression	Level of compression applied to automatic backups. Valid values are NONE, basic, low, medium, and high.	Yes
	Default: low.	
	NONE disables RMAN compression.	
bkup_set_section_size	Enables the use of the RMAN multisection backup feature. Valid values are yes and no.	Yes



Table 5-9 (Cont.) General Configuration Parameters (valid for all backup destinations except Local Storage (FRA))

Parameter	Description	Compatible with Oracle Managed Backup
bkup_section_size	RMAN section size that is used for automatic backups. The default value is 64G.	Yes
	Applicable only when bkup_set_section_size is set to yes.	
bkup_channels_node	The number of RMAN channels per node used for automatic backups. Valid values are between 1 and 32.	Yes
bkup_daily_time	Start time of the automatic daily backup expressed in 24-hour time format as hh:mm.	Exadata Cloud@Customer: Yes Exadata Cloud Service: No Not compatible with Oracle Managed Backup in Exadata Cloud Service. Scheduling responsibility resides with the Control Plane.
okup_archlog_frequency	Interval in minutes between automatic backups of archived database log files. Valid values are 15, 20, 30, 60, 120 through 1440 in 1-hour intervals expressed in minutes.	Yes
	Default: 30 for Exadata Cloud@Customer.	
bkup_10_day	This parameter controls the Level 0 day of the week for both OSS and NFS. Day of the week when a level 0 backup is taken.	Exadata Cloud@Customer: Yes Exadata Cloud Service: No Not compatible with Oracle Managed Backup in Exadata Cloud Service. Scheduling responsibility resides with the Control Plane.
	Valid values are mon, tue, wed, thu, fri, sat, sun. Longer formats, for example, Monday, Tuesday are also supported.	
	Applicable only when bkup_oss is set to yes.	
	Default: sun.	



Configuration Parameters for Object Storage Service (OSS) Destination

Table 5-10 Configuration Parameters for Object Storage Service (OSS) Destination

Parameter	Description	Compatible with Oracle Managed Backup
bkup_oss	Object storage service will be used as the backup destination. Valid values are yes and no.	No
bkup_oss_recovery_window	The retention period for the backups is up to 90. Applicable only when bkup_oss is set to yes. Default: 30.	No
bkup_oss_url	Location of the storage container that is used for backup to cloud storage. Applicable only when bkup_oss is set to yes.	No
bkup_oss_user	User name of the Oracle Cloud user having the write privileges on the cloud storage container specified in bkup_oss_url. Applicable only when bkup_oss is set to yes.	No
bkup_oss_passwd	The password of the Oracle Cloud user having the write privileges on the cloud storage container specified in bkup_oss_url. Applicable only when bkup_oss is set to yes.	No

Note:

Currently, Zero Data Loss Recovery Appliance (ZDLRA) destination is supported only on Exadata Cloud@Customer.

Configuration Parameters for Zero Data Loss Recovery Appliance (ZDLRA) Destination

Table 5-11 Configuration Parameters for Zero Data Loss Recovery Appliance (ZDLRA) Destination

Parameter	Description	Compatible with Oracle Managed Backup
bkup_zdlra	Enables backups to a Recovery Appliance. Valid values are yes and no.	No



Table 5-11 (Cont.) Configuration Parameters for Zero Data Loss Recovery Appliance (ZDLRA) Destination

Parameter	Description	Compatible with Oracle Managed Backup
bkup_zdlra_url	Location of the Recovery Appliance that is being used for backups. Applicable only when bkup_zdlra is set to yes.	No
bkup_zdlra_user	The virtual private catalog (VPC) user name for the Recovery Appliance specified in bkup_zdlra_url. Applicable only when bkup_zdlra is set to yes.	No
bkup_zdlra_passwd	The password of the Recovery Appliance user specified in bkup_zdlra_url. Applicable only when bkup_zdlra is set to yes.	No

For more information, see *Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups*.

Configuration Parameters for Network File System (NFS) Destination

Table 5-12 Configuration Parameters for Network File System (NFS) Destination

Parameter	Description	Compatible with Oracle Managed Backup
bkup_nfs	Enables backups to NFS mounted directory. Valid values are yes and no.	No
bkup_nfs_loc	The NFS mounted location, the directory provided must be a mount point and available on all nodes. Applicable only when bkup_nfs is set to yes.	No
bkup_nfs_recovery_windo w	The retention period for backups on NFS storage is expressed as a number of days up to 90. Applicable only when bkup_nfs is set to yes. Default: 30.	No





Currently, Network File System (NFS) destination is supported only on Exadata Cloud@Customer.

Configuration Parameters for Local Storage (FRA) Destination

Table 5-13 Configuration Parameters for Local Storage (FRA) Destination

Parameter	Description	Compatible with Oracle Managed Backup
bkup_disk	Enables backups to local Exadata storage. Valid values are yes and no.	No
bkup_disk_recovery_window	The retention period for backups on local Exadata storage is expressed as a number of days up to 14. Applicable only when bkup_disk is set to yes. Default: 7.	No



Currently, Local Storage (FRA) destination is supported only on Exadata Cloud@Customer.

Related Topics

- Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups
- dbaascli database backup

To configure Oracle Database with a backup storage destination, take database backups, query backups, and delete a backup, use the <code>dbaascli</code> database <code>backup</code> command.

dbaascli database recover

To recover a database, use the dbaascli database recover command.

dbaascli pdb backup

To backup a pluggable database (PDB), query PDB backups, and delete a PDB backup, use the dbaascli pdb backup command.

dbaascli pdb recover

To recover a pluggable database (PDB), use the dbaascli pdb recover command.

Backing Up a Container Database (CDB)



Before performing a backup, you must set up the backup configuration using <code>dbaasclidatabase backup --configure command</code> as a prerequisite. For more information, see <code>dbaasclidatabase backup</code>.

Related Topics

dbaascli database backup

To configure Oracle Database with a backup storage destination, take database backups, query backups, and delete a backup, use the dbaascli database backup command.

Backing Up a Pluggable Database (PDB)

You can also perform a backup of a specific PDB. This is useful if one or more PDBs need to be backed up immediately or adhoc need basis, instead of backing up the complete CDB which has its own schedule. For more information, see *dbaascli pdb backup*.

Related Topics

dbaascli pdb backup

To backup a pluggable database (PDB), query PDB backups, and delete a PDB backup, use the dbaascli pdb backup command.

Fetching Backup Job Status

As the backup operation is being run, its status can be monitored by providing the job ID that is displayed to the user when the backup command is executed. For more information, see *dbaascli database backup* and *dbaascli pdb backup*.

Related Topics

dbaascli database backup

To configure Oracle Database with a backup storage destination, take database backups, query backups, and delete a backup, use the <code>dbaascli database backup command</code>.

dbaascli pdb backup

To backup a pluggable database (PDB), query PDB backups, and delete a PDB backup, use the <code>dbaascli</code> <code>pdb</code> <code>backup</code> command.

How to Recover a Database

To perform recovery of the database, there are various options depending on the type of fault, availability of data, and its' backup and recovery requirement. For more information, see *dbaascli database recover*.

- Recovering a PDB
- Fetching Recover Job Status

Related Topics

dbaascli database recover

To recover a database, use the dbaascli database recover command.

Recovering a PDB



You can also recover a particular PDB instead of complete CDB whenever that can be avoided. It reduces the impact of the outage as only the particular PDB is being recovered while the rest of the CDB and PDBs are still available for business and applications. For more information, see *dbaascli pdb recover*.

Related Topics

dbaascli pdb recover
 To recover a pluggable database (PDB), use the dbaascli pdb recover command.

Fetching Recover Job Status

Similar to backup, the recovery commands' status can be monitored by providing the job ID that is displayed to the user when the recovery command is executed. To know the status of recovery operation: For more information, see *dbaascli database recover* and *dbaascli pdb recover*.

Related Topics

- dbaascli database recover
 To recover a database, use the dbaascli database recover command.
- dbaascli pdb recover
 To recover a pluggable database (PDB), use the dbaascli pdb recover command.

Configuring and Customizing Backups with bkup_api

In addition to the console-based automated backup option, there is a command line backup utility, $bkup_api$, which can allow for further customization. If configuring backups using $bkup_api$ instead of the console, then do not enable backups for your database in the console.



bkup_api will be deprecated in a future release. Use the dbaascli database backup, dbaascli pdb backup, dbaascli database recover, and dbaascli pdb recover commands to backup and recover container databases and pluggable databases. For more information, see *User Configured Backup*.

- Customizing Backup Settings by Using a Generated Configuration File
 You can customize backup settings for a database deployment by generating a file
 containing the current customizable settings, editing the file, and then using the file to
 update the backup settings.
- Customizing Which System Files Are Backed Up
 By default, backups via the console or bkup_api backup certain system files in addition to
 the database files themselves.
- Customizing Which Database Configuration Files Are Backed Up
 By default, backups through the console or bkup_api backup certain database
 configuration files in addition to the database files themselves.



Related Topics

User Configured Backup

It is the user's responsibility to configure and execute backup operations using dbaascli according to their preferences.

Customizing Backup Settings by Using a Generated Configuration File

You can customize backup settings for a database deployment by generating a file containing the current customizable settings, editing the file, and then using the file to update the backup settings.



WARNING:

In general, bkup api configured backups, as described in this section, **should not** be used in conjunction with console-enabled automatic backups, other than the exceptions noted specifically below. If using parameters, other than those noted as safe below, then do not enable console-based backups; otherwise, conflicting conditions or over-writes of settings can occur, and backups may not execute successfully.

To generate a configuration file with the current backup settings and use it to update the settings:

Connect to a virtual machine as opc user.

For detailed instructions, see Connecting to a Virtual Machine with SSH.

Start a root user command shell:

sudo -s

3. Use the bkup_api get config command to generate a file containing the current backup settings for the database deployment:

/var/opt/oracle/bkup api/bkup api get config [--file=filename] -dbname=dbname

Where:

filename is an optional parameter used to specify a name for the file that is generated

dbname is the database name for the database that you want to act on

Edit the parameter values in the generated file to change any settings you want to customize in the backup configuration.

The following parameters can be modified to customize the backup configuration:





Compatible with Console Automatic Backups=Yes indicates the parameter is safe to change, even when using console-based automatic backups. If using parameters with Compatible with Console Automatic Backups=No, then do not enable backups through the console.

Table 5-14 Backup Configuration Parameters - Cron Parameters Specific to bkup_api

Parameter	Description	Compatible with Console Automatic Backups*
bkup_cron_entry	Enables the automatic backup configuration. Valid values are yes and no.	No
bkup_cfg_files	for ZDLRA, backups of the system/ database configuration will not occur.	No

Table 5-15 Backup Configuration Parameters - General RMAN Configuration Parameters (valid for all backup destinations except Local Storage (FRA))

Parameter	Description	Compatible with Console Automatic Backups*
bkup_rman_compression	Level of compression applied to automatic backups.	Yes
	Valid values are NONE, basic, low, medium, and high.	
	Default value is low.	
	A value of NONE disables rman compression.	
	If RMAN compression is enabled, then any TDE encrypted datafile will be decrypted, compressed, and RMAN encrypted.	
bkup_set_section_size	Enables the use of the RMAN multisection backup feature. Valid values are yes and no.	Yes



Table 5-15 (Cont.) Backup Configuration Parameters - General RMAN Configuration Parameters (valid for all backup destinations except Local Storage (FRA))

Parameter	Description	Compatible with Console Automatic Backups*
bkup_section_size	RMAN section size that is used for automatic backups.	Yes
	Default value is 64G.	
	Applicable only when bkup_set_section_size is set to yes.	
bkup_channels_node	Number of RMAN channels per node used for automatic backups.	Yes
	Valid values are between 1 and 32.	
	Default value is 4.	
bkup_daily_time	Start time of the automatic daily backup expressed in 24-hour time as hh:mm.	Yes
bkup_archlog_frequency	Interval in minutes between automatic backups of archived database log files.	Yes
	Valid values are 15, 20, 30, 60, 120 through 1440 in 1 hour intervals expressed in minutes.	
	Default value is 30 for Exadata Cloud@Customer.	

Table 5-16 Backup Configuration Parameters - Local Storage (FRA) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_disk	Enables backups to local Exadata storage.	No
	Valid values are yes and no.	
bkup_disk_recovery_win dow	Retention period for backups on local Exadata storage, expressed as a number of days up to 14.	No
	Applicable only when bkup_disk is set to yes.	
	Default value is 7.	



Table 5-17 Backup Configuration Parameters - Network File System (NFS) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_nfs	Enables backups to NFS mounted directory.	No
	Valid values are yes and no.	
bkup_nfs_loc	The NFS mounted location, the directory provided must be a mountpoint and available on all nodes.	No
bkup_nfs_recovery_window	Retention period for backups on NFS storage, expressed as a number of days up to 90.	No
	Applicable only when bkup_nfs is set to yes.	
	Default value is 30.	
bkup_oss_10_day	This parameter control the Level 0 day of the week for both OSS and NFS.	Yes
	Day of the week when a level 0 backup is taken and stored on cloud storage or for NFS.	
	Valid values are mon, tue, wed, thu, fri, sat, sun.	
	Applicable only when bkup_nfs is set to yes.	
	Default value is sun.	

Table 5-18 Backup Configuration Parameters - Object Storage Service (OSS) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_oss	Enables backups to cloud storage.	No
	Valid values are yes and no.	
bkup_oss_recovery_window	Retention period for backups to cloud storage, expressed as a number of days up to 90.	No
	Applicable only when bkup_oss is set to yes.	
	Default value is 30.	
bkup_oss_url	Location of the storage container that is used for backup to cloud storage.	No
	Applicable only when bkup_oss is set to yes.	



Table 5-18 (Cont.) Backup Configuration Parameters - Object Storage Service (OSS) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_oss_user	User name of the Oracle Cloud user having write privileges on the cloud storage container specified in bkup_oss_url.	No
	Applicable only when bkup_oss is set to yes.	
bkup_oss_passwd	Password of the Oracle Cloud user having write privileges on the cloud storage container specified in bkup_oss_url.	No
	Applicable only when bkup_oss is set to yes.	
bkup_oss_10_day	This parameters control the Level 0 day of the week for both OSS and NFS.	Yes
	Day of the week when a level 0 backup is taken and stored on cloud storage.	
	Valid values are mon, tue, wed, thu, fri, sat, sun.	
	Applicable only when bkup_oss is set to yes.	
	Default value is sun.	



Zero Data Loss Recovery Appliance (ZDLRA) parameters are only valid for Exadara Cloud@Customer installations.

Table 5-19 Backup Configuration Parameters - Zero Data Loss Recovery Appliance (ZDLRA) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_zdlra	Enables backups to a Recovery Appliance.	No
	Valid values are yes and no.	
bkup_zdlra_url	Location of the Recovery Appliance that is being used for backups.	No
	Applicable only when bkup_zdlra is set to yes.	



Table 5-19 (Cont.) Backup Configuration Parameters - Zero Data Loss Recovery Appliance (ZDLRA) Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_zdlra_user	The virtual private catalog (VPC) user name for the Recovery Appliance specified in bkup_zdlra_url. Applicable only when	No
	bkup_zdlra is set to yes.	
bkup_zdlra_passwd	Password of the Recovery Appliance user specified in bkup_zdlra_url.	No
	Applicable only when bkup_zdlra is set to yes.	

Table 5-20 Backup Configuration Parameters - RMAN Catalog Support Parameters

Parameter	Description	Compatible with Console Automatic Backups*
bkup_use_rcat	Enables the use of an existing RMAN recovery catalog. Valid values are yes and no.	Yes (only for NFS and OSS backups)
bkup_rcat_user	Recovery catalog user name. Applicable only when bkup_use_rcat is set to yes.	Yes (only for NFS and OSS backups)
bkup_rcat_passwd	Password for recovery catalog user specified in bkup_rcat_user.	Yes (only for NFS and OSS backups)
	Applicable only when bkup_use_rcat is set to yes.	
bkup_rcat_conn	Connection string for the RMAN recovery catalog. Applicable only when bkup_use_rcat is set to yes.	Yes (only for NFS and OSS backups)

Only the above parameters noted with *Compatible with Console Automatic Backups = Yes are safe to alter in conjunction with console-based automatic backups. If any other parameters are to be altered, then do not enable backups through the console.

5. Use the bkup_api set config command to update the backup settings using the file containing your updated backup settings:

/var/opt/oracle/bkup_api/bkup_api set config --file=filename -dbname=dbname

Where:

filename is used to specify the name of the file that contains the updated backup settings



dbname is the database name for the database that you are acting on

6. You can use the bkup_api configure_status command to check the status of the configuration update:

```
/var/opt/oracle/bkup api/bkup api configure status
```

7. Exit the root user command shell:

exit



any changes you make by using the bkup_api command are not reflected in the Oracle Database Exadata Cloud@Customer console.

Related Topics

- Disabling Automatic Backups to Facilitate Manual Backup and Recovery Management
- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

Customizing Which System Files Are Backed Up

By default, backups via the console or bkup_api backup certain system files in addition to the database files themselves.

If you need different system files backed up, then use these steps to change which system files get backed up. It is safe to alter parameters pertaining to system file backups in conjunction with the use of console-based automated backups.

If your backup configuration includes $bkup_cfg_files=yes$, then each backup includes system configuration files and directories specified in the oscfg.spec file.

To change which system files and directories are backed up:

- Connect to a virtual machine as opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Switch to oracle user.
- 3. Edit the contents of the oscfg.spec file.

This file is located under <code>/var/opt/oracle/dbaas_acfs/bkup/dbname</code>, where <code>dbname</code> is the name of the database that is associated with the backup configuration.

Following is an example of the default contents of the oscfg.spec file:

```
## OS Configuration Files
#
# Doc Spec
oscfg.spec
```



```
#
# Directories
/etc/rc.d
/home/oracle/bkup
#
# Single files
/home/oracle/.bashrc
/etc/crontab
/etc/sysctl.conf
/etc/passwd
/etc/group
/etc/oraInst.loc
/etc/oratab
/etc/fstab
```

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

Customizing Which Database Configuration Files Are Backed Up

By default, backups through the console or bkup_api backup certain database configuration files in addition to the database files themselves.

If you need different database configuration files backed up, then use these steps to change which database configuration files get backed up. It is safe to alter parameters pertaining to database configuration file backups in conjunction with the use of console-based automated backups.

If your backup configuration includes $bkup_cfg_files=yes$, then each backup includes database configuration files and directories specified in the dbcfg.spec file.

To change which database configuration files are backed up:

- 1. Connect to a virtual machine as opc user.
 - For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Switch to oracle user.
- 3. Edit the contents of the dbcfg.spec file.

This file is located under <code>/var/opt/oracle/dbaas_acfs/bkup/dbname</code>, where <code>dbname</code> is the name of the database that is associated with the backup configuration.

Following is an example of the contents of the dbcfg.spec file:

```
### Oracle_Home configuration files.
#
# Doc Spec
dbcfg.spec
# DB id
dbid
#
# Directories
/u02/app/oracle/product/dbversion/dbhome_n/admin/dbname/xdb_wallet
```



```
/u02/app/oracle/admin/dbname/xdb wallet
/u02/app/oracle/admin/dbname/db wallet
# Note: tde wallet must be backed up in a different location than
DATA bkup.
/u02/app/oracle/admin/dbname/tde wallet
/u02/app/oracle/admin/dbname/cat wallet
#/u01/app/oraInventory
# Single files
/var/opt/oracle/dbaas acfs/dbname/opc/opcdbname.ora
/u02/app/oracle/product/dbversion/dbhome n/dbs/opcdbname.ora
/u02/app/oracle/product/dbversion/dbhome n/dbs/orapwinstancename
/u02/app/oracle/product/dbversion/dbhome n/network/admin/
listener.ora
/u02/app/oracle/product/dbversion/dbhome n/network/admin/sqlnet.ora
/u02/app/oracle/product/dbversion/dbhome n/network/admin/
tnsnames.ora
/u02/app/oracle/product/dbversion/dbhome n/rdbms/lib/env rdbms.mk
/u02/app/oracle/product/dbversion/dbhome n/rdbms/lib/ins rdbms.mk
# Creq
/var/opt/oracle/creg/instancename.ini
```

Related Topics

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

Creating an On-Demand Backup by Using the bkup_api Utility

You can use the bkup_api utility to create an on-demand backup of a complete database or an individual pluggable database (PDB):



bkup_api will be deprecated in a future release. Use the dbaascli database backup, dbaascli pdb backup, dbaascli database recover, and dbaascli pdb recover commands to backup and recover container databases and pluggable databases. For more information, see *User Configured Backups and Recovery*.

Note:

Using this method for a manual backup is safe to use in conjunction with automatic backups managed through the Console. Manual backups done this way will appear in the console after some time due to synchronization.

To change which database configuration files are backed up:



1. Connect as the oracle user to a compute node.

For detailed instructions, see Connecting to a Compute Node with SSH.

2. Start a root-user command shell:

```
# sudo -s
```

- 3. Enter the bkup api command:
 - To create a backup that follows the current retention policy, use the following bkup api command:

```
# /var/opt/oracle/bkup api/bkup api bkup start --dbname=dbname
```

where dbname is the database name for the database that you want to back up.

 To create an on-demand backup of a specific PDB, use the following bkup_api command:

```
# /var/opt/oracle/bkup_api/bkup_api bkup_start --dbname=dbname --
pdb=pdbname
```

• To create a long-term backup of the complete database that persists until you delete it, use the following bkup api command:

```
# /var/opt/oracle/bkup api/bkup api bkup start --keep --dbname=dbname
```

By default, the long-term backup is given a timestamp-based tag. To specify a custom backup tag, add the --tag option to the bkup_api command.

For example, to create a long-term backup with the tag monthly, use the following command:

```
# /var/opt/oracle/bkup_api/bkup_api bkup_start --keep --tag=monthly --
dbname=dbname
```

To create an on-demand RMAN level 0 backup, use the following bkup_api

```
# /var/opt/oracle/bkup_api/bkup_api bkup_start --level0 --
dbname=dbname
```

You can use this option to manually perform an RMAN level 0 (full) backup if the scheduled weekly level 0 backup fails or following a major structural change in the database, such as adding a new data file or tablespace. This option is only valid for backup configurations that use cloud storage only.

• To create an on-demand backup that includes an image copy of the database data files, use the following bkup api command:

```
# /var/opt/oracle/bkup_api/bkup_api bkup_start --datafiles --
dbname=dbname
```



You can use this option to manually perform a full image backup to cloud storage if the scheduled weekly full backup fails or following a major structural change in the database, such as adding a new data file or tablespace. This option is only valid for backup configurations that use cloud storage and local Exadata storage.

- 4. After you start an on-demand backup, the backup process runs in the background. To check the progress of the backup process, run the following bkup_api command on the same compute node where the backup is running:
 - # /var/opt/oracle/bkup api/bkup api bkup status --dbname=dbname
- **5.** Exit the root-user command shell and disconnect from the compute node:
 - # exit
 # exit

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

Disabling Automatic Backups to Facilitate Manual Backup and Recovery Management

Backups, configured in the Exadata Database Service on Cloud@Customer console, API or bkup_api work for a variety of backup and recovery use cases. If you require use cases not supported by the cloud-managed backups, then you can manage database backup and recovery manually, using the Oracle Recovery Manager (RMAN) utility. For information about using RMAN, see the *Oracle Database Backup and Recovery User's Guide for Release 19*.

Managing backup and recovery, using RMAN, on Exadata Database Service on Cloud@Customer requires taking full ownership of both database and archive log backups, and the cloud-managed backups should no longer be used. Before manual backups are started, the cloud-managed backup functionality should be disabled. This is needed so the cloud backup jobs do not purge archive logs before they are manually backed up and do not conflict with the manual backups.

You can use the $bkup_api$ utility to disable cloud-managed backups, including disabling the automatic archive log purge job, by following this procedure:



If you execute these steps, then the automation will no longer purge/backup the archive logs in the FRA for the database.

Connect as the opc user to the first compute node.
 For detailed instructions, see Connecting to a Compute Node with SSH.



2. Start a root-user command shell:

```
sudo -s
```

3. Use the bkup_api get config command to generate a file containing the current backup settings for the database deployment:

```
/var/opt/oracle/bkup_api/bkup_api get config [--file=filename] --
dbname=dbname
```

Where:

- filename is an optional parameter used to specify a name for the file that is generated
- dbname is the database name for the database that you want to act on
- 4. Edit the parameter values in the generated file to change the following parameters.

This will remove the backup crontab entries and disable all automatic backups. If the values are set to yes, then set to no.

```
bkup_cron_entry=no
bkup_archlog_cron_entry=no
bkup_nfs=no
bkup_oss=no
bkup_local=no
```

5. Use the bkup_api set config command to update the backup settings using the file containing your updated backup settings:

```
/var/opt/oracle/bkup_api/bkup_api set config --file=filename --
dbname=dbname
```

Where:

- filename is an optional parameter used to specify a name for the file that is generated
- dbname is the database name for the database that you want to act on

The job to set the configuration will take several minutes to complete.

6. You can use the bkup_api configure_status command to check the status of the configuration update:

```
/var/opt/oracle/bkup api/bkup api configure status --dbname=dbname
```

Where:

dbname is the database name for the database that you want to act on

The **Configure backup status** starts as **running** and then moves to **finished** when complete.



7. Run the bkup_api get config command again and verify the settings listed above are set to no.

/var/opt/oracle/bkup_api/bkup_api get config [--file=filename] -dbname=dbname

Where:

- filename is an optional parameter used to specify a name for the file that is generated
- dbname is the database name for the database that you want to act on



After making these changes, no backups, including archive log backups, are made by the cloud automation. Ensure that manual RMAN backups are in place to avoid filling the archive log location.



Changes made using the bkup_api command are not reflected in the Oracle Exadata Database Service on Cloud@Customer console.

8. Exit the root-user command shell:

exit

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- Oracle Database Backup and Recovery User's Guide for Release 19

Customizing Real Time Redo Transport (RTRT) Behavior for Recovery Appliance Backups

Real Time Redo Transport can be enabled or disabled using dbaascli. This is available from dbaastools 21.4.1 release.

For example, to enable RTRT for the database *myTestDB*:

dbaascli database backup --dbName myTestDB --configure -enableRTRT

For more information, see dbaascli database backup.



Note:

- Enabling or disabling RTRT works only for Oracle Database version 12.2 and higher.
- If you have enabled Data Guard association between databases, then after enabling RTRT on the Primary database, you must manually copy the password file from the Primary to the Standby database. To learn more about copying the password file from the primary to the standby database, refer to 12c: Data Guard Physical Standby Managing password files in a RAC Physical Standby (Doc ID 1984091.1).

Related Topics

- dbaascli database backup
 To configure Oracle Database with a backup storage destination, take database backups,
 query backups, and delete a backup, use the dbaascli database backup command.
- 12c: Data Guard Physical Standby Managing password files in a RAC Physical Standby (Doc ID 1984091.1)
- About Real-Time Redo Transport

Alternative Backup Methods

Learn about alternative backup methods that are available in addition to the OCI Console.

Backup for databases on Exadata Database Service on Cloud@Customer can be accomplished through several methods in addition to the automatic backups configured in the console. Generally, the console (or the OCI API / CLI that correspond to it) is the preferred method as it provides the simplest and most automated method. In general, it is preferable to leverage the OCI Console, OCI API, or OCI Command-Line over alternative management methods. However, if required actions cannot be completed through the preferred methods, two other options are available to manually configure backups: bkup_api and Oracle Recovery Manager (RMAN).

Note:

bkup_api will be deprecated in a future release. Use the dbaascli database backup, dbaascli pdb backup, dbaascli database recover, and dbaascli pdb recover commands to backup and recover container databases and pluggable databases. For more information, see *User Configured Backup*.

RMAN is the backup tool included with the Oracle Database. For information about using RMAN, see the *Oracle Database Backup and Recovery User's Guide for Release 19*. Using RMAN to back up databases on Exadata Database Service on Cloud@Customer provides the most flexibility in terms of backup options, but also the most complexity.



Note:

While using RMAN for restoring databases backed up through any method described herein is considered safe, RMAN should NEVER be used to set up backups in conjunction with either console (and OCI API / CLI), nor in conjunction with <code>bkup_api</code>. If you choose to orchestrate backups manually leveraging RMAN, you should not use either console automated backups, nor should you use <code>bkup_api</code>. You must first completely disable console based automated backups. For more information, see <code>Disabling Automatic Backups</code> to <code>Facilitate Manual Backup</code> and <code>Recovery Management</code>.

The <code>bkup_api</code> method offers a middle ground between RMAN and console automated backups in terms of flexibility and simplicity. Use <code>bkup_api</code> if needed functionality is not supported with console automated backups, but when you wish to avoid complexity of using RMAN directly. In certain cases, <code>bkup_api</code> can be used to modify the console automated backup configuration, but this is not generally the case. Generally, <code>bkup_api</code> must be used instead of enabling backups in the console.

Recovering a Database Using Oracle Recovery Manager (RMAN)

Related Topics

- User Configured Backup
 It is the user's responsibility to configure and execute backup operations using dbaascli according to their preferences.
- Disabling Automatic Backups to Facilitate Manual Backup and Recovery Management

Recovering a Database Using Oracle Recovery Manager (RMAN)

If you backed up your database using <code>bkup_api</code>, then you can manually restore that database backup by using the Oracle Recovery Manager (RMAN) utility. For information about using RMAN, see the *Oracle Database Backup and Recovery User's Guide for Release 19*.

Note:

While recovering using RMAN is safe, you must not use RMAN to initiate backups or edit backup setting in conjunction with either <code>backup_api</code> usage or in conjunction with automated console backups. Doing so could result in conflicting conditions or over-writes of settings, and backups may not execute successfully.

Related Topics

Oracle Database Backup and Recovery User's Guide for Release 19



Patch and Update an Exadata Database Service on Cloud@Customer System

Learn to update and patch the Exadata Database Service on Cloud@Customer System

- Perform User Managed Maintenance Updates
- Patching and Updating an Exadata Database Service on Cloud@Customer System
 Learn how to perform patching operations on Exadata database virtual machines and
 Database Homes by using the Console, API, or the CLI.
- Patching and Updating an Exadata Database Service on Cloud@Customer System Manually

This topic describes the procedures for patching and updating various components in Exadata Database Service on Cloud@Customer outside of the cloud automation. For information related to patching and updating with dbaascli, refer to "Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli".

Perform User Managed Maintenance Updates

Maintaining a secure Exadata Cloud@Customer system in the best working order requires you to perform the following tasks regularly:

- Patching the Oracle Grid Infrastructure and Oracle Database software on the VM Cluster virtual machines. For information and instructions, see Patching and Updating an Exadata Cloud@Customer System.
- Updating the operating system on the VM Cluster virtual machines. For information and instructions, see Updating Guest VM Operating System and Oracle Clusterware Configuration and Administration.

Related Topics

- Patching and Updating an Exadata Database Service on Cloud@Customer System
 Learn how to perform patching operations on Exadata database virtual machines and
 Database Homes by using the Console, API, or the CLI.
- Updating Guest VM Operating System
 Learn to update the operating system image on Exadata Cloud@Customer VM cluster nodes in an automated manner from the OCI console and APIs.
- Administering Oracle Clusterware

Patching and Updating an Exadata Database Service on Cloud@Customer System

Learn how to perform patching operations on Exadata database virtual machines and Database Homes by using the Console, API, or the CLI.

For information and instructions on patching the system by using the dbaascli utility, see Patching and Updating an Exadata Database Service on Cloud@Customer System Manually.



For more information and examples for applying database quarterly patches on Exadata Cloud@Customer refer to My Oracle Support note: *How to Apply Database Quarterly Patch on Exadata Cloud Service and Exadata Cloud at Customer Gen 2 (Doc ID 2701789.1)*.

For more guidance on achieving continuous service during patching operations, see the *Application Checklist for Continuous Service for MAA Solutions* white paper.

- Patching and Updating VM Clusters and Database Homes
 Learn how to perform patching operations on VM Cluster Grid Infrastructure (GI) and Database Homes using the Console or API
- Updating Guest VM Operating System
 Learn to update the operating system image on Exadata Cloud@Customer VM cluster nodes in an automated manner from the OCI console and APIs.
- Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster Learn to upgrade Oracle Grid Infrastructure on an Exadata Cloud@Customer VM cluster using the Oracle Cloud Infrastructure Console or API.
- Upgrading Oracle Databases
 Learn to upgrade Oracle Database 19c (Long Term Release) using the Console and the API.

Related Topics

- Patching and Updating an Exadata Database Service on Cloud@Customer System Manually
- https://support.oracle.com/epmos/faces/DocContentDisplay?id=2701789.1
- Application Checklist for Continuous Service for MAA Solutions

Patching and Updating VM Clusters and Database Homes

Learn how to perform patching operations on VM Cluster Grid Infrastructure (GI) and Database Homes using the Console or API

- About Patching and Updating VM Cluster's GI and Database Homes
- Prerequisites for Patching and Updating an Exadata Database Service on Cloud@Customer System
 Check and apply the latest Cloud patches that are dowloaded and made available by Oracle on the CPS host.
- Using the Console for Patching and Updating VM Cluster's GI and Database Homes
 - Learn how to use the console to view the history of patch operations on VM cluster and Database Homes, apply patches, and monitor the status of patch operations.
- Using the API for Patching and Updating VM Cluster and Database Homes
 Use various API features to help manage patching an Oracle Exadata Database
 Service on Cloud@Customer system.

About Patching and Updating VM Cluster's GI and Database Homes

Patching a VM cluster updates components on each of the VM guests in the VM cluster. VM cluster patching updates the grid infrastructure (GI) and Database Home



patching updates the Oracle Database software shared by the databases in that home.

For more information on available patches, see My Oracle Support note https://support.oracle.com/epmos/faces/DocContentDisplay?id=2333222.1.

Consider the following best practices:

- Because patching a system requires a reboot, plan to run the operations at a time when they will have minimal impact on users.
- Oracle recommends that you back up your databases before you apply any patches. For information about backing up the databases, see Managing Database Backup and Recovery on Exadata Database Service on Cloud@Customer.
- Your Oracle Grid Infrastructure must be at the same or higher version than the database version you want to patch to. This may require you to first patch a VM cluster before you patch the Databases Homes within that system.
- To patch a database to a version other than the database version of the current home, move the database to a Database Home running the target version. See *Using the Console to Move a Database to Another Home*.

Related Topics

- Manage Database Backup and Recovery on Oracle Exadata Database Service on Cloud@Customer
 - Learn how to work with the backup and recovery facilities provided by Oracle Exadata Database Service on Cloud@Customer.
- Using the Console to Move a Database to Another Home
 You can update the version of a VM cluster database by moving it to a Database Home that is running the version of Oracle Database you are interested in.

Prerequisites for Patching and Updating an Exadata Database Service on Cloud@Customer System

Check and apply the latest Cloud patches that are dowloaded and made available by Oracle on the CPS host.

Ensure that the following conditions are met to avoid patching failures:

- The /u01 directory on the database host file system has at least 15 GB of free space for the execution of patching processes.
- The Oracle Clusterware is up and running on the VM cluster.
- All nodes of the VM cluster are up and running.

Using the Console for Patching and Updating VM Cluster's GI and Database Homes

Learn how to use the console to view the history of patch operations on VM cluster and Database Homes, apply patches, and monitor the status of patch operations.

Oracle recommends that you use the precheck action to ensure your VM cluster or Database Home has met the requirements for the patch you want to apply.

- Using the Console to Perform a Grid Infrastructure Patch Operation on a VM Cluster Learn to apply Grid Infrastructure patches on a VM cluster.
- Using the Console to Perform a Patch Operation on a Database Home Learn to apply patches on a Database Home.



- Using the Console to View Update History
 - Each update history entry represents an attempted patch operation and indicates whether the operation was successful or failed. You can retry a failed patch operation. Repeating an operation results in a new patch history entry.
- Using the Console to Move a Database to Another Home
 You can update the version of a VM cluster database by moving it to a Database
 Home that is running the version of Oracle Database you are interested in.

Using the Console to Perform a Grid Infrastructure Patch Operation on a VM Cluster

Learn to apply Grid Infrastructure patches on a VM cluster.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- **3.** In the list of VM clusters, click the VM cluster on which you want to perform a patch operation.
- 4. Under Oracle Grid Infrastructure Version, click View Updates.
- 5. Review the scope:
 - **VM Cluster:** Automatically set to the context from which you have launched this page.
 - Database Home: Automatically set to the context from which you have launched this page. If you have not set the context, then select the Database Home first.
- 6. Review the list of available patches for the VM cluster.
- 7. Click the Actions icon (three dots) for the patch you are interested in, and then click one of the following actions:
 - **Precheck:** Check for any prerequisites to make sure that the patch can be successfully applied. Oracle highly recommends that you run this operation before you apply a patch. Precheck does not cause any availability impact to the cluster, everything remains operational.
 - Apply Patch: Applies the selected patch.
- 8. Confirm when prompted.

The patch list displays the status of the operation. While the precheck is running, the patch's status shows Checking. While a patch is being applied, the patch's status shows Applying and the VM cluster's status shows Updating. During patching, lifecycle operations on the VM cluster and its resources are temporarily unavailable. If patching completes successfully, the patch's status changes to Applied and the VM cluster's status changes to Available. You can view more details about an individual patch operation by clicking **Update History**. Grid Infrastructure patching is done in a rolling fashion, node by node, and the cluster resources will be stopped and restarted on each node.

Using the Console to Perform a Patch Operation on a Database Home

Learn to apply patches on a Database Home.



1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster where the Database Home is located.
- 4. Under Resources, click Database Homes.
- 5. In the list of Database Homes, click the Database Home on which you want to perform a patch operation.
- 6. Under Database Software Version, click View Patches.
- **7.** Review the scope:
 - Database Home: Automatically set to the context from which you have launched this page.
- 8. Review the list of available patches for the Database Home.

The **Oracle Provided Database Software Images** tab displays generally-available Oracle Database software images that you can use to patch your database. Oracle images that can be used for patching have the update Type of "Patch".

The **Custom Database Software Images** tab allows you to select a database software image that you have created in advance. Use the **Select a Compartment** selector to specify the compartment that contains the database software image.

- 9. Click the Actions icon (three dots) for the patch you are interested in, and then click one of the following actions:
 - **Precheck:** Check for any prerequisites to make sure that the patch can be successfully applied. Oracle highly recommends that you run this operation before you apply a patch. The Precheck does not cause any availability impact to the cluster, everything remains operational.
 - Apply: Applies the selected patch.
- **10.** Confirm when prompted.

The patch list displays the status of the operation. While the precheck is running, the patch's status shows <code>Checking</code>. While a patch is being applied, the patch's status shows <code>Applying</code>, the status of the Database Home and the databases in it display as <code>Updating</code>, and lifecycle operations on the VM cluster and its resources are temporarily unavailable. Patches are applied to the Database Home in a rolling fashion, node by node, and each database in the home is stopped and then restarted. This may result in temporary service disruption. If patching completes successfully, the patch's status changes to <code>Applied</code> and the Database Home's status changes to <code>Available</code>. You can view more details about an individual patch operation by clicking <code>Update History</code>.

Using the Console to View Update History

Each update history entry represents an attempted patch operation and indicates whether the operation was successful or failed. You can retry a failed patch operation. Repeating an operation results in a new patch history entry.

Update history views in the Console do not show patches that were applied by using command line tools such as <code>dbaascli</code>.



- Using the Console to View the Update History of a VM Cluster
 Learn how to view the history of patches applied on a VM cluster.
- Using the Console to View the Update History of a Database Home Learn how to view the history of patches applied on a Database Home.

Using the Console to View the Update History of a VM Cluster

Learn how to view the history of patches applied on a VM cluster.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster you are interested in.
- 4. Under Oracle Grid Infrastructure Version, click View Patches.
- 5. Click Update History.

The history of patch operations for that VM cluster is displayed, along with the history of patch operations on its Database Homes.

Using the Console to View the Update History of a Database Home

Learn how to view the history of patches applied on a Database Home.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster where the Database Home is located.
- 4. Under Resources, click Database Homes.

A list of Database Homes is displayed.

- 5. In the list of Database Homes, click the Database Home you are interested in.
- 6. Under Database Software Version, click View Patches.
- Click Update History.

The history of patch operations for that Database Home is displayed, along with the history of patch operations on the VM cluster to which it belongs.

Using the Console to Move a Database to Another Home

You can update the version of a VM cluster database by moving it to a Database Home that is running the version of Oracle Database you are interested in.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.



A list of VM Clusters is displayed for the chosen Compartment.

- In the list of VM clusters, click the VM cluster where the database you want to move is located.
- 4. Under Resources, click Database Homes.
- 5. In the list of Database Homes, click the Database Home you are interested in.
 - A list of databases is displayed.
- 6. In the list of databases, click the database you are interested in.
- 7. Click Move Database.
- 8. Select the target Database Home.
- 9. Click Move Database.

The database will be stopped in the current home and then restarted in the destination home.

10. Confirm the move operation.

The database is moved in a rolling fashion. The database instance will be stopped, node by node, in the current home and then restarted in the destination home. While the database is being moved, the Database Home and Database statuses display as <code>Updating</code>. The Database Home location, shown under **Database Version**, displays as <code>Moving Database</code>. When the operation completes, Database Home is updated with the current home. Datapatch is executed automatically, as part of the database move, to complete post-patch SQL actions for all patches, including one-offs, on the new Database Home. If the database move operation is unsuccessful, then the status of the database displays as <code>Failed</code>, and the <code>Database Home</code> field provides information about the reason for the failure.

Using the API for Patching and Updating VM Cluster and Database Homes

Use various API features to help manage patching an Oracle Exadata Database Service on Cloud@Customer system.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

Use these API operations to manage patching VM clusters, Database Homes and Databases.

VM cluster:

UpdateVmCluster

Database Homes:

- CreateDbHome
- UpdateDbHome
- DeleteDbHome

Database:

- CreateDatabase
- UpdateDatabase
- DeleteDatabase



Use <code>UpdateVMCluster</code> to patch the Oracle Grid Infrastructure on the VM Cluster. Use <code>UpdateDbHome</code> to patch the Database Software of the Database Home. Use <code>UpdateDatabase</code> to move a database to a different Database Home, thereby updating the database to the same version as the target Database Home.

For the complete list of APIs for the Database service, see "Database Service API".

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- UpdateVmCluster
- CreateDbHome
- UpdateDbHome
- DeleteDbHome
- CreateDatabase
- UpdateDatabase
- DeleteDatabase
- Database Service API

Updating Guest VM Operating System

Learn to update the operating system image on Exadata Cloud@Customer VM cluster nodes in an automated manner from the OCI console and APIs.

This automated feature simplifies and speeds up VM cluster patching, makes patching less error-prone, and eliminates the need to use Patch Manager.

When you apply a patch, the system runs a precheck operation to ensure that your Exadata Cloud@Customer VM cluster, database system, or Database Home meets the requirements for that patch. If the precheck is not successful, then the patch is not applied, and the system displays a message that the patch cannot be applied because the precheck failed. A separate precheck operation that you can run in advance of the planned update is also available.

- Supported Software Versions and Update Restrictions
 Review the list of supported software versions and update restrictions.
- Using the Console to Update Guest VM Operating System
 To update the guest VM operating system with the Console, be prepared to provide values for the fields required.
- Using the API to Update Guest VM Operating System
 Review the list of API calls to update guest VM operating system.

Supported Software Versions and Update Restrictions

Review the list of supported software versions and update restrictions.

- Only images for Exadata major versions 20 and above are supported.
- In addition to performing minor version updates to the Exadata VM Cluster images, you can update to a new major version if the currently installed version is



- 19.2 or higher. For example, if the Exadata Cloud@Customer VM cluster is on version 20, then you can update it to version 21.
- The latest 4 (N to N-3) or more minor versions of each major version of the Exadata VM Cluster images are available through the console to apply.
- If you have an Exadata infrastructure maintenance operation scheduled to start within the next 24 hours, then the Exadata Image update feature is not available.

Using the Console to Update Guest VM Operating System

To update the guest VM operating system with the Console, be prepared to provide values for the fields required.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of cloud VM clusters, click the name of the cluster you want to patch to display the cluster details.
- 4. In the **Version** section, to the right of the **Updates Available**, click **View Updates** to display the Updates page.
- **5.** Review the list of available software updates and locate the operating system patch you are applying.
- 6. Click the Actions icon (three dots) at the end of the row listing the patch you are interested in, and then click one of the following actions:
 - Run Precheck. Precheck checks the prerequisites to ensure that the patch can be successfully applied. Oracle highly recommends that you run the precheck operation before you apply a patch. The reason is that things can change in a database any time, and the precheck you run just before running a patch may find errors that the previous precheck did not find.

Note:

If the precheck fails, the system displays a message in the **Apply Exadata OS Image Update** dialog that the last precheck has failed. Oracle recommends that you run the precheck again. Click the Actions icon (three dots)at the end of the row listing the OS patch to view the dialog.

- Apply Exadata OS Image Update. This link displays the Apply Exadata Image
 Update dialog that you use to apply the patch. The dialog shows the name of the
 database system you are patching, the current version of the database, and the new
 version of the database after the patch is applied. To start the process, click Apply
 Exadata OS Image Update.
- **Copy OCID.** This copies the Oracle Cloud ID. This can be used when troubleshooting a patch or to give to Support when contacting them.



Note:

While the patch is running:

- Run Precheck and Apply OS Image Update are not available.
 When the patch has completed, these actions are available again.
- If the Exadata infrastructure containing this VM cluster is scheduled for maintenance that conflicts with the patching operation, the patch fails and the system displays a message explaining why. After the infrastructure maintenance is complete, run the patch operation again.
- 7. Confirm when prompted.

The patch list displays the status of the operation in the Version section of the database details page. Click **View Updates** to view more details about an individual patch status and to display any updates that are available to run. If no new updates are available, the system displays a message that says **No Updates Available**.

Using the API to Update Guest VM Operating System

Review the list of API calls to update guest VM operating system.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use these API operations to upgrade the Oracle Grid Infrastructure in a VM cluster and view the cluster's update history:

- ListVmClusterUpdates
- GetVmClusterUpdate
- ListVmClusterUpdateHistoryEntries
- GetVmClusterUpdateHistoryEntry
- UpdateVmCluster

For the complete list of APIs, see *Database Service API*.

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- ListVmClusterUpdates
- GetVmClusterUpdate
- ListVmClusterUpdateHistoryEntries
- GetVmClusterUpdateHistoryEntry
- UpdateVmCluster



Database Service API

Upgrading Oracle Grid Infrastructure on an Exadata Cloud@Customer VM Cluster

Learn to upgrade Oracle Grid Infrastructure on an Exadata Cloud@Customer VM cluster using the Oracle Cloud Infrastructure Console or API.

Upgrading enables you to provision Oracle Database Homes and databases that use the most current Oracle Database software.

- About Upgrading Oracle Grid Infrastructure
 Upgrading the Oracle Grid Infrastructure (GI) on a VM cluster involves upgrading all the compute nodes in the instance. The upgrade is performed in a rolling fashion, with only one node being upgraded at a time.
- Using the Console to Manage Oracle Grid Infrastructure Upgrade
 You can use the Console to perform a precheck prior to upgrading your Oracle Grid
 Infrastructure (GI) and to perform the GI upgrade operation.
- Using the API to Manage Oracle Grid Infrastructure Upgrade
 Review the list of API calls to manage Oracle Grid Infrastructure upgrade.

About Upgrading Oracle Grid Infrastructure

Upgrading the Oracle Grid Infrastructure (GI) on a VM cluster involves upgrading all the compute nodes in the instance. The upgrade is performed in a rolling fashion, with only one node being upgraded at a time.

- Oracle recommends running an upgrade precheck to identify and resolve any issues that would prevent a successful upgrade.
- You can monitor the progress of the upgrade operation by viewing the associated work requests.
- If you have an Exadata infrastructure maintenance operation scheduled to start within the next 24 hours, then the GI upgrade feature is not available.
- During the upgrade, you cannot perform other management operations such as starting, stopping, or rebooting nodes, scaling CPU, provisioning or managing Database Homes or databases, restoring a database, or editing IORM settings. The following Data Guard operations are not allowed on the VM cluster undergoing a GI upgrade:
 - Enable Data Guard
 - Switchover
 - Failover to the database using the VM cluster (a failover operation to standby on another VM cluster is possible)

Related Topics

Work Requests Integration

Using the Console to Manage Oracle Grid Infrastructure Upgrade

You can use the Console to perform a precheck prior to upgrading your Oracle Grid Infrastructure (GI) and to perform the GI upgrade operation.

- Using the Console to Precheck Your VM Cluster Prior to Upgrading
- Using the Console to Upgrade Oracle Grid Infrastructure of a VM Cluster



Using the Console to Precheck Your VM Cluster Prior to Upgrading

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of cloud VM clusters, click the name of the cluster you want to patch to display the cluster details.
- 4. Under Version, click the View Updates link beside the Updates Available field.
- 5. Click **View Updates** to view the list of available patches and upgrades.
- Click the Actions icon (three dots) at the end of the row listing the Oracle Grid Infrastructure (GI) upgrade, then click Run Precheck.
- 7. In the **Confirm** dialog, confirm you want to upgrade to begin the precheck operation.

Using the Console to Upgrade Oracle Grid Infrastructure of a VM Cluster

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of cloud VM clusters, click the name of the cluster you want to patch to display the cluster details.
- 4. Under Version, click the View Updates link beside the Updates Available field.
- 5. Click **View Updates** to view the list of available patches and upgrades.
- 6. Click the Actions icon (three dots) at the end of the row listing the Oracle Grid Infrastructure (GI) upgrade, then click **Upgrade Grid Infrastructure**.
- 7. In the Upgrade Grid Infrastructure dialog, confirm you want to upgrade the GI by clicking **Upgrade Grid Infrastructure**.
 - If you haven't run a precheck, you have the option of clicking **Run Precheck** in this dialog to precheck your cloud VM cluster prior to the upgrade.

Using the API to Manage Oracle Grid Infrastructure Upgrade

Review the list of API calls to manage Oracle Grid Infrastructure upgrade.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use these API operations to upgrade the Oracle Grid Infrastructure in a VM cluster and view the cluster's update history:

- ListVmClusterUpdates
- GetVmClusterUpdate



- ListVmClusterUpdateHistoryEntries
- GetVmClusterUpdateHistoryEntry
- UpdateVmCluster

For the complete list of APIs, see Database Service API.

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- ListVmClusterUpdates
- GetVmClusterUpdate
- ListVmClusterUpdateHistoryEntries
- GetVmClusterUpdateHistoryEntry
- UpdateVmCluster
- Database Service API

Upgrading Oracle Databases

Learn to upgrade Oracle Database 19c (Long Term Release) using the Console and the API.

The upgrade is accomplished by moving the Exadata database to a Database Home that uses the target software version. For Oracle Database release and software support timelines, see *Release Schedule of Current Database Releases (Doc ID 742060.1)*.

- Prerequisites to Upgrade Oracle Databases
 Review the list of prerequisites to upgrade an Exadata Cloud@Customer Oracle Database instance.
- About Upgrading an Oracle Database
 Before you upgrade the database, become familiar with the following procedures to
 prepare your database for upgrade.
- How the Upgrade Operation Is Performed by the Database Service
 Familiarize yourself with what the Database service does during the upgrade process.
- Rolling Back an Oracle Database Unsuccessful Upgrade
 If your upgrade does not complete successfully, then you have the option of performing a rollback.
- After Upgrading an Oracle Database
 After a successful upgrade, note the following:
- Using the Console to Manage Oracle Database Upgrade
 Oracle recommends that you use the precheck action to ensure that your database has met the requirements for the upgrade operation.
- Using the API to Upgrade Oracle Databases
 Review the list of API calls to upgrade Oracle Databases.

Related Topics

Release Schedule of Current Database Releases (Doc ID 742060.1)



Prerequisites to Upgrade Oracle Databases

Review the list of prerequsites to upgrade an Exadata Cloud@Customer Oracle Database instance.

- The Exadata Cloud@Customer system software must use Oracle Linux 7 (OL7).
 See How to update the Exadata System Software (DomU) to 19 from 18 on the Exadata Cloud Service in OCI for instructions on manually updating the operating system.
- The Oracle Grid Infrastructure must be version 19c. If patches are available for your Grid Infrastructure, Oracle recommends applying them prior to performing a database upgrade.
- You must have an available Oracle Database Home that uses the two most recent versions of Oracle Database 19c available in Oracle Cloud Infrastructure. See Using the Console to Create Oracle Database Home on Exadata Cloud@Customer for information on creating a Database Home. You can use Oracle-published software images or a custom database software image based on your patching requirements to create Database Homes.
- You must ensure that all pluggable databases in the container database that is being upgraded can be opened. Pluggable databases that cannot be opened by the system during the upgrade can cause an upgrade failure.

Your Oracle database must be configured with the following settings in order to upgrade:

- The database must be in archive log mode.
- The database must have flashback enabled.

See the *Oracle Database documentation* for your database's release version to learn more about these settings.

Related Topics

- How to update the Exadata System Software (DomU) to 19 from 18 on the Exadata Cloud Service in OCI (Doc ID 2521053.1)
- Using the Console to Create Oracle Database Home on Exadata Database Service on Cloud@Customer
 - To create an Oracle Database home in an existing VM cluster with the Console, be prepared to provide values for the fields required.
- Manage Oracle Database Software Images
 Learn about Database Software Image resource type and how you can use it to create Oracle Databases and Oracle Database Homes and to patch databases.
- Oracle Database Documentation

About Upgrading an Oracle Database

Before you upgrade the database, become familiar with the following procedures to prepare your database for upgrade.

- Database upgrades involve database downtime. Keep this in mind when scheduling your upgrade.
- Oracle recommends that you back up your database and test the new software version on a test system or a cloned version of your database before you upgrade



- a production database. See *Creating an On-Demand Backup by Using the bkup_api Utility* for information on creating an on-demand manual backup.
- Oracle recommends running an upgrade precheck operation for your database prior to attempting an upgrade so that you can discover any issues that need mitigation prior to the time you plan to perform the upgrade. The precheck operation does not affect database availability and can be performed at any time that is convenient for you.
- If your databases use Data Guard, you will need to disable or remove the Data Guard association prior to upgrading.
- An upgrade operation cannot take place while an automatic backup operation is underway. Before upgrading, Oracle recommends disabling automatic backups and performing a manual backup. See Creating an On-Demand Backup by Using the bkup_api Utility and Customizing the Automatic Backup Configuration for more information.
- After upgrading, you cannot use automatic backups taken prior to the upgrade to restore the database to an earlier point in time.
- If you are upgrading a database that uses version 11.2 software, the resulting version 19c database will be a non-container database (non-CDB).

Related Topics

- Configuring and Customizing Backups with bkup_api
 In addition to the console-based automated backup option, there is a command line
 backup utility, bkup_api, which can allow for further customization. If configuring backups
 using bkup_api instead of the console, then do not enable backups for your database in
 the console.
- Creating an On-Demand Backup by Using the bkup_api Utility
 You can use the bkup_api utility to create an on-demand backup of a complete
 database or an individual pluggable database (PDB):

How the Upgrade Operation Is Performed by the Database Service

Familiarize yourself with what the Database service does during the upgrade process.

- Executes an automatic precheck. This allows the system to identify issues needing mitigation and to stop the upgrade operation.
- Sets a guaranteed restore point, enabling it to perform a flashback in the event of an upgrade failure.
- Moves the database to a user-specified Oracle Database Home that uses the desired target software version.
- Runs the Database Upgrade Assistant (DBUA) software to perform the upgrade.

Rolling Back an Oracle Database Unsuccessful Upgrade

If your upgrade does not complete successfully, then you have the option of performing a rollback.

Details about the failure are displayed on the **Database Details** page in the Console, allowing you to analyze and resolve the issues causing the failure.

A rollback resets your database to the state prior to the upgrade. All changes to the database made during and after the upgrade will be lost. The rollback option is provided in a banner message displayed on the database details page of a database following an unsuccessful



Patch and Update an Exadata Database Service on Cloud@Customer System

upgrade operation. See *Using the Console to Roll Back a Failed Database Upgrade* for more information.

Related Topics

Using the Console to Roll Back a Failed Database Upgrade

After Upgrading an Oracle Database

After a successful upgrade, note the following:

- Check that automatic backups are enabled for the database if you disabled them prior to upgrading. See Customizing the Automatic Backup Configuration for more information.
- Edit the Oracle Database

COMPATIBLE

parameter to reflect the new Oracle Database software version. See *What Is Oracle Database Compatibility?* for more information.

- If your database uses a <code>database_name.env</code> file, ensure that the variables in the file have been updated to point to the 19c Database Home. These variables should be automatically updated during the upgrade process.
- If you are upgrading a non-container database to Oracle Database version 19c, you can convert the database to a pluggable database after converting. See How to Convert Non-CDB to PDB (Doc ID 2288024.1) for instructions on converting your database to a pluggable database.
- If your old Database Home is empty and will not be reused, you can remove it. See *Using the Console to Delete an Oracle Database Home* for more information.

Related Topics

- Configuring and Customizing Backups with bkup_api
 In addition to the console-based automated backup option, there is a command
 line backup utility, bkup_api, which can allow for further customization. If
 configuring backups using bkup_api instead of the console, then do not enable
 backups for your database in the console.
- What Is Oracle Database Compatibility?
- How to Convert Non-CDB to PDB Step by Step Example (Doc ID 2288024.1)
- Using the Console to Delete an Oracle Database Home
 To delete an Oracle Database home with the Console, use this procedure.

Using the Console to Manage Oracle Database Upgrade

Oracle recommends that you use the precheck action to ensure that your database has met the requirements for the upgrade operation.

- Using the Console to Run Oracle Database Upgrade Precheck or Perform Upgrade
- Using the Console to Roll Back a Failed Database Upgrade
- Using the Console to View the Upgrade History of a Database



Using the Console to Run Oracle Database Upgrade Precheck or Perform Upgrade

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of VM clusters, click the name of the VM cluster that contains the database you want to upgrade.
- 4. In the list of databases on the **VM Cluster Details** page, click the name of the database you want to upgrade to view the **Database Details** page.
- 5. Click Upgrade.
- 6. In the Upgrade Database dialog, select the following:
 - Oracle Database version: The drop-down selector lists only Oracle Database
 versions that are compatible with an upgrade from the current software version the
 database is using. The target software version must be higher than the database's
 current version.
 - Target Database Home: Select a Database Home for your database. The list of
 Database Homes is limited to those homes using the most recent versions of Oracle
 Database 19c software. Moving the database to the new Database Home results in
 the database being upgraded to the major release version and patching level of the
 new Database Home.
- 7. Click one of the following:
 - **Run Precheck:** This option starts an upgrade precheck to identify any issues with your database that need mitigation before you perform an upgrade.
 - Upgrade Database: This option starts upgrade operation. Oracle recommends
 performing an upgrade only after you have performed a successful precheck on the
 database.

Using the Console to Roll Back a Failed Database Upgrade

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of VM clusters, click the name of the VM cluster that contains the database with the failed upgrade.
- Find the database that was unsuccessfully upgraded, and click its name to display details about it.
- 5. The database must display a banner at the top of the details page that includes a **Rollback** button and details about what issues caused the upgrade failure.
- 6. Click Rollback.
- 7. In the **Confirm rollback** dialog, confirm that you want to initiate a rollback to the previous Oracle Database version.



Using the Console to View the Upgrade History of a Database

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the name of the VM cluster that contains the database you want to upgrade
- In the list of databases on the VM Cluster Details page, click the name of the database for which you want to view the upgrade history.
- On the Database Details page, under Database Version, click the View link that is displayed for databases that have been upgraded.

This link does not appear for databases that have not been updated.

The **Updates History** page is displayed. The table displayed on this page shows precheck and upgrade operations performed on the database.

Using the API to Upgrade Oracle Databases

Review the list of API calls to upgrade Oracle Databases.

For information about using the API and signing requests, see *REST APIs* and *Security Credentials*. For information about SDKs, see *Software Development Kits and Command Line Interface*.

Use the following APIs to manage database upgrades::

- getDatabaseUpgradeHistoryEntry
- ListDatabaseUpgradeHistoryEntries
- UpgradeDatabase

For the complete list of APIs, see Database Service API.

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface
- getDatabaseUpgradeHistoryEntry
- ListDatabaseUpgradeHistoryEntries
- UpgradeDatabase
- Database Service API

Patching and Updating an Exadata Database Service on Cloud@Customer System Manually

This topic describes the procedures for patching and updating various components in Exadata Database Service on Cloud@Customer outside of the cloud automation. For



information related to patching and updating with dbaascli, refer to "Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli".



For more guidance on achieving continuous service during patching operations, see the *Application Checklist for Continuous Service for MAA Solutions* white paper.

- Updating Software Manually
 For daylight savings time and some routine or one-off patches it can be necessary for you to patch software manually.
- Updating the Guest VM Operating System Manually
 Learn about standard Exadata tools and techniques you can use to update the operating system components on the Exadata Database Service on Cloud@Customer Guest VMs.

Related Topics

- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli
 Learn to use the dbaascli utility to perform patching operations for Oracle Grid
 Infrastructure and Oracle Database on an Exadata Cloud@Customer system.
- Application Checklist for Continuous Service for MAA Solutions

Updating Software Manually

For daylight savings time and some routine or one-off patches it can be necessary for you to patch software manually.

To perform routine patching of Oracle Database and Oracle Grid Infrastructure software, Oracle recommends that you use the facilities provided by Oracle Exadata Database Service on Cloud@Customer. However, under some circumstances, it can be necessary for you to patch the Oracle Database or Oracle Grid Infrastructure software manually:

- Daylight Savings Time (DST) Patching: Because they cannot be applied in a rolling fashion, patches for the Oracle Database DST definitions are not included in the routine patch sets for Exadata Database Service on Cloud@Customer. If you need to apply patches to the Oracle Database DST definitions, you must do so manually. See My Oracle Support Doc ID 412160.1.
- **Non-routine or One-off Patching:** If you encounter a problem that requires a patch which is not included in any routine patch set, then work with Oracle Support Services to identify and apply the appropriate patch.

For general information about patching Oracle Database, refer to information about patch set updates and requirements in *Oracle Database Upgrade Guide* for your release.

Related Topics

 https://support.oracle.com/epmos/faces/DocumentDisplay? cmd=show&type=NOT&id=412160.1

Updating the Guest VM Operating System Manually

Learn about standard Exadata tools and techniques you can use to update the operating system components on the Exadata Database Service on Cloud@Customer Guest VMs.



You are responsible for managing patches and updates to the operating system environment on the Database Server Virtual Machines (VMs). For more information, read about updating Exadata Database Machine servers in *Oracle Exadata Database Machine Maintenance Guide*.

- Preparing for an Operating System Update
 To prepare for an operating system update for Oracle Exadata Database Service on Cloud@Customer, review this checklist of tasks.
- Updating the Operating System on All Virtual Machines of an Oracle Exadata
 Database Service on Cloud@Customer System
 To update the operating system on the Database Server Virtual Machines (VMs), use the patchmar tool.
- Installing Additional Operating System Packages
 Review these guidelines before you install additional operating system packages for Oracle Exadata Database Service on Cloud@Customer.

Related Topics

Updating Oracle Exadata Database Machine Database Servers

Preparing for an Operating System Update

To prepare for an operating system update for Oracle Exadata Database Service on Cloud@Customer, review this checklist of tasks.

Before you update your operating system, do each of these preparation tasks:

Determine the latest software update. Before you begin an update, to determine the latest software to use, review Exadata Cloud Service Software Versions in My Oracle Support note 2333222.1.

Related Topics

 https://support.oracle.com/epmos/faces/DocumentDisplay? cmd=show&type=NOT&id=2333222.1

Updating the Operating System on All Virtual Machines of an Oracle Exadata Database Service on Cloud@Customer System

To update the operating system on the Database Server Virtual Machines (VMs), use the patchmgr tool.



Customers who do not have My Oracle Support patch download privilege may obtain the Exadata patchmgr update utility and recent Exadata System Software releases using the Exadata Cloud@Customer Gen 2 utility exadata_updates.sh. For more information, see My Oracle Support Doc 2730739.1.

The patchmgr utility manages the entire update of one or more virtual machines remotely, including the pre-restart, restart, and post-restart steps of an Oracle Exadata Database Service on Cloud@Customer system.



You can run the utility either from one of your Oracle Exadata Database Service on Cloud@Customer virtual machines, or from another server running Oracle Linux. The server on which you run the utility is known as the **driving system**. You cannot use the driving system to update itself. Therefore, if the driving system is one of the virtual machines in a VM cluster that you are updating, then you must run the patchmgr utility more than once. The following scenarios describe typical ways of performing the updates:

- Non-Exadata Driving System
 The simplest way to run the update the system is to use a separate Oracle Linux server to update all virtual machines in one operation.
- Exadata Virtual Machine Driving System
 You can use one virtual machine to drive the updates for the rest of the virtual machines
 in the VM cluster. Then, you can use one of the updated nodes to drive the update on the
 original driving system. For example, consider updating a half rack system with four
 virtual machines; node1, node2, node3, and node4. You could first use node1 to drive the
 updates of node2, node3, and node4. Then, you could use node2 to drive the update of
 node1.

The driving system requires root user SSH access to each virtual machine being updated.

The following procedure is based on an example that assumes the following:

- The system has two virtual machines, node1 and node2.
- The target Exadata software version is 18.1.4.0.0.180125.3.
- Each node is used as the driving system to update the other node.
- Gather the environment details.
 - a. Using SSH, connect to *node1* as the opc user. For detailed instructions, see *Connecting to a Compute Node with SSH*.
 - b. Start a root user command shell.

```
sudo su -
```

c. Run the following command to determine the current Exadata software version.

```
imageinfo -ver
```

For example:

```
# imageinfo -ver 19.2.13.0.0.200428
```

d. Switch to the grid user, and identify all nodes in the cluster.

```
su - grid
```

olsnodes



For example:

```
olsnodes
node1
node2
```

- 2. Configure the driving system.
 - a. Switch back to the root user on node1 and check whether an SSH key pair (id_rsa and id_rsa.pub) exists. If not, then generate it.

```
ls /root/.ssh/id rsa*
ls: cannot access /root/.ssh/id rsa*: No such file or directory
ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key (/root/.ssh/id rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /root/.ssh/id rsa.
Your public key has been saved in /root/.ssh/id rsa.pub.
The key fingerprint is:
93:47:b0:83:75:f2:3e:e6:23:b3:0a:06:ed:00:20:a5
root@nodel.example.com
The key's randomart image is:
+--[ RSA 2048]---+
|0.. + .
0.
      0 *
     . 0 0
| . .
        =
| o . S =
        = .
    + 00
  . . + .
```

b. Distribute the public key to the target nodes, and verify this step. In the example, the only target node is node2.

```
scp -i ~root/.ssh/id_rsa.pub opc@node2:/tmp/id_rsa.node1.pub
ls -al /tmp/id_rsa.node1.pub
-rw-r--r-- 1 opc opc 442 Feb 28 03:33 /tmp/id_rsa.node1.pub
date
Wed Feb 28 03:33:45 UTC 2018
```

c. On the target node (node2 in the example), add the root public key of node1 to the root authorized keys file.

```
cat /tmp/id_rsa.node1.pub >> ~root/.ssh/authorized_keys
```



d. Download patchmgr into /root/patch on the driving system (node1 in this example). You can download the patchmgr bundle from Oracle Support by using My Oracle Support Patch ID 21634633. Always obtain the latest available Exadata patchmgr update utility to install any Exadata System Software release.

For further information, see also <code>dbnodeupdate.sh</code> and <code>dbserver.patch.zip</code>: Updating Exadata Database Server Software using the <code>DBNodeUpdate</code> Utility and <code>patchmgr</code>: My Oracle Support Doc ID 1553103.1.

e. Unzip the patchmgr bundle.

Depending on the version that you downloaded, the name of your ZIP file can differ.

```
cd /root/patch/18.1.4.0.0.180125.3
unzip dbserver.patch.zip
Archive: p21634633 181400 Linux-x86-64.zip creating:
dbserver patch 5.180228.2/
creating: dbserver patch 5.180228.2/ibdiagtools/
inflating: dbserver_patch_5.180228.2/ibdiagtools/cable_check.pl
inflating: dbserver patch 5.180228.2/ibdiagtools/setup-ssh
inflating: dbserver patch 5.180228.2/ibdiagtools/VERSION FILE
extracting: dbserver patch 5.180228.2/ibdiagtools/xmonib.sh
inflating: dbserver patch 5.180228.2/ibdiagtools/monitord
inflating: dbserver patch 5.180228.2/ibdiagtools/checkbadlinks.pl
creating: dbserver patch 5.180228.2/ibdiagtools/topologies/
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/
VerifyTopologyUtility.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/
verifylib.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/Node.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/Rack.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/Group.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/topologies/Switch.pm
inflating: dbserver_patch_5.180228.2/ibdiagtools/topology-zfs
inflating: dbserver patch 5.180228.2/ibdiagtools/dcli
creating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
remoteScriptGenerator.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
CommonUtils.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
SolarisAdapter.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
LinuxAdapter.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
remoteLauncher.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
remoteConfig.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/spawnProc.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/netcheck/
runDiagnostics.pm
inflating: dbserver\_patch\_5.180228.2/ibdiagtools/netcheck/OSAdapter.pm
inflating: dbserver patch 5.180228.2/ibdiagtools/SampleOutputs.txt
inflating: dbserver patch 5.180228.2/ibdiagtools/infinicheck
inflating: dbserver patch 5.180228.2/ibdiagtools/ibping test
inflating: dbserver patch 5.180228.2/ibdiagtools/tar ibdiagtools
inflating: dbserver patch 5.180228.2/ibdiagtools/verify-topology
```



```
inflating: dbserver patch 5.180228.2/installfw exadata ssh
creating: dbserver patch 5.180228.2/linux.db.rpms/
inflating: dbserver patch 5.180228.2/md5sum files.lst
inflating: dbserver patch 5.180228.2/patchmgr
inflating: dbserver patch 5.180228.2/xcp
inflating: dbserver patch 5.180228.2/ExadataSendNotification.pm
inflating: dbserver patch 5.180228.2/ExadataImageNotification.pl
inflating: dbserver patch 5.180228.2/kernelupgrade oldbios.sh
inflating: dbserver patch 5.180228.2/cellboot usb pci path
inflating: dbserver patch 5.180228.2/exadata.img.env
inflating: dbserver patch 5.180228.2/README.txt
inflating: dbserver patch 5.180228.2/exadataLogger.pm
inflating: dbserver patch 5.180228.2/patch bug 26678971
inflating: dbserver patch 5.180228.2/dcli
inflating: dbserver patch 5.180228.2/patchReport.py
extracting: dbserver patch 5.180228.2/dbnodeupdate.zip
creating: dbserver patch 5.180228.2/plugins/
inflating: dbserver patch 5.180228.2/plugins/010-
check 17854520.sh
inflating: dbserver patch 5.180228.2/plugins/020-
check 22468216.sh
inflating: dbserver patch 5.180228.2/plugins/040-
check 22896791.sh
inflating: dbserver patch 5.180228.2/plugins/000-check dummy bash
inflating: dbserver patch 5.180228.2/plugins/050-
check 22651315.sh
inflating: dbserver patch 5.180228.2/plugins/005-
check 22909764.sh
inflating: dbserver patch 5.180228.2/plugins/000-check dummy perl
inflating: dbserver patch 5.180228.2/plugins/030-
check 24625612.sh
inflating: dbserver patch 5.180228.2/patchmgr functions
inflating: dbserver patch 5.180228.2/exadata.img.hw
inflating: dbserver patch 5.180228.2/libxcp.so.1
inflating: dbserver patch 5.180228.2/imageLogger
inflating: dbserver patch 5.180228.2/ExaXMLNode.pm
inflating: dbserver patch 5.180228.2/fwverify
```

f. In the directory that contains the patchmgr utility, create the dbs_group file, which contains the list of virtual machines to update. Include the nodes listed after running the olsnodes command in step 1, except for the driving system. In this example, dbs group only contains node2.

```
cd /root/patch/18.1.4.0.0.180125.3/dbserver_patch_5.180228
cat dbs_group
node2
```

3. Run a patching precheck operation.

```
./patchmgr -dbnodes dbs_group -precheck -iso_repo zipped_iso_file -target version target-version -nomodify at prereq
```





Run the precheck operation with the <code>-nomodify_at_prereq</code> option to prevent any changes to the system that could impact the backup you take in the next step. Otherwise, the backup might not be able to roll the system back to its original state, should it be necessary.

The output should look similar to the following example:

```
./patchmgr -dbnodes dbs group -precheck -iso repo /root/patch/
18.1.4.0.0.180125.3/exadata ol6 18.1.4.0.0.180125.3 Linux-x86-64.zip -
target version 18.1.4.0.0.180125.3 -nomodify at prereq
       patchmgr release: 5.180228 (always check MOS 1553103.1 for the
latest release of dbserver.patch.zip)
NOTE
WARNING Do not interrupt the patchmgr session.
WARNING Do not resize the screen. It may disturb the screen layout.
WARNING Do not reboot database nodes during update or rollback.
WARNING Do not open logfiles in write mode and do not try to alter them.
********************
*********
2018-02-28 21:22:45 +0000
                             :Working: DO: Initiate precheck on 1
node(s)
2018-02-28 21:24:57 +0000 :Working: DO: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:26:15 +0000 :SUCCESS: DONE: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:26:47 +0000 :Working: DO: dbnodeupdate.sh running a
precheck on node(s).
2018-02-28 21:28:23 +0000 :SUCCESS: DONE: Initiate precheck on
node(s).
```

4. Back up the current system.

```
./patchmgr -dbnodes dbs_group -backup -iso_repo zipped_iso_file -target version target-version -allow active network mounts
```

Note:

Ensure that you take the backup at this point, before any modifications are made to the system.

The output should look similar to the following example:

```
./patchmgr -dbnodes dbs_group -backup -iso_repo /root/patch/
18.1.4.0.0.180125.3/exadata_ol6_18.1.4.0.0.180125.3_Linux-x86-64.zip -
target version 18.1.4.0.0.180125.3 -allow active network mounts
```



```
******************
**********
      patchmgr release: 5.180228 (always check MOS 1553103.1 for
the latest release of dbserver.patch.zip)
NOTE
WARNING Do not interrupt the patchmgr session.
WARNING Do not resize the screen. It may disturb the screen layout.
WARNING Do not reboot database nodes during update or rollback.
WARNING Do not open logfiles in write mode and do not try to alter
them
*****************
**********
2018-02-28 21:29:00 +0000
                           :Working: DO: Initiate backup on 1
node(s).
2018-02-28 21:29:00 +0000
                           :Working: DO: Initiate backup on
node(s)
2018-02-28 21:29:01 +0000
                          :Working: DO: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:30:18 +0000 :SUCCESS: DONE: Check free space
and verify SSH equivalence for the root user to node2
2018-02-28 21:30:51 +0000
                           :Working: DO: dbnodeupdate.sh
running a backup on node(s).
2018-02-28 21:35:50 +0000
                           :SUCCESS: DONE: Initiate backup on
node(s).
2018-02-28 21:35:50 +0000
                          :SUCCESS: DONE: Initiate backup on
1 node(s).
```

- 5. Remove all custom RPMs from the target virtual machines. Custom RPMs are reported in precheck results. They include RPMs that were manually installed after the system was provisioned.
 - If you are updating the system from version 12.1.2.3.4.170111, and the precheck results include krb5-workstation-1.10.3-57.el6.x86_64, then remove it. This item is considered a custom RPM for this version.
 - Do not remove exadata-sun-vm-computenode-exact or oracle-ofed-release-guest. These two RPMs are handled automatically during the update process.
- 6. Perform the update. To ensure that the update process in not interrupted, use the command nohup. For example:

```
nohup ./patchmgr -dbnodes dbs\_group -upgrade -nobackup -iso_repo zipped_iso_file -target_version target-version - allow active network mounts &
```

The output should look similar to the following example:

```
nohup ./patchmgr -dbnodes dbs_group -upgrade -nobackup -iso_repo / root/patch/18.1.4.0.0.180125.3/
exadata_ol6_18.1.4.0.0.180125.3_Linux-x86-64.zip -target_version
18.1.4.0.0.180125.3 -allow_active_network_mounts &
```



```
*********
       patchmgr release: 5.180228 (always check MOS 1553103.1 for the
latest release of dbserver.patch.zip)
NOTE
NOTE Database nodes will reboot during the update process.
NOTE
WARNING Do not interrupt the patchmgr session.
WARNING Do not resize the screen. It may disturb the screen layout.
WARNING Do not reboot database nodes during update or rollback.
WARNING Do not open logfiles in write mode and do not try to alter them.
*******************
*******
2018-02-28 21:36:26 +0000
                             :Working: DO: Initiate prepare steps on
node(s).
2018-02-28 21:36:26 +0000 :Working: DO: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:37:44 +0000
                            :SUCCESS: DONE: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:38:43 +0000
                             :SUCCESS: DONE: Initiate prepare steps
on node(s).
2018-02-28 21:38:43 +0000
                             :Working: DO: Initiate update on 1
node(s).
2018-02-28 21:38:43 +0000
                              :Working: DO: Initiate update on node(s)
2018-02-28 21:38:49 +0000
                              :Working: DO: Get information about any
required OS upgrades from node(s).
2018-02-28 21:38:59 +0000
                              :SUCCESS: DONE: Get information about
any required OS upgrades from node(s).
2018-02-28 21:38:59 +0000
                             :Working: DO: dbnodeupdate.sh running an
update step on all nodes.
2018-02-28 21:48:41 +0000
                             :INFO : node2 is ready to reboot.
2018-02-28 21:48:41 +0000
                              :SUCCESS: DONE: dbnodeupdate.sh running
an update step on all nodes.
2018-02-28 21:48:41 +0000
                              :Working: DO: Initiate reboot on node(s)
                              :SUCCESS: DONE: Initiate reboot on
2018-02-28 21:48:57 +0000
node(s)
2018-02-28 21:48:57 +0000
                             :Working: DO: Waiting to ensure node2 is
down before reboot.
2018-02-28 21:56:18 +0000
                             :Working: DO: Initiate prepare steps on
node(s).
2018-02-28 21:56:19 +0000
                             :Working: DO: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:57:37 +0000
                              :SUCCESS: DONE: Check free space and
verify SSH equivalence for the root user to node2
2018-02-28 21:57:42 +0000 :SEEMS ALREADY UP TO DATE: node2
2018-02-28 21:57:43 +0000
                             :SUCCESS: DONE: Initiate update on
node(s)
```

7. After the update operation completes, verify the version of the Exadata software on the virtual machine that was updated.

```
imageinfo -ver
18.1.4.0.0.180125.3
```



- 8. Repeat steps 2 through 7 of this procedure using the updated virtual machine as the driving system to update the remaining virtual machine. In this example update, you would now use node2 to update node1.
- **9.** As root On each virtual machine, run the uptrack-install command to install the available ksplice updates.

```
uptrack-install --all -y
uptrack-install --all -y
```

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.
- https://support.oracle.com/epmos/faces/DocumentDisplay? cmd=show&type=NOT&id=2730739.1
- https://support.oracle.com/epmos/faces/DocumentDisplay? cmd=show&type=NOT&id=1553103.1
- https://support.oracle.com/epmos/faces/ui/patch/PatchDetail.jspx? patchId=21634633

Installing Additional Operating System Packages

Review these guidelines before you install additional operating system packages for Oracle Exadata Database Service on Cloud@Customer.

You are permitted to install and update operating system packages on Oracle Exadata Database Service on Cloud@Customer as long as you do not modify the kernel or InfiniBand-specific packages. However, Oracle technical support, including installation, testing, certification and error resolution, does not apply to any non-Oracle software that you install.

Also be aware that if you add or update packages separate from an Oracle Exadata software update, then these package additions or updates can introduce problems when you apply an Oracle Exadata software update. Problems can occur because additional software packages add new dependencies that can interrupt an Oracle Exadata update. For this reason, Oracle recommends that you minimize customization.

If you install additional packages, then Oracle recommends that you have scripts to automate the removal and reinstallation of those packages. After an Oracle Exadata update, if you install additional packages, then verify that the additional packages are still compatible, and that you still need these packages.

For more information, refer to Oracle Exadata Database Machine Maintenance Guide.

Related Topics

Installing, Updating and Managing Non-Oracle Software



Use Oracle Data Guard with Exadata Database Service on Cloud@Customer

Learn to configure and manage Data Guard associations in your VM cluster.

- About Using Oracle Data Guard with Exadata Database Service on Cloud@Customer
 This topic explains how to use the Console or the API to manage Data Guard
 associations in your VM cluster.
- Prerequisites for Using Oracle Data Guard with Exadata Database Service on Cloud@Customer
 - Review the list of prerequisites for using Data Guard with Exadata Database Service on Cloud@Customer.
- Working with Data Guard
 Oracle Data Guard ensures high availability, data protection, and disaster recovery for
 enterprise data.
- Using the Console to Manage Oracle Data Guard Associations
 Learn how to enable a Data Guard association between databases, change the role of a
 database in a Data Guard association using either a switchover or a failover operation,
 and reinstate a failed database.
- Using the API to Manage Data Guard Associations on an Exadata Database Service on Cloud@Customer System

 Learn how to use the API to manage Data Guard associations on an Exadata Database Service on Cloud@Customer system.

About Using Oracle Data Guard with Exadata Database Service on Cloud@Customer

This topic explains how to use the Console or the API to manage Data Guard associations in your VM cluster.

When you use the Console or the API to enable Data Guard for an Exadata database compute node database:

- The standby database is a physical standby.
- The versions of peer databases (primary and standby) are identical.
- You are limited to one standby database for each primary database.
- The standby database is deployed as an open, read-only database (Active Data Guard).

To configure a Data Guard system across regions or between on-premises and Exadata database compute nodes, or to configure your database with multiple standbys, you must access the database host directly and set up Data Guard manually.

For complete information on Oracle Data Guard, see the *Data Guard Concepts and Administration* documentation on the *Oracle Document Portal*.

Related Topics

- Data Guard Concepts and Administration
- Oracle Document Portal



Prerequisites for Using Oracle Data Guard with Exadata Database Service on Cloud@Customer

Review the list of prerequisites for using Data Guard with Exadata Database Service on Cloud@Customer.

Compute Nodes

A VM cluster Data Guard implementation requires two Exadata database compute nodes, one containing the primary database and one containing the standby database.

Password

For Data Guard operations to work, the SYS password and the TDE wallet password of the primary and standby databases must all be the same.

Compute Nodes

A VM cluster Data Guard implementation requires two Exadata database compute nodes, one containing the primary database and one containing the standby database.

When you enable Data Guard for an Exadata database compute node database, the Exadata database compute node with the database to be used as the standby must already exist before you enable Data Guard.

Password

For Data Guard operations to work, the SYS password and the TDE wallet password of the primary and standby databases must all be the same.

If you change any one of these passwords, you must update the rest of the passwords to match.

If you make any change to the TDE wallet (such as adding a master key for a new PDB or changing the wallet password), you must copy the wallet from the primary to the standby so that Data Guard can continue to operate. For Oracle Database versions earlier than 12.2, if you change the SYS password on one of the peers, you need to manually sync the password file between the DB systems.

Working with Data Guard

Oracle Data Guard ensures high availability, data protection, and disaster recovery for enterprise data.

The Data Guard implementation requires two databases, one in a primary role and one in a standby role. The two databases compose a Data Guard association. Most of your applications access the primary database. The standby database is a transactionally consistent copy of the primary database.

Data Guard maintains the standby database by transmitting and applying redo data from the primary database. If the primary database becomes unavailable, you can use Data Guard to switch or fail over the standby database to the primary role.

Switchover

A switchover reverses the primary and standby database roles.



Failover

A failover transitions the standby database into the primary role after the existing primary database fails or becomes unreachable.

Reinstate

Reinstates a database into the standby role in a Data Guard association.

Switchover

A switchover reverses the primary and standby database roles.

Each database continues to participate in the Data Guard association in its new role. A switchover ensures no data loss. You can use a switchover before you perform planned maintenance on the primary database. Performing planned maintenance on a Exadata database compute node with a Data Guard association is typically done by switching the primary to the standby role, performing maintenance on the standby, and then switching it back to the primary role.

Failover

A failover transitions the standby database into the primary role after the existing primary database fails or becomes unreachable.

A failover might result in some data loss when you use **Maximum Performance** protection mode.

Reinstate

Reinstates a database into the standby role in a Data Guard association.

You can use the reinstate command to return a failed database into service after correcting the cause of failure.



You can't terminate a primary database that has a Data Guard association with a peer (standby) database. Delete the standby database first. Alternatively, you can switch over the primary database to the standby role, and then terminate the former primary.

You can't terminate a VM cluster that includes Data Guard enabled databases. You must first remove the Data Guard association by terminating the standby database.

Using the Console to Manage Oracle Data Guard Associations

Learn how to enable a Data Guard association between databases, change the role of a database in a Data Guard association using either a switchover or a failover operation, and reinstate a failed database.

When you enable Data Guard, a separate Data Guard association is created for the primary and the standby database.



 Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System

Learn to enable Data Guard association between databases.

- Using the Console To View and Edit Data Guard Associations
 You can switch between Data Guard types based on the Oracle Database software license type you have deployed.
- Using the Console To Perform a Database Switchover
 You initiate a switchover operation by using the Data Guard association of the
 primary database.
- Using the Console To Perform a Database Failover
 You initiate a failover operation by using the Data Guard association of the standby
 database.
- Using the Console To Reinstate a Database
 After you fail over a primary database to its standby, the standby assumes the primary role and the old primary is identified as a disabled standby.
- Using the Console To Terminate a Data Guard Association on an Exadata
 Database Service on Cloud@Customer System
 On a VM cluster, you remove a Data Guard association by terminating the standby database.

Using the Console to Enable Data Guard on an Exadata Database Service on Cloud@Customer System

Learn to enable Data Guard association between databases.



When you enable Data Guard, replication of data happens only over the client network.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

- 2. Choose your Compartment.
 - A list of VM Clusters is displayed for the chosen Compartment.
- 3. In the list of VM clusters, click the VM cluster that contains the database for which you want to assume the primary role, and then click the name of that database.
- 4. Under Resources, click Data Guard Associations.
- 5. Click Enable Data Guard.
- 6. On the Enable Data Guard page, configure your Data Guard association.
 - Data Guard association details:
 - Select a Data Guard type, Active Data Guard or Data Guard, based on the Oracle Database software license type you have deployed. If you have deployed Oracle Database Enterprise Edition Extreme Performance (License Included), then you may choose either Data Guard or Active



Data Guard. If you have deployed Bring Your Own License (BYOL) Oracle Database Enterprise Edition without the Active Data Guard option, then you would select Data Guard, which is the default.

- * Active Data Guard: Active Data Guard is a licensed option to the Oracle Database Enterprise Edition and enables advanced capabilities that extend the basic Data Guard functionality. These capabilities include Real-Time Query and DML Offload, Automatic Block Repair of physical data corruptions, Standby Block Change Tracking, Far Sync, Global Data Services, and Application Continuity.
- * Data Guard: Oracle Data Guard ensures high availability, data protection, and disaster recovery for enterprise data. Data Guard provides a comprehensive set of services that create, maintain, manage, and monitor one or more standby databases to enable production Oracle databases to survive disasters and data corruptions. Data Guard maintains these standby databases as transactionally consistent copies of the production database.
- Protection mode: The protection mode used for this Data Guard association.
 - Maximum Performance provides the highest level of data protection that is possible without affecting the performance of a primary database.
 - Maximum Availability provides the highest level of protection of data with zero data loss synchronous transport without compromising the availability of the database.
- Transport type: The redo transport type used for this Data Guard association.
 - Async Asynchronous transport mode used with Maximum Performance protection mode.
 - Sync Synchronous transport mode used with Maximum Performance and Maximum Availability protection mode.
- Select peer VM cluster: Specify the following values for the standby:
 - Peer Region: Currently, the peer region is auto-populated and you cannot change it. The primary and secondary databases could be running on two different VM clusters on a shared Exadata Database Service on Cloud@Customer system, or on two geographically separated Exadata Database Service on Cloud@Customer systems managed from a single Oracle Cloud Infrastructure region.
 - Peer Exadata: Select the Exadata Database Service on Cloud@Customer infrastructure where the standby database is located. Click the CHANGE COMPARTMENT hyperlink to choose a compartment.
 - Peer VM Cluster: Select the Exadata database compute node that contains the standby database. Click the CHANGE COMPARTMENT hyperlink to choose a compartment.
- Choose Database Home: Select an existing Database Home or create one as applicable.
 - Select an existing Database Home: If one or more Database Homes already exist for the database version you have selected, then this option is selected by default. And, you will be presented with a list of Database Homes. Select a Database Home from the list.



Note:

Although only Database homes of the same version and RU are listed, the homes displayed may have different one-off patches than the primary. Though acceptable to have different one-offs, best practice is to have identical database homes between primary and standby.

- Create a new Database Home: If no Database Homes exist for the database version you have selected, then this option is selected by default.
- Configure standby database:
 - Provide a unique name for the database:



You cannot modify the db_name, db_unique_name, and SID prefix after creating the database.

Optionally, specify a unique name for the database. This attribute defines the value of the <code>db_unique_name</code> database parameter. The value is case insensitive. The <code>db_unique_name</code> must contain only the permitted characters.

Review the following guidelines when selecting a database name:

- maximum of 30 characters
- * can contain alphanumeric and underscore () characters
- begin with an alphabetic character
- unique across the fleet/tenancy

If a unique name is not entered, then the db_unique_name defaults to the following format <db name> <3 char unique string> <region-name>.

- Database password: Enter the database admin password of the primary database in the Database password field. This same database admin password will be used for the standby database.
 - The admin password and the TDE password must be the same. If they are not, follow the instructions in *Changing the Database Passwords* to align them.
- (Optional) Select Show Advanced Options.
 - Provide the Oracle SID prefix: Optionally, specify the Oracle SID prefix for the database. The instance number is automatically appended to the SID prefix to become the instance_name database parameter. If not provided, then the SID prefix defaults to the first 12 characters of the db unique name.

Review the following guidelines when selecting a database name:

- maximum of 12 characters
- contain only alphanumeric characters



- * begin with an alphabetic character
- unique in the VM cluster

7. Click Enable Data Guard.

When the association is created, the details for a database and its peer display their respective roles as **Primary** or **Standby**.

Related Topics

- Network Requirements for Oracle Exadata Database Service on Cloud@Customer
 To provide secure and reliable network connectivity for different application and
 management functions, Exadata Database Service on Cloud@Customer uses different
 networks.
- Changing the Database Passwords
 To change the SYS password, or to change the TDE wallet password, use this procedure.

Using the Console To View and Edit Data Guard Associations

You can switch between Data Guard types based on the Oracle Database software license type you have deployed.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster that contains the primary database you want to switch Data Guard type.
- 4. Click the name of the primary database.
- 5. Under Resources, click Data Guard Associations.

A list of Data Guard Associations is displayed with the **Data Guard Type** you have chosen for each Data Guard Association.

- For the Data Guard Association on which you want to perform a Data Guard type switchover, click the Actions icon (three dots), and then click Edit Data Guard Association.
- 7. Select an applicable Data Guard type and then click **Edit Data Guard**.

Using the Console To Perform a Database Switchover

You initiate a switchover operation by using the Data Guard association of the primary database.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.



- 3. In the list of VM clusters, click the VM cluster that contains the primary database you want to switch over.
- 4. Click the name of the primary database.
- 5. Under Resources, click Data Guard Associations.
- **6.** For the Data Guard association on which you want to perform a switchover, click the Actions icon (three dots), and then click **Switchover**.
- In the Switchover Database dialog box, enter the database admin password, and then click OK.

This database should now assume the role of the standby, and the standby should assume the role of the primary in the Data Guard association.

Using the Console To Perform a Database Failover

You initiate a failover operation by using the Data Guard association of the standby database.

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster that contains the primary database's peer standby you want to fail over to.
- 4. Click the name of the standby database.
- 5. Under Resources, click Data Guard Associations.
- **6.** For the Data Guard association on which you want to perform a failover, click the Actions icon (three dots), and then click **Failover**.
- In the Failover Database dialog box, enter the database admin password, and then click OK.

This database should now assume the role of the primary, and the old primary's role should display as **Disabled Standby**.

Using the Console To Reinstate a Database

After you fail over a primary database to its standby, the standby assumes the primary role and the old primary is identified as a disabled standby.

After you correct the cause of failure, you can reinstate the failed database as a functioning standby for the current primary by using its Data Guard association.

Before you can reinstate a version 12.2 or later database, you must perform some steps on the database host to stop the database or start it in MOUNT mode.



Set your <code>ORACLE_UNQNAME</code> environment variable to the value of the Database Unique Name, and then run these commands:

```
srvctl stop database -d db-unique-name -o abort
srvctl start database -d db-unique-name -o mount
```

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster that contains the primary database.
- Click the name of the primary database.
- 5. Under Resources, click Data Guard Associations.

You will see the database you want to reinstate listed.

- 6. Click the Actions icon (three dots), and then click Reinstate.
- In the Reinstate Database dialog box, enter the database admin password, and then click OK.

This database should now be reinstated as the standby in the Data Guard association.

Using the Console To Terminate a Data Guard Association on an Exadata Database Service on Cloud@Customer System

On a VM cluster, you remove a Data Guard association by terminating the standby database.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.

VM Clusters is selected by default.

2. Choose your Compartment.

A list of VM Clusters is displayed for the chosen Compartment.

- 3. In the list of VM clusters, click the VM cluster that contains the standby database you want to terminate.
- Click the name of the standby database.
- For the standby database you want to terminate, click the Actions icon (three dots), and then click **Terminate**.
- In the Terminate Database dialog box, enter the name of the database, and then click OK.



Using the API to Manage Data Guard Associations on an Exadata Database Service on Cloud@Customer System

Learn how to use the API to manage Data Guard associations on an Exadata Database Service on Cloud@Customer system.

For information about using the API and signing requests, see REST APIs and Security Credentials. For information about SDKs, see Software Development Kits and Command Line Interface.

The following table lists the REST API endpoints to manage Data Guard associations.

Operation	REST API Endpoint
Create a Data Guard association.	CreateDataGuardAssociation
View details of the specified Data Guard association's configuration information.	GetDataGuardAssociation
View the list of all Data Guard associations for the specified database.	ListDataGuardAssociations
Perform a switchover to transition a primary database of a Data Guard association into standby role.	SwitchoverDataGuardAssociation
Perform a failover to transition a standby database identified by the databaseId parameter into the specified Data Guard association's primary role after the existing primary database fails or becomes unreachable.	FailoverDataGuardAssociation
Reinstate a database identified by the	ReinstateDataGuardAssociation
databaseId parameter into standby role in a Data Guard association.	For more information, see Using the Console To Reinstate a Database.
Delete a standby database.	DeleteDatabase

For the complete list of APIs, see Database Service API.

Migrate to Exadata Database Service on Cloud@Customer

For general guidance on methods and tools to migrate databases to Oracle Cloud Infrastructure database services, including Exadata Cloud@Customer see "Migrating Databases to the Cloud".

A recommended approach for migrating to Exadata Cloud@Customer is using Zero Downtime Migration

Moving to Oracle Cloud Using Zero Downtime Migration

Related Topics

Migrating Databases to the Cloud

Moving to Oracle Cloud Using Zero Downtime Migration



Oracle now offers the Zero Downtime Migration service, a quick and easy way to move onpremises databases to Oracle Cloud Infrastructure.

Zero Downtime Migration leverages Oracle Active Data Guard to create a standby instance of your database in an Oracle Cloud Infrastructure system. You switch over only when you are ready, and your source database remains available as a standby. Use the Zero Downtime Migration service to migrate databases individually or at the fleet level. See *Move to Oracle Cloud Using Zero Downtime Migration* for more information.

Related Topics

Move to Oracle Cloud Using Zero Downtime Migration

Overview of Exadata Cloud@Customer Gen1 to Out-of-Place Cloud Upgrade to Exadata Database Service on Cloud@Customer Gen2 Infrastructure

Gen1 is the first generation of Exadata Database Service on Cloud@Customer, which is deployed in conjunction with Gen1 Oracle Cloud At Customer (OCC) as Control Plane deployed in the customer data center. Exadata Database Service on Cloud@Customer Gen2 is managed from Oracle Cloud Infrastructure (OCI) Control Plane, which runs in OCI public cloud.

Out-of-Place Cloud Upgrade to Exadata Database Service on Cloud@Customer Gen2 Infrastructure: If you are running Exadata Cloud@Customer Gen1 on X6 or X7 infrastructure, with this offering Oracle will replace Gen1 X6 or X7 infrastructure with new Gen2 Exadata Cloud@Customer Infrastructure, and provide instructions to use Oracle Zero Downtime Migration (ZDM) to migrate your databases on the Exadata Cloud@Customer Gen1 platform to Exadata Cloud@Customer Gen2 platform. Replacing your Exadata Cloud@Customer Gen1 X6 or X7 infrastructure and migrating your databases to the Exadata Cloud@Customer Gen2 platform is called an out-of-place cloud upgrade.

- Scope for Exadata Cloud@Customer Gen1 to Gen2 Out-of-Place Cloud Upgrade
- Hardware and Software Required for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure Review this checklist to prepare for the out-of-place cloud upgrade to new Gen2 infrastructure:
- Using Oracle Zero Downtime Migration (ZDM) to Migrate Oracle Databases
 Use ZDM to migrate Oracle databases from Exadata Cloud@Customer Gen1 to Exadata Cloud@Customer Gen2 infrastructure.
- During Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure
- Post Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure
 The upgrade will move your resources into Exadata Cloud@Customer Gen 2 Cloud
 Control Plane and onto the new generation hardware.
- Best Practices for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2
 Infrastructure
 - For the purpose of the upgrade, the recommended tool to use is Oracle Zero Downtime Migration (ZDM).



Scope for Exadata Cloud@Customer Gen1 to Gen2 Out-of-Place Cloud Upgrade

- Exadata Cloud@Customer X6 and X7 System Shapes are eligible for the out-ofplace upgrade.
- Databases on Exadata Cloud@Customer Gen1 which participate in a Data Guard configuration are supported by migration. In this case, the primary should be migrated to Exadata Cloud@Customer Gen2 using the regular procedure. Once migration is done, the Data Guard configuration should be set up on the Exadata Cloud@Customer Gen2 side using the regular Gen2 procedure.
- Upgrade from Exadata Cloud@Customer Gen1 to Gen2 is done only when the software versions are compatible on the source and target systems.
 - Oracle Database software: The source and target must be at the same major version. For example, both the source and target must be at version 19c. However, the target can have a higher patch level than the source. For example, the patch versions can be 19.3 for the source and 19.8 for the target. The corresponding equivalence for 12.2 is, both source and the target must be at Oracle Database software version 12.2.0.1, but the patch levels can be 2019JulyRU on the source and 2020octRU on the target.
 - Non-Container Database (CDB) to non-CDB.
 - Multitenant deployment (CDB/PDB) to Multitenant deployment (CDB/PDB).
 - Single-instance Oracle Database: After migration, single-instance database source will be converted to Oracle Real Application Clusters (Oracle RAC) database on the target.
- Permitted differences in software versions include:
 - Oracle Grid Infrastructure
 - Exadata software
 - Guest VM operating system
 - DBaaS tools
- Oracle Databases created on Exadata Cloud@Customer Gen1 using backend tools, dbaasapi and dbaascli, are supported as well besides Oracle Databases created using the Gen1 Console.
- All supported versions of Oracle Database on Exadata Cloud@Customer Gen1
 are supported and will be migrated to the same major version on the target. The
 Gen2 environment will be on the latest supported version of Exadata
 Cloud@Customer Gen2 for the Guest VM operating system and Oracle Grid
 Infrastructure.

Note that the following are not in scope for the out-of-place cloud upgrade to new Gen2 hardware:

- Exadata Cloud@Customer Gen1 deployment using Exadata Cloud@Customer Gen1 features not yet available on Gen2 are not expected to use the upgrade procedures until the relevant feature or equivalent is available on Gen2.
- Only Exadata Cloud@Customer upgrade is in scope as part of the procedure here. Upgrade or migration of OCC itself is not in the scope.



 You can reverse the upgrade until both the primary and secondary hardware is at your site. Loss of data is possible depending on the application usage and cutover time. Once the Exadata Cloud@Customer Gen1 hardware is shipped back to Oracle, you cannot reverse the upgrade and you cannot revert to Exadata Cloud@Customer Gen1 as well.

Hardware and Software Required for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure

Review this checklist to prepare for the out-of-place cloud upgrade to new Gen2 infrastructure:

- Setup Exadata Cloud@Customer Gen2 Environment
 - A functioning base Exadata Cloud@Customer Gen2 deployment is a pre-requisite for starting any Exadata Cloud@Customer Gen1 to Gen2 out-of-place upgrade.
 - For more information to setup your Gen2 Exadata Cloud@Customer, see *Preparing for Exadata Cloud@Customer*.
- Setup Hardware to Migrate Oracle Databases using Oracle Zero Downtime Migration (ZDM). For more information, see Prepare a Host for Zero Downtime Migration Software Installation
- Configure network
 - Provide network access path from the Exadata Cloud@Customer Gen1 servers and the Gen2 servers to the ZDM servers used for the upgrade.
 - Provide network access and SSH access from the ZDM server to the respective Exadata Cloud@Customer infrastructure.
 - For any client access to the target databases, ensure that a network path is available from the client host to the new Exadata Cloud@Customer Gen2 deployed databases.

Software

- The upgrade will require minimum versions of the software stack so prior to the upgrade, install the appropriate version of Oracle Grid Infrastructure on the target Exadata Cloud@Customer Gen2 infrastructure.
- Oracle Database versions supported on Exadata Cloud@Customer Gen1 will
 continue to be supported. On the target Gen2 infrastructure, install appropriate
 versions of the Oracle Database software and the one-off patches that exist in the
 source database.
- Complete all requirements for ZDM servers in terms of installation, configuration, network access, and SSH access.

Security

- Exadata Cloud@Customer Gen2 does not use Oracle Advanced Support Gateway Security (OASG) so cannot request OASG logs.
- Ensure that automatic backup is not configured on the Gen2 target prior to migration.

Related Topics

- Preparing for Exadata Database Service on Cloud@Customer
 Review OCI as well as the site, network and storage requirements to prepare and deploy
 Exadata Database Service on Cloud@Customer in your data center.
- Prepare a Host for Zero Downtime Migration Software Installation



 Best Practices for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure

For the purpose of the upgrade, the recommended tool to use is Oracle Zero Downtime Migration (ZDM).

Using Oracle Zero Downtime Migration (ZDM) to Migrate Oracle Databases

Use ZDM to migrate Oracle databases from Exadata Cloud@Customer Gen1 to Exadata Cloud@Customer Gen2 infrastructure.

To familiarize yourself with the features of ZDM, see *Setting Up Zero Downtime Migration Software*. As the first step, download, install and configure ZDM on the host identified for the ZDM server.

Zero Downtime Migration supports both online and offline (backup and recovery) migration. For Exadata Cloud@Customer upgrade from Gen1 to Gen2, it is recommended to use ZDM Physical Migration. Specifically, it is recommended to use Online Migration with Direct Data Transfer (online physical migration (MIGRATION_METHOD=ONLINE_PHYSICAL) using direct data transfer (DATA_TRANSFER_MEDIUM=DIRECT). Online Migration with Direct Data Transfer is available with Zero Downtime Migration 21.2 and supports direct data transfer for the physical migration methodology. This new feature allows users to avoid using an intermediate store for backups (normally NFS or the OCI Object Storage). ZDM leverages either active database duplication (for 11.2 databases) or restore from service (for 12+ databases). You can use this method to do migrate your Exadata Cloud@Customer Gen1 databases to Exadata Cloud@Customer Gen2. Examples of the command-line and response files are provided below for reference.

For more information, see:

- Introduction to Zero Downtime Migration
- Preparing for Database Migration
- Migrating Your Database with Zero Downtime Migration

Example 5-4 Active Duplicate

```
zdmcli migrate database -sourcedb z19tgt1 -sourcenode
scaqae03client01vm06 -srcauth zdmauth -srcarg1 user:opc -srcarg2
identity file:/home/giusr/.ssh/id gen1vm -srcarg3
sudo location:/usr/bin/sudo -targetnode tgt1 -rsp /home/giusr/
activeduplicate zdm online 19c.rsp -tgtauth zdmauth -tgtarg1 user:opc -
tgtarg2 identity file:/home/giusr/.ssh/dbaas sshkey.priv -tgtarg3
sudo location:/usr/bin/sudo -schedule NOW -tdekeystorepasswd
ZDM GET SRC INFO ..... COMPLETED
ZDM GET TGT INFO ..... COMPLETED
ZDM PRECHECKS SRC ..... COMPLETED
ZDM PRECHECKS TGT ..... COMPLETED
ZDM SETUP SRC ..... COMPLETED
ZDM SETUP TGT ..... COMPLETED
ZDM PREUSERACTIONS ..... COMPLETED
ZDM PREUSERACTIONS TGT ..... COMPLETED
ZDM VALIDATE SRC ..... COMPLETED
ZDM VALIDATE TGT ..... COMPLETED
```



ZDM DISCOVER SRC	COMPLETED
ZDM COPYFILES	COMPLETED
ZDM PREPARE TGT	COMPLETED
ZDM SETUP TDE TGT	COMPLETED
ZDM DUPLICATE TGT	COMPLETED
ZDM FINALIZE TGT	COMPLETED
ZDM CONFIGURE DG SRC	COMPLETED
ZDM SWITCHOVER SRC	COMPLETED
ZDM SWITCHOVER TGT	COMPLETED
ZDM POST DATABASE OPEN TGT	COMPLETED
ZDM DATAPATCH TGT	COMPLETED
ZDM MANIFEST TO CLOUD	COMPLETED
ZDM_POST_MIGRATE_TGT	COMPLETED
ZDM_POSTUSERACTIONS	COMPLETED
ZDM_POSTUSERACTIONS_TGT	COMPLETED
ZDM_CLEANUP_SRC	COMPLETED
ZDM_CLEANUP_TGT	COMPLETED

Example 5-5 Active Duplicate Response File

```
TGT DB UNIQUE NAME=z19tgt1 uniq2
MIGRATION METHOD=ONLINE PHYSICAL
DATA TRANSFER MEDIUM=DIRECT
PLATFORM TYPE=EXACC
SRC_HTTP_PROXY_URL=
SRC_HTTP_PROXY_PORT=
SRC CONFIG LOCATION=
SRC BASTION HOST IP=
SRC BASTION PORT=
SRC BASTION USER=
SRC_BASTION_IDENTITY_FILE=
SRC HOST IP=
SRC TIMEZONE=
SRC OSS PROXY HOST=
SRC OSS PROXY PORT=
SRC_SSH_RETRY_TIMEOUT=
SRC PDB NAME=
SRC DB LISTENER PORT=
TGT HTTP PROXY URL=
TGT_HTTP_PROXY_PORT=
TGT_CONFIG_LOCATION=
TGT_BASTION_HOST_IP=
TGT BASTION PORT=
TGT_BASTION_USER=
TGT_BASTION_IDENTITY_FILE=
TGT HOST IP=
TGT_SSH_TUNNEL_PORT=
TGT SSH RETRY TIMEOUT=
TGT OSS PROXY HOST=
TGT OSS PROXY PORT=
TGT DATADG=
TGT REDODG=
TGT RECODG=
TGT DATAACFS=
```



```
TGT REDOACFS=
TGT RECOACFS=
BACKUP PATH=
HOST=
OPC CONTAINER=
SRC ZDLRA WALLET LOC=
TGT ZDLRA WALLET LOC=
ZDLRA CRED ALIAS=
NONCOBTOPDB CONVERSION=FALSE
NONCOBTOPDB SWITCHOVER=TRUE
SKIP FALLBACK=TRUE
TGT RETAIN DB UNIQUE NAME=
TGT SKIP DATAPATCH=FALSE
MAX DATAPATCH DURATION MINS=
DATAPATCH WITH ONE INSTANCE RUNNING=
SHUTDOWN SRC=
SKIP SRC SERVICE RETENTION=
SRC RMAN CHANNELS=6
TGT RMAN CHANNELS=16
ZDM LOG OSS PAR URL=
ZDM BACKUP FULL SRC MONITORING INTERVAL=10
ZDM BACKUP INCREMENTAL SRC MONITORING INTERVAL=10
ZDM BACKUP DIFFERENTIAL SRC MONITORING INTERVAL=10
ZDM CLONE TGT MONITORING INTERVAL=10
ZDM OSS RESTORE TGT MONITORING INTERVAL=10
ZDM OSS RECOVER TGT MONITORING INTERVAL=10
ZDM BACKUP RETENTION WINDOW=
ZDM BACKUP TAG=
ZDM USE EXISTING BACKUP=
ZDM OPC RETRY WAIT TIME=
ZDM OPC RETRY COUNT=
ZDM SRC TNS ADMIN=
ZDM CURL LOCATION=
ZDM USE EXISTING UNDO SIZE=
ZDM SKIP DG CONFIG CLEANUP=
ZDM RMAN COMPRESSION ALGORITHM=LOW
ZDM SRC DB RESTORE SERVICE NAME=
ZDM RMAN DIRECT METHOD=ACTIVE DUPLICATE
```

Example 5-6 Restore from Service



ZDM_PREUSERACTIONS	COMPLETED
<pre>ZDM_PREUSERACTIONS_TGT</pre>	COMPLETED
ZDM_VALIDATE_SRC	COMPLETED
ZDM_VALIDATE_TGT	COMPLETED
<pre>ZDM_DISCOVER_SRC</pre>	COMPLETED
ZDM_COPYFILES	COMPLETED
ZDM_PREPARE_TGT	COMPLETED
ZDM_SETUP_TDE_TGT	COMPLETED
ZDM_RESTORE_TGT	COMPLETED
ZDM_RECOVER_TGT	COMPLETED
ZDM_FINALIZE_TGT	COMPLETED
ZDM_CONFIGURE_DG_SRC	COMPLETED
ZDM_SWITCHOVER_SRC	COMPLETED
ZDM_SWITCHOVER_TGT	COMPLETED
<pre>ZDM_POST_DATABASE_OPEN_TGT</pre>	COMPLETED
ZDM_DATAPATCH_TGT	COMPLETED
ZDM_MANIFEST_TO_CLOUD	COMPLETED
<pre>ZDM_POST_MIGRATE_TGT</pre>	COMPLETED
ZDM_POSTUSERACTIONS	COMPLETED
<pre>ZDM_POSTUSERACTIONS_TGT</pre>	COMPLETED
ZDM_CLEANUP_SRC	COMPLETED
ZDM_CLEANUP_TGT	COMPLETED

Example 5-7 Restore from Service Response File

```
TGT DB UNIQUE NAME=z12tgt1s uniq
MIGRATION METHOD=ONLINE PHYSICAL
DATA TRANSFER MEDIUM=DIRECT
PLATFORM TYPE=EXACC
SRC_HTTP_PROXY_URL=
SRC_HTTP_PROXY_PORT=
SRC CONFIG LOCATION=
SRC BASTION HOST IP=
SRC_BASTION_PORT=
SRC BASTION USER=
SRC_BASTION_IDENTITY_FILE=
SRC HOST IP=
SRC TIMEZONE=
SRC OSS PROXY HOST=
SRC_OSS_PROXY_PORT=
SRC SSH RETRY TIMEOUT=
SRC PDB NAME=
SRC DB LISTENER PORT=
TGT HTTP PROXY URL=
TGT_HTTP_PROXY_PORT=
TGT CONFIG LOCATION=
TGT_BASTION_HOST_IP=
TGT BASTION PORT=
TGT BASTION USER=
TGT BASTION IDENTITY FILE=
TGT HOST IP=
TGT_SSH_TUNNEL_PORT=
TGT_SSH_RETRY_TIMEOUT=
TGT OSS PROXY HOST=
```



```
TGT OSS PROXY PORT=
TGT DATADG=
TGT REDODG=
TGT RECODG=
TGT DATAACFS=
TGT REDOACFS=
TGT RECOACFS=
BACKUP PATH=
HOST=
OPC CONTAINER=
SRC ZDLRA WALLET LOC=
TGT ZDLRA WALLET LOC=
ZDLRA CRED ALIAS=
NONCOBTOPDB CONVERSION=FALSE
NONCOBTOPDB SWITCHOVER=TRUE
SKIP FALLBACK=TRUE
TGT RETAIN DB UNIQUE NAME=
TGT SKIP DATAPATCH=FALSE
MAX DATAPATCH DURATION MINS=
DATAPATCH WITH ONE INSTANCE RUNNING=
SHUTDOWN SRC=
SKIP SRC SERVICE RETENTION=
SRC RMAN CHANNELS=6
TGT RMAN CHANNELS=16
ZDM LOG OSS PAR URL=
ZDM BACKUP FULL SRC MONITORING INTERVAL=10
ZDM BACKUP INCREMENTAL SRC MONITORING INTERVAL=10
ZDM BACKUP DIFFERENTIAL SRC MONITORING INTERVAL=10
ZDM CLONE TGT MONITORING INTERVAL=10
ZDM OSS RESTORE TGT MONITORING INTERVAL=10
ZDM OSS RECOVER TGT MONITORING INTERVAL=10
ZDM BACKUP RETENTION WINDOW=
ZDM BACKUP TAG=
ZDM USE EXISTING BACKUP=
ZDM OPC RETRY WAIT TIME=
ZDM OPC RETRY COUNT=
ZDM SRC TNS ADMIN=
ZDM CURL LOCATION=
ZDM USE EXISTING UNDO SIZE=
ZDM SKIP DG CONFIG CLEANUP=
ZDM RMAN COMPRESSION ALGORITHM=LOW
ZDM SRC DB RESTORE SERVICE NAME=
ZDM RMAN DIRECT METHOD=
```

Related Topics

- Introduction to Zero Downtime Migration
- Preparing for Database Migration
- Migrating Your Database with Zero Downtime Migration

During Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure



Monitoring: Oracle will monitor the Exadata Cloud@Customer Gen2 installation from the beginning of the installation just like a regular Gen2 install.

Backups: Backups are done from the Exadata Cloud@Customer Gen1 VM cluster and they will continue to work during the upgrade. Post-migration to Exadata Cloud@Customer Gen2, backups to the Gen1 Oracle Cloud At Customer (OCC) Object Storage Service (OSS) is not allowed and you must use supported backup methods for Exadata Cloud@Customer Gen2.

Post Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure

The upgrade will move your resources into Exadata Cloud@Customer Gen 2 Cloud Control Plane and onto the new generation hardware.

Use the Gen2 OCI Console to manage your Exadata Cloud@Customer Gen2 infrastructure, clusters, databases, and users/groups.

The software stack is upgraded to newer versions, for example, as follows:

Exadata software: 19.x or later
 Oracle Grid Infrastructure: 19C

Guest VM operating system: Oracle Linux 7

DBaaS Tools: 20.x

CSI: You will have a new CSI for your Cloud account.



The software stack will be upgraded to the latest versions at that point in time when you perform Out-of-Place Cloud Upgrade to New Gen2 Hardware.

Patching: The infrastructure patching process and notification are different in Gen2. For more information, see *Maintaining an Exadata Cloud@Customer System*.



Post-migration to Exadata Cloud@Customer Gen2, Oracle recommends using supported backup methods for Exadata Cloud@Customer Gen2. It's your responsibility to manually manage any backups to the Gen1 Oracle Cloud At Customer (OCC) Object Storage Service (OSS), and Oracle does not offer it through the OCI Console, API, or CLI.

Related Topics

- Perform User Managed Maintenance Updates
- About Oracle Managed Exadata Cloud@Customer Infrastructure Maintenance Updates
 Oracle performs patches and updates to all of the Oracle-managed system components
 on Exadata Cloud@Customer.



Best Practices for Out-of-Place Cloud Upgrade to New Exadata Cloud@Customer Gen2 Infrastructure

For the purpose of the upgrade, the recommended tool to use is Oracle Zero Downtime Migration (ZDM).

Some recommended best practices in the context of ZDM's usage for the Gen1 to Gen2 upgrade are:

While all methods of Physical migration are supported, it is recommended to use
 Online Migration with Direct Data Transfer.



It is not recommended to use either Gen1 Oracle Cloud At Customer OSS or OCI Object Storage for this migration.

- Set ZDM RMAN COMPRESSION ALGORITHM to LOW.
- The target database Oracle Home must be at the same patch level or at a higher patch level as the source.
- The target database Oracle Home must have all the one-off patches as the source Oracle Home.
- Perform a validation run before the actual run.
- For a CDB source database, it is required to have all the PDBs on the source to be online.

Related Topics

• Zero Downtime Migration Process Phases



6

Autonomous Database on Exadata Cloud@Customer

What's New in ADB-D on Exadata Cloud@Customer

Here's a summary of the noteworthy ADB-D on Exadata Cloud@Customer additions and enhancements.

Introduction to ADB-D on Exadata Cloud@Customer

Oracle Autonomous Database on Exadata Cloud@Customer combines the benefits of a self-driving, self-securing, and self-repairing database management system and the security and control offered by having it deployed securely on-premise behind your firewall.

Managing Autonomous Exadata VM Clusters

An Autonomous Exadata VM Cluster is a set of symmetrical VMs across all Compute nodes.

· Managing Encryption Keys on External Devices

Learn how to store and manage database encryption keys.

Managing Autonomous Container Databases

Learn how you can create, view, move, change backup policies, manage maintenance schedules, and perform other Oracle Autonomous Container Database management.

Managing Autonomous Databases

An Autonomous Database resource is a user database. When you create an Autonomous Database, you choose the Autonomous Container Database for it and you specify "Data Warehouse" or "Transaction Processing" as its workload type to create an Autonomous Data Warehouse database or an Autonomous Transaction Processing database.

Connecting to Autonomous Databases

Applications and tools connect to an autonomous database using Oracle Net Services (also known as SQL*Net). Oracle Net Services enables a network session from a client application to an Oracle Database server.

- Patching ADB on Exadata Cloud@Customer Infrastructure
- Using Autonomous Data Guard with Autonomous Database on Exadata Cloud@Customer

Learn how to enable a Data Guard association between databases, change the role of a database in a Data Guard association using either a switchover or a failover operation, and reinstate a failed database.

Using Performance Hub to Analyze Database Performance

Use the Performance Hub tool to analyze and tune the performance of a selected Oracle Exadata Database Service on Cloud@Customer Autonomous Database.

What's New in ADB-D on Exadata Cloud@Customer

Here's a summary of the noteworthy ADB-D on Exadata Cloud@Customer additions and enhancements.

- Character Set Selection
- Enhanced Resource Tracking for Autonomous Database
- Longer Database Name
- Create a New Autonomous Database Instance from Backup
- Multiple Autonomous VM Cluster Support
- Automatic Failover with a Standby Autonomous Container Database
- X9M-2 System Support
- · Fractional OCPU and GB Storage
- Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OKV) Integration
- Infrastructure Patching
- Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled Autonomous Databases
- ADB-D on Exadata Cloud@Customer: Monitor Performance with Autonomous Database Metrics
- ADB-D on Exadata Cloud@Customer: Autonomous Data Guard
- Access Control List (ACL) to Restrict Access to Autonomous Databases
- Oracle Key Vault (OKV) Integration
- X8M-2 System Support
- Per-Second Billing for Autonomous Database OCPU Usage
- Oracle Autonomous Database on Oracle Exadata Database Service on Cloud@Customer

Character Set Selection

- Services: Database
- Release Date: May 17, 2022

This feature enhancement enables you to specify the database character set and the national character set while creating an ADB.

- While creating an ADB, you can choose only the character sets supported. To get the complete list of supported character sets, use ListAutonomousDatabaseCharacterSets API.
- You cannot change the character set after creating an ADB.
- You can only set the character sets while creating an ADB. Character set selection is not supported for cloning (meta or full) or creating from a backup.



- The CDB will remain using AL32UTF8 for the database character set and AL16UTF16 for the national character set.
- Each ADB in an ACD can have different combinations of database/national character sets.

Related Topics

- Create an Autonomous Database
- API to Manage Autonomous Databases

Enhanced Resource Tracking for Autonomous Database

Services: Database

• Release Date: May 10, 2022

Identify where the reclaimable OCPUs are located to reclaim them to create new database resources or for scaling automation when a certain threshold is reached.

You can create multiple AVMCs on an Exadata Infrastructure resource. The OCPUs that you allocate while provisioning the AVMC resource will be the **Total OCPUs** available for its Autonomous Databases. When you create multiple AVMCs, each AVMC can have its own value for total OCPUs.

At an AVMC or ACD level, the total number of OCPUs available for creating databases is called **Available OCPUs**.

This feature enhancement provides better resource usage tracking:

Reclaimable OCPUs:

When an Autonomous Database is terminated or scaled down, the number of OCPUs allocated to it is not immediately returned to the available OCPUs at its parent AVMC level for the overall deployment. They continue to be included in the count of OCPUs available to its parent container database until that parent container database is restarted. These OCPUs are called **reclaimable OCPUs**. Reclaimable OCPUs at the parent AVMC level are the sum of reclaimable OCPUs of all its ACDs. When an ACD is restarted, it returns all its reclaimable OCPUs to the available OCPUs at its parent AVMC level.

Failure free ADB Provisioning with Provisionable OCPUs:

Based on the resource utilization on each node; not all the values of the available OCPUs can be used to provision or scale Autonomous Databases. For example, suppose you have 20 OCPUs available at the AVMC level, not all the values from 1 to 20 OCPUs can be used to provision or scale Autonomous Databases depending on the resource availability at the node level. The list of OCPU values that can be used to provision or scale an Autonomous Database is called **Provisionable OCPUs**.

On the console, when you try to provision or scale an Autonomous Database, the OCPU count will be validated against the list of provisionable OCPUs, and if the value is not provisionable, you will be provided with the two nearest provisionable OCPU values. Alternatively, if you want to see the complete list of provisionable OCPU values for an Autonomous Exadata VM Cluster, you can use the following API:

GetAutonomousContainerDatabase returns a list of provisionable OCPU values that can be used to create a new Autonomous Database in the given Autonomous Container Database. See GetAutonomousContainerDatabase for more details.



GetAutonomousDatabase returns a list of provisionable OCPU values that can be used for scaling a given Autonomous Database. See GetAutonomousDatabase for more details.

Autonomous VM Clusters

As a Fleet Administrator, you will be able to identify:

- Total OCPUs: The number of CPU cores allocated to the VM Cluster.
- **Exadata Storage (TB):** The storage allocated to the VM Cluster in TBs.
- Total Autonomous Database Storage (TB): Total Autonomous Database Storage storage allocated to the Autonomous VM Cluster.
- Available Autonomous Database Storage (TB): Storage available to create Autonomous Databases in the Autonomous VM Cluster
- Total Memory: The memory allocated to the VM Cluster in GB.
- Total Local Storage (GB): Total Local Storage in the Exadata Infrastructure.
- Available OCPUs: CPU cores available for allocation to ADBs.
- Reclaimable OCPUs: Sum of all the reclaimable OCPUs in all the ACDs in the Autonomous VM Cluster.
- Available ACDs: The number of ACDs you can create in the AVM using the available resources.
- Total ACDs: Number of ACDs customers want to create in the AVM.
- Which ACDs have a lot of reclaimable OCPUs and restart them when needed.

Autonomous Container Database

As a Database Administrator, you will be able to identify:

- Total OCPUs: The number of CPU cores allocated to the VM cluster.
- Available OCPUs: Sum of OCPU available on the Autonomous VM Cluster + Reclaimable OCPU within the same ACD.
- Reclaimable OCPUs: When an Autonomous Database is terminated or scaled down, the number of OCPUs allocated to it is not immediately returned to the available OCPUs at its parent AVMC level for the overall deployment. They continue to be included in the count of OCPUs available to its parent container database until that parent container database is restarted. These OCPUs are called reclaimable OCPUs. Reclaimable OCPUs at the parent AVMC level are the sum of reclaimable OCPUs of all its ACDs. When an ACD is restarted, it returns all its reclaimable OCPUs to the available OCPUs at its parent AVMC level.



You cannot create an ACD if 2 OCPUs are not available in the VM Cluster or Exadata Infrastructure.

Autonomous Database

As a Database Administrator, you will be able to identify the OCPU count that you can use to provision or scale an ADB.



- OCPU: The number of OCPU cores to be made available to the database.
- **Storage:** The quantity of storage available to store data in the database, in terabytes.
- While provisioning an ADB, if you specify an OCPU count that the service cannot provision in the existing ACD, then the service displays an error message and suggests 2 values in close proximity to the value that you have specified. For example, assume that you are creating an ADB with 15 OCPUs on a Quarter Rack Exadata Infrastructure that has 20 OCPUs available. However, there are only 10 OCPUs available on each node. In this case, the service will not be able to provision the ADB because 15 OCPUs is less than the split threshold of 16 OCPUs. Therefore, the nearest possible values are 17 and 18.
- While scaling an ADB, if you specify an OCPU count that the service cannot use to scale the ADB, then the service displays an error message and suggests 2 values in close proximity to the value that you have specified.

Table 6-1 REST API Endpoints to Track and Manage Resource Usage

REST API Endpoint	Description		
GetAutonomousVmCluster	View a list of available OCPU, reclaimable OCPU, available Autonomous Database storage, and available ACDs.		
GetAutonomousContainerDatabase	 View a list of available OCPU, total OCPU, and reclaimable OCPU. View an array of provisionable OCPUs. 		
GetAutonomousDatabase	View an array of scalable OCPUs.		

Related Topics

- View a List of Autonomous Exadata VM Clusters
- View Details of an Autonomous Exadata VM Cluster
- Restart an Autonomous Container Database
- Create an Autonomous Data Guard Enabled Autonomous Container Database
 Follow these steps to create an Autonomous Data Guard Enabled Autonomous
 Container Database on an Oracle Exadata Cloud@Customer system.
- Create an Autonomous Data Guard Enabled Autonomous Database
- Scale the CPU Core Count or Storage of an Autonomous Database
- Clone an Autonomous Database
- Clone an Autonomous Database Backup
- GetAutonomousContainerDatabase
- GetAutonomousDatabase

Longer Database Name

Services: Database

Release Date: May 03, 2022



The length of the database name has been extended from 14 characters to 30 characters. Specify a user-friendly name that you can use to identify the database. The database name must contain only the permitted characters.

Review the following guidelines when selecting a database name:

- maximum of 30 characters
- · contain only alphanumeric characters
- begin with an alphabetic character
- must not contain spaces

Create a New Autonomous Database Instance from Backup

Services: Database

Release Date: April 12, 2022

Restore an Autonomous Database (ADB) backup to an Autonomous Container Database (ACD) on the same or a different Autonomous Virtual Machine (AVM) running on the existing or different Autonomous Exadata Cloud@Customer system.

Prerequisites and Limitations

- If you are using customer-managed keys, then the target AVM/ACD will require access to the source Oracle Key Vault (OKV) for the keys.
- The target AVM must have access to the backup destination of the source for the restore to be possible.
- You can only use the Full Clone option to create a database clone.
- You cannot use disk-based backups to create ADB instances from backups.
- Target ACD must be on the same or higher version as the source.
- One ADB restore per AVM. The limit applies only to the target AVM.

Related Topics

- Clone an Autonomous Database
- Clone an Autonomous Database Backup
- Clone a Standby Database
- Clone a Standby Database Backup

Multiple Autonomous VM Cluster Support

Services: Database

Release Date: March 15, 2022

Multi-VM Cluster supports heterogeneous computing environments in which Autonomous and Non-Autonomous VM clusters can coexist on an Exadata Infrastructure.

With Multiple VM Cluster support you can:

Create multiple Autonomous VM Clusters on an Exadata Infrastructure



- Schedule separate maintenance runs for each Autonomous VM Cluster
- Use different license models for each Autonomous Database

Related Topics

- Create an Autonomous Exadata VM Cluster
- View Details of an Autonomous Exadata VM Cluster
- Schedule Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a
 maintenance window to determine the time your quarterly infrastructure maintenance will
 begin.
- View Details of an Autonomous Container Database
- Create an Autonomous Database
- View Details of an Autonomous Database
- Clone an Autonomous Database

Automatic Failover with a Standby Autonomous Container Database

Services: Database

Release Date: January 18, 2022

With Fast-Start Failover (FSFO), the system automatically detects the failure of the primary Autonomous Container Database and then fails over to a designated standby Autonomous Container Database.

Automatic failover is optional while configuring Autonomous Data Guard. You can enable or disable automatic failover after configuring Autonomous Data Guard.

Related Topics

- Managing a Standby Autonomous Container Database
 Enabling Autonomous Data Guard on an Autonomous Container Database creates a standby (peer) Autonomous Container Database that provides data protection, high availability, and facilitates disaster recovery for the primary database.
- Perform a Failover to Standby Autonomous Container Database
 Initiate a failover operation by using the Data Guard association of the standby database.
- Perform a Switchover to Standby or Primary Autonomous Container Database
 Initiate a switchover operation by using the Data Guard association of the primary database.
- Reinstate Data Guard Enabled Standby Autonomous Container Database
 After you fail over a primary database to its standby, the standby assumes the primary role and the old primary is identified as a disabled standby.

X9M-2 System Support

Services: Database

Release Date: September 28, 2021



Oracle Exadata Cloud@Customer comes in different infrastructure shapes to support workloads of different sizes. In this release, the capability of Oracle Exadata Cloud@Customer has been extended to support X9M-2 system.

For more information, see Available Exadata Infrastructure Hardware Shapes.

Related Topics

Available Exadata Infrastructure Hardware Shapes

Fractional OCPU and GB Storage

Services: Database

Release Date: June 15, 2021

Create Autonomous Databases with less than 1 OCPU count using fractional units from 0.1 to 0.9 OCPU and GB sizing between 32 GB and the maximum usable storage for your Exadata shape.

Related Topics

- Create an Autonomous Database
- Scale the CPU Core Count or Storage of an Autonomous Database
- Clone an Autonomous Database

Autonomous Data Guard Enabled Autonomous Database and Oracle Key Vault (OKV) Integration

Services: Database

Release Date: June 15, 2021

Integrate your on-premises Oracle Key Vault (OKV) with Autonomous Data Guard enabled Autonomous Databases on Exadata Cloud@Customer and use customer-managed keys stored in Oracle Key Vault to secure your critical data.

Related Topics

- Managing Encryption Keys on External Devices
 Learn how to store and manage database encryption keys.
- Create an Autonomous Data Guard Enabled Autonomous Container Database
 Follow these steps to create an Autonomous Data Guard Enabled Autonomous
 Container Database on an Oracle Exadata Cloud@Customer system.
- Create an Autonomous Data Guard Enabled Autonomous Database
- Operations Performed Using the APIs
 Learn how to use the API to manage Autonomous Data Guard Enabled
 Autonomous Container Database.
- Rotate CDB Encryption Key
- Rotate ADB Encryption Key

Infrastructure Patching



Services: Database

Release Date: May 04, 2021

ADB-Dedicated maintenance involves patching Exadata Infrastructure(EI) Autonomous VM Cluster, and Autonomous Container Database (ACD).

Related Topics

Patching ADB on Exadata Cloud@Customer Infrastructure

Access Control List (ACL) to Restrict Access to Autonomous Data Guard Enabled Autonomous Databases

Services: Database

Release Date: January 26, 2021

An access control list (ACL) provides additional protection to your database by allowing only the clients with specific IP addresses to connect to the database. You can add IP addresses individually, or in CIDR blocks.

Related Topics

- Create an Autonomous Data Guard Enabled Autonomous Database
- Manage Access Control List of an Autonomous Database

ADB-D on Exadata Cloud@Customer: Monitor Performance with Autonomous Database Metrics

Services: Database

Release Date: December 15, 2020

You can monitor the health, capacity, and performance of your Autonomous Databases with metrics, alarms, and notifications. You can use Oracle Cloud Infrastructure console or Monitoring APIs to view metrics.

Related Topics

Monitor Performance with Autonomous Database Metrics

ADB-D on Exadata Cloud@Customer: Autonomous Data Guard

Services: Database

Release Date: November 17, 2020

Enabling Autonomous Data Guard on an Autonomous Container Database on dedicated Exadata infrastructure creates a standby (peer) Autonomous Container Database that provides data protection, high availability, and facilitates disaster recovery for the primary database.



Related Topics

 Using Autonomous Data Guard with Autonomous Database on Exadata Cloud@Customer

Learn how to enable a Data Guard association between databases, change the role of a database in a Data Guard association using either a switchover or a failover operation, and reinstate a failed database.

Access Control List (ACL) to Restrict Access to Autonomous Databases

Services: Database

Release Date: November 10, 2020

An access control list (ACL) provides additional protection to your database by allowing only the clients with specific IP addresses to connect to the database. You can add IP addresses individually, or in CIDR blocks.

Related Topics

- Access Control Lists (ACLs) for ADB-D on Exadata Cloud@Customer
- Create an Autonomous Database
- Manage Access Control List of an Autonomous Database
- Clone an Autonomous Database

Oracle Key Vault (OKV) Integration

Services: Database

Release Date: October 27, 2020

Integrate your on-premises Oracle Key Vault (OKV) with Autonomous Database on Exadata Cloud@Customer to secure your critical data on-premises.

Oracle Key Vault integration enables you to take complete control of your encryption keys and store them securely on an external, centralized key management device.

Related Topics

Managing Encryption Keys on External Devices
 Learn how to store and manage database encryption keys.

X8M-2 System Support

Services: Database

Release Date: September 25, 2020

Release Notes: ADB-D on Exadata Cloud@Customer: X8M-2 System Support

Per-Second Billing for Autonomous Database OCPU Usage

Services: Database



Release Date: July 21, 2020

 Release Notes: Exadata Cloud@Customer: Per-Second Billing for Autonomous Database OCPU Usage

Oracle Autonomous Database on Oracle Exadata Database Service on Cloud@Customer

Services: Database

Release Date: June 23, 2020

Release Notes: Exadata Cloud@Customer: Oracle Autonomous Database

Introduction to ADB-D on Exadata Cloud@Customer

Oracle Autonomous Database on Exadata Cloud@Customer combines the benefits of a self-driving, self-securing, and self-repairing database management system and the security and control offered by having it deployed securely on-premise behind your firewall.

After purchasing Autonomous Database on Exadata Cloud@Customer and creating, provisioning and activating its Exadata Infrastructure hardware and Oracle Cloud resource, several additional resource types become available in the **Exadata Cloud@Customer** section of the Oracle Cloud Infrastructure console: Autonomous Exadata VM Clusters, Autonomous Container Databases and Autonomous Databases. You use these resources to create and manage your secure, on-premise deployment of Oracle Autonomous Database.

- Database System Architecture Overview
- User Roles
- Available Exadata Infrastructure Hardware Shapes
- Access Control Lists (ACLs) for ADB-D on Exadata Cloud@Customer

Database System Architecture Overview

Oracle Autonomous Database on Oracle Exadata Database Service on Cloud@Customer has a four-level database architecture model that makes use of Oracle multitenant database architecture.

- Resource Types
- Deployment Order

Resource Types

Each level of the architecture model corresponds to one of the following resources types:

Oracle Exadata Database Service on Cloud@Customer infrastructure: Hardware
rack that includes compute nodes and storage servers, tied together by a high-speed,
low-latency InfiniBand network and intelligent Exadata software.

Oracle Exadata Database Service on Cloud@Customer infrastructure is common for both Autonomous and Non-Autonomous resources.



For a list of the hardware and Oracle Cloud resource characteristics of Oracle Exadata Database Service on Cloud@Customer infrastructure resources that support Autonomous Databases, see Available Exadata Infrastructure Hardware Shapes.

- Only the Oracle Exadata Database Service on Cloud@Customer
 Infrastructures deployed before Oracle announced support for Autonomous
 Databases on Oracle Exadata Database Service on Cloud@Customer do not
 support Autonomous resources listed below. Please contact your Oracle sales
 representative to understand the infrastructure upgrades required for
 supporting Oracle Autonomous Databases.
- You can create only one Autonomous VM cluster in an Exadata Infrastructure.
- Oracle Exadata Database Service on Cloud@Customer infrastructure cannot simultaneously have both Autonomous and Exadata VM clusters.
- Autonomous VM clusters on Exadata Database Service on Cloud@Customer infrastructure: VM cluster is a set of symmetrical VMs across all Compute nodes. Autonomous Container and Database run all the VMs across all nodes enabling high availability. It consumes all the resources of the underlying Exadata Infrastructure.

Before you can create any Autonomous Databases on your Exadata Database Service on Cloud@Customer infrastructure, you must create an Autonomous VM cluster network, and you must associate it with a VM cluster.

- Autonomous Container Database: Provides a container for multiple Autonomous Databases.
- Autonomous Database: You can create multiple autonomous databases within the same autonomous container database. You can configure Oracle Autonomous Database for either transaction processing or data warehouse workloads.

Deployment Order

You must create the dedicated Exadata infrastructure resources in the following order:

- **1. Exadata Infrastructure.** For more information, see *Preparing for Exadata Cloud@Customer* and *Provisioning Exadata Cloud@Customer System.*
- Autonomous Exadata VM cluster. For more information, see Managing Autonomous Exadata VM Clusters.
- **3. Autonomous Container Database.** For more information, see *Managing Autonomous Container Databases*.
- **4. Autonomous Database.** For more information, see *Managing Autonomous Databases*.

Related Topics

- Preparing for Exadata Database Service on Cloud@Customer
 Review OCI as well as the site, network and storage requirements to prepare and
 deploy Exadata Database Service on Cloud@Customer in your data center.
- Using the Console to Provision Exadata Database Service on Cloud@Customer Infrastructure
 - Learn how to provision an Exadata Database Service on Cloud@Customer system.



- Managing Autonomous Exadata VM Clusters
 An Autonomous Exadata VM Cluster is a set of symmetrical VMs across all Compute nodes.
- Managing Autonomous Container Databases
 Learn how you can create, view, move, change backup policies, manage maintenance schedules, and perform other Oracle Autonomous Container Database management.
- Managing Autonomous Databases
 An Autonomous Database resource is a user database. When you create an Autonomous Database, you choose the Autonomous Container Database for it and you specify "Data Warehouse" or "Transaction Processing" as its workload type to create an Autonomous Data Warehouse database or an Autonomous Transaction Processing database.

User Roles

Your organization may choose to split the administration of the Oracle Autonomous Database on Oracle Exadata Database Service on Cloud@Customer into the following roles:

- Fleet Administrator. Fleet administrators create, monitor and manage Autonomous
 Exadata Infrastructure and Autonomous Container Database resources. They must also
 setup customer managed Backup Destinations, such as Recovery Appliance and NFS to
 be used by Autonomous Databases. A fleet administrator must have permissions for
 using the networking resources required by the Oracle Exadata Database Service on
 Cloud@Customer infrastructure, and permissions to manage the infrastructure and
 container database resources.
- Database Administrator. Database administrators create, monitor and manage
 Autonomous Databases. They also create and manage users within the database.
 Database administrators must have permissions for using container databases, for
 managing autonomous databases and backups, and for using the related networking
 resources. At the time of provisioning an Autonomous Database, the administrator
 provides user credentials for the automatically created ADMIN account, which provides
 administrative rights to the new database.
- Database User. Database users are the developers who write applications that connect
 to and use an Autonomous Database to store and access the data. Database users do
 not need Oracle Cloud Infrastructure accounts. They gain network connectivity to and
 connection authorization information for the database from the database administrator.

Available Exadata Infrastructure Hardware Shapes

Resource Limits

The following tables list the resource limits, both enforced and recommended for dedicated Autonomous Database deployments on Oracle Cloud and Exadata Cloud@Customer.



The limits listed in the following tables apply to all the Exadata Systems supported by a dedicated Autonomous Database. Exceptions (if any) are highlighted accordingly.



Table 6-2 Enforced Resource Limits (Maximum)

Resource	Quarter Rack	Half Rack	Full Rack
Autonomous Databases	1000 (920 on Exadata X7 system)	2000 (1840 on Exadata X7 system)	4000 (3680 on Exadata X7 system)
Autonomous Container Databases	12	12	12

Table 6-3 Recommended Resource Limits (Maximum)

Resource	Quarter Rack	Half Rack	Full Rack
Autonomous Databases per Autonomous Container Database	200	200	200
Autonomous Databases per Autonomous Container Database with Autonomous Data Guard Configured	25	25	25



It is possible to provision more Autonomous Databases than those recommended in the Recommended Resource Limits table, especially with fractional OCPUs. However, this implies compromising the Service Level Objectives (SLOs) to return an application online following an unplanned outage or a planned maintenance activity. To know the SLO details for dedicated Autonomous Database deployments, see *Availability Service Level Objectives (SLOs)*.

Oracle Exadata X9M-2 System Model Specifications

The following table lists the Exadata Infrastructure resource shapes that Oracle Autonomous Database on Oracle Exadata Cloud@Customer supports.

Table 6-4 Oracle Exadata Cloud@Customer X9M-2 System Specifications

Specification	Exadata X9M-2 Quarter Rack	Exadata X9M-2 Half Rack	Exadata X9M-2 Full Rack
Number of Compute Nodes	2	4	8
Total Maximum Number of Enabled CPU Cores	124	248	496
Total RAM Capacity	2780 GB	5560 GB	11120 GB
Total Persistent Memory Capacity	4.5 TB	9.0 TB	18.0 TB
Number of Exadata Storage Servers	3	6	12
Maximum Database Size, No Local Backup	153 TB	307 TB	615 TB
Maximum Database Size, Local Backup (Exadata Cloud@Customer only)	a 76 TB	153 TB	307 TB

For more information, see *Oracle Exadata Database Service on Exadata Cloud@Customer X9M* datasheet.



Oracle Exadata X8M-2 System Model Specifications

The following table lists the Exadata Infrastructure resource shapes that Oracle Autonomous Database on Oracle Exadata Cloud@Customer supports.

Table 6-5 Oracle Exadata Cloud@Customer X8M-2 System Specifications

Specification	Exadata X8M-2 Quarter Rack	Exadata X8M-2 Half Rack	Exadata X8M-2 Full Rack
Number of Compute Nodes	2	4	8
Total Maximum Number of Enabled CPU Cores	100	200	400
Total RAM Capacity	2780 GB	5560 GB	11120 GB
Persistent Memory	4.5 TB	9.0 TB	18.0 TB
Number of Exadata Storage Servers	3	6	12
Maximum Database Size, No Local Backup	119 TB	239 TB	479 TB
Maximum Database Size, Local Backup (Exadata Cloud@Customer only)	59 TB	119 TB	239 TB

Oracle Exadata X8-2 System Model Specifications

The following table lists the Exadata Infrastructure resource shapes that Oracle Autonomous Database on Oracle Exadata Cloud@Customer supports.

Table 6-6 Oracle Exadata Cloud@Customer X8-2 System Specifications

Specification	Exadata X8-2 Quarter Rack	Exadata X8-2 Half Rack	Exadata X8-2 Full Rack
Shape Name	Exadata.Quarter3.1	Exadata.Half3.200	Exadata.Full3.400
Number of Compute Nodes	2	4	8
Total Maximum Number of Enabled CPU Cores	100	200	400
Total RAM Capacity	1440 GB	2880 GB	5760 GB
Number of Exadata Storage Servers	3	6	12
Maximum Database Size, No Local Backup	119 TB	238 TB	476 TB
Maximum Database Size, Local Backup (Exadata Cloud@Customer only)	59 TB	119 TB	239 TB

Related Topics

- Availability Service Level Objectives (SLOs)
- Oracle Exadata Database Service on Exadata Cloud@Customer X9M

Access Control Lists (ACLs) for ADB-D on Exadata Cloud@Customer

An access control list (ACL) provides additional protection to your database by allowing only the clients with specific IP addresses to connect to the database. You can add IP addresses individually, or in CIDR blocks.

You can optionally create an ACL during database provisioning, or at any time thereafter. You can also edit an ACL at any time. Enabling an access control list with an empty list of IP



addresses makes the database inaccessible. For more information, see "Manage Access Control List of an Autonomous Database".

Note the following about using an ACL with your Autonomous Database:

- The Autonomous Database Service console is not subject to ACL rules.
- Oracle Application Express (APEX), RESTful services, and SQL Developer Web are not subject to ACLs. Choosing to enable an ACL disables these features automatically.
- Performance Hub is not subject to ACL rules.
- While creating a database, if setting ACL fails, then provisioning the database also fails.
- Updating ACL is allowed if the database is in Available and AvailableNeedsAttention states.
- Restoring a database does not overwrite the existing ACLs.
- Cloning a database, full and metadata, will have the same access control settings as the source database. You can make changes as necessary.
- All CDB operations are allowed during ACL update. However, ADB operations are not allowed during ACL update.

Related Topics

Manage Access Control List of an Autonomous Database

Managing Autonomous Exadata VM Clusters

An Autonomous Exadata VM Cluster is a set of symmetrical VMs across all Compute nodes.

Autonomous Container and Database run all the VMs across all nodes enabling high availability. It consumes all the resources of the underlying Exadata Infrastructure.

After you have created the Autonomous Exadata VM Cluster, you can create up to 12 Autonomous Container Database resources on it, depending on the capacity of your Exadata Infrastructure hardware, as described in *Available Exadata Infrastructure Hardware Shapes*.

- About Autonomous Exadata VM Clusters
- Create an Autonomous Exadata VM Cluster
- View a List of Autonomous Exadata VM Clusters
- View Details of an Autonomous Exadata VM Cluster
- Schedule Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a maintenance window to determine the time your quarterly infrastructure maintenance will begin.
- Change the License Type on an Autonomous VM Cluster
- Move an Autonomous Exadata VM Cluster to Another Compartment
- Terminate an Autonomous Exadata VM Cluster
- Using the API to Manage Autonomous Exadata VM Clusters



Related Topics

Available Exadata Infrastructure Hardware Shapes

About Autonomous Exadata VM Clusters

- Please contact your Oracle sales representative to understand the infrastructure upgrades required for supporting Oracle Autonomous Databases.
- Create multiple Autonomous Exadata VM Clusters on a single Exadata Infrastructure resource.
- Create both Autonomous Exadata VM Clusters and Exadata VM Clusters on the same Exadata Infrastructure.
- Support for multiple VM Clusters lets you:
 - Schedule separate maintenance runs for each Autonomous VM Cluster on the same Exadata Infrastructure.
 - Choose different license models for Autonomous Databases on the same Exadata Infrastructure.
 - Create and test Autonomous Data Guard between Autonomous Exadata VM Clusters on the same Exadata Infrastructure.
 - Customize compute, storage, and memory of each Autonomous Exadata VM Cluster configuration for the intended workload.

Create an Autonomous Exadata VM Cluster

Follow these steps to create an Autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. Click Create Autonomous Exadata VM Cluster.
- 4. In the Create Autonomous Exadata VM Cluster dialog, enter the following general information:
 - Compartment: Specify the compartment in which the Autonomous Exadata VM Cluster will be created.
 - Display Name: A user-friendly description or other information that helps you easily identify the infrastructure resource. The display name does not have to be unique. Avoid entering confidential information.
 - Exadata Infrastructure: Select an Exadata Infrastructure.
 - VM Cluster Network: Select a VM Cluster Network.
 - Configure Autonomous VM Cluster Resources



Note:

The minimum and maximum values for these parameters change in relation to each other, for example, the OCPU count allocation will impact the number of ACDs customers can create.

- Node Count: Number of database servers in the Exadata infrastructure.
 You cannot modify the node count.
- Maximum number of Autonomous Container Databases for the Autonomous VM Cluster: The number of ACDs specified represents the upper limit on ACDs. These ACDs must be created separately as needed. ACD creation also requires 2 available OCPUs per node.
- OCPU count per node: Specify the OCPU count for each individual VM.
 The minimum value is 5 OCPUs per VM.
- Database memory per OCPU (GB): The memory per OCPU allocated for the Autonomous Databases in the Autonomous VM CLuster.
- Allocate Storage for Local Backups: Check this option to configure the Exadata storage to enable local database backups.
- Autonomous Database storage for the Autonomous VM Cluster (TB):
 Data storage allocated for Autonomous Database creation in the Autonomous VM Cluster.
- 5. Configure automatic maintenance.
 - a. Click Edit Maintenance Preferences.

On the Edit Maintenance Preferences page do the following:

- No preference: The system assigns a date and start time for infrastructure maintenance.
- **Specify a schedule:** Choose your preferred month, week, weekday, start time, and lead time for infrastructure maintenance.
 - Under Maintenance months, specify at least one month for each quarter during which Exadata infrastructure maintenance will take place. You can select more than one month per quarter. If you specify a long lead time for advanced notification (for example, 4 weeks), you may wish to specify 2 or 3 months per quarter during which maintenance runs can occur. This will ensure that your maintenance updates are applied in a timely manner after accounting for your required lead time. Lead time is discussed in the following steps.
 - Optional. Under Week of the month, specify which week of the month maintenance will take place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week. Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days. If you do not specify a week of the month, Oracle will run the maintenance update in a week to minimize disruption.
 - Optional. Under Day of the week, specify the day of the week on which the maintenance will occur. If you do not specify a day of the week, Oracle will run the maintenance update on a weekend day to minimize disruption.



- Optional. Under Start hour, specify the hour during which the maintenance run will begin. If you do not specify a start hour, Oracle will pick the least disruptive time to run the maintenance update.
- Under Lead Time, specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message. Your lead time ensures that a newly released maintenance update is scheduled to account for your required minimum period of advanced notification.
- b. Click Save Changes.
- **6.** Choose the license type you wish to use.

Your choice affects metering for billing. You have the following options:

- **Bring your own license**: If you choose this option, make sure you have proper entitlements to use for new service instances that you create.
- License included: With this choice, the cost of the cloud service includes a license for the Database service.
- 7. The following Advanced Options are available:
 - **Time zone**: The default time zone for the Exadata Infrastructure is UTC, but you can specify a different time zone. The time zone options are those supported in both the Java.util.TimeZone class and the Oracle Linux operating system.

Note:

If you want to set a time zone other than UTC or the browser-detected time zone, then select the **Select another time zone** option, select a **Region or contry**, and then select the corresponding **Time zone**.

If you do not see the region or country you want, then select **Miscellaneous**, and then select an appropriate **Time zone**.

- Tags: Optionally, you can apply tags. If you have permissions to create a resource, you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.
- 8. Click Create Autonomous Exadata VM Cluster.

Related Topics

Resource Tags

View a List of Autonomous Exadata VM Clusters

Follow these steps to view a list of autonomous Exadata VM clusters on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.



Autonomous VM Cluster view page displays details that include total and available OCUPs, Reclaimable OCUPs, total and available storage in TB, and total and available ACDs.

View Details of an Autonomous Exadata VM Cluster

Follow these steps to view detailed information about an autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. In the list of Autonomous Exadata VM Clusters, click the display name of the Exadata VM cluster you wish to view details.

(or)

- a. Click Exadata Infrastructure.
- In the list of Exadata Infrastructure, click the display name of the Exadata Infrastructure you wish to view details.
 Infrastructure Details page is displayed.
- c. Under Resources, click Autonomous Exadata VM Clusters.
- d. In the list of Autonomous Exadata VM Clusters, click the display name of the Autonomous Exadata VM Clusters you wish to view details. Or, click the action menu (three dots), and then select View Details. Autonomous Exadata VM Clusters Details page is displayed.

Autonomous VM Cluster Details page displays details that include total and available OCPUs, Reclaimable OCPUs, total and available storage in TB, and total and available ACDs.

Schedule Oracle-Managed Infrastructure Updates

Exadata Cloud Service updates are released on a quarterly basis. You can set a maintenance window to determine the time your quarterly infrastructure maintenance will begin.

You can also view scheduled maintenance runs and the maintenance history of your Autonomous Exadata VM Cluster in the Oracle Cloud Infrastructure Console.

- Set the Automatic Maintenance Schedule for Autonomous Exadata VM Cluster
- View or Edit the Time of the Next Scheduled Maintenance for Autonomous Exadata VM Cluster
- View the Maintenance History of Autonomous Exadata VM Cluster

Set the Automatic Maintenance Schedule for Autonomous Exadata VM Cluster

Learn how to set the maintenance schedule for an Autonomous Exadata VM Cluster on an Oracle Exadata Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.



- 3. In the list of Autonomous Exadata VM Clusters, find the Autonomous Exadata VM Cluster you want to set the maintenance window for and click its highlighted name.
- **4.** On the **Autonomous Exadata VM Cluster Details** page, under **Maintenance**, click the edit link in the **Maintenance Details** field.
- 5. In the Edit Automatic Maintenance page, select Specify a schedule.
- 6. Under Maintenance months, specify at least one month for each quarter during which Autonomous Exadata VM Cluster maintenance will take place.
 - You can select more than one month per quarter. If you specify a long lead time for advanced notification (for example, 4 weeks), you may wish to specify 2 or 3 months per quarter during which maintenance runs can occur. This will ensure that your maintenance updates are applied in a timely manner after accounting for your required lead time. Lead time is discussed in the following steps.
- Optional. Under Week of the month, specify which week of the month maintenance will take place.
 - Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week. Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days. If you do not specify a week of the month, Oracle will run the maintenance update in a week to minimize disruption.
- 8. Optional. Under Day of the week, specify the day of the week on which the maintenance will occur.
 - If you do not specify a day of the week, Oracle will run the maintenance update on a weekend day to minimize disruption.
- 9. Optional. Under Start hour, specify the hour during which the maintenance run will begin. If you do not specify a start hour, Oracle will pick the least disruptive time to run the maintenance update.
- **10. Under Lead Time**, specify the minimum number of weeks ahead of the maintenance event you would like to receive a notification message.
 - Your lead time ensures that a newly released maintenance update is scheduled to account for your required minimum period of advanced notification.
- 11. Click Save Changes.

View or Edit the Time of the Next Scheduled Maintenance for Autonomous Exadata VM Cluster

Learn how to view and edit the time of the next scheduled maintenance.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. In the list of Autonomous Exadata VM Clusters, find the Autonomous Exadata VM Cluster you want to set the maintenance window for and click its highlighted name.
- 4. On the Autonomous Exadata VM Cluster details page, under Maintenance, click the view link in the Next Maintenance field.
- 5. On the **Maintenance** page, scheduled maintenance events are listed.



- **6.** *Optional*. To change the time of the next scheduled maintenance, click the **Edit** link in the **Scheduled Start Time** field.
- In the Edit Infrastructure Maintenance Scheduled Start Time page, enter a
 date and time in the Scheduled Start time field.

The following restrictions apply:

- You can reschedule the infrastructure maintenance to a date no more than 180 days from the prior infrastructure maintenance. If a new maintenance release is announced prior to your rescheduled maintenance run, the newer release will be applied on your specified date. You can reschedule your maintenance to take place earlier than it is currently scheduled. You cannot reschedule the maintenance if the current time is within 2 hours of the scheduled maintenance start time.
- Oracle reserves certain dates each quarter for internal maintenance operations, and you cannot schedule your maintenance on these dates.

View the Maintenance History of Autonomous Exadata VM Cluster

Learn how to view the maintenance history for an Autonomous Exadata VM Cluster.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. In the list of Autonomous Exadata VM Clusters, find the Autonomous Exadata VM Cluster you want to set the maintenance window for and click its highlighted name.
- On the Autonomous Exadata VM Cluster details page, under Maintenance, click the view link in the Next Maintenance field.
- 5. Click **Maintenance History** to see a list of past maintenance events including details on their completion state.

Change the License Type on an Autonomous VM Cluster

Follow these steps to update the license type of an autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. In the list of Autonomous Exadata VM Clusters, click the display name of the Exadata VM cluster you wish to administer.
- 4. Click Update License Type.
- 5. On the Update License Type dialog box, choose one of the following license types.
 - Bring Your Own License (BYOL): Select this option if your organization already owns Oracle Database software licenses that you want to use on the VM cluster.
 - License Included: Select this option to subscribe to Oracle Database software licenses as part of Exadata Database Service on Cloud@Customer.

Updating the license type does interrupt the operation of the VM cluster.



6. Click Save Changes.

Move an Autonomous Exadata VM Cluster to Another Compartment

Follow these steps to move an autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system from one compartment to another compartment.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- 3. In the list of Autonomous Exadata VM Clusters, click the display name of the Exadata VM cluster you wish to administer.
- 4. Click Move Resource.
- 5. Select the new compartment.
- 6. Click Move Resource.

Terminate an Autonomous Exadata VM Cluster

Follow these steps to terminate an autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. In the list of Autonomous Exadata VM Clusters, click the display name of the Exadata VM cluster you wish to administer.
- 3. Click Terminate.
- Confirm that you wish to terminate your Autonomous Exadata VM Cluster in the confirmation dialog.
- 5. Click Terminate VM Cluster.

Using the API to Manage Autonomous Exadata VM Clusters

For information about using the API and signing requests, see REST APIs and Security Credentials. For information about SDKs, see Software Development Kits and Command Line Interface.

The following table lists the REST API endpoints to manage Autonomous Exadata VM Clusters.

Operation	REST API Endpoint
Create an Autonomous Exadata VM Cluster	CreateAutonomousVmCluster
View a list of Autonomous Exadata VM Clusters	ListAutonomousVmClusters
View details of an Autonomous Exadata VM Cluster	GetAutonomousVmCluster
Change the license type of an Autonomous VM Cluster	UpdateAutonomousVmCluster



Operation	REST API Endpoint
Move an Autonomous Exadata VM Cluster to another compartment	ChangeAutonomousVmClusterCompartment
Terminate an Autonomous Exadata VM Cluster	DeleteAutonomousVmCluster

Managing Encryption Keys on External Devices

Learn how to store and manage database encryption keys.

There are two options to store and manage database encryption keys for your autonomous databases on Exadata Cloud@Customer:

- 1. In the Guest VM on the Exadata Infrastructure.
- On an external key management device. Oracle Key Vault is the currently supported device.
- About Oracle Key Vault

Oracle Key Vault is a full-stack, security-hardened software appliance built to centralize the management of keys and security objects within the enterprise.

- Overview of Key Store
 - Integrate your on-premises Oracle Key Vault (OKV) with Autonomous Database on Exadata Cloud@Customer to secure your critical data on-premises.
- Required IAM Policy for Managing OKV on Oracle Exadata Database Service on Cloud@Customer

Review the identity access management (IAM) policy for managing OKV on Oracle Exadata Database Service on Cloud@Customer Systems.

- Tagging Resources
 - You can apply tags to your resources to help you organize them according to your business needs.
- Moving Resources to a Different Compartment
 You can move vaults from one compartment to another.
- Setting Up Your Exadata Cloud@Customer to Work With Oracle Key Vault
- Managing Your Key Store

About Oracle Key Vault

Oracle Key Vault is a full-stack, security-hardened software appliance built to centralize the management of keys and security objects within the enterprise.



The Oracle Key Vault is a customer-provisioned and managed system and it is not part of Oracle Cloud Infrastructure managed services.

Related Topics

Oracle Key Vault



Overview of Key Store

Integrate your on-premises Oracle Key Vault (OKV) with Autonomous Database on Exadata Cloud@Customer to secure your critical data on-premises.

Oracle Key Vault integration enables you to take complete control of your encryption keys and store them securely on an external, centralized key management device.

OKV is optimized for Oracle wallets, Java keystores, and Oracle Advanced Security Transparent Data Encryption (TDE) master keys. Oracle Key Vault supports the OASIS KMIP standard. The full-stack, security-hardened software appliance uses Oracle Linux and Oracle Database technology for security, availability, and scalability, and can be deployed on your choice of compatible hardware.

OKV also provides a REST interface for clients to auto-enroll endpoints and setup wallets and keys. For Autonomous Databases on Exadata Cloud@Customer to connect to OKV REST interface, create a key store in your tenancy to store the IP address and administrator credentials of your OKV. Exadata Cloud@Customer will not store the admin password required to connect to the OKV appliance. Ensure that you create a secret with Oracle's Vault Service, which will store the password required for autonomous databases to connect to OKV for key management.

For more information, see "Oracle Key Vault".

Related Topics

Oracle Key Vault

Required IAM Policy for Managing OKV on Oracle Exadata Database Service on Cloud@Customer

Review the identity access management (IAM) policy for managing OKV on Oracle Exadata Database Service on Cloud@Customer Systems.

A **policy** is an IAM document that specifies who has what type of access to your resources. It is used in different ways: to mean an individual statement written in the policy language; to mean a collection of statements in a single, named "policy" document (which has an Oracle Cloud ID (OCID) assigned to it), and to mean the overall body of policies your organization uses to control access to resources.

A **compartment** is a collection of related resources that can be accessed only by certain groups that have been given permission by an administrator in your organization.

To use Oracle Cloud Infrastructure, you must be given the required type of access in a policy written by an administrator, whether you're using the Console, or the REST API with a software development kit (SDK), a command-line interface (CLI), or some other tool. If you try to perform an action, and receive a message that you don't have permission, or are unauthorized, then confirm with your administrator the type of access you've been granted, and which compartment you should work in.

For administrators: The policy in "Let database admins manage DB systems" lets the specified group do everything with databases and related database resources.

If you're new to policies, then see "Getting Started with Policies" and "Common Policies". If you want to dig deeper into writing policies for databases, then see "Details for the Database Service".



Related Topics

- Let database admins manage DB systems
- Getting Started with Policies
- Common Policies
- Details for the Database Service

Tagging Resources

You can apply tags to your resources to help you organize them according to your business needs.

You can apply tags at the time you create a resource, or you can update the resource later with the desired tags. For general information about applying tags, see "Resource Tags".

Related Topics

Resource Tags

Moving Resources to a Different Compartment

You can move vaults from one compartment to another.

After you move a vault to a new compartment, inherent policies apply immediately and affect access to the vault. Moving a vault doesn't affect access to any keys or secrets that the vault contains. You can move a key or secret from one compartment to another independently of moving the vault it's associated with. For more information, see "Managing Compartments".

Related Topics

Managing Compartments

Setting Up Your Exadata Cloud@Customer to Work With Oracle Key Vault

Prerequisites

- Ensure that OKV is setup and the network is accessible from the Exadata client network.
- Ensure that the REST interface is enabled from the OKV user interface.
- 3. Create "OKV REST Administrator" user. You can use any qualified username of your choice, for example, "okv_rest_user". While creating, ensure that the "OKV REST Administrator" user has the create end point and create end point group privileges. While provisioning Autonomous Database, you must use the same "OKV REST Administrator" user credentials.
- Gather OKV administrator credentials and IP address, which is required to connect to OKV.
- Open the ports 443, 5695, and 5696 for egress on the client network to access the OKV server.



For more information, see Network Port Requirements, Managing Oracle Key Vault Users, and Managing Administrative Roles and User Privileges

- Step 1: Create a Vault in OCI Vault Service and Add a Secret to the Vault to Store OKV REST Administrator Password
- Step 2: Create a Dynamic Group and a Policy Statement for Key Store to Access Secret in OCI Vault
- Step 3: Create a Dynamic Group and a Policy Statement for Exadata Infrastructure to Key Store
- Step 4: Create a Policy Statement for Database Service to Use Secret from OCI Vault Service
- Step 5: Create Key Store

Related Topics

- Network Port Requirements
- Managing Oracle Key Vault Users
- Managing Administrative Roles and User Privileges

Step 1: Create a Vault in OCI Vault Service and Add a Secret to the Vault to Store OKV REST Administrator Password

Your Exadata Cloud@Customer infrastructure communicates with OKV over REST each time an Autonomous Container Database is provisioned to register the Autonomous Container Database and request a wallet on OKV. Therefore, Exadata infrastructure needs access to the REST admin credentials.

These credentials can be stored securely in the Oracle Vault Service in OCI as a Secret and accessed by your Exadata Cloud@Customer infrastructure only when needed. These credentials are not accessible by a human operator administering the Exadata infrastructure.

To store OKV administrator password in OCI Vault service, create a vault by following the instructions outlined in "Managing Vaults" and create a Secret in that vault by following the instructions outlined in "Managing Secrets".

Related Topics

- Managing Vaults
- Managing Secrets

Step 2: Create a Dynamic Group and a Policy Statement for Key Store to Access Secret in OCI Vault

To grant your Key Store resources permission to access Secret in OCI Vault, you create an IAM dynamic group that identifies these resources and then create an IAM policy that grants this dynamic group access to the Secret you created in the OCI Vaults and Secrets.

When defining the dynamic group, you identify your Key Store resources by specifying the OCID of the compartment containing your Key Store.

1. Copy the OCID of the compartment containing your Key Store resource.



You can find this OCID on the Compartment Details page of the compartment.

2. Create a dynamic group by following the instructions in "To create a dynamic group" in Oracle Cloud Infrastructure Documentation. When following these instructions, enter a matching rule of this format:

```
ALL {resource.compartment.id ='<compartment-ocid>'}
```

where **<compartment-ocid>** is the OCID of the compartment containing your Key Store resource.

3. After creating the dynamic group, navigate to (or create) an IAM policy in a compartment higher up in your compartment hierarchy than the compartment containing your vaults and secrets. Then, add a policy statement of this format:

```
allow dynamic-group <dynamic-group> to use secret-family in
compartment <vaults-and-secrets-compartment>
```

where **<dynamic-group>** is the name of the dynamic group you created and **<vaults-and-secrets-compartment>** is the name of the compartment in which you created your vaults and secrets.

Related Topics

To create a dynamic group

Step 3: Create a Dynamic Group and a Policy Statement for Exadata Infrastructure to Key Store

To grant your Exadata infrastructure resources permission to access Key Store, you create an IAM dynamic group that identifies these resources and then create an IAM policy that grants this dynamic group access to the Key Store you created.

When defining the dynamic group, you identify your Exadata infrastructure resources by specifying the OCID of the compartment containing your Exadata infrastructure.

 Copy the OCID of the compartment containing your Exadata infrastructure resource.

You can find this OCID on the Compartment Details page of the compartment.

2. Create a dynamic group by following the instructions in "To create a dynamic group" in Oracle Cloud Infrastructure Documentation. When following these instructions, enter a matching rule of this format:

```
ALL {resource.compartment.id = '<compartment-ocid>'}
```

where **<compartment-ocid>** is the OCID of the compartment containing your Exadata infrastructure resource.



3. After creating the dynamic group, navigate to (or create) an IAM policy in a compartment higher up in your compartment hierarchy than the compartment containing your Key Store. Then, add a policy statement of this format:

Allow dynamic-group <dynamic-group> to use keystores in compartment <key-store-compartment>

where **<dynamic-group>** is the name of the dynamic group you created and **<key-store-compartment>** is the name of the compartment in which you created your Key Store.

Step 4: Create a Policy Statement for Database Service to Use Secret from OCI Vault Service

To grant the Autonomous Database service permission to use the secret in OCI Vault to log in to the OKV REST interface, navigate to (or create) an IAM policy in a compartment higher up in your compartment hierarchy than the compartment containing your OCI Vaults and Secrets. Then, add a policy statement of this format:

allow service database to read secret-family in compartment <vaults-andsecrets-compartment>

where <*vaults-and-secrets-compartment*> is the name of the compartment in which you created your OCI Vaults and Secrets.

Once the OCI Vault is set up and the IAM configuration is in place, you are now ready to deploy your Oracle Key Vault 'Key Store' in OCI and associate it with your Exadata Cloud@Customer VM Cluster.

Step 5: Create Key Store

Follow these steps to create a Key Store to connect to an on-premises encryption key appliance such as Oracle Key Vault (OKV).

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- Choose your Compartment.
- 3. Click **Key Stores**.

Key Stores page displays the list name of key stores, the number of databases associated with each database, and the date on which each key store was created.

- 4. Click Create Key Store.
- 5. In the **Create Key Store** dialog, enter the following general information:
 - Name your key store: A user-friendly description or other information that helps you easily identify the Key Store resource. Avoid entering confidential information.
 - Oracle Key Vault connection settings
 - Connection IP addresses: Enter the IP address of the OKV appliance. You can specify a comma-delimited list of IP addresses, for example, 193.10.20.1, 193.10.20.1.
 - Administrator username: Enter the user name of the OKV REST administrator.



- Administrator Password Secret: The administrator password is stored with the secret management service within OCI. Select the OCI Vault in your tenancy that contains OKV REST administrator password stored as Secret.
- Tags: Optionally, you can apply tags. If you have permission to create a
 resource, you also have permission to apply free-form tags to that resource.
 To apply a defined tag, you must have permission to use the tag namespace.
 For more information about tagging, see Resource Tags. If you are not sure if
 you should apply tags, skip this option (you can apply tags later) or ask your
 administrator. Avoid entering confidential information.
- 6. Click Create Key Store.
- 7. Ensure that you use the same "OKV REST Administrator" user credentials, for example, "okv rest user", while provisioning Autonomous Database.

For more information, see *Managing Vaults*, *Managing Keys*, and *Managing Secrets*.

Related Topics

- Managing Vaults
- Managing Keys
- Managing Secrets

Managing Your Key Store

View Key Store Details

Follow these steps to view Key Store details that include Oracle Key Vault (OKV) connection details and the list of associated databases.

Edit Key Store Details

You can edit a Key Store only if it is not associated with any CDBs.

Move a Key Store to Another Compartment

Follow these steps to move a Key Store on an Oracle Exadata Cloud@Customer system from one compartment to another compartment.

Delete a Key Store

You can delete a Key Store only if it is not associated with any CDBs.

- View Key Store Associated Autonomous Container Database Details
 Follow these steps to view details of the Autonomous Container Database associated with a Key Store.
- Using the API to Manage Key Store Learn how to use the API to manage key store.

View Key Store Details

Follow these steps to view Key Store details that include Oracle Key Vault (OKV) connection details and the list of associated databases.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- Choose your Compartment.



3. Click Key Stores.

Key Stores page displays the list name of Key Stores, the number of databases associated with each database, and the date on which each Key Store was created.

- Click the name of the Key Store or click the Actions icon (three dots), and then click View Details.
- 5. Click the link in the Administrator Password Secret field to view secret details.

Edit Key Store Details

You can edit a Key Store only if it is not associated with any CDBs.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose your Compartment.
- Click Key Stores.
- Click the name of the Key Store or click the Actions icon (three dots), and then click View Details.
- On the Key Store Details page, click Edit.
- 6. On the Edit Key Store page, make changes as needed, and then click Save Changes.

Move a Key Store to Another Compartment

Follow these steps to move a Key Store on an Oracle Exadata Cloud@Customer system from one compartment to another compartment.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose your Compartment.
- 3. Click **Key Stores**.
- Click the name of the Key Store or click the Actions icon (three dots), and then click View Details.
- 5. On the **Key Store Details** page, click **Move Resource**.
- 6. On the Move Resource to a Different Compartment page, select the new compartment.
- 7. Click Move Resource.

Delete a Key Store

You can delete a Key Store only if it is not associated with any CDBs.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose your Compartment.
- Click Key Stores.
- Click the name of the Key Store or click the Actions icon (three dots), and then click View Details.
- On the Key Store Details page, click **Delete**.
- 6. On the Delete Key Store dialog, click **Delete**.



View Key Store Associated Autonomous Container Database Details

Follow these steps to view details of the Autonomous Container Database associated with a Key Store.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Choose your Compartment.
- 3. Click **Key Stores**.

Key Stores page displays the list name of Key Stores, the number of databases associated with each database, and the date on which each Key Store was created.

- Click the name of the Key Store or click the Actions icon (three dots), and then click View Details.
- Click the name of the associated database or click the Actions icon (three dots), and then click View Details.

Using the API to Manage Key Store

Learn how to use the API to manage key store.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

The following table lists the REST API endpoints to manage key store.

Operation	REST API Endpoint
Create OKV Key Store	CreateKeyStore
View OKV Key Store	GetKeyStore
Update OKV Key Store	UpdateKeyStore
Delete OKV Key Store	DeleteKeyStore
Change Key store compartment	ChangeKeyStoreCompartment
Choose between customer-managed and Oracle-managed encryption	CreateAutonomousContainerDatabase
Get the Key Store (OKV or Oracle-managed) and OKV wallet name	GetAutonomousContainerDatabase
Rotate OKV and Oracle-managed key	RotateAutonomousContainerDatabaseKey
Get the Key store (OKV or Oracle-managed) and OKV wallet name	GetAutonomousDatabase
Rotate OKV and Oracle-managed key	RotateAutonomousDatabaseKey
Get the Key Store (OKV or Oracle-managed) and OKV wallet name	GetAutonomousDatabaseBackup

Related Topics

REST APIs



- Security Credentials
- · Software Development Kits and Command Line Interface

Managing Autonomous Container Databases

Learn how you can create, view, move, change backup policies, manage maintenance schedules, and perform other Oracle Autonomous Container Database management.

An Autonomous Container Database resource provides a container for your Autonomous Databases. You can create multiple Autonomous Container Database resources in a single Autonomous Exadata VM Cluster resource, but you must create at least one before you can create any Autonomous Databases.

- Create an Autonomous Container Database
- · View a List of Autonomous Container Databases
- View Details of an Autonomous Container Database
- Rotate CDB Encryption Key
- Change the Backup Retention Policy of an Autonomous Container Database
- Change the Maintenance Schedule of an Autonomous Container Database
- Restart an Autonomous Container Database
- Move an Autonomous Container Database to Another Compartment
- Terminate an Autonomous Container Database
- Using the API to Manage Autonomous Container Databases

Create an Autonomous Container Database

Follow these steps to create an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. Click Create Autonomous Container Database.

The Create Autonomous Container Database page is displayed.

- **4.** Provide the following basic information:
 - Compartment: Choose the compartment in which your autonomous container database will be created.
 - Display Name: Enter a user-friendly description or other information that helps you
 easily identify the autonomous container database. The display name does not have
 to be unique. Avoid entering confidential information.
- Select the Autonomous Exadata VM Cluster you wish to use to create your autonomous container database.
- 6. Optionally, you can configure an automatic maintenance schedule.
 - a. Click Modify Maintenance.
 - **b.** To configure the maintenance schedule, select **Specify a schedule**.



Choose your preferred month, week, weekday, and start time for autonomous container database maintenance.

- Under Week of the month, specify which week of the month maintenance will take place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week. Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days.
- Under Day of the week, specify the day of the week on which the maintenance will occur.
- Under Start hour, specify the hour during which the maintenance run will begin.
- c. Click Save Changes.
- Select a Backup Destination Type:
 - Object Storage: Stores backups in an Oracle-managed object storage container on Oracle Cloud Infrastructure. Optionally, you can use this field to specify your corporate HTTP proxy. We recommend using an HTTP proxy when possible for enhanced security.
 - Network File System (NFS): Stores backups in one of your previously defined backup destinations that uses Network File System (NFS) storage.
 - Select a Backup Destination.
 - Recovery Appliance: Stores backups in one of your previously defined backup destinations that uses Oracle Zero Data Loss Recovery Appliance.
 - Select a Backup Destination.
 - Provide a unique name for the database.
 - Provide a VPC user name and password.
- **8.** The following Advanced Options are available:
 - Backup retention period: Customize the retention period for automatic backups. For Recovery Appliance, you cannot select the retention period.
 - Encryption Key: Choose an encryption option, Encrypt using Oraclemanaged keys or Encrypt using customer-managed keys. The default option is Oracle-managed keys.

To use customer-managed keys, select the **Encrypt using customer-managed keys** option, select the compartment where you have created the Key Store, and then select the Key Store. As part of the CDB creation, a new wallet is created for the CDB in Oracle Key Vault (OKV). Also, a TDE Master Key is generated for the CDB and added to the wallet in OKV.



Note:

- Autonomous Container Databases and Autonomous Databases only support 256-bit Hardware Security Module (HSM) Vault keys.
- Validate OKV Key encryption post restart: OKV TDE Maser Key is validated every time you start or restart your ACD. Start or restart fails if the key is not validated. Work requests and life cycle states indicate the reason for failure.
- View OKV keys post database restore: When you restore a CDB, the master key associated with that backup is restored as well.
- Enable CDB backups to capture wallet name: CDB backups information about the wallet associated with the backup.
- OKV Wallet or TDE Master Key on CDB deletion: If you delete a CDB, then the wallet and TDE Master Key remains in OKV and will not be deleted.
- Tags: Optionally, you can apply tags. If you have permissions to create a resource, you also have permissions to apply free-form tags to that resource. To apply a defined tag, you must have permissions to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.
- 9. Click Create Autonomous Container Database.

View a List of Autonomous Container Databases

There are two ways to view a list of autonomous container databases on an Oracle Exadata Database Service on Cloud@Customer system.

- View the List of Autonomous Container Databases in an Autonomous Exadata VM Cluster
- View the List of Autonomous Container Databases in a Compartment

View the List of Autonomous Container Databases in an Autonomous Exadata VM Cluster

Follow these steps to view a list of an autonomous container databases in a given autonomous Exadata VM cluster on an Oracle Exadata Database Service on Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Exadata VM Clusters.
- Click the display name of the Autonomous Exadata VM Cluster that you interested in.
 In the Autonomous Exadata VM Clusters Details page, a list of Autonomous Container Databases is displayed under Resources.



You can also filter out to view Autonomous Container Databases in a particular compartment. Under **List Scope**, select a compartment from the **Compartment** drop-down list.

View the List of Autonomous Container Databases in a Compartment

Follow these steps to view a list of an autonomous container databases in a given compartment on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Click Autonomous Container Databases.
- 3. Under List Scope, select a compartment from the Compartment drop-down list.

View Details of an Autonomous Container Database

Follow these steps to view detailed information about an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the database you wish to view details.

On the Autonomous Container Database Details page encryption details are displayed under **Encryption**.

If you have chosen customer-managed keys while creating the database, then you will see a link to the **Encryption Key Store** and **OKV Wallet Name**.



OKV Wallet Name represents the name of the wallet in which keys for this CDB are generated on the OKV.

Click the **Key Store** link to view details.

If you have chosen Oracle-managed keys while creating the database, then you will not see the link to **Encryption Key Store** and **OKV Wallet Name**.

Rotate CDB Encryption Key

Follow these steps to rotate the TDE Master key. On key rotation, the ACD life cycle goes through the regular updating state and returns to available.

You can rotate the TDE Master key as many times as you want. The new TDE Master Key is stored in the same wallet in which the previous key was stored. Rotating the TDE Master Key leads to the new key being generated in OKV and assigned to this database. You can view all of the keys in OKV.



Note:

You can rotate both Oracle-managed and customer-managed encryption keys.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the database you wish to view details.
- 4. On the Autonomous Container Database Details page, click Rotate Encryption Key.
- 5. On the Rotate Encryption Key dialog, click Rotate Encryption Key.

Change the Backup Retention Policy of an Autonomous Container Database

Follow these steps to update the backup retention policy of an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.

Note:

By default, database backups are retained for 30 days if you have chosen Object Storage or NFS as a backup destination. You have the option of retaining backups for 7, 15, 30, or 60 days. If you have chosen Local storage as a backup destination, then by default, database backups are retained for a maximum of 7 days. If you have chosen Recovery Appliance as a backup destination, then you cannot update the backup retention policy.

The current backup retention policy for an Autonomous Container Database is displayed on the Autonomous Container Database details page.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Click Autonomous Container Databases.
- In the list of Autonomous Container Databases, click the display name of the container database you are interested in.
- 4. On the Autonomous Container Database details page, under **Backup**, click the **Edit** link in the **Backup retention policy** field.
- 5. Specify a backup retention period from the list of choices.
- 6. Click Update.

Change the Maintenance Schedule of an Autonomous Container Database

Follow these steps to change the maintenance schedule of an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.



- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database you are interested in.
- 4. On the Autonomous Container Database details page, under **Maintenance**, click the edit link in the **Maintenance Details** field.
- 5. In the Edit Automatic Maintenance dialog that opens, configure automatic maintenance schedule.
 - No preference: The system assigns a date and start time for container database maintenance.
 - Specify a schedule: Choose your preferred month, week, weekday, and start time for container database maintenance.
- 6. Click Save Changes.

Restart an Autonomous Container Database

Follow these steps to restart an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.

The restart of an autonomous container database occurs in a rolling fashion, first stopping and starting one of the container database's database instances and then stopping and starting its other database instance.



You cannot restart an autonomous container database if a backup is in progress on any of its autonomous databases.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database you are interested in.

Autonomous Container Database details page is displayed.

Autonomous Container Database details page displays details that include total OCPU, available OCPU, reclaimable OCPU, and database memory per OCPU in GB.

- 4. On the Autonomous Container Database details page, click **Restart**.
- 5. In the confirmation dialog, type the name of the Autonomous Container Database.
- 6. Click Restart.

(or)

a. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



- b. Click Autonomous Container Databases.
- c. In the list of Autonomous Container Databases, click the Actions icon (three dots) for the container database you are interested in, and then select Restart.
- d. In the confirmation dialog, type the name of the Autonomous Container Database.
- e. Click Restart.

Move an Autonomous Container Database to Another Compartment

Follow these steps to move an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system from one compartment to another compartment.

Note:

- To move an autonomous container database you must have the right to manage it in its current compartment and in the compartment you are moving it to.
- As soon as you move an autonomous container database to a different compartment, the policies that govern the new compartment apply immediately and affect access to the autonomous container database. Therefore, both your and other Oracle Cloud users' access to it may change, depending on the policies governing the user account's access to resources. For example, a user may lose the ability to create autonomous databases in the autonomous container database, given its new compartment.
- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- In the list of Autonomous Container Databases, click the display name of the container database you wish to move.
- 4. Click Move Resource.
- Select the new compartment.
- 6. Click Move Resource.

Terminate an Autonomous Container Database

Follow these steps to terminate an autonomous container database on an Oracle Exadata Database Service on Cloud@Customer system.



You must terminate all Autonomous Databases within a container database before you can terminate the container database itself.



- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.
- 4. Click **Terminate**.
- In the confirmation dialog, type the name of the Autonomous Container Database, and then click Terminate Autonomous Container Database.

Using the API to Manage Autonomous Container Databases

For information about using the API and signing requests, see REST APIs and Security Credentials. For information about SDKs, see Software Development Kits and Command Line Interface.

The following table lists the REST API endpoints to manage Autonomous Container Databases.

Operation	REST API Endpoint
Create an Autonomous Container Database	CreateAutonomousContainerDatabase
View a list of Autonomous Container Databases	ListAutonomousContainerDatabases
View details of an Autonomous Container Database	GetAutonomousContainerDatabase
Change the backup retention policy of an Autonomous Container Database	UpdateAutonomousContainerDatabase
Change the maintenance schedule of an Autonomous Container Database	UpdateAutonomousContainerDatabase
Restart an Autonomous Container Database	RestartAutonomousContainerDatabase
Move an Autonomous Container Database to another compartment	ChangeAutonomousContainerDatabaseComp artment
Terminate an Autonomous Container Database	TerminateAutonomousContainerDatabase

Managing Autonomous Databases

An Autonomous Database resource is a user database. When you create an Autonomous Database, you choose the Autonomous Container Database for it and you specify "Data Warehouse" or "Transaction Processing" as its workload type to create an Autonomous Data Warehouse database or an Autonomous Transaction Processing database.

You can create hundreds of Autonomous Databases on an Exadata Infrastructure. As described in *Available Exadata Infrastructure Hardware Shapes*, the maximum is determined by the capacity of your Exadata Infrastructure hardware.

- Create an Autonomous Database
- Manage Access Control List of an Autonomous Database
- View a List of Autonomous Databases



- View Details of an Autonomous Database
- Rotate ADB Encryption Key
- Set the Password of an Autonomous Database's ADMIN User
- Scale the CPU Core Count or Storage of an Autonomous Database
- Enable or Disable Auto Scaling for an Autonomous Database
- Move an Autonomous Database to Another Compartment
- Stop or Start an Autonomous Database
- Restart an Autonomous Database
- Back Up an Autonomous Database Manually
- Restore an Autonomous Database
- Clone an Autonomous Database
- Clone an Autonomous Database Backup
- Clone a Standby Database
- Clone a Standby Database Backup
- Terminate an Autonomous Database
- API to Manage Autonomous Databases
- Monitor Performance with Autonomous Database Metrics

Related Topics

Available Exadata Infrastructure Hardware Shapes

Create an Autonomous Database

Follow these steps to create an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. Click Create Autonomous Database.
- 4. In the Create Autonomous Database dialog, enter the following:

Basic Database Information

- Compartment: Select the compartment of the Autonomous Database.
- Display Name: A user-friendly description or other information that helps you easily identify the resource. The display name does not have to be unique. Avoid entering confidential information.
- Database Name: The database name must consist of letters and numbers only, starting with a letter. The maximum length is 14 characters. Avoid entering confidential information.

Workload Type

Select the desired workload type.

Data Warehouse



Transaction Processing

See *About Autonomous Database* for information about each workload type. **Autonomous Container Database:** Select an Autonomous Container Database.

Compartment: Specify the compartment containing the Autonomous Container Database you wish to use.

Configure the database

 OCPU Count: Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

Create Autonomous Databases with less than 1 OCPU count using fractional units. Fractional OCPU supports up to 10 Autonomous Databases per core with the smallest OCPU count being 0.1 and up to 0.9 fractional OCPU with an increment of 0.1. Fractional OCPU is for less than one OCPU only. For OCPU equal to or greater than one, the increment must be in integer.

Default: 1

Minimum: 0.1

Maximum: Set by quota

Increment between 0.1 and 0.9: 0.1

Increment between 1 and maximum: 1

Auto scaling: Deselect Auto Scaling to disable auto scaling. By default auto scaling is enabled to allow the system to automatically use up to three times more CPU and IO resources to meet workload demand.

Fractional OCPU auto-scaling behaves the same way as integer OCPU auto-scaling. However, there is a subtle difference between fractional OCPU auto-scaling and integer OCPU auto-scaling behaviors. Fractional OCPU auto-scaling will scale three times the base OCPU and then round it off to a whole number.

For example, 0.1 OCPU can auto-scale up to 1 OCPU, 0.5 OCPU can auto-scale up to 2 OCPU, 0.7 OCPU can auto-scale up to 3 OCPU, and so on.

• Storage (GB): Specify the storage you wish to make available to your Autonomous Database, in GB. The available storage depends on the infrastructure shape and what is already consumed by other Autonomous Databases.

Default: 1024 GBMinimum: 32 GBIncrement: 1 GB

Administrator Credentials

Set the password for the Autonomous Database Admin user by entering a password that meets the following criteria. Use this password when accessing the Autonomous Database service console and when using an SQL client tool.

- Contains from 12 to 30 characters
- Contains at least one lowercase letter
- Contains at least one uppercase letter



- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Configure network access You can optionally create an ACL during database provisioning, or at any time thereafter.

- Select the Enable database level access control checkbox.
- Click Access Control Rule.



The database-level access control will be enabled without any IP addresses in the access control list. Enabling an access control list with an empty list of IP addresses makes the database inaccessible to all clients

- Specify the following types of addresses in your list by using the IP notation type drop-down selector:
 - IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Advanced Options:

- Encryption Key: ADB inherits encryption settings from the parent ACD. If the parent
 ACD is configured for customer-managed OKV-based encryption, then the child ADB
 will also have a TDE Master Key generated and managed in the same OKV wallet
 used to store ACD master keys. Additionally, any backups taken on the Autonomous
 Database will have the OKV based key associated with it.
- Management: Choose a Character Set and National Character from the drop-down list.
- **Tags:** Optionally, you can apply tags. If you have permission to create a resource, you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see *Resource Tags*. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.
- 5. Click Create Autonomous Database.



Note:

The following naming restrictions apply to Autonomous Transaction Processing and Autonomous Data Warehouse databases:

- Names associated with databases terminated within the last 60 days cannot be used when creating a new database.
- A database name cannot be used concurrently for both an Autonomous Data Warehouse and an Autonomous Transaction Processing database.

Related Topics

- · About Autonomous Database
- Resource Tags

Manage Access Control List of an Autonomous Database

Enabling an access control list with an empty list of IP addresses makes the database inaccessible.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Choose your Compartment.
- 3. In the list of Autonomous Databases, click the display name of the database you want to administer.
- Under Network in the database details, find the Access Control List field and click Edit to enable or disable your database-level access control and make changes to the ACL rules.

Note:

Autonomous Data Guard enabled Automonous databases:

- You can only view ACLs for standby databases.
- You can reset ACL for both the primary and standby databases from the primary database details page. You cannot configure ACL from the standby database details page.
- 5. In the Access Control List dialog, add or modify entries, as applicable.

If you are editing an ACL, the ACL's existing entries display in the Access Control List dialog. Do not overwrite the existing values unless you intend to replace one or more entries. To add new ACL entries, click + Access Control Rule.

You can specify the following types of addresses in your list by using the IP notation type drop-down selector:

IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.



 CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Click + Access Control Rule to add additional access rules to your list.

To remove an access control rule, simply delete the entry from the list. Deleting all access control rules from the ACL will render the database inaccessible because the allow list is empty.

To disable the database-level access control configuration, clear the **Enable database level access control** checkbox. Once ACL is disabled and the configuration is saved, all the access control rules are removed from the ACL and no longer applicable.

6. Click Save Changes.

If the **Lifecycle State** is **Available** when you click **Save**, the Lifecycle State changes to **Updating** until the ACL update is complete. The database is still up and accessible, there is no downtime. When the update is complete the **Lifecycle State** returns to **Available** and the network ACL rules from the access control list are in effect.

View a List of Autonomous Databases

Follow these steps to view a list of autonomous databases on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.

View Details of an Autonomous Database

Follow these steps to view detailed information about an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you wish to view details.

On the Autonomous Container Database Details page encryption details are displayed under **Encryption**.

If you have chosen customer-managed keys while creating the database, then you will see a link to the **Encryption Key Store** and **OKV Wallet Name**. Click the **Key Store** link to view details.

If you have chosen Oracle-managed keys while creating the database, then you will not see the link to **Encryption Key Store** and **OKV Wallet Name**.

Rotate ADB Encryption Key

Follow these steps to rotate the TDE Master key. On key rotation, the ADB life cycle goes through the regular updating state and returns to available.

You can rotate the TDE Master key as many times as you want. The new TDE Master Key is stored in the same wallet in which the previous key was stored. Rotating the TDE Master Key

leads to the new key being generated in OKV and assigned to this database. You can view all of the keys in OKV.



You can rotate both Oracle-managed and customer-managed encryption keys.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to view details.
- **4.** On the Autonomous Database Details page, from the **More Actions** drop-down list, select **Rotate Encryption Key**.
- 5. On the Rotate Encryption Key dialog, click Rotate Encryption Key.

Set the Password of an Autonomous Database's ADMIN User

Follow these steps to set the ADMIN database user's password for an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you wish to administer.
- 4. From the More Actions drop-down list, select Admin Password.

The Admin Password dialog opens.

5. Enter a password for the Autonomous Database.

The password must meet the following criteria:

- Contains from 12 to 30 characters
- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of case
- Is not one of the last four passwords used for the database
- Is not a password you previously set within the last 24 hours
- **6.** Enter the password again in the **Confirm Password** field.
- Click Update.



Scale the CPU Core Count or Storage of an Autonomous Database

Follow these steps to scale the CPU core count or storage an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system up or down.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you wish to view details.
- 4. Click Scale Up/Down.
- 5. Enter a new value for CPU Core Count or Storage.
 - OCPU Count: Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

The selected OCPU count is validated against a list of provisionable OCPUs, and if the database can not be scaled up to the chosen OCPU count, you will be provided with the two nearest provisionable OCPU values.

Based on the resource utilization on each node; not all the values of the available OCPUs can be used to provision or scale Autonomous Databases. For example, suppose you have 20 OCPUs available at the AVMC level, not all the values from 1 to 20 OCPUs can be used to provision or scale Autonomous Databases depending on the resource availability at the node level. The list of OCPU values that can be used to provision or scale an Autonomous Database is called **Provisionable OCPUs**.

On the console, when you try to provision or scale an Autonomous Database, the OCPU count will be validated against the list of provisionable OCPUs, and if the value is not provisionable, you will be provided with the two nearest provisionable OCPU values. Alternatively, if you want to see the complete list of provisionable OCPU values for an Autonomous Exadata VM Cluster, you can use the following API:

GetAutonomousDatabase returns a list of provisionable OCPU values that can be used for scaling a given Autonomous Database. See GetAutonomousDatabase for more details.

The default is no change. For databases that do not need a full core, you can increment the OCPU value from 0.1 to 0.9 (in increments of 0.1). For databases using 1 or more OCPU cores, you must increment the number of assigned OCPU by one or more full cores. For example, you cannot assign 3.5 OCPU to a database. The next available number of OCPU above 3 is 4.

Default: Current value

Minimum: 0.1

Maximum: Set by quota

Increment between 0.1 and 0.9: 0.1

Increment between 1 and maximum: 1



Auto scaling: Deselect Auto Scaling to disable auto-scaling. By default, auto-scaling is enabled to allow the system to automatically use up to three times more CPU and IO resources to meet workload demand.

Fractional OCPU auto-scaling behaves the same way as integer OCPU auto-scaling. However, there is a subtle difference between fractional OCPU auto-scaling and integer OCPU auto-scaling behaviors. Fractional OCPU auto-scaling will scale three times the base OCPU and then round it off to a whole number.

For example, 0.1 OCPU can auto-scale up to 1 OCPU, 0.5 OCPU can auto-scale up to 2 OCPU, 0.7 OCPU can auto-scale up to 3 OCPU, and so on.

• Storage (GB): Specify the storage you wish to make available to your Autonomous Database, in GB. The available storage depends on the infrastructure shape and what is already consumed by other Autonomous Databases.

Default: Current value

Minimum: 32 GBIncrement: 1 GB

6. Click Update.

Related Topics

- Service Limits
- GetAutonomousDatabase

Enable or Disable Auto Scaling for an Autonomous Database

Oracle Autonomous Database on Oracle Exadata Database Service on Cloud@Customer systems provides an auto scaling feature that automatically increases the number of cores an automonomous database during periods of increased demand and, as demand returns to normal, automatically decreases the number of cores down to the databases's base number.

Note the following points regarding the auto scaling feature:

- With auto scaling enabled, the database can use up to three times more CPU and IO resources than specified by the number of OCPUs currently shown in the Scale Up/Down dialog.
- If auto scaling is disabled while more CPU cores are in use than the database's currently assigned number of cores, then Autonomous Database scales the number of CPU cores in use down to the assigned number.
- Enabling auto scaling does not change the concurrency and parallelism settings for the predefined services.

Follow these steps to enable or disable auto scaling for an autonomous database.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to view details.
- 4. Click Scale Up/Down.



- Check Auto Scaling to enable the auto scaling feature, or uncheck Auto Scaling to disable the feature.
- 6. Click Update.

Move an Autonomous Database to Another Compartment

Follow these steps to move an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system from one compartment to another compartment.

Note:

- To move an autonomous database you must have the right to manage it in its current compartment and in the compartment you are moving it to.
- As soon as you move an autonomous database to a different compartment, the
 policies that govern the new compartment apply immediately and affect access
 to the autonomous database. Therefore, both your and other Oracle Cloud
 users' access to it may change, depending on the policies governing the user
 account's access to resources. For example, a user may lose the ability to
 manage the autonomous databae, given its new compartment.
- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to move.
- 4. From the More Actions drop-down list, select Move Resource.
- 5. Select the new compartment.
- 6. Click Move Resource.

Stop or Start an Autonomous Database

Follow these steps to stop or start an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you wish to view details.
- 4. Click Stop (or Start).
 - When you stop your Autonomous Database, billing stops for CPU usage. Billing for storage continues when the database is stopped.
- Confirm that you want to stop or start your Autonomous Database in the confirmation dialog.



Note:

Stopping your database has the following consequences:

- On-going transactions are rolled back.
- You will not be able to connect to your database using database clients or tools.

Restart an Autonomous Database

To resolve some autonomous database issues with minimal downtime on Exadata Database Service on Cloud@Customer systems, you can restart the database.

Restarting an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system is equivalent to manually stopping and then starting the database. Using restart allows you to minimize downtime and requires only a single action.

Follow these steps to restart an autonomous database.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to restart.
- 4. Click Restart.
- 5. Confirm that you want to restart your Autonomous Database in the confirmation dialog.

The system stops and then immediately starts your database.

Back Up an Autonomous Database Manually

Oracle Autonomous Database automatically backs up autonomous databases on an Oracle Exadata Database Service on Cloud@Customer system. In addition, you can manually back up an autonomous database should the need arise.



During the backup operation, your autonomous database remains available. However, lifecycle management operations such as stopping it, scaling it, or terminating it are disabled.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to back up.



- 4. On the Details page, under Resources, click Backups.
- 5. Click Create Manual Backup.
- In the Create Manual Backup dialog, enter a name for your backup. Avoid entering confidential information.
- 7. Click Update.

The backup operation begins. This operation may take several hours to complete, depending on the size of the database.

Optionally, you can check the state of your backup in the list of backups on the database details page. For some states, an information icon is displayed to provide additional details regarding the state or ongoing operations like deletions. The backup has one of the following states:

- Creating
- Active
- Deleting
- Deleted
- Failed

Restore an Autonomous Database

You can use any existing manual or automatic backup to restore and recover an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system, or you can restore and recover the database to any point in time during the retention period of its automatic backups.



Restoring an autonomous database puts the database in the unavailable state during the restore operation. You cannot connect to a database in this state. The only lifecycle management operation supported in the unavailable state is terminate.

- Restore from a Backup
- Restore to a Point in Time

Restore from a Backup

Follow these steps to restore an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system from a specific backup.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you want to clone.
- **4.** From the **More Actions** drop-down list, select **Restore**.



- 5. Specify the date range for a list of backups to display.
- 6. Select the backup.
- Click Restore.

Restore to a Point in Time

Follow these steps to restore an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system to a specific point in time.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you want to restore.
- From the More Actions drop-down list, select Restore.
- Click Specify Timestamp.
- 6. Enter a timestamp.

Your Autonomous Database decides which backup to use for faster recovery. The timestamp input allows you to specify precision to the seconds level (YYYY-MM-DD HH: MM: SS GMT).

7. Click Restore.

Clone an Autonomous Database

Follow these steps to clone an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

You can use the cloning feature to create a point-in-time copy of your Autonomous Database for purposes such as testing, development, or analytics. To clone only the database schema of your source database, choose the metadata clone option.

Clone Types

The clone feature offers the following two types of Autonomous Database clones:

- The full-clone option creates a database that includes the metadata and data from the source database.
- The metadata-clone option creates a database that includes only the metadata from the source database.

Steps

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you want to clone.
- 4. From the More Actions drop-down list, select Create Clone.
- On the Create Autonomous Database Clone page, provide the following information:



In the **Clone Type** section, select the type of clone you want to create. Choose either **Full Clone** or **Metadata Clone**.

Clone Source: The clone source selection allows you to specify whether the clone is created from a running database or from a database backup. Select one of the following options:

- Clone from a database instance: Creates a clone of a running database as it exists at the current moment.
- Clone from a backup: Creates a clone from a database backup. If you choose this option, select one of the following options:
 - Specify a timestamp: Creates a point-in-time clone. The timestamp has to be between the first and latest backups of the database.
 - Select from a list of backups: Creates a clone using all data from the specified backup. To limit your list of backups to a specific date range, enter the starting date in the From field and the ending date in the To field.

Provide basic information for the Autonomous Database.

- Choose a compartment: Your current compartment is the default selection but you
 can select a different compartment in which to create the clone from the drop-down
 list.
- **Source database name**: The name of the source database displays in the read-only Source database name field.
- **Display name**: Enter a description or other information to identify the database clone. You can change the display name any time and it does not have to be unique. Avoid entering confidential information.
- **Database name**: Enter a database name for the clone that contains only letters and numbers, begins with a letter. Avoid entering confidential information.
- Three additional fields are displayed if you opt to clone from a backup.
 - Exadata Infrastructure: You can choose to create the database clone in the same Exadata Infrastructure where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
 - Autonomous Exadata VM Cluster: You can choose to create the database clone in the same Autonomous Exadata VM Cluster where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
- Choose autonomous container database in compartment: You can choose to
 create the database clone in the same compartment and container database as the
 source database, or you can choose a different compartment by clicking CHANGE
 COMPARTMENT, and a different container database by choosing one from the dropdown list.

Configure the database

- OCPU Count: Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.
 - The selected OCPU count is validated against a list of provisionable OCPUs, and if the database can not be scaled up to the chosen OCPU count, you will be provided with the two nearest provisionable OCPU values.



You can use the *GetAutonomousContainerDatabase* API to get a complete list of provisionable OCPU values.

The default is 1. However, you can assign a fractional OCPU value from 0.1 to 0.9 (in increments of 0.1) to databases that do not need a full OCPU. For databases that need 1 or more OCPU cores, you must specify the number of assigned OCPUs as an integer. For example, you cannot assign 3.5 OCPU to a database. The next available number of OCPU above 3 is 4.

Default: 1Minimum: 0.1

Maximum: Set by quota

Increment between 0.1 and 0.9: 0.1

Increment between 1 and maximum: 1

Storage (GB): Specify the amount of storage, in GB, that you want to make available to your cloned Autonomous Database, and it depends on the storage available to use. For full clones, the size of the source database determines the minimum amount of storage you can make available.

Default: 1024 GBMinimum: 32 GBIncrement: 1 GB

 Auto scaling: Enabling autoscaling allows the system to automatically use up to three times more CPU and I/O resources to meet workload demand.

Create administrator credentials

Set the password for the Autonomous Database administrator user by entering a password that meets the following criteria.

- Password cannot be one of the three most recently used passwords of the source database
- Between 12 and 30 characters long
- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Use this password when accessing the service console and when using a SQL client tool.

Configure Network Access

You can change the access control list to enable or disable database-level access control or add or modify entries to the access control list.

- Click Modify Access Control.
- Select the Enable database level access control check box.
- Click Access Control Rule.



Note: The database-level access control will be enabled without any IP addresses in the access control list. Enabling an access control list with an empty list of IP addresses makes the database inaccessible to all clients.

- Specify the following types of addresses in your list by using the IP notation type drop-down selector:
 - IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Advanced Options:

Encryption Key:

- Clone from a database instance: The source and the target ACD must be the same Keystore type. When the source is OKV, the target must also be the same OKV destination.
- Clone from a backup: The source and the target ACDs can be different
 Keystore types. When the source is OKV, the target must also be the same OKV
 destination.
- Tags: Optionally, you can apply tags. If you have permission to create a resource, you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.

6. Click Create Autonomous Database Clone.

The Console displays the details page for the new clone of your database and the service begins provisioning the Autonomous Database. Note the following:

- The new clone displays the **Provisioning** lifecycle state until the provisioning process completes.
- The source database remains in the Available lifecycle state.
- Backups associated with the source database are not cloned for either the full-clone or the metadata-clone option.

The **Clone source** is displayed in the **General Information** section of the cloned database details page. Click the name to view details of the source database. Note that if the source database is deleted, then this key/value pair is not displayed.

Related Topics

- GetAutonomousContainerDatabase
- Resource Tags

Clone an Autonomous Database Backup

Follow these steps to clone an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

You can use the cloning feature to create a point-in-time copy of your Autonomous Database for purposes such as testing, development, or analytics. To clone only the database schema of your source database, choose the metadata clone option.



Clone Types

The clone feature offers the following two types of Autonomous Database clones:

- The full-clone option creates a database that includes the metadata and data from the source database.
- The metadata-clone option creates a database that includes only the metadata from the source database.

Steps

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you want to clone.
- 4. Under Resources, click Backups.
- 5. In the list of backups, find the backup that you want to clone, click the action icon (three dots), and then click **Create Clone**.
- On the Create Autonomous Database Clone page, provide the following information:

In the Clone Type section, select Full Clone.

Clone Source: The clone source section displays the source backup details.

Provide basic information for the Autonomous Database.

- Choose a compartment: Your current compartment is the default selection but you can select a different compartment in which to create the clone from the drop-down list.
- **Source database name**: The name of the source database displays in the read-only Source database name field.
- **Display name**: Enter a description or other information to identify the database clone. You can change the display name any time and it does not have to be unique. Avoid entering confidential information.
- Database name: Enter a database name for the clone that contains only letters and numbers, begins with a letter. Avoid entering confidential information.
- Exadata Infrastructure: You can choose to create the database clone in the same Exadata Infrastructure where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
- Autonomous Exadata VM Cluster: You can choose to create the database clone in the same Autonomous Exadata VM Cluster where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
- Choose autonomous container database in compartment: You can choose
 to create the database clone in the same compartment and container
 database as the source database, or you can choose a different compartment
 by clicking CHANGE COMPARTMENT, and a different container database by
 choosing one from the drop-down list.



Note:

When the target Autonomous Exadata VM Cluster is the same as the source, then the database name cannot be the same as the source database name.

Configure the database

• **OCPU Count**: There is a minimum requirement of 2 OCPUs for an ADB clone from Backup. After the clone, you can resize to a lower value if needed.

Note:

The time taken to clone an ADB depends on the OCPU Count and the network bandwidth between the Backup Destination and the target ACD.

Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

The selected OCPU count is validated against a list of provisionable OCPUs, and if the database can not be scaled up to the chosen OCPU count, you will be provided with the two nearest provisionable OCPU values.

You can use the *GetAutonomousContainerDatabase* API to get a complete list of provisionable OCPU values.

The default is 1. However, you can assign a fractional OCPU value from 0.1 to 0.9 (in increments of 0.1) to databases that do not need a full OCPU. For databases that need 1 or more OCPU cores, you must specify the number of assigned OCPUs as an integer. For example, you cannot assign 3.5 OCPU to a database. The next available number of OCPU above 3 is 4.

- Default: 2
- Minimum: 2
- Maximum: Set by quota
- Storage (GB): Specify the amount of storage, in GB, that you want to make available
 to your cloned Autonomous Database, and it depends on the storage available to
 use.
 - Default/Minimum: Allocated storage of the source database
 - Increment: 1 GB
- Auto scaling: Enabling autoscaling allows the system to automatically use up to three times more CPU and I/O resources to meet workload demand.

Create administrator credentials

Set the password for the Autonomous Database administrator user by entering a password that meets the following criteria.

- Password cannot be one of the three most recently used passwords of the source database
- Between 12 and 30 characters long



- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Use this password when accessing the service console and when using a SQL client tool.

Configure Network Access

You can change the access control list to enable or disable database-level access control or add or modify entries to the access control list.

- Click Modify Access Control.
- Select the Enable database level access control check box.
- Click Access Control Rule.

Note: The database-level access control will be enabled without any IP addresses in the access control list. Enabling an access control list with an empty list of IP addresses makes the database inaccessible to all clients.

- Specify the following types of addresses in your list by using the IP notation type drop-down selector:
 - IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Advanced Options:

- Encryption Key:
 - Clone from a database instance: The source and the target ACD must be the same Keystore type. When the source is OKV, the target must also be the same OKV destination.
 - Clone from a backup: The source and the target ACDs can be different Keystore types. When the source is OKV, the target must also be the same OKV destination.
- Tags: Optionally, you can apply tags. If you have permission to create a
 resource, you also have permission to apply free-form tags to that resource.
 To apply a defined tag, you must have permission to use the tag namespace.
 For more information about tagging, see *Resource Tags*. If you are not sure if
 you should apply tags, skip this option (you can apply tags later) or ask your
 administrator. Avoid entering confidential information.

7. Click Create Autonomous Database Clone.

The Console displays the details page for the new clone of your database and the service begins provisioning the Autonomous Database. Note the following:

- The new clone displays the **Provisioning** lifecycle state until the provisioning process completes.
- The source database remains in the Available lifecycle state.



Related Topics

- GetAutonomousContainerDatabase
- Resource Tags

Clone a Standby Database

Follow these steps to clone a standby autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

You can use the cloning feature to create a point-in-time copy of your Autonomous Database for purposes such as testing, development, or analytics.

Clone Types: The clone feature offers the full-clone option to create a database that includes the metadata and data from the source database.

Steps

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the primary database.
- 4. Under Resources, click Autonomous Data Guard.
- 5. In the list of standby databases, find the database that you want to clone, and then click the display name to view details.
- 6. From the More Actions drop-down list, select Create Clone.
- **7.** On the Create Autonomous Database Clone page, provide the following information:

In the Clone Type section, select Full Clone.

Clone Source: You can clone the standby database only from a backup.

- Clone from a backup: Creates a clone from a database backup. If you choose this option, select one of the following options:
 - Specify a timestamp: Creates a point-in-time clone.
 - Select from a list of backups: Creates a clone using all data from the specified backup. To limit your list of backups to a specific date range, enter the starting date in the From field and the ending date in the To field.

Provide basic information for the Autonomous Database.

- Choose a compartment: Your current compartment is the default selection but you
 can select a different compartment in which to create the clone from the drop-down
 list.
- **Source database name**: The name of the source database displays in the read-only Source database name field.
- **Display name**: Enter a description or other information to identify the database clone. You can change the display name any time and it does not have to be unique. Avoid entering confidential information.
- **Database name**: Enter a database name for the clone that contains only letters and numbers, begins with a letter. Avoid entering confidential information.
- Three additional fields are displayed if you opt to clone from a backup.



- Exadata Infrastructure: You can choose to create the database clone in the same Exadata Infrastructure where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
- Autonomous Exadata VM Cluster: You can choose to create the
 database clone in the same Autonomous Exadata VM Cluster where the
 source database resides, or you can choose a different compartment by
 clicking CHANGE COMPARTMENT and choosing one from the dropdown list.
- Choose autonomous container database in compartment: You can choose
 to create the database clone in the same compartment and container
 database as the source database, or you can choose a different compartment
 by clicking CHANGE COMPARTMENT, and a different container database by
 choosing one from the drop-down list.

Configure the database

 OCPU Count: There is a minimum requirement of 2 OCPUs for an ADB clone from Backup. After the clone, you can resize to a lower value if needed. Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

The default is 1. However, you can assign a fractional OCPU value from 0.1 to 0.9 (in increments of 0.1) to databases that do not need a full OCPU. For databases that need 1 or more OCPU cores, you must specify the number of assigned OCPUs as an integer. For example, you cannot assign 3.5 OCPU to a database. The next available number of OCPU above 3 is 4.

Default: 1Minimum: 0.1

Maximum: Set by quota

- Increment between 0.1 and 0.9: 0.1

Increment between 1 and maximum: 1

• **Storage (GB)**: Specify the amount of storage, in GB, that you want to make available to your cloned Autonomous Database, and it depends on the storage available to use. For full clones, the size of the source database determines the minimum amount of storage you can make available.

Default: 1024 GBMinimum: 32 GBIncrement: 1 GB

Auto scaling: Enabling autoscaling allows the system to automatically use up
to three times more CPU and I/O resources to meet workload demand.

Create administrator credentials

Set the password for the Autonomous Database administrator user by entering a password that meets the following criteria.

- Password cannot be one of the three most recently used passwords of the source database
- Between 12 and 30 characters long



- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Use this password when accessing the service console and when using a SQL client tool.

Configure Network Access

You can change the access control list to enable or disable database-level access control or add or modify entries to the access control list.

- Click Modify Access Control.
- Select the Enable database level access control check box.
- Click Access Control Rule.

Note: The database-level access control will be enabled without any IP addresses in the access control list. Enabling an access control list with an empty list of IP addresses makes the database inaccessible to all clients.

- Specify the following types of addresses in your list by using the IP notation type drop-down selector:
 - IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Advanced Options:

- Encryption Key:
 - Clone from a database instance: The source and the target ACD must be the same Keystore type. When the source is OKV, the target must also be the same OKV destination.
 - Clone from a backup: The source and the target ACDs can be different Keystore types. When the source is OKV, the target must also be the same OKV destination.
- Tags: Optionally, you can apply tags. If you have permission to create a resource, you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.

8. Click Create Autonomous Database Clone.

The Console displays the details page for the new clone of your database and the service begins provisioning the Autonomous Database. Note the following:

- The new clone displays the **Provisioning** lifecycle state until the provisioning process completes.
- The source database remains in the **Available** lifecycle state.



 Backups associated with the source database are not cloned for either the fullclone or the metadata-clone option.

The **Clone source** is displayed in the **General Information** section of the cloned database details page. Click the name to view details of the source database. Note that if the source database is deleted, then this key/value pair is not displayed.

Related Topics

Resource Tags

Clone a Standby Database Backup

Follow these steps to clone an autonomous database backup on an Oracle Exadata Database Service on Cloud@Customer system.

You can use the cloning feature to create a point-in-time copy of your Autonomous Database for purposes such as testing, development, or analytics. To clone only the database schema of your source database, choose the metadata clone option.

Clone Types

The clone feature offers the following two types of Autonomous Database clones:

- The full-clone option creates a database that includes the metadata and data from the source database.
- The metadata-clone option creates a database that includes only the metadata from the source database.

Steps

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the primary database.
- 4. Under Resources, click Autonomous Data Guard.
- 5. In the list of standby databases, find the database that you want to clone, and then click the display name to view details.
- 6. Under Resources, click Backups.
- 7. In the list of backups, find the backup that you want to clone, click the action icon (three dots), and then click **Create Clone**.
- 8. On the Create Autonomous Database Clone page, provide the following information:

In the Clone Type section, select Full Clone.

Clone Source: The clone source section displays the source backup details.

Provide basic information for the Autonomous Database.

- Choose a compartment: Your current compartment is the default selection but you can select a different compartment in which to create the clone from the drop-down list.
- **Source database name**: The name of the source database displays in the read-only Source database name field.



- **Display name**: Enter a description or other information to identify the database clone. You can change the display name any time and it does not have to be unique. Avoid entering confidential information.
- **Database name**: Enter a database name for the clone that contains only letters and numbers, begins with a letter. Avoid entering confidential information.
- **Exadata Infrastructure:** You can choose to create the database clone in the same Exadata Infrastructure where the source database resides, or you can choose a different compartment by clicking **CHANGE COMPARTMENT** and choosing one from the drop-down list.
- Autonomous Exadata VM Cluster: You can choose to create the database clone in the same Autonomous Exadata VM Cluster where the source database resides, or you can choose a different compartment by clicking CHANGE COMPARTMENT and choosing one from the drop-down list.
- Choose autonomous container database in compartment: You can choose to
 create the database clone in the same compartment and container database as the
 source database, or you can choose a different compartment by clicking CHANGE
 COMPARTMENT, and a different container database by choosing one from the dropdown list.



When the target Autonomous Exadata VM Cluster is the same as the source, then the database name cannot be the same as the source database name.

Configure the database

• **OCPU Count**: There is a minimum requirement of 2 OCPUs for an ADB clone from Backup. After the clone, you can resize to a lower value if needed.

Note:

The time taken to clone an ADB depends on the OCPU Count and the network bandwidth between the Backup Destination and the target ACD.

Specify the number of OCPU for your database. The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

The default is 1. However, you can assign a fractional OCPU value from 0.1 to 0.9 (in increments of 0.1) to databases that do not need a full OCPU. For databases that need 1 or more OCPU cores, you must specify the number of assigned OCPUs as an integer. For example, you cannot assign 3.5 OCPU to a database. The next available number of OCPU above 3 is 4.

Default: 2Minimum: 2

Maximum: Set by quota



- **Storage (GB)**: Specify the amount of storage, in GB, that you want to make available to your cloned Autonomous Database, and it depends on the storage available to use.
 - Default/Minimum: Allocated storage of the source database
 - Increment: 1 GB
- Auto scaling: Enabling autoscaling allows the system to automatically use up to three times more CPU and I/O resources to meet workload demand.

Create administrator credentials

Set the password for the Autonomous Database administrator user by entering a password that meets the following criteria.

- Password cannot be one of the three most recently used passwords of the source database
- Between 12 and 30 characters long
- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Use this password when accessing the service console and when using a SQL client tool.

Configure Network Access

You can change the access control list to enable or disable database-level access control or add or modify entries to the access control list.

- Click Modify Access Control.
- Select the Enable database level access control check box.
- Click Access Control Rule.

Note: The database-level access control will be enabled without any IP addresses in the access control list. Enabling an access control list with an empty list of IP addresses makes the database inaccessible to all clients.

- Specify the following types of addresses in your list by using the IP notation type drop-down selector:
 - IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.

Advanced Options:

- Encryption Key:
 - Clone from a database instance: The source and the target ACD must be the same Keystore type. When the source is OKV, the target must also be the same OKV destination.



- Clone from a backup: The source and the target ACDs can be different Keystore types. When the source is OKV, the target must also be the same OKV destination.
- **Tags**: Optionally, you can apply tags. If you have permission to create a resource, you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see Resource Tags. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.

9. Click Create Autonomous Database Clone.

The Console displays the details page for the new clone of your database and the service begins provisioning the Autonomous Database. Note the following:

- The new clone displays the **Provisioning** lifecycle state until the provisioning process completes.
- The source database remains in the **Available** lifecycle state.

Related Topics

Resource Tags

Terminate an Autonomous Database

Follow these steps to terminate an Autonomous Database on an Oracle Exadata Database Service on Cloud@Customer system.



WARNING:

Terminating an Autonomous Database permanently deletes it. The database data will be lost when the system is terminated. However, automatic backups are not deleted if you have chosen Recovery Appliance or NFS as a backup destination. You can delete automatic backups directly from the Recovery Appliance or NFS.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to terminate.
- From the **More Actions** drop-down list, select **Terminate**.
- Confirm that you wish to terminate your Autonomous Database in the confirmation dialog.
- 6. Click Terminate Autonomous Database.

API to Manage Autonomous Databases

For information about using the API and signing requests, see REST APIs and Security Credentials. For information about SDKs, see Software Development Kits and Command Line Interface.



The following table lists the REST API endpoints to manage Autonomous Databases.

REST API Endpoint
CreateAutonomousDatabase
ListAutonomousDatabases
GetAutonomousDatabase
ListAutonomousDatabaseCharacterSets
UpdateAutonomousDatabase
UpdateAutonomousDatabase
UpdateAutonomousDatabase
ChangeAutonomousDatabaseCompartment
StartAutonomousDatabase
StopAutonomousDatabase
RestartAutonomousDatabase
CreateAutonomousDatabaseBackup
ListAutonomousDatabaseBackups
RestoreAutonomousDatabase
CreateAutonomousDatabase
DeleteAutonomousDatabase

Monitor Performance with Autonomous Database Metrics

You can monitor the health, capacity, and performance of your Autonomous Databases with metrics, alarms, and notifications. You can use Oracle Cloud Infrastructure console or Monitoring APIs to view metrics.

- View Top Six Metrics for an Autonomous Database
 Displays the top six metrics that are available in the metrics section on the Autonomous Database details page.
- View Aggregated Metrics for Autonomous Databases in a Compartment Learn to view aggregated metrics for Autonomous Databases in a compartment.
- Autonomous Database Metrics and Dimensions
 You can limit the instances where you see metrics with dimensions. The available
 dimensions include: workload type, instance display name, region, and the
 instance OCID.



View Top Six Metrics for an Autonomous Database

Displays the top six metrics that are available in the metrics section on the Autonomous Database details page.

To view metrics you must have the required access as specified in an Oracle Cloud Infrastructure policy (whether you're using the Console, the REST API, or other tools). See Getting Started with Policies for information on policies.

Perform the following prerequisite steps as necessary:

- Open the Oracle Cloud Infrastructure console by clicking the hamburger menu next to Oracle Cloud.
- From the Oracle Cloud Infrastructure left navigation list click Oracle Databases > Exadata Cloud@Customer.
- On the Autonomous Databases page select an Autonomous Database from the links under the Name column.

To view metrics for an Autonomous Database instance:

- 1. On the Autonomous Database Details page, under Resources, click Metrics.
- 2. There is a chart for each metric. In each chart, you can select the **Interval and Statistic** or use the default values.
- To create an alarm on a metric, click Options and select Create an Alarm on this Query.

See Managing Alarms for information on setting and using alarms.

For more information about metrics see Database Metrics.

You can also use the Monitoring API to view metrics. See Monitoring API for more information.

View Aggregated Metrics for Autonomous Databases in a Compartment

Learn to view aggregated metrics for Autonomous Databases in a compartment.

To view metrics you must have the required access as specified in an Oracle Cloud Infrastructure policy (whether you're using the Console, the REST API, or other tool). See Getting Started with Policies for information on policies

Perform the following prerequisite steps as necessary:

- Open the Oracle Cloud Infrastructure console by clicking the hamburger menu next to Oracle Cloud.
- From the left navigation list click Solutions and Platform > Monitoring > Service Metrics.

To use the metrics service to view Autonomous Database metrics:

- 1. On the Service Metrics page, under **Compartment** select your compartment.
- 2. On the Service Metrics page, under **Metric Namespace** select **oci autonomous database**.
- 3. If there are multiple Autonomous Databases in the compartment you can show metrics aggregated across the Autonomous Databases by selecting **Aggregate Metric Streams**.



- 4. If you want to limit the metrics you see, next to **Dimensions** click **Add** (click **Edit** if you have already added dimensions).
 - a. In the **Dimension Name** field select a dimension.
 - b. In the **Dimension Value** field select a value.
 - c. Click Done.
 - d. In the Edit dimensions dialog click +Additional Dimension to add an additional dimension. Click x to remove a dimension.

To create an alarm on a specific metric, click **Options** and select **Create an Alarm on this Query**. See Managing Alarms for information on setting and using alarms.

Autonomous Database Metrics and Dimensions

You can limit the instances where you see metrics with dimensions. The available dimensions include: workload type, instance display name, region, and the instance OCID.

Use dimensions by selecting values in the Oracle Cloud Infrastructure Console Service Metrics page or by setting dimension values with the API. See View Aggregated Metrics for Autonomous Databases in a Compartment to view metrics and to select metric dimensions.

See Database Metrics for a list of the database metrics and dimensions.

Connecting to Autonomous Databases

Applications and tools connect to an autonomous database using Oracle Net Services (also known as SQL*Net). Oracle Net Services enables a network session from a client application to an Oracle Database server.

When a network session is established, Oracle Net Services acts as the data courier for both the client application and the database. It is responsible for establishing and maintaining the connection between the client application and the database, as well as exchanging messages between them. It supports a variety of connection types to autonomous databases, including:

- Oracle Call Interface (OCI), which is used by many applications written in C language. Examples include Oracle utilities such as Oracle SQL*Plus, SQL*Loader, and Oracle Data Pump.
- ODBC drivers, which can be used by applications running on Microsoft Windows, are layered over Oracle Call Interface (OCI).
- JDBC OCI, which can be used by Java language applications, is layered over Oracle Call Interface (OCI). The Oracle SQLcl command-line interface uses JDBC OCI.
- JDBC Thin Driver, also for Java applications, is a pure Java driver. Oracle SQL Developer supports JDBC Thin Driver connections.

Third-party products and custom applications can use any of these connection types.

Oracle Autonomous Database provides several pairs of database services to use when connecting to autonomous databases. In each pair, one of the pair provides a secure TCP (TCPS) connection using the TLS protocol, and the other provides a TCP connection. In all other respects, the two members of a pair are the same. To ensure



security of data in transit, Oracle strongly recommends that you use a secure connection, even if the database is only available through a private network. If you are familiar with using an Oracle Database within your own data center, you may not have previously used these secure connections.

To provide the secure TCPS connection, certification authentication uses an encrypted key stored in a *wallet* on both the client (where the application is running) and the server (where the autonomous database is running). The key on the client must match the key on the server to make a connection. A wallet contains a collection of files, including the key and other information needed to connect to your database . All communications between the client and the server are encrypted.

- Download the Wallet for an Autonomous Database
- Get the APEX and SQL Developer Web URLs for an Autonomous Database

Download the Wallet for an Autonomous Database

Follow these steps to download the wallet for an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database whose wallet you wish to download.
- 4. Click DB Connections.
- 5. Select the **DB Connection** option.
- 6. In the Download Wallet dialog, enter a wallet password in the **Password** field and confirm the password in the **Confirm Password** field.

The password must be at least 8 characters long and must include at least 1 letter and either 1 numeric character or 1 special character.



This password protects the downloaded Client Credentials wallet. This wallet is not the same as the Transparent Data Encryption (TDE) wallet for the database; therefore, use a different password to protect the Client Credentials wallet.

7. Click **Download** to save the client security credentials zip file.

By default the filename is <code>Wallet_databasename.zip</code>. You can save this file as any filename you want.

You must protect this file to prevent unauthorized database access.

The zip file includes the following:

- tnsnames.ora and sqlnet.ora: Network configuration files storing connect descriptors and SQL*Net client side configuration.
- cwallet.ora and ewallet.p12: Auto-open SSO wallet and PKCS12 file. PKCS12 file is protected by the wallet password provided in the UI.



- keystore.jks and truststore.jks: Java keystore and truststore files. They are protected by the wallet password provided while downloading the wallet.
- ojdbc.properties: Contains the wallet related connection property required for JDBC connection. This should be in the same path as tnsnames.ora.



Wallet files, along with the Database user ID and password, provide access to data in your autonomous database. Store wallet files in a secure location. Share wallet files only with authorized users. If wallet files are transmitted in a way that might be accessed by unauthorized users (for example, over public email), transmit the wallet password separately and securely.

Get the APEX and SQL Developer Web URLs for an Autonomous Database

Follow these steps to get the URLs to use to connect to APEX (Oracle Application Express) and Oracle SQL Developer Web in an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database whose APEX and SQL URLs you wish to get.
- 4. Click DB Connections.
- 5. Select the **Application Connection** option.
- **6.** Application URLs are displayed in plain text in the **Application URL** field. Copy the URL string using the **Copy** link.

Paste the URL into a browser running on a system with network access to your autonomous database.

Patching ADB on Exadata Cloud@Customer Infrastructure

- Overview of ADB on Exadata Cloud@Customer Infrastructure Patching
- Specifying When Maintenance Can Occur
- · Specifying What Kind of Patches to Apply

Overview of ADB on Exadata Cloud@Customer Infrastructure Patching

ADB-Dedicated maintenance involves patching Exadata Infrastructure(EI) Autonomous VM Cluster, and Autonomous Container Database (ACD).



- Autonomous Exadata Infrastructure/Exadata Infrastructure (EI): IB Switches, Storage cells, Dom0 operating system, and so on.
- Autonomous VM clusters (AVM): Grid Infrastructure (GI), and Guest VM operating system patching.
- Autonomous Container Database (ACD): Oracle Database patching.

The patching is done every quarter. Although there is no order dependency between EI/AVM/ ACD, it is preferred to patch in the sequence EI, AVM, and then ACD.

Oracle schedules and performs all patching and other maintenance operations on all dedicated Exadata infrastructure resources. You can also specify when such maintenance operations can occur, and what kind of patching is performed.

Specifying When Maintenance Can Occur

In general, Oracle schedules and performs entire fleet maintenance spread throughout each quarter. You can let Oracle handle maintenance scheduling, or you can set a specific maintenance window when Oracle can begin maintenance operations. You set this maintenance window at the Autonomous Exadata Infrastructure level, and it applies to all Autonomous Container Databases and Autonomous Databases created in the Autonomous Exadata Infrastructure resource as well as to the resource itself.

Additionally, you can set a maintenance window for each individual Autonomous Container Database, thereby setting the window for all of its contained Autonomous Databases.



Oracle recommends that you set a maintenance window for at least Exadata Infrastructure resources. Doing so will prevent maintenance operations from occurring at times that would be disruptive to regular database operations.

You can set the maintenance window for an Exadata Infrastructure and Autonomous Container Database resources when you create them or you can set or change it later. Once a maintenance activity is scheduled based on the maintenance window you set, you can manage the actual timing of the activity, even to the point of changing the patch version, applying the patch immediately, or skipping the activity.

Related Topics

- Using the Console to Create Oracle Exadata Database Service on Cloud@Customer Infrastructure
 - To create your Oracle Exadata Database Service on Cloud@Customer infrastructure, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to Configure Oracle-Managed Infrastructure Updates
 Exadata Cloud Service updates are released on a quarterly basis. You can set a
 maintenance window to determine the time your quarterly infrastructure maintenance will
 begin.
- Patch and Update an Exadata Database Service on Cloud@Customer System
 Learn to update and patch the Exadata Database Service on Cloud@Customer System
- Create an Autonomous Container Database



Change the Maintenance Schedule of an Autonomous Container Database

Specifying What Kind of Patches to Apply

One standard maintenance operation is to apply database software patches to your Autonomous Container Databases and, by extension, the Autonomous Databases created in them. By default, Oracle applies quarterly Release Updates (RUs). Currently, the Release Update Revision (RUR) maintenance type is not supported.

To help you decide whether to have Oracle apply RUs or RURs to a given Autonomous Container Database, see My Oracle Support Note 2285040.1.

Related Topics

https://support.oracle.com/epmos/faces/DocContentDisplay?id=2285040.1

Using Autonomous Data Guard with Autonomous Database on Exadata Cloud@Customer

Learn how to enable a Data Guard association between databases, change the role of a database in a Data Guard association using either a switchover or a failover operation, and reinstate a failed database.

- Enabling Autonomous Data Guard on an Autonomous Container Database
 When you enable Data Guard, a separate Data Guard association is created for the primary and the standby database.
- Enabling Autonomous Data Guard on an Autonomous Database
 Autonomous Databases inherit Data Guard settings from the parent container database.
- Maintenance Scheduling and Patching Data Guard Enabled Autonomous Container Database
 Follow those stops to change the maintenance schedule of a Data Guard of

Follow these steps to change the maintenance schedule of a Data Guard enabled Autonomous Container Database.

Enabling Autonomous Data Guard on an Autonomous Container Database

When you enable Data Guard, a separate Data Guard association is created for the primary and the standby database.



Replication of data happens only over the client network.

Create an Autonomous Data Guard Enabled Autonomous Container Database
 Follow these steps to create an Autonomous Data Guard Enabled Autonomous
 Container Database on an Oracle Exadata Cloud@Customer system.



 View Details of a Data Guard Enabled Primary or Standby Autonomous Container Database

Follow these steps to view detailed information about a primary or standby Autonomous Container Database on an Oracle Exadata Database Service on Cloud@Customer system.

- Rotate CDB Encryption Key
- Managing a Standby Autonomous Container Database
 Enabling Autonomous Data Guard on an Autonomous Container Database creates a
 standby (peer) Autonomous Container Database that provides data protection, high
 availability, and facilitates disaster recovery for the primary database.
- Perform a Failover to Standby Autonomous Container Database
 Initiate a failover operation by using the Data Guard association of the standby database.
- Perform a Switchover to Standby or Primary Autonomous Container Database
 Initiate a switchover operation by using the Data Guard association of the primary database.
- Reinstate Data Guard Enabled Standby Autonomous Container Database
 After you fail over a primary database to its standby, the standby assumes the primary role and the old primary is identified as a disabled standby.
- Terminate a Data Guard Enabled Primary Autonomous Container Database
 Follow these steps to terminate an autonomous container database on an Oracle Exadata Cloud@Customer system.
- Terminate a Data Guard Enabled Standby Autonomous Container Database
 Follow these steps to terminate an autonomous container database on an Oracle Exadata Cloud@Customer system.
- Operations Performed Using the APIs
 Learn how to use the API to manage Autonomous Data Guard Enabled Autonomous
 Container Database.

Related Topics

Network Requirements for Oracle Exadata Database Service on Cloud@Customer
 To provide secure and reliable network connectivity for different application and
 management functions, Exadata Database Service on Cloud@Customer uses different
 networks.

Create an Autonomous Data Guard Enabled Autonomous Container Database

Follow these steps to create an Autonomous Data Guard Enabled Autonomous Container Database on an Oracle Exadata Cloud@Customer system.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. Click Create Autonomous Container Database.

The Create Autonomous Container Database page is displayed.

- **4.** Provide the following basic information:
 - Compartment: Choose the compartment in which your autonomous container database will be created.



- **Display Name**: Enter a user-friendly description or other information that helps you easily identify the autonomous container database. The display name does not have to be unique. Avoid entering confidential information.
- Select the Autonomous Exadata VM Cluster you wish to use to create your autonomous container database.

Note:

If the selected Autonomous Exadata VM Cluster does not have 2 available OCPUs per node, which is the minimum requirement for creating an Autonomous Container Database, then this field is greyed out. Select an Autonomous Exadata VM Cluster that has enough resources to create an autonomous container database.

- 6. Under Configure Autonomous Data Guard, select the Enable Autonomous Data Guard checkbox and provide the following details.
 - Peer Autonomous Container Database Compartment: Choose the compartment in which your standby autonomous container database will be created.
 - **Display Name:** Enter a user-friendly description or other information that helps you easily identify the autonomous container database. The display name does not have to be unique. Avoid entering confidential information.
 - Select peer Autonomous Exadata VM Cluster: Specify the following values for the standby:
 - Peer Region: Currently, the peer region is auto-populated and you cannot change it. The primary and secondary databases must run on two Autonomous Exadata VM Cluster on two separate Exadata infrastructures even if they are in the same region.
 - Peer Exadata: Select the Exadata Cloud@Customer infrastructure where the standby database will be created. Click the CHANGE COMPARTMENT hyperlink to choose a compartment.
 - Peer Autonomous Exadata VM Cluster: Select the Autonomous VM
 Cluster in which the standby ACD must be created. Click the CHANGE
 COMPARTMENT hyperlink to choose a compartment.

Note:

If the selected Autonomous Exadata VM Cluster does not have 2 available OCPUs per node, which is the minimum requirement for creating an Autonomous Container Database, then this field is greyed out. Select an Autonomous Exadata VM Cluster that has enough resources to create an Autonomous Container Database.

- Data Protection Mode: Specify the protection mode used for this Data Guard association.
 - Maximum Performance: Provides the highest level of data protection that
 is possible without compromising the availability of a primary database.



Maximum Availability: Provides the highest level of data protection that is
possible without affecting the performance of a primary database. This is the
default protection mode.

See Oracle Data Guard Concepts and Administration for more information about Oracle Data Guard Protection Modes.

- 7. Optionally, you can configure an automatic maintenance schedule.
 - a. Click Modify Schedule.
 - b. Optionally, you can change the maintenance patch type. Select either Release Update (RU) or Release Update Revision (RUR).



You can set maintenance type only for primary.

Release Update (RU): Autonomous Database installs only the most current release update.

Release Update Revision (RUR): Autonomous Database installs the release update plus additional fixes.

For more information, see Management Operations.

c. To configure the maintenance schedule, select **Specify a schedule**.

Choose your preferred month, week, weekday, and start time for autonomous container database maintenance.

- Under Week of the month, specify which week of the month maintenance will take place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a duration of 7 days. Weeks start and end based on calendar dates, not days of the week. Maintenance cannot be scheduled for the fifth week of months that contain more than 28 days.
- Under Day of the week, specify the day of the week on which the maintenance will occur.
- Under Start hour, specify the hour during which the maintenance run will begin.
- d. Click Save Changes.
- 8. Select a Backup Destination Type:
 - Object Storage: Stores backups in an Oracle-managed object storage container on Oracle Cloud Infrastructure. Optionally, you can use this field to specify your corporate HTTP proxy. We recommend using an HTTP proxy when possible for enhanced security.
 - **Network File System (NFS)**: Stores backups in one of your previously defined backup destinations that uses Network File System (NFS) storage.
 - Select a Backup Destination.
 - Recovery Appliance: Not Supported.
- 9. The following Advanced Options are available:
 - **Backup retention period**: Customize the retention period for automatic backups.



 Encryption Key: Choose an encryption option, Encrypt using Oraclemanaged keys or Encrypt using customer-managed keys. The default option is Oracle-managed keys.

To use customer-managed keys, select the **Encrypt using customer-managed keys** option, select the compartment where you have created the Key Store, and then select the Key Store. As part of the CDB creation, a new wallet is created for the CDB in Oracle Key Vault (OKV). Also, a TDE Master Key is generated for the CDB and added to the wallet in OKV.

Note:

- Autonomous Container Databases and Autonomous Databases only support 256-bit Hardware Security Module (HSM) Vault keys.
- Validate OKV Key encryption post restart: OKV TDE Master Key is validated every time you start or restart your ACD. Start or restart fails if the key is not validated. Work requests and life cycle states indicate the reason for failure.
- View OKV keys post database restore: When you restore a CDB, the master key associated with that backup is restored as well.
- Enable CDB backups to capture wallet name: CDB backups information about the wallet associated with the backup.
- OKV Wallet or TDE Master Key on CDB deletion: If you delete a CDB, then the wallet and TDE Master Key remains in OKV and will not be deleted.
- Tags: Optionally, you can apply tags. If you have permission to create a
 resource, you also have permission to apply free-form tags to that resource.
 To apply a defined tag, you must have permission to use the tag namespace.
 For more information about tagging, see *Resource Tags*. If you are not sure if
 you should apply tags, skip this option (you can apply tags later) or ask your
 administrator. Avoid entering confidential information.

10. Click Create Autonomous Container Database.

Related Topics

- Oracle Data Guard Protection Modes
- Management Operations
- Resource Tags

View Details of a Data Guard Enabled Primary or Standby Autonomous Container Database

Follow these steps to view detailed information about a primary or standby Autonomous Container Database on an Oracle Exadata Database Service on Cloud@Customer system.

 Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



- Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the database you wish to view details.
- 4. In the Autonomous Container Database Details page, check the Autonomous Data Guard association status and peer database state.
- 5. Under Resources, click Autonomous Data Guard to view association details.

Rotate CDB Encryption Key

Follow these steps to rotate the TDE Master key. On key rotation, the ACD life cycle goes through the regular updating state and returns to available.

You can rotate the TDE Master key as many times as you want. The new TDE Master Key is stored in the same wallet in which the previous key was stored. Rotating the TDE Master Key leads to the new key being generated in OKV and assigned to this database. You can view all of the keys in OKV.



You can rotate both Oracle-managed and customer-managed encryption keys.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Click Autonomous Container Databases.
- In the list of Autonomous Container Databases, click the display name of the primary or standby database you wish to view details.
- On the Autonomous Container Database Details page, click Rotate Encryption Key.
- 5. On the Rotate Encryption Key dialog, click Rotate Encryption Key.

Managing a Standby Autonomous Container Database

Enabling Autonomous Data Guard on an Autonomous Container Database creates a standby (peer) Autonomous Container Database that provides data protection, high availability, and facilitates disaster recovery for the primary database.

If the primary Autonomous Container Database becomes unavailable because of a region failure, a failure of the Autonomous Exadata Infrastructure, or the failure of the Autonomous Container Database, itself, then it automatically fails over to the standby Autonomous Container Database if Automatic Failover is enabled. The role of the failed primary database becomes *Disabled Standby* and, after a brief period of time, the standby database assumes the role of the primary database.

Besides hardware failures and regional outages, the following table lists database health conditions that also trigger automatic failover:



Table 6-7 Database Health Condition

Database Health Condition	Description
Datafile Write Errors	The system initiates a fast-start failover if write errors occur in any data files, including temp files, system data files, and undo files.
Corrupted Dictionary	Dictionary corruption of a critical database. Currently, this state can be detected only when the database is open.
Corrupted Controlfile	Controlfile is permanently damaged because of a disk failure.

Note:

- After automatic failover concludes, a message displays on the details page of the disabled standby database advising you that failover has occurred.
- Automatic failover is optional while configuring Autonomous Data Guard.
 You can enable or disable automatic failover after configuring
 Autonomous Data Guard.
- The FastStartFailoverLagLimit configuration attribute establishes an
 acceptable limit, in seconds, up to which the standby database can fall
 behind the primary database, with respect to the redo applied. If the limit
 is reached, then a fast-start failover does not occur. This attribute is used
 when fast-start failover is enabled and the configuration is operating in
 maximum performance mode.

The FastStartFailOverLagLimit attribute:

- Has a default value of 30 seconds
- Cannot be configured
- Is only applicable when in maximum performance protection mode

After the service resolves the issues with the former primary Autonomous Container Database, you can perform a manual switchover to return both databases to their initial roles.

Once you provision the standby database, you can perform various management tasks related to the standby database, including:

- Manually switching over a primary database to a standby database
- Manually failing over a primary database to a standby database
- Reinstating a primary database to standby role after failover
- Terminating a standby database



Perform a Failover to Standby Autonomous Container Database

Initiate a failover operation by using the Data Guard association of the standby database.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.
- Click the name of the standby database associated with the primary Autonomous Container Database that you want to failover.
- 5. Click Failover.
- In the Confirm Manual Failover to Standby dialog box, enter the name of the Autonomous Container Database you want to failover, and then click Failover.

Alternatively,

- **a.** Under **Resources**, click Autonomous Data Guard to display a list of peer databases for the primary database you are managing.
- **b.** For the Data Guard association on which you want to perform a failover, click the Actions icon (three dots), and then click **Failover**.
- c. In the Confirm Manual Failover to Standby dialog box, enter the name of the Autonomous Container Database you want to failover, and then click **Failover**.



After successful completion of failover, the standby ACDs role will change to primary and the primay's role will become disabled-standby.

Perform a Switchover to Standby or Primary Autonomous Container Database

Initiate a switchover operation by using the Data Guard association of the primary database.

- You can perform Switchover only when both primary and standby are in available state.
- You cannot perform switchover if patching or maintenance is in progress on primary or standby.
- After switchover, the maintenance preference for new standby and primary will remain same as old standby and primary.
- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.
- 4. Click the name of the primary or secondary database.
- 5. Click Switchover.



6. In the confirmation dialog box, click **Switchover**.

Alternatively,

- a. Under Resources, click Data Guard Associations.
- **b.** For the Data Guard association on which you want to perform a switchover, click the Actions icon (three dots), and then click **Switchover**.
- c. In the Confirm Switchover to Standby dialog box, click **Swichover**.

This database should now assume the role of the standby, and the standby should assume the role of the primary in the Data Guard association.

Reinstate Data Guard Enabled Standby Autonomous Container Database

After you fail over a primary database to its standby, the standby assumes the primary role and the old primary is identified as a disabled standby.

After the operations team correct the cause of failure, you can reinstate the failed database as a functioning standby for the current primary by using its Data Guard association. you can reinstate the failed database as a functioning standby for the current primary by using its Data Guard association.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.
- 4. Click the name of the **Disabled Standby** database.
- 5. Under Resources, click Autonomous Data Guard...
- 6. For the Data Guard association on which you want to reinstate this database, click the Actions icon (three dots), and then click **Reinstate**.
- 7. In the Reinstate Database dialog box, click **Reinstate**.

This database should now be reinstated as the standby in the Data Guard association. You can now perform a switchover operation to revert the respective databases to their original roles.

Terminate a Data Guard Enabled Primary Autonomous Container Database

Follow these steps to terminate an autonomous container database on an Oracle Exadata Cloud@Customer system.

You must terminate all Autonomous Databases within a container database before you can terminate the container database itself. Terminating Autonomous Container Database will disable Autonomous Data Guard, which affects high availability and disaster recovery of your Autonomous Databases.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.



- 4. In the Autonomous Container Database Details page, select **Terminate** from the More Actions drop-down list.
- 5. Click Terminate.
- In the confirmation dialog, type the name of the Autonomous Container Database, and then click Terminate Autonomous Container Database.

Terminate a Data Guard Enabled Standby Autonomous Container Database

Follow these steps to terminate an autonomous container database on an Oracle Exadata Cloud@Customer system.

You can terminate a standby Autonomous Container Database even if there are standby Autonomous Databases inside it. However, you cannot terminate standby Autonomous Databases inside a standby Autonomous Container Database. To terminate a standby Autonomous Database, you must first terminate the primary Autonomous Database. Terminating Autonomous Container Database will disable Autonomous Data Guard, which affects high availability and disaster recovery of your Autonomous Databases.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the infrastructure resource you are interested in.
- In the Autonomous Container Database Details page, select Terminate from the More Actions drop-down list.
- 5. Click Terminate.
- 6. In the confirmation dialog, type the name of the Autonomous Container Database, and then click **Terminate Autonomous Container Database**.

Operations Performed Using the APIs

Learn how to use the API to manage Autonomous Data Guard Enabled Autonomous Container Database.

For information about using the API and signing requests, see "REST APIs" and "Security Credentials". For information about SDKs, see "Software Development Kits and Command Line Interface".

The following table lists the REST API endpoints to manage Autonomous Data Guard Enabled Autonomous Container Database.

Operation	REST API Endpoint
Creates Autonomous Container Databases (update to the existing API)	CreateAutonomousContainerDatabase
View details of the specified Autonomous Container Database	GetAutonomousContainerDatabase
View a list of Autonomous Container Databases with Autonomous Data Guard associations	ListAutonomousContainerDatabaseDataguar dAssociations
Fetch details of an Autonomous Container Database Autonomous Data Guard associations	GetAutonomousContainerDatabaseDataguard Association



Operation	REST API Endpoint
Fail over the standby Autonomous Container Database identified by the autonomousContainerDatabaseId parameter to the primary Autonomous Container Database after the existing primary Autonomous Container Database fails or becomes unreachable.	FailoverAutonomousContainerDatabaseData guardAssociation
Switch over the primary Autonomous Container Database of an Autonomous Data Guard peer association to standby role. The standby Autonomous Container Database associated with autonomousContainerDatabaseDataguardAssociationId assumes the primary Autonomous Container Database role.	SwitchoverAutonomousContainerDatabaseDa taguardAssociation
Reinstate a disabled standby Autonomous Container Database identified by the autonomousContainerDatabaseId parameter to an active standby Autonomous Container Database.	ReinstateAutonomousContainerDatabaseDat aguardAssociation
View a list of the Autonomous Data Guard-enabled databases associated with the specified Autonomous Database.	ListAutonomousDatabaseDataguardAssociat ions
Fetch details of an Autonomous Database Autonomous Data Guard associations	GetAutonomousDatabaseDataguardAssociati on
Fetches details such as peer database role, lag time, transport lag, and state	GetAutonomousDatabase

Related Topics

- REST APIs
- Security Credentials
- Software Development Kits and Command Line Interface

Enabling Autonomous Data Guard on an Autonomous Database

Autonomous Databases inherit Data Guard settings from the parent container database.

- View Autonomous Data Guard Enablement
 Autonomous Data Guard settings are configured on the Autonomous Container
 Databases in which the databases are running.
- Create an Autonomous Data Guard Enabled Autonomous Database
- View Details of a Data Guard Enabled Primary or Standby Autonomous Database
 Follow these steps to view detailed information about a primary or standby
 Autonomous Database on an Oracle Exadata Database Service on
 Cloud@Customer system.
- Rotate ADB Encryption Key



View Autonomous Data Guard Enablement

Autonomous Data Guard settings are configured on the Autonomous Container Databases in which the databases are running.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Container Databases.

This page displays if an autonomous database is Data Guard enabled or not, and if enabled, then the role of the database in the Data Guard association.

Create an Autonomous Data Guard Enabled Autonomous Database

Follow these steps to create an autonomous database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. Click Create Autonomous Database.
- 4. In the Create Autonomous Database dialog, enter the following:

Basic Database Information

- **Compartment:** Select the compartment of the Autonomous Database.
- Display Name: A user-friendly description or other information that helps you easily identify the resource. The display name does not have to be unique. Avoid entering confidential information.
- Database Name: The database name must consist of letters and numbers only, starting with a letter. Avoid entering confidential information.

Workload Type

Select the desired workload type. See *Autonomous Data Warehouse* and *Autonomous Transaction Processing* for information about each workload type.

Autonomous Container Database: Select the Autonomous Data Guard-enabled Autonomous Container Databases checkbox, and then select an Autonomous Container Database.

Compartment: Specify the compartment containing the Autonomous Container Database you wish to use.

Database CPU Core Count and Storage Configuration

 OCPU Count: The total number of cores available to all databases within the Autonomous Exadata Infrastructure depends on the infrastructure shape and what is already allocated to other Autonomous Databases.

The selected OCPU count is validated against a list of provisionable OCPUs, and if the database can not be scaled up to the chosen OCPU count, you will be provided with the two nearest provisionable OCPU values.

Based on the resource utilization on each node; not all the values of the available OCPUs can be used to provision or scale Autonomous Databases. For example, suppose you have 20 OCPUs available at the AVMC level, not all the values from 1



to 20 OCPUs can be used to provision or scale Autonomous Databases depending on the resource availability at the node level. The list of OCPU values that can be used to provision or scale an Autonomous Database is called **Provisionable OCPUs**.

On the console, when you try to provision or scale an Autonomous Database, the OCPU count will be validated against the list of provisionable OCPUs, and if the value is not provisionable, you will be provided with the two nearest provisionable OCPU values. Alternatively, if you want to see the complete list of provisionable OCPU values for an Autonomous Exadata VM Cluster, you can use the following API:

GetAutonomousContainerDatabase returns a list of provisionable OCPU values that can be used to create a new Autonomous Database in the given Autonomous Container Database. See GetAutonomousContainerDatabase for more details.

Deselect Auto Scaling to disable auto-scaling. By default, auto-scaling is enabled to allow the system to automatically use up to three times more CPU and IO resources to meet workload demand.

• Storage (TB): Specify the storage you wish to make available to your Autonomous Database, in terabytes. The available storage depends on the infrastructure shape and what is already consumed by other Autonomous Databases.

Administrator Credentials

Set the password for the Autonomous Database Admin user by entering a password that meets the following criteria. You use this password when accessing the Autonomous Database service console and when using an SQL client tool.

- Contains from 12 to 30 characters
- Contains at least one lowercase letter
- Contains at least one uppercase letter
- Contains at least one number
- Does not contain the double quotation mark (")
- Does not contain the string "admin", regardless of casing

Configure network access

You can optionally create an ACL during database provisioning, or at any time thereafter.

- a. Cick Modify Access Control.
- b. In the Edit Access Control List dialog, select the Enable database level access control checkbox.
- c. Under the Primary database access control list, specify the following types of addresses in your list by using the IP notation type drop-down selector: IP Address allows you to specify one or more individual public IP addresses. Use commas to separate your addresses in the input field.
 - CIDR Block allows you to specify one or more ranges of public IP addresses using CIDR notation. Use commas to separate your CIDR block entries in the input field.
- d. Under Standby database access control, do the following:



(Default) Same as primary database: Leave as is if you want the same access control list for the secondary database.

Define standby database access control: Initialized with the same details as primary. Add or modify entries, as applicable.

Advanced Options

Tags: Optionally, you can apply tags. If you have permission to create a resource, then you also have permission to apply free-form tags to that resource. To apply a defined tag, you must have permission to use the tag namespace. For more information about tagging, see *Resource Tags*. If you are not sure if you should apply tags, skip this option (you can apply tags later) or ask your administrator. Avoid entering confidential information.

Encryption Key: ADB inherits encryption settings from the parent ACD. If the parent ACD is configured for customer-managed OKV-based encryption, then the child ADB will also have TDE Master Key generated and managed in the same OKV wallet used to store ACD master keys. Additionally, any backups taken on the Autonomous Database will have the OKV-based key associated with it.

5. Click Create Autonomous Database.



The following naming restrictions apply to Autonomous Transaction Processing and Autonomous Data Warehouse databases:

- Names associated with databases terminated within the last 60 days cannot be used when creating a new database.
- A database name cannot be used concurrently for both an Autonomous Data Warehouse and an Autonomous Transaction Processing database.

Related Topics

- About Autonomous Database
- GetAutonomousContainerDatabase
- Resource Tags

View Details of a Data Guard Enabled Primary or Standby Autonomous Database

Follow these steps to view detailed information about a primary or standby Autonomous Database on an Oracle Exadata Database Service on Cloud@Customer system.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Databases, click the display name of the database you wish to view details.
- **4.** In the Autonomous Database Details page, check the Autonomous Data Guard association status and peer database state.
- 5. Under Resources, click Autonomous Data Guard to view association details.



Rotate ADB Encryption Key

Follow these steps to rotate the TDE Master key. On key rotation, the ADB life cycle goes through the regular updating state and returns to available.

You can rotate the TDE Master key as many times as you want. The new TDE Master Key is stored in the same wallet in which the previous key was stored. Rotating the TDE Master Key leads to the new key being generated in OKV and assigned to this database. You can view all of the keys in OKV.



You can rotate both Oracle-managed and customer-managed encryption keys.

- Open the navigation menu. Under Oracle Database, click Exadata Cloud@Customer.
- 2. Click Autonomous Databases.
- In the list of Autonomous Databases, click the display name of the database you wish to view details.
- **4.** On the Autonomous Database Details page, from the **More Actions** drop-down list, select **Rotate Encryption Key**.
- 5. On the Rotate Encryption Key dialog, click Rotate Encryption Key.

Maintenance Scheduling and Patching Data Guard Enabled Autonomous Container Database

Follow these steps to change the maintenance schedule of a Data Guard enabled Autonomous Container Database.

- Configure Automatic Maintenance Schedule for a Data Guard Enabled Autonomous Container Database
- View the Next Scheduled Maintenance Run of a Data Guard Enabled Autonomous Container Database
- View the Maintenance History of a Data Guard Enabled Autonomous Container Database
- Immediately Patch a Data Guard Enabled Autonomous Container Database
- Reschedule or Skip scheduled Maintenance for Data Guard Enabled Autonomous Container Database

Configure Automatic Maintenance Schedule for a Data Guard Enabled Autonomous Container Database

1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.



- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database you are interested in.
- 4. On the Autonomous Container Database details page, under **Maintenance**, click the edit link in the **Maintenance Details** field. In the Edit Automatic Maintenance dialog that opens, you can configure both the maintenance schedule and the patch type.

Note:

The standby database will have **No preference** by default. Standby Maintenance depends on the primary maintenance schedule.

5. Optionally, you can change the maintenance patch type. To edit this setting, select either Release Update (RU) or Release Update Revision (RUR).

Release Update (RU): Autonomous Database installs only the most current release update.

Release Update Revision (RUR): Autonomous Database installs the release update plus additional fixes.

Note:

Standby will be always patched before primary and the default gap between standby and primary is 7 days. You have have an option to change the default gap to anytime between 1 - 7 days.

- 6. To configure the maintenance schedule, select Specify a schedule in the Configure the automatic maintenance schedule section. Choose your preferred month, week, weekday, and start time for container database maintenance.
 - Under Maintenance months, specify at least one month for each maintenance quarter during which you want Autonomous Exadata Infrastructure maintenance to occur.

Note:

Maintenance quarters begin in February, May, August, and November, with the first maintenance quarter of the year beginning in February.

- Under Week of the month, specify which week of the month maintenance will take
 place. Weeks start on the 1st, 8th, 15th, and 22nd days of the month, and have a
 duration of 7 days. Weeks start and end based on calendar dates, not days of the
 week. Maintenance cannot be scheduled for the fifth week of months that contain
 more than 28 days.
- Under Day of the week, specify the day of the week on which the maintenance will occur.
- Under Start hour, specify the hour during which the maintenance run will begin.
- Choose the buffer period between primary and standby maintenance execution.
 Buffer period is the number of days before which the standby Autonomous Container



Using Autonomous Data Guard with Autonomous Database on Exadata Cloud@Customer

Database Maintenance will be scheduled before primary Autonomous Container Database Maintenance

7. Click Save Changes.

View the Next Scheduled Maintenance Run of a Data Guard Enabled Autonomous Container Database

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database you are interested in.
- On the Autonomous Container Database details page, under Maintenance, click the View link in the Next Maintenance field.
- On the Maintenance page, under Autonomous Database Maintenance, click Maintenance.

In the list of maintenance events, you can the details of scheduled maintenance runs. Maintenance event details include the following:

- The status of the scheduled maintenance run
- The type of maintenance run (quarterly software maintenance or a critical patch)
- The OCID of the maintenance event
- The start time and date of the maintenance

View the Maintenance History of a Data Guard Enabled Autonomous Container Database

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database you are interested in.
- On the Autonomous Container Database details page, under Maintenance, click the View link in the Next Maintenance field.
- On the Maintenance page, under Autonomous Database Maintenance, click Maintenance History.

In the list of past maintenance events, you can click on an individual event title to read the details of the maintenance that took place. Maintenance event details include the following:

- The category of maintenance (quarterly software maintenance or a critical patch)
- Whether the maintenance was scheduled or unplanned
- The OCID of the maintenance event
- The start time and date of the maintenance



Immediately Patch a Data Guard Enabled Autonomous Container Database

Note:

Patching primary immediately will result in standby being patched first, if standby is not already patched.

- 1. Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the Autonomous Container Database that you want to patch.
- 4. On the Autonomous Container Database Details page, in the Maintenance section, click the View link in the Next Maintenance field to display the Maintenance page for the Autonomous Container Database that you want to patch.
- In the Autonomous Container Database section, click Patch Now in the Scheduled Start Time field to display the Run Maintenance dialog.
- 6. Click **Patch Now** to start the patching operation.

Reschedule or Skip scheduled Maintenance for Data Guard Enabled Autonomous Container Database



Skipping primary will skip standby also. If standby is patched, then skipping on primary is not allowed.

- Open the navigation menu. Under Oracle Database, click Exadata Database Service on Cloud@Customer.
- 2. Click Autonomous Databases.
- 3. In the list of Autonomous Container Databases, click the display name of the container database that you want to manage.
- 4. On the Autonomous Container Database details page, in the **Maintenance** section, click the **View** link in the **Next Maintenance** field.
- 5. On the Maintenance page, any container database maintenance events planned for the next 15 days will appear in the list of maintenance events.
 - To skip scheduled maintenance for a container database, click **Skip**.



Note:

You cannot skip scheduled maintenance more than twice, consecutively.

To reschedule maintenance, click **Edit** and enter a start time for the update in the Edit Maintenance dialog. Ensure that your specified container database maintenance window is later in the quarter than your scheduled Exadata infrastructure maintenance.

Using Performance Hub to Analyze Database Performance

Use the Performance Hub tool to analyze and tune the performance of a selected Oracle Exadata Database Service on Cloud@Customer Autonomous Database.

With this tool, you can view real-time and historical performance data. When you view historical data in the Performance Hub, you are viewing statistics collected as part of the hourly snapshots of your database.

Note:

Performance Hub supports only Autonomous Databases.

- Performance Hub Features
- Time Range Selector
- Time Zone Selector
- ASH Analytics Tab
- SQL Monitoring Tab
- Blocking Sessions Tab
- Using the Oracle Cloud Infrastructure Console

Performance Hub Features

The Performance Hub window consists of a graphical Time Range display that you use to select the time period of all data to be displayed. It includes the following tabs that display performance data:

- ASH Analytics
- SQL Monitoring
- Blocking Sessions

These tabs, described in detail below, provide information that you can use to analyze the performance of a selected database, including the following:

- How much of the database is waiting for a resource, such as CPU or disk I/O
- Whether database performance degraded over a given time period and what could be the likely cause.




- Which specific modules may be causing a load on the system, and where most of database time is being spent on this module.
- Which SQL statements are the key contributors to changes in database performance, and which executions are causing them.
- Which user sessions are causing performance bottlenecks.
- Which sessions are currently blocking and if there are outstanding requests for a lock.

Time Range Selector

The time range selector is displayed at the top of the Performance Hub page. It consists of a graphically displayed time field as shown in the following illustration. Note that the selected time range applies to all charts and graphs in the Performance Hub window.

Figure 6-1 Time Range Selector



The time range field (#1 in the above illustration) shows database activity in chart form for the specified Time Range period. The time range is the amount of time being monitored.

Use the Quick Select selector to set the time range. The menu includes five time choices, Last Hour, Last 8 Hours, Last 24 Hours, Last Week, and Custom. The default time range is Last Hour. To specify a custom time range, you can also click the Time Range field. This opens the Custom Time Range dialog, allowing you to specify a custom range.

The Activity graph displays the average number of active sessions broken down by CPU, User I/O, and Wait. Maximum threads are shown as a red line above the time field.

The sliding box (circled at right in the above illustration) on the time range chart is known as the time slider. The time slider selects a section of the time range (#2 in the above illustration) shown in the time range field. It shows the time being analyzed. In the illustration, the arrows inside the time slider point to the vertical 'handle' elements on the left and right boundaries of the slider box. The time slider works as follows:

- To change the start and end time of the analysis while keeping the same amount of time between them, left click anywhere inside the box. Then slide the box left or right along the time range without changing its size. The selected times are displayed below the time graph.
- To increase or decrease the length of time being analyzed, left click either one of the handles and drag it left or right to expand or contract the box.
- To refresh the data in Performance Hub according to the time range chosen, click Refresh (upper right corner of the window).



Note:

The time slider provides an extra display feature in the Workload tab. See the description in the Workload section of this page.

Use the Quick Select menu to set the time duration. The menu includes the following five time choices: Last Hour, Last 8 Hours, Last 24 Hours, Last Week, and Custom. The default Time Range is Last Hour. The time slider selects the time period of the data displayed in Performance Hub. The time slider has a different default time period based on the selected Time Range.

Time Zone Selector

The Time Zone selector is located above the time range field, beside the Quick Select and Time Range selectors. By default, when you open Performance Hub, the tool displays data in UTC (Coordinated Universal Time) time. You can use the time zone selector to change the time zone to either your local web browser time, or the time zone setting of the database you are working with. When you change the time zone, Performance Hub's reports display data in your specified time zone.

ASH Analytics Tab

Displayed by default, the ASH (Active Session History) Analytics tab shows ASH analytics charts to explore ASH data. You use it to drill down into database performance across multiple dimensions such as Consumer Group, Wait Class, SQL ID, and User Name. In the ASH Analytics tab, you can select an Average Active Sessions dimension and view the top activity for that dimension for the selected time period. For more information on ASH, see Active Session History (ASH) in Oracle Database Concepts.

SQL Monitoring Tab

The SQL Monitoring tab is not displayed by default. To view it, click **SQL Monitoring** on the Performance Hub page.

SQL statements are only monitored if they have been running for at least five seconds or if they are run in parallel. The table in this section displays monitored SQL statement executions by dimensions including Last Active Time, CPU Time, and Database Time. The table displays currently running SQL statements and SQL statements that completed, failed, or were terminated. The columns in the table provide information for monitored SQL statements including Status, Duration, and SQL ID.

The Status column has the following icons:

- A spinning icon indicates that the SQL statement is executing.
- A green check mark icon indicates that the SQL statement completed its execution during the specified time period.
- A red cross icon indicates that the SQL statement did not complete. The icon displays when an error occurs because the session was terminated.



A clock icon indicates that the SQL statement is queued.

To terminate a running or queued SQL statement, click Kill Session.

You can also click an **SQL ID** to go to the corresponding Real-time SQL Monitoring page. This page provides extra details to help you tune the selected SQL statement.

Blocking Sessions Tab

The Performance Hub blocking sessions tab displays the current blocking and waiting sessions in a hierarchical display. You can view detailed information about each blocking session, and can view the sessions blocked by each blocking session. You can also use the tab to inspect or drill down into the SQL involved, to determine the cause of the blocking. You can perform several operations in the tab, including killing one or more of the listed sessions to resolve a waiting session problem.

The hierarchical display nests waiting sessions underneath the session that they are blocked by in an easily viewable parent-child relationship. The hierarchy can contain any number of levels to correctly represent the structure of the sessions involved.

The sessions listed include sessions that are waiting for a resource and sessions that hold a resource that is being waited on that creates the blocking condition.

Using the Oracle Cloud Infrastructure Console

- Navigate to Performance Hub in the Oracle Cloud Infrastructure Console Interface of an Autonomous Database
- View the Average Active Sessions Data by a Selected Dimension
- Filter Average Active sessions Data
- View the SQL Monitoring Report
- View the Blocking and Waiting Sessions

Navigate to Performance Hub in the Oracle Cloud Infrastructure Console Interface of an Autonomous Database

- 1. Open the navigation menu. Under Oracle Database, click Exadata Cloud at Customer.
- 2. Choose your Compartment.
- Click Autonomous Databases.
- 4. In the list of Autonomous Databases, click the display name of the database you want to analyze using Performance Hub reports.
- 5. Click Performance Hub.

View the Average Active Sessions Data by a Selected Dimension

1. Go to the Performance Hub page of the Oracle Cloud Infrastructure Console for the database which you want to manage.

See To navigate to Performance Hub in the Oracle Cloud Infrastructure Console interface of an Autonomous Database for more information.



- The database name is displayed at the top of the Performance Hub page.
- The time period for which information is available on the Performance Hub is displayed in the **Time Range** field. The selected time period is indicated on the time slider graph by the adjustable time slider box.

The **ASH Analytics** tab is displayed with the top activity for a selected dimension in the selected time period.

- 2. Use the **Quick Select** selector to set the exact time period for which data is displayed in the ASH Analytics tables and graphs.
 - By default, the last hour is selected. The time range is the total amount of time available for analysis.
- 3. Use the box on the time slider to further narrow down the time period for which performance data is displayed on the **ASH Analytics** tab.
- **4.** Select a dimension in the **Average Active Sessions** drop-down list to display ASH analytics by that dimension.

When the **Consumer Group** dimension is selected, the data is categorized by default to the High, Medium, or Low service name that is associated with the Autonomous Database.

Optionally, you can:

- Click the Maximum Threads check box to view the number of Max CPU Threads. The red line on the chart shows this limit.
- Click the Total Activity check box to view a black border that denotes total
 activity of all the components of the selected dimension on the chart. This
 option is selected by default when you use the filtering capabilities to only view
 the data for a particular component within a dimension. For information on
 filtering Average Active Sessions data, see Filter Average Active Sessions
 Data.
- 5. For the dimension selected in the **Average Active Sessions** drop-down list, you can further drill down into session details by selecting dimensions in the two sections at the bottom of the ASH Analytics tab.

By default, the following dimensions are selected:

- SQL ID by Consumer Group, which displays the SQL statements with the top
 average active sessions activity for consumer groups for the selected time
 period. You can right-click the bar charts to sort the SQL statements in
 ascending or descending order or click the SQL ID to go the SQL Details
 page.
- User Session by Consumer Group, which displays the user sessions with the
 top average active sessions activity for consumer groups for the selected time
 period. You can right-click the bar charts to sort the user sessions in
 ascending or descending order or click the user session to go to the User
 Session page.

Filter Average Active sessions Data

- 1. Go to the Performance Hub page of the Oracle Cloud Infrastructure Console for the database which you want to manage.
 - See To navigate to Performance Hub in the Oracle Cloud Infrastructure Console interface of an Autonomous Database for more information.



- The database name is displayed at the top of the Performance Hub page.
- The time period for which information is available on the Performance Hub is displayed in the **Time Range** field. The selected time period is indicated on the time slider graph by the adjustable time slider box.

The **ASH Analytics** tab is displayed with the top activity for a selected dimension in the selected time period.

2. Use the **Quick Select** selector to set the exact time period for which data is displayed in the ASH Analytics tables and graphs.

By default, the last hour is selected. The time range is the total amount of time available for analysis.

- 3. Use the adjustable time slider box to further narrow down the time period for which performance data is displayed on the **ASH Analytics** tab.
- In the ASH Analytics tab, select a dimension in the Average Active Sessions by dropdown list.

By default, **Consumer Group** is selected.

The chart is displayed. Each color in the chart denotes a component of the selected dimension. For example, the Consumer Group dimension has High, Medium, and Low, which are predefined service names assigned to your Autonomous Database to provide different levels of concurrency and performance.

5. Click a component in the legend.

The selected component is displayed in the **Applied Filters** field and the chart is updated to only display data pertaining to that component. The total activity, which includes all the components of the dimension, is defined by a black outline and is displayed by default when you filter data.

View the SQL Monitoring Report

1. Go to the Performance Hub page of the Oracle Cloud Infrastructure Console for the database which you want to manage.

See To navigate to Performance Hub in the Oracle Cloud Infrastructure Console interface of an Autonomous Database for more information.

- The database name is displayed at the top of the Performance Hub page.
- The time period for which information is available on the Performance Hub is displayed in the **Time Range** field. The selected time period is indicated on the time slider graph by the adjustable time slider box.
- 2. Click **SQL Monitoring** to display the SQL monitoring tab.
- Optionally, you can get detailed information on a specific SQL statement by clicking an ID number in the SQL ID column.

When you click an ID number, the Real-time SQL Monitoring page is displayed.

4. Click **Download Report** to download the report data for your selected SQL statement.

View the Blocking and Waiting Sessions

1. Go to the Performance Hub page of the Oracle Cloud Infrastructure Console for the database which you want to manage.



See To navigate to Performance Hub in the Oracle Cloud Infrastructure Console interface of an Autonomous Database for more information.

- The database name is displayed at the top of the Performance Hub page.
- The time period for which information is available on the Performance Hub is displayed in the **Time Range** field. The selected time period is indicated on the time slider graph by the adjustable time slider box.
- Click Blocking Sessions to display details about current blocking and waiting sessions.

Analysis of historical sessions is not supported.

3. Click the link in each column of the table to view the details of the listed blocking and waiting sessions, as shown in the following table.



If you see an error message that says the server failed to get performance details for the selected session at the selected time, try the selection again. If the same error message is displayed, try a different time selection. If that fails, contact Oracle Support.

Table 6-8 Blocking and Waiting Sessions

Tab Column	Description
User Name	This is the name of the user.
Status	The status indicates whether the session is active, inactive, or expired.
Lock	This is the lock type for the session. Click the lock type to display a table with more information about the session lock. It lists the Lock Type, Lock Mode, Lock Request, Object Type, Subobject Type, Time, ID1, ID2, Lock Object Address, and Lock Address of the selected session.
User Session	The user session lists the Instance, SID, and Serial number.
SQL ID	This is the ID of the SQL associated with the session.
Wait Event	This is the wait event for the session. Click the wait event to show additional wait event details.
Object Name	This is the name of the locked database object.
Blocking Time	This is the time that a blocking session has been blocking a session.
Wait Time	This is the time that a session has been waiting.

Setting the Minimum Wait Time



- Killing a Session
- Displaying Lock Details
- Displaying Wait Event Information
- Displaying Session Details
- Displaying SQL Details

Setting the Minimum Wait Time

The minimum wait time works like a filter for the Blocking Sessions information. It sets the minimum time that a session must wait before it is displayed in the tab. For example, if the minimum wait time is set to three seconds, and a session has waited only two seconds, it is not displayed in the table. But if you change the minimum wait time to one second, the session that waited only two seconds is added to the display.



The minimum wait time default setting is three seconds.

Killing a Session

1. Click the check box at the left of the session **User Name** to select a session.

The Kill Session button is enabled.

2. Click Kill Session.

The Kill Session confirmation dialog box is displayed.

3. Click Kill Session to end the session.

Displaying Lock Details

1. In the session **Lock** column, click the name of the lock type (Lock or Exclusive Lock) for the session.

The Wait Event Details message box is displayed.

2. Note the information in the table and use as needed to determine any action to take.

Displaying Wait Event Information

 In the session Wait Event column, click the name of the wait event for the selected session.

The **Session Lock Information** table is displayed.

2. Note the information in the message box and use as needed to determine any action to take.

Displaying Session Details



- 1. In the session **User Session** column, click the session identifier for the session. The Performance Hub Session Details page is displayed.
- 2. Optionally, move the time slider to display a specific time range of the session.
- 3. Use the Session Details page to explore additional details about the session.

Displaying SQL Details

- In the session SQL ID column, click the SQL ID associated with the session.
 The Performance Hub SQL Details page is displayed.
- 2. Optionally, move the time slider to display a specific time range of the session.
- 3. Select one or more of the following tabs, note the information in them, and take any action needed.
 - Summary. This tab displays the SQL Overview and Source details.
 - **ASH Analytics**. This tab displays the SQL average active sessions.
 - Execution Statistics. This tab displays the SQL plans and plan details.
 - SQL Monitoring. This tab displays information about monitored SQL executions.
 - SQL Text. This tab displays the SQL.



7

Reference Guides for Exadata Database Service on Cloud@Customer

- Using the dbaascli Utility with Exadata Database Service on Cloud@Customer Learn to use the dbaascli utility on Exadata Cloud@Customer.
- Monitoring and Managing Exadata Storage Servers with ExaCLI
 Learn to use the ExaCLI command-line utility to perform monitoring and management
 functions on Exadata storage servers in the Exadata Cloud Service.
- Oracle Exadata Database Service on Cloud@Customer Events
 Exadata Cloud@Customer resources emit events, which are structured messages that indicate changes in resources.
- Policy Details for Exadata Database Service on Cloud@Customer
 Learn to write policies to control access to Exadata Database Service on Cloud@Customer resources.
- Managing Exadata Resources with Oracle Enterprise Manager Cloud Control
 To manage and monitor Exadata Cloud and Exadata Cloud@Customer resources, use
 Oracle Enterprise Manager Cloud Control.
- Security Guide for Exadata Database Service on Cloud@Customer Systems
 This guide describes security for an Oracle Exadata Cloud@Customer System. It
 includes information about the best practices for securing the Oracle Exadata
 Cloud@Customer System.
- Troubleshooting Exadata Database Service on Cloud@Customer Systems
 These topics cover some common issues you might run into and how to address them.

Using the dbaascli Utility with Exadata Database Service on Cloud@Customer

Learn to use the dbaascli utility on Exadata Cloud@Customer.

- About Using the dbaascli Utility on Exadata Database Service on Cloud@Customer
 You can use the dbaascli utility to perform various database lifecycle and administration
 operations on Exadata Cloud@Customer such as creating an Oracle Database, patching
 an Oracle Database, managing pluggable databases (PDBs), scaling the CPU core count
 in disconnected mode, and more.
- Creating Oracle Database Using dbaascli
 Using dbaascli, you can create an Oracle Database by first creating an Oracle Database home of desired version, followed by creating a database in that Oracle Database home.
- Changing the Database Passwords
 To change the SYS password, or to change the TDE wallet password, use this procedure.

Managing Exadata Database Service on Cloud@Customer Software Images
Using the Dbaascli Utility

You can list and download the Oracle database software images on an Exadata Database Service on Cloud@Customer instance, which can then be used for provisioning a database home.

- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli
 Learn to use the dbaascli utility to perform patching operations for Oracle Grid
 Infrastructure and Oracle Database on an Exadata Cloud@Customer system.
- Updating Cloud Tooling Using dbaascli
 To update the cloud tooling release for Oracle Exadata Database Service on Cloud@Customer, complete this procedure.
- Release Notes
 Review the changes made in various releases of dbaascli.
- dbaascli Command Reference
 Use these commonly used commands to manage Exadata Cloud@Customer.

About Using the dbaascli Utility on Exadata Database Service on Cloud@Customer

You can use the <code>dbaascli</code> utility to perform various database lifecycle and administration operations on Exadata Cloud@Customer such as creating an Oracle Database, patching an Oracle Database, managing pluggable databases (PDBs), scaling the CPU core count in disconnected mode, and more.

You must use the DBaaS console or command-line interface to scale resources. The capabilities of the <code>dbaascli</code> utility are in addition to, and separate from, the Oracle Cloud Infrastructure Console, API, or command-line interface (CLI). Unless specified differently, you need <code>root</code> access to <code>dbaascli</code> to run all administration commands.

To use the utility, you must be connected to an Exadata Cloud@Customer virtual machine. See *Connecting to a Virtual Machine with SSH*.

To get possible commands available with dbaascli, run dbaascli --help.

To get command-specific help, run dbaascli command --help. For example, dbaascli database create --help.

Creating Oracle Database Using dbaascli

Using dbaascli, you can create an Oracle Database by first creating an Oracle Database home of desired version, followed by creating a database in that Oracle Database home.

- Listing Available Software Images and Versions for Database
 To get a list of available supported versions for creating Oracle Database, use the dbaascli cswlib showImages command.
- Creating Oracle Database Home
 To create an Oracle Database home of desired version, use the dbaascli dbhome create command.



Creating Oracle Database In the Specified Oracle Database Home
 To create an Oracle Database in the specified Oracle Database home of desired version,
 use the dbaascli database create command.

Listing Available Software Images and Versions for Database

To get a list of available supported versions for creating Oracle Database, use the dbaascli cswlib showImages command.

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Start a root user command shell:

```
sudo -s
```

3. Run the following command:

```
dbaascli cswlib showImages
```

The command output lists the available database software images.

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli cswlib showImages.

Example 7-1 dbaascli cswlib showlmages

```
dbaascli cswlib showImages
DBAAS CLI version MAIN Executing command cswlib showImages
INFO : Log file => /var/opt/oracle/log/list/
list 2021-05-10 10:11:00.56966610630.log
########## List of Available DB Images #############
1.IMAGE TAG=19.8.0.0.0
VERSION=19.8.0.0.0
DESCRIPTION=19c JUL 2020 DB Image
IMAGE ALIASES=19000-19800,19000-JUL2020
2.IMAGE TAG=19.8.0.0.0-NC
VERSION=19.8.0.0.0
DESCRIPTION=19c JUL 2020 Non CDB Image
IMAGE ALIASES=19000-NC19800,19000-NCJUL2020
3.IMAGE TAG=19.9.0.0.0
VERSION=19.9.0.0.0
DESCRIPTION=19c OCT 2020 DB Image
IMAGE ALIASES=19000-19900,19000-OCT2020
4.IMAGE TAG=19.9.0.0.0-NC
VERSION=19.9.0.0.0
```



DESCRIPTION=19c OCT 2020 Non CDB Image IMAGE ALIASES=19000-NC19900,19000-NC0CT2020



You can specify the target version in dbaascli dbhome create command as --version value from the dbaascli cswlib showImages command output.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli cswlib showImages
 To view the list of available Database and Grid Infrastructure images, use the dbaascli cswlib showImages command.

Creating Oracle Database Home

To create an Oracle Database home of desired version, use the <code>dbaascli</code> <code>dbhome</code> <code>create</code> command.



You can create an Oracle Database home with a specified Oracle home name. If you do not specify, then this is computed automatically (recommended).

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- 2. Start a root user command shell:

sudo -s

3. Run the following command:

dbaascli dbhome create --version Oracle Home Version --imageTag image Tag Value

Where:

- --version specifies the Oracle Database version
- --imageTag specifies the Image Tag of the image to be used

For example:

dbaascli dbhome create --version 19.9.0.0.0





Specifying imageTag is optional. To view the Image Tags, refer to command dbaascli cswlib showImages. Image Tags are typically same as the version of the database. However, it is kept as a provision for cases where multiple images may need to be released for the same version - each catering to a specific customer requirement.

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli dbhome create.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli dbhome create
 To create an Oracle Database home of desired version, use the dbaascli dbhome create command.

Creating Oracle Database In the Specified Oracle Database Home

To create an Oracle Database in the specified Oracle Database home of desired version, use the dbaascli database create command.

You can use the dbaascli database create command to:

- Create a Container Database (CDB) or non-Container Database
- Create a CDB with pluggable databases (PDBs)
- Create an Oracle Database with the specified Character Set
- Create Oracle Databases on a subset of cluster nodes



Databases created on a subset of nodes will not be displayed in the OCI console.

- Create Oracle Database version 12.1.0.2 or higher with the release update JAN 2021 or higher. For databases with lower versions, it is recommended to use the OCI Console based API.
- Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Start a root user command shell:

sudo -s



3. Run the following command:

dbaascli database create --dbName database name --oracleHome Oracle Home Path

Where:

- --dbName specifies the name of the database
- --oracleHome specifies Oracle home location

To create a CDB, run the following command:

dbaascli database create --dbName database name --oracleHome Oracle Home Path

To create a non-CDB, run the following command:

dbaascli database create --dbName database name --oracleHome Oracle Home Path --createAsCDB false

When prompted, enter the sys and tde passwords.

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli database create.

- Running Prerequisite Checks Prior to Creating Oracle Database
 To run prerequisites checks, use the --executePrereqs command option. This will perform only the prerequisite checks without performing the actual Oracle
- Resuming or Reverting Oracle Database Creation Operation
 To resume or revert a failed database creation operation, use the --resume or --revert command option.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 - You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.
- · dbaascli database create

Database creation.

To create Oracle Database, use the <code>dbaascli</code> database <code>create</code> command. When prompted, enter the <code>sys</code> and <code>tde</code> passwords.

Running Prerequisite Checks Prior to Creating Oracle Database

To run prerequisites checks, use the --executePrereqs command option. This will perform only the prerequisite checks without performing the actual Oracle Database creation.

Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.



2. Start a root user command shell:

sudo -s

3. Run the following command:

dbaascli database create --dbName database name --oracleHome Oracle Home Path --executePrereqs

Where:

- --dbName specifies the name of the database
- --oracleHome specifies the Oracle home location
- 4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli database create.

Related Topics

Connecting to a Virtual Machine with SSH
You can connect to the virtual machines in an Exadata Database Service on
Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database create

To create Oracle Database, use the dbaascli database create command. When prompted, enter the sys and tde passwords.

Resuming or Reverting Oracle Database Creation Operation

To resume or revert a failed database creation operation, use the --resume or --revert command option.

For example:

dbaascli database create $\operatorname{--dbName}$ database name $\operatorname{--oracleHome}$ Oracle Home Path $\operatorname{--resume}$

Note:

- While using the --resume or --revert command options, ensure that you use
 the same command from the same node that was used for actual create
 operation flow.
- You can resume database creation only if there is a failure in the post database creation step.



Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database create
 To create Oracle Database, use the dbaascli database create command. When prompted, enter the sys and tde passwords.

Changing the Database Passwords

To change the SYS password, or to change the TDE wallet password, use this procedure.

The password that you specify in the **Database Admin Password** field when you create a new Exadata Database Service on Cloud@Customer instance or database is set as the password for the SYS, SYSTEM, TDE wallet, and PDB administrator credentials. Use the following procedures if you need to change passwords for an existing database.



if you are enabling Data Guard for a database, then the SYS password and the TDE wallet password of the primary and standby databases must all be the same.

Note:

Using the dbaascli to change the SYS password will ensure the backup/ restore automation can parallelize channels across all nodes in the cluster.

To Change the SYS Password for an Exadata Database Service on Cloud@Customer Database

- Log onto the Exadata Database Service on Cloud@Customer virtual machine as opc.
- **2.** Run the following command:

sudo dbaascli database changepassword --dbname database_name --user
SYS

To Change Database Passwords in a Data Guard Environment

1. Run the following command on the primary database:

dbaascli database changePassword —dbName <dbname> --user SYS -- prepareStandbyBlob true --blobLocation <location to create the blob file>



- 2. Copy the blob file created to all the standby databases and update the file ownership to oracle user.
- 3. Run the following command on all the standby databases:

```
dbaascli database changePassword -dbName <dbname> --user SYS --
standbyBlobFromPrimary <location of copies the blob file>
```

To Change the TDE Wallet Password for an Exadata Database Service on Cloud@Customer Database

- 1. Log onto the Exadata Database Service on Cloud@Customer virtual machine as opc.
- **2.** Run the following command:

sudo dbaascli tde changepassword --dbname database name

Managing Exadata Database Service on Cloud@Customer Software Images Using the Dbaascli Utility

You can list and download the Oracle database software images on an Exadata Database Service on Cloud@Customer instance, which can then be used for provisioning a database home.



You can create custom database software images for your Exadata Database Service on Cloud@Customer instances using the Console or API. These images are stored in Object Storage, and can be used to provision a Database Home in your Exadata instance. See Oracle Database Software Images more information.

You can control the version of Oracle binaries that is installed when you provision a new database on an Exadata Database Service on Cloud@Customer instance by maintaining the software images on the system. Oracle provides a library of cloud software images that you can view and download onto your instance by using the dbaascli utility.

- Listing Available Software Images and Versions for Database and Grid Infrastructure

 To produce a list of available supported versions for patching, use the dbaascli cswlib showImages command.
- To download a software image
 You can download available software images onto your Exadata Database Service on
 Cloud@Customer instance by using the cswlib download subcommand of the dbaascli
 utility.

Listing Available Software Images and Versions for Database and Grid Infrastructure

To produce a list of available supported versions for patching, use the <code>dbaascli cswlib showImages command</code>.

1. Connect to the virtual machine as the opc user.



For detailed instructions, see Connecting to a Virtual Machine with SSH.

2. Start a root user command shell:

```
sudo -s
```

3. Run the following command:

```
dbaascli cswlib showImages --product database
```

The command output lists the available database software images.

```
dbaascli cswlib showImages --product grid
```

The command output lists the available grid software images.

4. Exit the root user command shell:

exit

For more details on advanced supported options, see <code>dbaascli cswlib showImages</code>.

Example 7-2 dbaascli cswlib showlmages

```
[root@dg11lrg1 dbhome 1]# dbaascli cswlib showImages
DBAAS CLI version <version>
Executing command cswlib
      showImagesJob id: 00e89b1a-1607-422c-a920-22f44bec1953Log file
location:
      /var/opt/oracle/log/cswLib/showImages/
dbaastools 2022-05-11 08-49-12-AM 46941.log
###########
List of Available Database Images
#############
17.IMAGE TAG=18.17.0.0.0
   VERSION=18.17.0.0.0
   DESCRIPTION=18c JAN 2022 DB Image
18.IMAGE TAG=19.10.0.0.0
   VERSION=19.10.0.0.0
   DESCRIPTION=19c JAN 2021 DB Image
19.IMAGE TAG=19.11.0.0.0
   VERSION=19.11.0.0.0
   DESCRIPTION=19c APR 2021 DB Image
20.IMAGE TAG=19.12.0.0.0
  VERSION=19.12.0.0.0
  DESCRIPTION=19c JUL 2021 DB Image
21.IMAGE TAG=19.13.0.0.0
```



```
VERSION=19.13.0.0.0
DESCRIPTION=19c OCT 2021 DB Image
```

Images can be downloaded using their image tags. For details, see help using 'dbaascli cswlib download --help'. dbaascli execution completed

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli cswlib showlmages

To view the list of available Database and Grid Infrastructure images, use the dbaascli cswlib showImages command.

To download a software image

You can download available software images onto your Exadata Database Service on Cloud@Customer instance by using the cswlib download subcommand of the dbaascli utility.

- 1. Connect to a compute node as the opc user. For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- 2. Start a root-user command shell:

```
$ sudo -s #
```

3. Execute the dbaascli command with the cswlib download subcommand:

```
# dbaascli cswlib download [--version <software_version>] [--imageTag
<image tag
   value>]
```

The command displays the location of software images that are downloaded to your Exadata Database Service on Cloud@Customer environment.

The optional parameters are:

- version: specifies an Oracle Database software version. For example, 19.14.0.0.0.
- imageTag: specifies the image tag of the image.
- 4. Exit the root-user command shell:

```
# exit
$
```

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.



Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli

cswlib showImages command.

Learn to use the dbaascli utility to perform patching operations for Oracle Grid Infrastructure and Oracle Database on an Exadata Cloud@Customer system.

- Patching Databases using dbaascli
 Using dbaascli, you can choose to patch a database by patching Oracle home, or
 by moving the database to an Oracle home with the desired patch level.
- Patching Oracle Grid Infrastructure
 To apply a patch to Oracle Grid Infrastructure, use the grid patch command.
- Listing Available Software Images and Versions for Database and Grid
 Infrastructure
 To produce a list of available supported versions for patching, use the dbaascli
- Performing a Precheck Before Patching Databases and Grid Infrastructure You can perform a prerequisites-checking operation (also called a "precheck") for the commands in this topic using the applicable precheck flag.
- Resuming or Rolling Back a Patching Operation
 You can resume or revert a failed patching operation. Reverting a patch is known
 as a rollback.

Patching Databases using dbaascli

Using dbaascli, you can choose to patch a database by patching Oracle home, or by moving the database to an Oracle home with the desired patch level.

- Patching an Oracle home (in-place patching). This updates all databases located in the Oracle home.
- Moving a database to a different Oracle home that has the desired Oracle Database software version (out-of-place patching).
- Patching a Database Home (In-Place Database Patching)
 To patch an Oracle home, use the dbaascli dbHome patch command.
- Moving a Database to a Different Oracle Home (Out-of-Place Patching)
 To patch an Oracle Database by moving it to an Oracle home that is already at the desired patch level, use the dbaascli database move command.

Patching a Database Home (In-Place Database Patching)

To patch an Oracle home, use the dbaascli dbHome patch command.

This will patch all databases running in the specified home, and the databases will remain in the home after the patching is complete. The following apply to using the dbHome patch command for in-place patching operations:

- You can patch all of your database nodes or a subset of nodes.
- Multi-node patching takes place in a rolling fashion.
- Optionally, you can perform a software-only patch operation. Then, when you are ready, you can run datapatch to perform post-patch SQL actions.



You can patch an Oracle home containing one or more databases.

To patch an Oracle Home (dbhome):

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- Start a root user command shell:

```
sudo -s
```

3. Run the following command:

```
dbaascli dbhome patch --oracleHome dbhome_path --targetVersion Oracle_Database_version
```

Where:

- --oracleHome identifies the path of the Oracle home to be patched.
- --targetVersion specifies the target Oracle Database version to use for patching, specified as five numeric segments separated by periods (e.g. 19.12.0.0.0).

For example:

```
dbaascli dbhome patch --oracleHome /u02/app/oracle/product/19.0.0.0/dbhome 2 --targetVersion 19.9.0.0.0
```

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli dbHome patch.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli dbHome patch
 To patch Oracle home from one patch level to another, use the dbaascli dbHome patch command.

Moving a Database to a Different Oracle Home (Out-of-Place Patching)

To patch an Oracle Database by moving it to an Oracle home that is already at the desired patch level, use the <code>dbaascli database move command</code>.

After the database move operation is complete, the database runs using the Oracle Database software version of the target Oracle Home.

To patch a database by moving it to a different Oracle Home:

Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.



2. Start a root user command shell:

sudo -s

3. Run the following command:

dbaascli database move --oracleHome path_to_target_oracle_home -- dbname database name

Where:

- --oracleHome identifies the path of the target Oracle home that uses the desired Oracle Database software version. Note that the target Oracle home must exist in your system prior to using the database move command.
- --dbname specifies the name of the database that is being moved.

For example:

```
dbaascli database move --oracleHome /u02/app/oracle/product/ 19.0.0.0/dbhome_2 --dbname xyz
```

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli database move.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli database move
 To perform out-of-place patching, use the dbaascli database move command.

Patching Oracle Grid Infrastructure

To apply a patch to Oracle Grid Infrastructure, use the grid patch command.

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- 2. Start a root user command shell:

sudo -s

3. Run the following command:

```
dbaascli grid patch --targetVersion target software version number
```

Where --targetVersion identifies target software version that the Oracle Grid Infrastructure will be patched to.



For example:

```
dbaascli grid patch --targetVersion 19.11.0.0.0
```

4. Exit the root user command shell:

exit

For more details on advanced supported options, see dbaascli grid patch.

Patching Oracle Grid Infrastructure (GI) Using GI Software Image
 To patch Oracle Grid Infrastructure (GI) using GI software image, use this procedure.

Related Topics

- You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli grid patch
 To patch Oracle Grid Infrastructure to the specified minor version, use the dbaascli grid patch command.

Patching Oracle Grid Infrastructure (GI) Using GI Software Image

To patch Oracle Grid Infrastructure (GI) using GI software image, use this procedure.

Oracle Grid Infrastructure can also be patched by first creating a patched software image, and then using that image to perform the patching operation. This provides the advantage that an image can be created ahead of time outside of the patching window. It also helps in conflict resolution as any conflicts among the patches are highlighted during the image creation process without impacting the patching window.

Create a patched software image.

```
dbaascli grid patch --targetVersion < target_software_version_number> --
createImage
```

Once the patched software image creation is completed, the image can then be used for performing the patching operation.

2. Perform the patching operation.

```
dbaascli grid patch --targetVersion <target_software_version_number> --
imageLocation <location_of_patched_software_image>
```

Listing Available Software Images and Versions for Database and Grid Infrastructure

To produce a list of available supported versions for patching, use the dbaascli cswlib showImages command.

Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.



2. Start a root user command shell:

sudo -s

3. Run the following command:

```
dbaascli cswlib showImages --product database
```

The command output lists the available database software images.

```
dbaascli cswlib showImages --product grid
```

The command output lists the available grid software images.

4. Exit the root user command shell:

exit

For more details on advanced supported options, see <code>dbaascli cswlib showImages</code>.

Example 7-3 dbaascli cswlib showlmages

```
[root@dg11lrg1 dbhome 1]# dbaascli cswlib showImages
DBAAS CLI version <version>
Executing command cswlib
      showImagesJob id: 00e89b1a-1607-422c-a920-22f44bec1953Log file
location:
      /var/opt/oracle/log/cswLib/showImages/
dbaastools 2022-05-11 08-49-12-AM 46941.log
###########
List of Available Database Images
############
17.IMAGE TAG=18.17.0.0.0
   VERSION=18.17.0.0.0
   DESCRIPTION=18c JAN 2022 DB Image
18.IMAGE TAG=19.10.0.0.0
   VERSION=19.10.0.0.0
   DESCRIPTION=19c JAN 2021 DB Image
19.IMAGE TAG=19.11.0.0.0
   VERSION=19.11.0.0.0
   DESCRIPTION=19c APR 2021 DB Image
20.IMAGE TAG=19.12.0.0.0
  VERSION=19.12.0.0.0
  DESCRIPTION=19c JUL 2021 DB Image
21.IMAGE TAG=19.13.0.0.0
  VERSION=19.13.0.0.0
```



```
DESCRIPTION=19c OCT 2021 DB Image
```

Images can be downloaded using their image tags. For details, see help using 'dbaascli cswlib download --help'. dbaascli execution completed

Related Topics

- Connecting to a Virtual Machine with SSH
 - You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli cswlib showImages
 To view the list of available Database and Grid Infrastructure images, use the dbaascli cswlib showImages command.

Performing a Precheck Before Patching Databases and Grid Infrastructure

You can perform a prerequisites-checking operation (also called a "precheck") for the commands in this topic using the applicable precheck flag.

Running prechecks allows you to run only the precheck portion of the patching operation without performing actual patching. Oracle recommends running prechecks to discover software issues that could prevent successful patching.

To perform patching prechecks, first, connect to a virtual machine in your Exadata Cloud@Customer instance as the root user.

- Precheck for Oracle Home Patching (In-Place Patching)
 Use the --executePreregs flag with the dbaascli dbhome patch command.
- Precheck for Database Move Patching (Out-of-Place Patching)
 Use the --executePreregs flag with the dbaascli database move command.
- Precheck for Oracle Grid Infrastructure Patching
 Use the --executePreregs flag with the dbaascli grid patch command.

Precheck for Oracle Home Patching (In-Place Patching)

Use the --executePreregs flag with the dbaascli dbhome patch command.

- Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Start a root user command shell:

```
sudo -s
```

3. Run the following command:

```
dbaascli dbhome patch --oracleHome dbhome_path --targetVersion Oracle Database version --executePrereqs
```

Where:

--oracleHome identifies the path of the Oracle home to be prechecked.



- --targetVersion specifies the target Oracle Database version to be patched to, specified as five numeric segments separated by periods (e.g. 19.12.0.0.0).
- 4. Exit the root user command shell:

exit

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli dbHome patch

To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome</code> patch command.

Precheck for Database Move Patching (Out-of-Place Patching)

Use the --executePrereqs flag with the dbaascli database move command.

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- 2. Start a root user command shell:

sudo -s

3. Run the following command:

```
dbaascli database move --oracleHome path_to_target_oracle_home --dbname database name --executePrereqs
```

Where:

- --oracleHome identifies the path of the target Oracle Home that uses the
 desired Oracle Database software version. Note that the target Oracle Home
 must exist in your system prior to using the database move command.
- --dbname specifies the name of the database that is being moved
- 4. Exit the root user command shell:

exit

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database move

To perform out-of-place patching, use the dbaascli database move command.



Precheck for Oracle Grid Infrastructure Patching

Use the --executePrereqs flag with the dbaascli grid patch command.

- Connect to the virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Start a root user command shell:

sudo -s

3. Run the following command:

```
dbaascli grid patch --targetVersion target_software_version_number --
executePrereqs
```

Where --targetVersion identifies target software version that the Oracle Grid Infrastructure will be patched to, specified as five numeric segments separated by periods, for example, 19.12.0.0.0

4. Exit the root user command shell:

exit

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli grid patch

To patch Oracle Grid Infrastructure to the specified minor version, use the <code>dbaascli grid patch command</code>.

Resuming or Rolling Back a Patching Operation

You can resume or revert a failed patching operation. Reverting a patch is known as a rollback.

Resuming a Patch Operation

To resume a patching operation, use the --resume flag with the original patching command.

Rolling Back a Patch Operation

Use the --rollback flag with the original patching command to roll back (revert) a patching operation.

Resuming a Patch Operation

To resume a patching operation, use the --resume flag with the original patching command.

1. Connect to the virtual machine as the opc user.
For detailed instructions, see Connecting to a Virtual Machine with SSH.



2. Start a root user command shell:

sudo -s

3. Run the original patching command to resume a patching operation: For example:

```
dbaascli dbhome patch --oracleHome /u02/app/oracle/product/19.0.0.0/dbhome 2 --targetVersion 19.9.0.0.0 --resume
```

4. Exit the root user command shell:

exit

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli dbHome patch

To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome</code> patch command.

dbaascli grid patch

To patch Oracle Grid Infrastructure to the specified minor version, use the dbaascli grid patch command.

Rolling Back a Patch Operation

Use the --rollback flag with the original patching command to roll back (revert) a patching operation.

- 1. Connect to the virtual machine as the opc user.
 For detailed instructions, see *Connecting to a Virtual Machine with SSH*.
- 2. Start a root user command shell:

sudo -s

3. Run the original patching command to roll back (revert) a patching operation: For example:

dbaascli grid patch --targetVersion 19.11.0.0.0 --rollback



Note:

- Resume and Rollback operations are supported for Oracle Home patching,
 Oracle Grid Infrastructure patching, and database move operations.
- When resuming or rolling back a patching operation, you must run the
 resume or rollback command from the same node that was used to run the
 original patching command, and you must run the original command with
 the addition of the --resume or --rollback flag.
- 4. Exit the root user command shell:

exit

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli dbHome patch
 To patch Oracle home from one patch level to another, use the dbaascli dbHome patch command.
- dbaascli grid patch
 To patch Oracle Grid Infrastructure to the specified minor version, use the dbaascli grid patch command.

Updating Cloud Tooling Using dbaascli

To update the cloud tooling release for Oracle Exadata Database Service on Cloud@Customer, complete this procedure.

Cloud-specific tooling is used on the Exadata Cloud@Customer Guest VMs for local operations, including dbaascli commands.

The cloud tooling is automatically updated by Oracle when new releases are made available. If needed, you can follow the steps below to ensure you have the latest version of the cloud-specific tooling on all of the virtual machines in the VM cluster.



You can update the cloud-specific tooling by downloading and applying a software package containing the updated tools.

- Connect to a virtual machine as the opc user.
 For detailed instructions, see Connecting to a Virtual Machine with SSH.
- 2. Start a root user command shell:

sudo -s



3. To update to the latest available cloud tooling release, run the following command:

```
dbaascli admin updateStack --version LATEST
```

The command takes care of updating the cloud tooling release on all the nodes of the cluster.

For more details and other available options, refer to dbaascli admin updateStack --help.

Related Topics

- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.
- dbaascli admin updateStack
 To install or update a dbaastools RPM, use the dbaascli admin updateStack command.

Release Notes

Review the changes made in various releases of dbaascli.

- Release 22.2.1.1.0 (220713)
- Release 22.2.1.0.1 (220504)
- Release 22.1.1.1.0 (220301)
- Release 22.1.1.0.1 (220223)
- Release 21.4.1.1.0
- Release 21.3.1.2.0
- Release 21.3.1.1.0
- Release 21.3.1.0.1
- Release 21.2.1.x.x

Release 22.2.1.1.0 (220713)

- New dbaascli commands:
 - dbaascli dbHome getDatabases This command lists all the databases running from a given database Oracle home. The output is returned in JSON format to facilitate automation. For details, see dbaascli dbHome getDatabases --help.
 - dbaascli database getPDBs This command lists all the pluggable databases of a given container database. The output is returned in JSON format to facilitate automation. For details, see dbaascli database getPDBs --help.
 - dbaascli dbHome delete This command deletes a given database Oracle home. For details, see dbaascli dbHome delete --help.
 - dbaascli dataguard prepareStandbyBlob This command generates a blob file containing various files that are required on the standby site for a Data



Guard environment. For details, see dbaascli dataguard prepareStandbyBlob -- help.

- Grid Infrastructure (GI) Patching:
 - New optimized workflow
 - Introduced a way to create the Grid Infrastructure (GI) software image prior to patching. This GI image can be subsequently used for performing the GI patching operation. The advantage of this approach is that it results in reduced patching window as the image is already prepared. The GI stack on the node is not brought down to create the image. For details, see createImage option in dbaascli grid patch --help
 - Introduced a way to perform the Grid Infrastructure patching through the use of user specified GI software image, created using createImage option of the dbaascli grid patch command. For details, see imageLocation option in dbaascli grid patch -help.
- Change Password support in Data Guard environment:
 - Added support to change password in Data Guard environments. For details, see dbaascli database changePassword --help and dbaascli dataguard prepareStandbyBlob --help
- Data Guard configuration:
 - Added support to update Data Guard Automation Attributes (in the /var/opt/oracle/dg/dg.conf file). For details, see dbaascli dataguard --help.
- Various bug fixes and stability improvements

Release 22.2.1.0.1 (220504)

- New dbaascli commands:
 - Introduced dbaascli admin showLatestStackVersion to show the latest dbaastools version available for customers to download and install. The installation of dbaastools RPM can be performed by using the command dbaascli admin updateStack. For details see the dbaascli Command Reference section.
- Cloud Software Library:
 - Deprecated the support for BP activation (dbaascli cswlib activateBP) as BPs (Bundle Patches) are now replaced with RUs ("Release Updates"). Cloud deployment consumes RUs in the form of software images, identified with Image Tags. It is therefore recommended to use image tags while interfacing with Cloud Software Library (cswlib) commands. For details, see dbaasscli cswlib download -help.
 - Eliminated the need to download non-CDB images to create non-CDB databases.
 Now users can create the non-CDB database using regular images. For details, see createAsCDB option in dbaascli database create -help.
- Non-CDB Database Creation:
 - Enhanced database creation workflow to create a non-CDB database using standard database software image. For details, see createAsCDB option in dbaascli database create -help.
- Database Home Patching:



- New optimized workflow
- Grid Infrastructure Upgrade:
 - New optimized workflow
- Pluggable Database (PDB) Operations:
 - Deletion of PDB in Data Guard environments requires explicit
 acknowledgment to indicate that operations necessary on standby site are
 completed, by passing of additional argument -allStandByPrepared. For
 details, see dbaascli pdb delete --help.
- Provided rolling capability for database bounce operation. For details, see dbaascli database bounce -help.
- Various bug fixes and stability improvements

Release 22.1.1.1.0 (220301)

- New dbaascli commands:
 - Introduced dbaascli system getDBHomes to get all the database Oracle homes on the cluster. The output is returned in JSON format to facilitate automation.
 - Introduced dbaascli dbhome getDetails to get detailed information on a specific Oracle home. The output is returned in JSON format to facilitate automation.
- Cloud Software Library (cswlib):
 - Deprecated the support for dbaascli cswlib list command for cloud software library listing operations. The new command is dbaascli cswlib showImages that lists the images along with its of ImageTag. It is recommended to use Image tags to download the images from the cloud software library. For details on downloads using image tags, see dbaascli cswlib download help.
 - Various bug fixes and stability improvements

Release 22.1.1.0.1 (220223)

- Grid Infrastructure Upgrade:
 - New optimized workflow
- Database Backup and Recovery:
 - Internal update to metadata repository for backup metadata
 - Introduced deprecation messages for bkup_api commands as they are now replaced with dbaascli commands. For details, see dbaascli database backup --help and dbaascli database recover -help
- Pluggable Database (PDB) Operations:
 - Relocate operation of PDB is now supported. For details, see dbaascli pdb relocate -help.



- Revamped workflow for non-CDB to PDB conversion. For details, see dbaasclidetabase convertToPDB -help.
- Encryption Key Management:
 - Transparent Data Encryption (TDE) heartbeat-specific initialization parameters are set to the cloud recommended values for databases with 'Customer Managed Keys'.
- Cloud Software Library Management:
 - Revamped software library download of artifacts through imageTags. It is recommended to use imageTags to download the database and grid software images.
 For details, see dbaascli cswlib showimages and dbaascli cswlib download help
- Included AHF version 21.4.2
- Various bug fixes and stability improvements

Release 21.4.1.1.0

- Enabled encryption of the system level tablespaces (SYSTEM, SYSAUX, UNDO, and TEMP) for databases that will get created with this version of dbaastools onwards. This feature is enabled for Oracle Database version 19.6.0.0.0 and above.
- Grid Patching:
 - Prerequisite condition added to check for following file ownership to be owned by grid user.
 - * <gi home>/suptools/tfa/release/tfa home/jlib/jdev-rt.jar
 - * <gi home>/suptools/tfa/release/tfa home/jlib/jewt4.jar
- Database Patching:
 - Simultaneous database move operation is disallowed by default. A new option –
 allowParallelDBMove is introduced that can be used to override the default behavior
 for Oracle Database releases 12.2 and above.
 - Fixed issues related to move of standby databases being in MOUNT mode.
- Database Backup and Recovery:
 - Added new command-line options for database backup. For more details, refer to dbaascli database backup command reference.
 - Added new command-line options for database recovery. For more details, refer to dbaascli database recover command reference.
 - bkup api usage for backup and recovery operations will be deprecated in future.
 - To align with the Oracle recommended practice of using SYSBACKUP administrative privilege for Backup and Recovery operations, cloud automation creates a common administrative user C##DBLCMUSER with SYSBACKUP role at the CDB\$ROOT container level. Backup and Recovery operations are therefore performed with the user having the least required privileges. Credentials for this user are randomly generated and securely managed by cloud automation. If the user is not found or is LOCKED and EXPIRED, then cloud automation will recreate or unlock this user during the backup or



recovery operation. This change in the cloud automation is made starting with dbaastools version 21.4.1.1.0.

- Enhanced dbaascli resume functionality to resume any previous session by specifying the -sessionID <value> argument to the resume command. The session ID is shared in the dbaascli output as well as in the logs.
- Enhanced dbaascli help output to show the command usage.
- Deprecated the usage of dbaascli shell (interactive session). This will be completely unsupported after March 2022. It is recommended to execute complete dbaascli commands on command prompt as suggested in all document examples.
- Included Autonomous Health Framework (AHF) version 21.2.8.
- Various bug fixes and stability improvements.

Release 21.3.1.2.0

- Improved the timing of dbaascli operations with enhanced Control Plane metadata synchronization logic.
- Enhanced dbaascli logs to have millisecond-level information along with the associated thread.
- Introduced more prerequisite checks in database home patching and database move operations to catch potential failures scenarios with suggestions to corrective action.
- Database patching operations now retain the state of the databases to be same as it was prior to patching. For pluggable databases, pdb saved state is honored.
- Various bug fixes and stability improvements.

Release 21.3.1.1.0

- Added support to unlock PDB Admin user account as part of PDB creation, localClone, or remoteClone operation. For details, see option -- lockPDBAdminAccount in dbaascli pdb create --help.
- Fixed an issue that updates the database resource registered with Oracle Grid Infrastructure in existing environments with the correct value of database name.
- Enhanced PDB lifecycle operations.
- Various bug fixes and stability improvements.

Release 21.3.1.0.1

- Support for the following dbaascli commands to be run as oracle user.
 - dbaascli pdb bounce
 - dbaascli pdb close
 - dbaascli pdb connectString
 - dbaascli pdb create



- dbaascli pdb delete
- dbaascli pdb getDetails
- dbaascli pdb list
- dbaascli pdb localClone
- dbaascli pdb open
- dbaascli pdb remoteClone
- Revamped out-of-place patching of database. For details, see dbaascli database move -help.
- Timing related enhancements in Oracle Grid Infrastructure patching workflow. For details, see dbaascli grid patch -help.
- Deprecated the support for exadbcpatchmulti / dbaascli patch for patching operations. The dbaascli dbhome patch and dbaascli grid patch commands are provided for patching operation for database homes and Oracle Grid Infrastructure. Refer to the Patching Oracle Grid Infrastructure and Oracle Database Using dbaascli section for details. Also see, dbaascli Command Reference section.
- Deprecated the support for dbaascli tools patch command to bring consistency in the dbaascli command conventions. The new command is dbaascli admin updateStack. For details, see section *Updating Cloud Tooling using dbaascli*.
- Ability to run <code>dbaascli</code> in disconnected mode for long running operations. Executing <code>dbaascli</code> command with <code>--waitForCompletion</code> false gets you a job ID that can be queried later to get the status of the operation, using <code>dbaascli</code> job <code>getStatus</code> <code>-jobid</code> <code>job_id</code>. This is useful for long running operations where users may want to get the control back immediately after command execution. In this release, this option is available only for <code>dbaascli</code> <code>database</code> <code>create</code> command. More commands will be added in subsequent releases to have this support. The help output for those commands will reflect the support of <code>--waitForCompletion</code> option.
- Deprecated the support for dbaascli shell. It is recommended that users run the complete dbaascli commands on the command prompt as suggested in all the document examples. Execution of just dbaascli will show the output of its usage help instead of entering into a dbaascli shell.
- Various bug fixes and stability improvements.

Release 21.2.1.x.x

- Redesigned Oracle Grid Infrastructure patching operation and added ability to resume from failed point, patch on subset of nodes, instance draining, and other enhancements. For details, see <code>dbaascli grid patch --help</code>. Also refer to the Patching Oracle Grid Infrastructure and Oracle Database Using dbaascli section.
- Deprecated the support for exadbcpatchmulti / dbaascli patch for patching operations. dbaascli dbhome patch and dbaascli grid patch commands are provided for patching operation for database homes and Oracle Grid Infrastructure. Refer to the Patching Oracle Grid Infrastructure and Oracle Database Using dbaascli section for details. Also see, dbaascli Command Reference section.
- Deprecated the support for dbaascli tools patch command to bring consistency in the command conventions. The new command is dbaascli admin updateStack.



- Redesigned PDB management APIs for create, local clone, and remote clone operations. For details, see dbaascli pdb --help.
- Redesigned database delete API. For details, see dbaascli database delete -help.
- Revamped dbhome creation (support for custom software image, scale-out operation). For details, see dbaascli dbhome create --help.
- Support for database creation on subset of cluster nodes. For details, see dbaascli database create --help.
- Ability to run <code>dbaascli</code> in disconnected mode for long running operations. Executing <code>dbaascli</code> command with <code>--waitForCompletion</code> false gets you a job ID that can be queried later to get the status of the operation, using <code>dbaascli</code> job <code>getStatus -jobid</code> <code>job_id</code>. This is useful for long running operations where users may want to get the control back immediately after command execution. In this release, this option is available only for <code>dbaascli</code> <code>database</code> <code>create</code> command. More commands will be added in subsequent releases to have this support. The help output for those commands will reflect the support of <code>--waitForCompletion</code> option.
- Enhanced dbhome patching experience with introduction of multiple options like skipPDBs, continueWithDowntime, and so on. For details, see dbaascli dbhome patch --help.
- Support for better diagnostic collection. For details, see dbaascli diag collect --help.
- Minor improvements in the area of database upgrade automation.
- · Various bug fixes and stability improvements.

dbaascli Command Reference

Use these commonly used commands to manage Exadata Cloud@Customer.

- dbaascli admin updateStack
 - To install or update a dbaastools RPM, use the dbaascli admin updateStack command.
- dbaascli cpuscale get status
 - To check the status of current or last scale request performed when network connectivity between the Control Plane Server and OCI region is disrupted, use the dbaascli cpuscale get status command.
- · dbaascli cpuscale update
 - To scale up or down the CPU core count for a virtual machine in a VM cluster when network connectivity between the Control Plane Server and OCI region is disrupted, use the <code>dbaascli cpuscale update command</code>.
- dbaascli cswlib download
 - To download available software images and make them available in your Exadata Database Service on Cloud@Customer environment, use the dbaascli cswlib download command.
- dbaascli cswlib showlmages
 - To view the list of available Database and Grid Infrastructure images, use the dbaascli cswlib showImages command.



dbaascli database backup

To configure Oracle Database with a backup storage destination, take database backups, query backups, and delete a backup, use the dbaascli database backup command.

dbaascli database bounce

To shut down and restart a specified Exadata Database Service on Cloud@Customer database, use the dbaascli database bounce command.

dbaascli database changepassword

To change the password of a specified Oracle Database user, use the <code>dbaascli</code> database <code>changePassword</code> command. When prompted enter the user name for which you want to change the password and then enter the password.

dbaascli database convertToPDB

To convert the specified non-CDB database to PDB, use the <code>dbaascli</code> database <code>convertToPDB</code> command.

dbaascli database create

To create Oracle Database, use the dbaascli database create command. When prompted, enter the sys and tde passwords.

dbaascli database delete

To delete an Oracle Database, use the dbaascli database delete command.

dbaascli database getPDBs

To view the list of all pluggable databases in a container database, use the <code>dbaasclidatabase</code> <code>getPDBs</code> command.

dbaascli database modifyParameters

To modify or reset initialization parameters for an Oracle Database, use the <code>dbaasclidatabase</code> modifyParameters command.

dbaascli database move

To perform out-of-place patching, use the dbaascli database move command.

dbaascli database recover

To recover a database, use the dbaascli database recover command.

dbaascli database runDatapatch

To patch an Oracle Database, use the dbaascli database runDatapatch command.

dbaascli database start

To start an Oracle Database, use the dbaascli database start command.

dbaascli database stop

To stop an Oracle Database, use the dbaascli database stop command.

dbaascli database upgrade

To upgrade an Oracle Database, use the dbaascli database upgrade command.

dbaascli dataguard prepareStandbyBlob

To generate a blob file containing various files that are required on the standby site in case of a dataguard environment, use the <code>dbaascli</code> dataguard <code>prepareStandbyBlob</code> command.

dbaascli dataguard updateDGConfigAttributes

To update Data Guard automation attributes across all the cluster nodes, use the dbaascli dataguard updateDGConfigAttributes command.

dbaascli dbhome create

To create an Oracle Database home of desired version, use the <code>dbaascli</code> <code>dbhome</code> <code>create</code> command.



dbaascli dbHome delete

To delete a given Oracle Database home, use the dbaascli dbHome delete command.

dbaascli dbhome getDatabases

To view information about all Oracle Databases running from a given database Oracle home, use the <code>dbaascli</code> <code>dbHome</code> <code>getDatabases</code> command. Specify either the Oracle home location or Oracle home name.

dbaascli dbHome getDetails

To view information about a specific Oracle home, use the <code>dbaascli dbHome</code> <code>getDetails</code> command. Specify either the Oracle home location or Oracle home name.

dbaascli dbHome patch

To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome</code> patch command.

dbaascli diag collect

To collect diagnostics, use the dbaascli diag collect command.

dbaascli diag healthCheck

To run diagnostic health checks, use the dbaascli diag healthCheck command.

dbaascli grid configureTCPS

To configure TCPS for the existing cluster, use the <code>dbaascli grid configureTCPS command.</code>

dbaascli grid patch

To patch Oracle Grid Infrastructure to the specified minor version, use the dbaascli grid patch command.

dbaascli grid rotateTCPSCert

To rotate TCPS certificates, use the dbaascli grid rotateTCPSCert command.

dbaascli grid upgrade

To upgrade Oracle Grid Infrastrucure from one major version to another, use the dbaascli grid upgrade command.

dbaascli job getStatus

To view the status of a specified job, use the dbaascli job getStatus command.

- dbaascli patch db apply
- dbaascli patch db prereg

dbaascli pdb backup

To backup a pluggable database (PDB), query PDB backups, and delete a PDB backup, use the <code>dbaascli</code> pdb backup command.

dbaascli pdb bounce

To bounce a pluggable database (PDB), use the dbaascli pdb bounce command.

dbaascli pdb close

To close a pluggable database (PDB), use the dbaascli pdb close command.

dbaascli pdb connectString

To display Oracle Net connect string information for a pluggable database (PDB) run the dbaascli pdb connectString command.



dbaascli pdb create

To create a new pluggable database (PDB), use the dbaascli pdb create command.

dbaascli pdb delete

To delete a pluggable database (PDB) run the dbaascli pdb delete command.

dbaascli pdb getDetails

To view details of a pluggable database (PDB), use the <code>dbaascli pdb getDetails</code> command.

dbaascli pdb list

To view the list of pluggable databases (PDB) in a container database, use the <code>dbaasclipdb list command</code>.

dbaascli pdb localClone

To create a new pluggable database (PDB) as a clone of an existing PDB in the same container database (CDB), use the <code>dbaascli pdb localClone</code> command.

dbaascli pdb open

To open a pluggable database (PDB), use the dbaascli pdb open command.

dbaascli pdb recover

To recover a pluggable database (PDB), use the dbaascli pdb recover command.

dbaascli pdb relocate

To relocate the specified PDB from the remote database into local database, use the dbaascli pdb relocate command.

dbaascli pdb remoteClone

To create a new pluggable database (PDB) as a clone of an existing PDB in another container database (CDB), use the dbaascli pdb remoteClone command.

dbaascli system getDBHomes

To view information about all the Oracle homes, use the <code>dbaascli</code> system <code>getDBHomes</code> command.

dbaascli tde addSecondaryHsmKey

To add a secondary HSM (KMS) key to the existing HSM (KMS) configuration, use the dbaascli tde addSecondaryHsmKey command.

dbaascli tde changePassword

To change TDE keystore password as well as DB wallet password for the alias tde_ks_passwd, use the dbaascli tde changePassword command.

dbaascli tde enableWalletRoot

To enable $wallet_root$ spfile parameter for the existing database, use the <code>dbaascli tde enableWalletRoot</code> command.

dbaascli tde encryptTablespacesInPDB

To encrypt all the tablespaces in the specified PDB, use the $\tt dbaascli tde encryptTablespacesInPDB command.$

dbaascli tde fileToHsm

To convert FILE based TDE to HSM (KMS/OKV) based TDE, use the $\tt dbaasclitdefileToHsm$ command.

dbaascli tde getHsmKeys

To get TDE active key details, use the dbaascli tde getHsmKeys command.

dbaascli tde getMkidForKeyVersionOCID

To get Master Key ID associated with the KMS key version OCID, use the ${\tt dbaascli}$ tde ${\tt getMkidForKeyVersionOCID}$ command.



dbaascli tde getPrimaryHsmKey

To get primary HSM (KMS) key from the existing HSM (KMS) configuration, use the dbaascli tde getPrimaryHsmKey command.

dbaascli tde hsmToFile

To convert HSM (KMS/OKV) based TDE to FILE based TDE, use the dbaasclitde hsmToFile command.

dbaascli tde listKeys

To list TDE master keys, use the dbaascli tde listKeys command.

dbaascli tde removeSecondaryHsmKey

To remove secondary HSM (KMS) key from the existing HSM (KMS) configuration, use the dbaascli tde removeSecondaryHsmKey command.

dbaascli tde setKeyVersion

To set the version of the primary key to be used in DB/CDB or PDB, use the dbaascli tde setKeyVersion command.

dbaascli tde setPrimaryHsmKey

To change the primary HSM (KMS) key for the existing HSM (KMS) configuration, use the dbaascli tde setPrimaryHsmKey command.

dbaascli tde status

To display information about the keystore for the specified database, use the dbaascli tde status command.

dbaascli admin updateStack

To install or update a dbaastools RPM, use the dbaascli admin updateStack command.

Prerequisites

Run the command as the root user.

To use the utility, you must connect to an Exadata Database Service on Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli admin updateStack
[--resume]
[--prechecksOnly]
[--nodes]
[--force]
```

Where:

- --resume resumes the previous execution
- --prechecksOnly runs only the prechecks for this operation
- --nodes specifies a comma-delimited list of nodes to install the RPM on. If you do
 not pass this argument, then the RPM will be installed on all of the cluster nodes
- --force forces the installation of a lower RPM version



Example 7-4 dbaascli admin updateStack

```
dbaascli admin updateStack --location /var/opt/oracle/dbaas acfs/
dbaastools exa-1.0-1+MAIN 210507.0125.x86 64.rpm
DBAAS CLI version <version>
Executing command admin updatestack --location /var/opt/oracle/dbaas acfs/
dbaastools exa-1.0-1+MAIN 210507.0125.x86 64.rpm --force
INFO : Review log file => /var/opt/oracle/log/tooling/Update/
Update 2021-05-13 15:30:19.82522522804.log
====== Calling RPM update plugin =======
Loading PILOT...
Session ID of the current execution is: 93
Log file location: /var/opt/oracle/log/tooling/Update/
pilot 2021-05-13 03-30-21-PM
_____
Running Plugin initialization job
Completed Plugin initialization job
Running Default value initialization job
Completed Default_value_initialization job
Running Rpm version validation job
Completed Rpm version validation job
Running Rpm source validation job
Completed Rpm_source_validation job
_____
Running Disk space validate job
Completed Disk space validate job
_____
Running Rpm_download job
Completed Rpm download job
Running Rpm validation job
Running Rpm local installation job
Completed Rpm local installation job
Running Rpm remote installation job
Completed Rpm remote installation job
_____
Running Installed rpm backup job
Completed Installed rpm backup job
_____
Running Rpm cleanup job
Completed Rpm cleanup job
====== Calling exacloud config plugin =======
Loading PILOT...
Session ID of the current execution is: 94
Log file location: /var/opt/oracle/log/tooling/Update/
pilot 2021-05-13 03-31-07-PM
_____
Running Plugin initialize job
Completed Plugin initialize job
```



```
Running Validate grid job
Completed Validate grid job
_____
Running Validate setup scripts job
_____
Running Setup journal service job
-----
Running Setup users job
Completed Setup users job
_____
Running Create sudoers job
_____
Running TTY setup job
_____
Running Setup atp file handlers job
-----
Running Mount_atp_huge_pages job
Running Setup huge pages job
-----
Running Setup_rc_local job
-----
Running Update u02 ownership job
_____
Running Setup clean db logs cron job job
_____
Running Remove rpm update cron entries job
Completed Remove rpm update cron entries job
_____
Running Setup backup cron entries job
Completed Setup_backup_cron_entries job
_____
Running Setup acfs symlinks job
_____
Running Create acfs volume job
-----
Running Add oracle user to acfs resource job
Completed Add oracle_user_to_acfs_resource job
_____
Running Setup db agent wallet job
-----
Running Setup tcps wallet job
-----
Running Setup image encryption wallet job
Completed Setup image encryption wallet job
_____
Running Setup bashrc job
-----
Running Pin cluster nodes job
_____
Running Setup sys asmsnmp password job
-----
Running Configure network security job
_____
Running Setup tcps listeners job
```



```
_____
Running Populate grid creg job
Running Upgrade ahf job
Completed Upgrade ahf job
_____
Running Setup python job
Completed Setup python job
-----
Running Setup mysql job
Completed Setup mysql job
Running Enable SQL patch update job
Running Update ADBD listener configuration job
_____
Running Setup_ovm_templates job
-----
Running Synchronize config files job
Completed Synchronize config files job
Running Disable auto rpm update job
Completed Disable auto rpm update job
_____
Running Remove wget rpm job
Completed Remove wget rpm job
Running Toggle cleandb logs job
Completed Toggle cleandb logs job
-----
Running Setup backup assistant job
Completed Setup backup assistant job
Running Clean duplicate images job
Completed Clean duplicate images job
_____
Running Update sql net ora file job
Completed Update sql net ora file job
______
Running Update db env file job
Completed Update db env file job
Running Setup backup json metastore job
```

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli cpuscale get status

To check the status of current or last scale request performed when network connectivity between the Control Plane Server and OCI region is disrupted, use the dbaascli cpuscale get_status command.

Prerequisites

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

Displays various command execution states as it progresses from scheduled, running, and finally to success or failure.

dbaascli cpuscale get status

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli cpuscale update

To scale up or down the CPU core count for a virtual machine in a VM cluster when network connectivity between the Control Plane Server and OCI region is disrupted, use the dbaascli cpuscale update command.

To scale OCPUs up or down in a VM cluster in disconnected mode, run the <code>dbaascli</code> <code>cpuscale</code> update and <code>dbaascli</code> <code>cpuscale</code> <code>get_status</code> commands from any node inside a VM cluster to change the CPU core count for that cluster. If you have more than one VM cluster, then run a separate command from any node inside each VM cluster you want to scale up or down. These commands are designed to not work if issued during the normal connected mode and will time out after 600 seconds (10 minutes).

Prerequisites

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.



Syntax

Exadata Database Service on Cloud@Customer is considered to be in a **Disconnected** mode when there is a loss of connectivity with the DBaaS control plane running on Oracle Cloud Infrastructure (OCI).

```
dbaascli cpuscale update
--coreCount coreCount
--message message
```

Where:

- --coreCount specifies the number of CPUs that you want to scale up or down per VM in a cluster
- --message optionally, you can include a message for your reference

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli cswlib download

To download available software images and make them available in your Exadata Database Service on Cloud@Customer environment, use the dbaascli cswlib download command.

Prerequisites

Run the command as the root user.

To use the utility, you must connect to an Exadata Database Service on Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli cswlib download --version | --imageTag
[--product]
```

Where:

- --version specifies an Oracle home image version
- --imageTag specifies the image tag of the image
- --product specifies the image type. Valid values: database or grid

Example 7-5 dbaascli cswlib download --product --imageTag

```
[root@dg11lrg1 dbimage]# dbaascli cswlib download --product database --
imageTag 19.14.0.0.0

DBAAS CLI version <version>
Executing command cswlib download --product database --imageTag 19.14.0.0.0
Job id: 7da37d44-4a6f-4f8b-bc61-e82a5c68eb27
```



```
Image location=/var/opt/oracle/dbaas_acfs/dbnid/19.14.0.0.0
Download succeeded
Log file location: /var/opt/oracle/log/cswLib/download/
dbaastools_2022-05-12_03-54-05-PM_57011.log
dbaascli execution completed
```

Example 7-6 dbaascli cswlib download --version 19.9.0.0.0

```
[root@dg11lrg1 dbimage]# dbaascli cswlib download --product database --
imageTag 19.14.0.0.0

DBAAS CLI version <version>
Executing command cswlib download --product database --imageTag
19.14.0.0.0

Job id: 7da37d44-4a6f-4f8b-bc61-e82a5c68eb27

Image location=/var/opt/oracle/dbaas_acfs/dbnid/19.14.0.0.0

Download succeeded
Log file location: /var/opt/oracle/log/cswLib/download/
dbaastools_2022-05-12_03-54-05-PM_57011.log
dbaascli execution completed
```

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli cswlib showImages

To view the list of available Database and Grid Infrastructure images, use the dbaascli cswlib showImages command.

Run the command as the root user.

Syntax

```
cswlib showImages
[--product]
```

Where:

--product identifies Oracle home product type. Valid values: database or grid.

Example 7-7 dbaascli cswlib showlmages



#############

```
17.IMAGE TAG=18.17.0.0.0
  VERSION=18.17.0.0.0
   DESCRIPTION=18c JAN 2022 DB Image
18.IMAGE TAG=19.10.0.0.0
  VERSION=19.10.0.0.0
   DESCRIPTION=19c JAN 2021 DB Image
19.IMAGE TAG=19.11.0.0.0
  VERSION=19.11.0.0.0
   DESCRIPTION=19c APR 2021 DB Image
20.IMAGE TAG=19.12.0.0.0
 VERSION=19.12.0.0.0
  DESCRIPTION=19c JUL 2021 DB Image
21.IMAGE TAG=19.13.0.0.0
 VERSION=19.13.0.0.0
 DESCRIPTION=19c OCT 2021 DB Image
Images can be downloaded using their image tags. For details, see help using
'dbaascli cswlib download --help'.
dbaascli execution completed
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database backup

To configure Oracle Database with a backup storage destination, take database backups, query backups, and delete a backup, use the dbaascli database backup command.

Prerequisite

Run the command as the root user.

Syntax



Where:

```
--dbname: Oracle Database name.
--list | --start | --delete | --status | --getBackupReport | --configure |
--getConfig
--list: Returns database backup information.
    [--json: Specify the file name for JSON output.]
--start: Begins database backup.
       [--level0 | --level1 | --archival]
       [--level0: Creates a Level-0 (full) backup. ]
       [--level1: Creates a Level-1 (incremental) backup. ]
       [--archival: Creates an Archival full backup. ]
            -- tag: Specify backup tag.
--delete: Deletes Archival backup.
           --backupTag <value>
--status
           --uuid <value>
--getBackupReport: Returns backup report.
           --tag: Specify backup tag.
           -- json: Specify the file name for JSON output.
--configure: Configures database for backup.
           --configFile | --enableRTRT | --disableRTRT
           --configFile: Specify database backup configuration file.
           --enableRTRT: Enable Real Time Redo Transport.
           --disableRTRT: Disable Real Time Redo Transport.
--getConfig: Returns database backup configuration.
            [--configFile: Specify database backup configuration file.]
```

Note:

enablertrt and disablertrt are applicable only for ZDLRA backup destination on Exadata Database Service on Cloud@Customer.

Example 7-8 Examples

To get backup configuration for a database myTestDB:

```
dbaascli database backup --dbName myTestDB --getConfig --
configFile /tmp/configfile 1.txt
```



 To set backup configuration for a database myTestDB by modifying the config file with configuration details:

```
dbaascli database backup --dbName myTestDB --configure --configFile /tmp/configfile\_1\_modified.txt
```

To take backup of the database myTestDB:

```
dbaascli database backup --dbName myTestDB --start
```

 To query the status of backup request submitted with uuid 58fdcae0bd1c11eb92bc020017075151:

```
dbaascli database backup --dbName myTestDB --status --uuid 58fdcae0bd1c11eb92bc020017075151
```

To enable RTRT for the database myTestDB:

```
dbaascli database backup --dbName myTestDB --configure -enableRTRT
```

dbaascli database bounce

To shut down and restart a specified Exadata Database Service on Cloud@Customer database, use the dbaascli database bounce command.

Prerequisites

Run the command as the oracle user.

Syntax

```
dbaascli database bounce
[--dbname][--rolling <value>]
```

Where:

- --dbname specifies the name of the database
- --rolling specifies true or false to bounce the database in a rolling manner. Default value is false.

The command performs a database shutdown in immediate mode. The database is then restarted and opened. In Oracle Database 12c or later, all of the PDBs are also opened.

Example 7-9 dbaascli database bounce

dbaascli database bounce --dbname dbname



dbaascli database changepassword

To change the password of a specified Oracle Database user, use the <code>dbaascli</code> database <code>changePassword</code> command. When prompted enter the user name for which you want to change the password and then enter the password.

Prerequisites

Run the command as the root or oracle user.

Syntax

```
dbaascli database changePassword [--dbname <value>] [--user <value>]
{
    [--prepareStandbyBlob <value> [--blobLocation <value>]] | [--
standbyBlobFromPrimary <value>]
}
[--resume [--sessionID <value>]]
```

Where:

- --dbname specifies the name of the Oracle Database that you want to act on
- --user specifies the user name whose password change is required
- --prepareStandbyBlob specifies true to generate a blob file containing the artifacts needed to change the password in a Data Guard environment. Valid values: true|false
- --blobLocation specifies the custom path where blob file will be generated
- --standbyBlobFromPrimary specifies the standby blob file, which is prepared from the primary database
- --resume specifies to resume the previous execution
 - --sessionID specifies to resume a specific session ID

Example 7-10 dbaascli database changePassword

dbaascli database changepassword --dbname db19

dbaascli database convertToPDB

To convert the specified non-CDB database to PDB, use the dbaascli database convertToPDB command.

Syntax



```
[--targetPDBName <value>] [--waitForCompletion <value>] [--resume [--sessionID <value>]]
```

Where:

- --dbname specifies the name of Oracle Database
- --cdbName specifies the name of the target CDB in which the PDB will be created. If the CDB does not exist, then it will be created in the same Oracle home as the source non-CDB
- --executePreregs specifies to run only the pre-conversion checks
- --copyDatafiles specifies to create a new copy of the data files instead of using the ones from the source database
- --backupPrepared flag to acknowledge that a proper database backup is in place for the non-CDB prior to performing the conversion to PDB
- --targetPDBName specifies the name of the PDB that will be created as part of the operation
- --waitForCompletion specifies false to run the operation in the background. Valid values: true|false
- --resume specifies to resume the previous execution
 - --sessionID specifies to resume a specific session ID

Example 7-11 dbaascli database convertToPDB

To run pre-conversion prechecks:

```
dbaascli database convertToPDB --dbname ndb19 --cdbname cdb19 --backupPrepared --executePrereqs
```

To run a full conversion with a copy of the data files from the non-CDB:

```
dbaascli database convertToPDB --dbname tst19 --cdbname cdb19 --copyDatafiles
```

dbaascli database create

To create Oracle Database, use the <code>dbaascli</code> database <code>create</code> command. When prompted, enter the <code>sys</code> and <code>tde</code> passwords.

Use this command to create Oracle Database version 12.1.0.2 or higher with the release update JAN 2021 or higher. For databases with lower versions, it is recommended to use the OCI Console based API.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.



Syntax

```
dbaascli database create --dbName --oracleHome | --oracleHomeName
[--dbSID]
[--dbNCharset]
[--tdeConfigMethod]
[--kmsKeyOCID]
[--nodeList]
[--executePrereqs | --skipPrereqs]
[--dbLanguage]
[--dbTerritory]
[--fraDestination]
[--fraSizeInMB]
[--resume]
[--dbUniqueName]
[--revert]
[--dbCharset]
[--honorNodeNumberForInstance]
[--waitForCompletion]
[--sgaSizeInMB]
[--pdbName]
[--pdbAdminUserName]
[--datafileDestination]
[--pgaSizeInMB]
[--createAsCDB]
```

Where:

- --dbname specifies the name of the database
- --oracleHome specifies the location of the Oracle home
- --oracleHomeName specifies the name of the Oracle home
- --dbSID specifies the SID of the database
- --dbNCharset specifies database national character set
- --tdeConfigMethod specifies TDE configuration method. Valid values: FILE, KMS
- --kmsKeyOCID specifies KMS key OCID to use for TDE. This is applicable only if KMS is selected for TDE
- --nodeList specifies a comma-delimited list of nodes for the database
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values: yes or no
- --skipPrereqs specifies yes to skip the prereqs for this operation. Valid values:
 yes or no
- --dbLanguage specifies the database language
- --dbTerritory specifies the database territory
- --fraDestination specifies ASM disk group name to use for database Fast Recovery Area
- --fraSizeInMB specifies the Fast Recovery Area size value in megabyte unit



- --resume resumes the previous execution
- --dbUniqueName specifies database unique name
- --revert rolls back the previous run
- --dbCharset specifies database character set
- --honorNodeNumberForInstance specifies true or false to indicate instance name to be suffixed with the cluster node numbers. Default value: true
- --waitForCompletion specifies false to run the operation in the background. Valid values: true or false
- --sgaSizeInMB specifies the sga target value in megabyte unit
- --pdbName specifies the name of the PDB
- --pdbAdminUserName specifies the PDB admin user name
- --datafileDestination specifies the ASM disk group name to use for database datafiles
- --pgaSizeInMB specifies the pga aggregate target value in megabyte unit
- --createAsCDB specifies true or false to create the database as CDB or non-CDB

Example 7-12 dbaascli database create

```
dbaascli database create --dbName db19 --oracleHomeName myhome19 --dbSid db19sid --nodeList node1,node2 --createAsCDB true
```

Related Topics

Connecting to a Virtual Machine with SSH
You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database delete

To delete an Oracle Database, use the dbaascli database delete command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli database delete --dbname
[--deleteArchiveLogs]
[--deleteBackups]
[--precheckOnly]
[--waitForCompletion]
```

Where:



- --dbname specifies the name of the database.
- --deleteArchiveLogs specifies true or false to indicate deletion of database archive logs.
- --deleteBackups specifies true or false to indicate deletion of database backups.
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values: yes or no.
- --waitForCompletion specifies false to run the operation in the background.
 Valid values: true or false.

Example 7-13 dbaascli database delete

```
dbaascli database delete --dbname db19
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database getPDBs

To view the list of all pluggable databases in a container database, use the <code>dbaasclidatabase</code> getPDBs command.

Run the command as the root or oracleuser.

Syntax

```
dbaascli database getPDBs --dbname <value>
```

Where:

--dbname specifies the name of the container database

Example 7-14 dbaascli database getPDBs --dbname



```
"nodeName" : "node1",
      "openMode" : "READ WRITE"
    } ,
    "node2" : {
     "nodeName" : "node2",
      "openMode" : "READ WRITE"
  },
  "pdbConnectStrings" : [ {
    "serviceName" : "service name",
    "connectString" : "connect_string"
  "pdbSize" : "4GB",
  "pdbUsedSize" : "1GB"
}, {
  "pdbName" : "PDB1 RO",
  "pdbUID" : "2745723926",
 "cpuCount" : null,
 "storageAllocated" : "UNLIMITED",
  "storageUsed" : "4448MB",
  "guid": "DD9EEA40A3DED7DEE053FD00000ABB27",
  "dbid": "2745723926",
  "conId" : "4",
  "resourceOCIDSettings" : null,
  "pdbNodeLevelDetails" : {
    "node1" : {
      "nodeName" : "node1",
      "openMode" : "READ ONLY"
    } ,
    "node2" : {
      "nodeName" : "node2",
      "openMode" : "MOUNTED"
   }
  },
  "pdbConnectStrings" : null,
  "pdbSize" : "4GB",
  "pdbUsedSize" : "1GB"
}, {
  "pdbName" : "PDB1_RO_1",
 "pdbUID" : "25959692",
 "cpuCount" : null,
  "storageAllocated" : "UNLIMITED",
  "storageUsed" : "4448MB",
  "guid" : "DDA4C3F0C6FB731FE053FD00000A3523",
  "dbid": "25959692",
  "conId" : "7",
  "resourceOCIDSettings" : null,
  "pdbNodeLevelDetails" : {
    "node1" : {
      "nodeName" : "node1",
      "openMode" : "MOUNTED"
    },
    "node2" : {
      "nodeName" : "node2",
      "openMode" : "MOUNTED"
```

```
}
 "pdbConnectStrings" : null,
 "pdbSize" : "4GB",
 "pdbUsedSize" : "3GB"
}, {
 "pdbName" : "PDB2",
 "pdbUID" : "39259040",
 "cpuCount" : null,
 "storageAllocated" : "UNLIMITED",
 "storageUsed" : "4448MB",
 "guid" : "DDA030AADC3A7E9EE053FD00000ADA57",
 "dbid": "39259040",
 "conId" : "5",
 "resourceOCIDSettings" : null,
 "pdbNodeLevelDetails" : {
   "node1" : {
     "nodeName" : "node1",
      "openMode" : "MOUNTED"
   },
   "node2" : {
     "nodeName" : "node2",
     "openMode" : "READ WRITE"
   }
 },
 "pdbConnectStrings" : [ {
   "serviceName" : "service name",
    "connectString" : "connect string"
 } ],
 "pdbSize" : "4GB",
 "pdbUsedSize" : "3GB"
 "pdbName" : "PDB2 CLONE",
 "pdbUID": "1178852238",
 "cpuCount" : null,
 "storageAllocated" : "UNLIMITED",
 "storageUsed": "4448MB",
 "guid" : "DDA04CED0E4CF791E053FD00000A7AD4",
 "dbid" : "1178852238",
 "conId" : "6",
 "resourceOCIDSettings" : null,
 "pdbNodeLevelDetails" : {
   "node1" : {
     "nodeName" : "node1",
     "openMode" : "READ WRITE"
   },
   "node2" : {
     "nodeName" : "node2",
      "openMode" : "READ WRITE"
 },
 "pdbConnectStrings" : [ {
   "serviceName" : "service name",
   "connectString" : "connect string"
 } ],
```

```
"pdbSize" : "4GB",
  "pdbUsedSize" : "1GB"
} ]
dbaascli execution completed
```

dbaascli database modifyParameters

To modify or reset initialization parameters for an Oracle Database, use the dbaascli database modifyParameters command.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli database modifyParameters --dbname --setParameters | --
resetParameters | --responseFile
[--backupPrepared]
[--instance]
[--allowBounce]
```

Where:

- --dbname specifies the name of the database.
- --setParameters specifies a comma-delimited list of parameters to modify with new values. For example: parameter1=valueA,parameter2=valueB, and so on
- --resetParameters specifies a comma-delimited list of parameters to be reset to their corresponding default values. For example, parameter1=valueA,parameter2=valueB, and so on
- --responseFile specifies the absolute location of the response JSON file to modify the database parameters
- --backupPrepared acknowledges that a proper database backup is in place prior to modifying critical or sensitive parameters.
- --instance specifies the name of the instance on which the parameters will be processed. If not specified, then the operation will be performed at the database level.
- --allowBounce grants permission to bounce the database in order to reflect the changes on applicable static parameters.

Example 7-15 dbaascli database modifyParameters

```
dbaascli database modify
Parameters --dbname dbname --set
Parameters "log archive dest state 17=ENABLE"
```



dbaascli database move

To perform out-of-place patching, use the dbaascli database move command.

Prerequisites

- Before performing a move operation, ensure that all of the database instances associated with the database are up and running.
- Run the command as the root user.

Syntax

```
dbaascli database move --oracleHome | --oracleHomeName
--dbname
[--resume]
        [--sessionID]
[--skipPDBs]
[--continueWithDbDowntime]
[--allowParallelDBMove]
[--rollback]
[--skipDatapatch]
[--skipClosedPDBs]
[--executePrereqs]
```

Where:

- database move moves the database from one home to another home
- --oracleHome specifies Oracle home path
- --oracleHomeName specifies the name of Oracle home
- --dbname specifies the name of the database
- --resume resumes the previous run
 - --sessionID specifies to resume a specific session ID
- --skipPdbs skips running the datapatch on a specified comma-delimited list of PDBs. For example: pdb1,pdb2...
- --continueWithDbDowntime continues patching with database downtime. This option can be used in environments wherein there is only one active instance up and the patching operation can be continued even with a downtime.
- --allowParallelDBMove allows database move in parallel.
- --rollback rolls back the patches applied
- --skipDatapatch skips datapatch execution on the databases
- --skipClosedPDBs skips running datapatch on closed PDBs
- --executePrereqs runs prereqs



Example 7-16 dbaascli database move

dbaascli database move --dbname testdb1 --oracleHome /u02/app/oracle/product/12.1.0/dbhome 2

dbaascli database recover

To recover a database, use the dbaascli database recover command.

Prerequisite

- Run the command as the root user.
- Database must have been configured with backup storage destination details where backups are stored.

Syntax

Where:

Example 7-17 Examples

To recover the database myTestDb to latest:

```
dbaascli database recover --dbname myTestDb --start --latest
```



• To query the status of recovery request submitted with uuid 2508ea18be2911eb82d0020017075151:

```
dbaascli database recover --dbname myTestDb --status --uuid 2508ea18be2911eb82d0020017075151
```

dbaascli database runDatapatch

To patch an Oracle Database, use the dbaascli database runDatapatch command.

Prerequisites

- Before performing a runDatapatch operation, ensure that all of the database instances associated with the database are up and running.
- Run the command as the root user.

Syntax

```
dbaascli database runDatapatch --dbname
[--resume]
        [--sessionID]
[--skipPdbs | --pdbs]
[--executePrereqs]
[--patchList]
[--skipClosedPdbs]
[--rollback]
```

Where:

- --dbname specifies the name of the database
- --resume resumes the previous run
 - --sessionID specifies to resume a specific session ID
- --skipPdbs skips running the datapatch on a specified comma-delimited list of PDBs. For example: pdb1,pdb2...
- --pdbs runs the datapatch only on a specified command-delimited list of PDBs. For example: pdb1,pdb2...
- --executePreregs runs prerequisite checks
- --patchList applies or rolls back the specified comma-delimited list of patches.
 For example: patch1,patch2...
- --skipClosedPdbs skips running the datapatch on closed PDBs
- --rollback rolls back the patches applied

dbaascli database runDatapatch --dbname db19



dbaascli database start

To start an Oracle Database, use the dbaascli database start command.

Prerequisites

Run the command as the root user.

Syntax

```
dbaascli database start
[--dbname]
[--mode]
```

Where:

- --dbname specifies the name of the database
- --mode specifies mount or nomount to start database in the corresponding mode

The command starts and opens the database. In Oracle Database 12c or later, all of the PDBs are also opened.

Example 7-18 dbaascli database start

```
dbaascli database start --dbname dbname --mode mount
```

dbaascli database stop

To stop an Oracle Database, use the dbaascli database stop command.

Prerequisites

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli database stop
[--dbname]
[--mode]
```

Where:

- --dbname specifies the name of the database that you want to stop
- --mode specifies the mode of the database. Valid values: abort, immediate, normal, transactional

The command performs a database shutdown in immediate mode. No new connections or new transactions are permitted. Active transactions are rolled back, and all connected users are disconnected.



Example 7-19 dbaascli database stop

```
dbaascli database stop --dbname db19
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli database upgrade

To upgrade an Oracle Database, use the dbaascli database upgrade command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli database upgrade --dbname --targetHome | --targetHomeName
[--standBy | --allStandbyPrepared]
[--removeGRP]
[--increaseCompatibleParameter]
[--executePrereqs | --postUpgrade | --revert]
[--upgradeOptions]
```

Where:

- --dbname (mandatory) specifies the name of the database.
- --targetHome specifies the target Oracle home location
- --targetHomeName specifies the name of the target Oracle Database home
- --standBy use this option to upgrade standby databases in Data Guard configurations
- --allStandbyPrepared required for Data Guard configured primary databases.
 Flags to acknowledge that all the required operations are performed on the standby databases prior to upgrading primary database
- --removeGRP automatically removes the Guaranteed Restore Point (GRP) backup only if the database upgrade was successful
- --increaseCompatibleParameter automatically increases the compatible
 parameter as part of the database upgrade. The parameter will get increased only
 if the database upgrade was successful
- --executePrereqs runs only the preupgrade checks
- --postUpgrade use this option if postupgrade fails and needs to rerun the postupgrade steps
- --revert reverts an Oracle Database to its original Oracle home



--upgradeOptions use this option to pass DBUA-specific arguments to perform the
Oracle Database upgrade. Refer to the corresponding Oracle documentation for the
supported arguments and options.

Example 7-20 dbaascli database upgrade pre-upgrade requisite checks

dbaascli database upgrade --dbbname dbname --targetHome Target Oracle home location --executePrereqs

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli dataguard prepareStandbyBlob

To generate a blob file containing various files that are required on the standby site in case of a dataguard environment, use the dbaascli dataguard prepareStandbyBlob command.

Run the command as the root or oracle user.

Syntax

dbaascli dataguard prepareStandbyBlob --dbname <value> --blobLocation <value>

Where:

- --dbname specifies the Oracle Database name
- --blobLocation specifies the custom path where the blob file will be generated

dbaascli dataguard updateDGConfigAttributes

To update Data Guard automation attributes across all the cluster nodes, use the <code>dbaasclidataguard updateDGConfigAttributes command</code>.

Run the command as the root or oracleuser.

Syntax

dbaascli dataguard updateDGConfigAttributes --attributes <value>

Where:

--attributes contains the Data Guard automation attributes that are to be modified.
 Accepts comma-delimited values in the format <attribute=value>. Attributes must be predefined in the Data Guard configuration file.



dbaascli dbhome create

To create an Oracle Database home of desired version, use the dbaascli dbhome create command.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli dbhome create --version
[--oracleHome]
[--oracleHomeName]
[--enableUnifiedAuditing]
[--imageTag]
```

Where:

- --version specifies the version of Oracle Home specified as five numeric segments separated by periods, for example, 19.12.0.0.0
- --oracleHome specifies the location of Oracle home
- --oracleHomeName specifies user-defined Oracle home name. If not provided, then
 the default name will be used
- --enableUnifiedAuditing specifies true or false to enable or disable unified auditing link option in Oracle home
- --imageTag specifies Oracle home image tag

Example 7-21 dbaascli dbhome create

```
dbaascli dbhome create --version 19.11.0.0.0
```

Alternatively, dbaascli dbhome create --version 19.8.0.0.0.0 --imageTag 19.8.0.0.0 for cases where image tags are different from version.

dbaascli dbHome delete

To delete a given Oracle Database home, use the dbaascli dbHome delete command.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli dbHome delete
{ --oracleHome <value>
| --oracleHomeName <value> } [--resume [--sessionID <value>]]
```



Where:

- --oracleHome specifies the location of the Oracle home
- --oracleHomeName specifies the name of the Oracle home
- --resume resumes the previous execution
 - --sessionID specifies to resume a specific session ID

dbaascli dbhome getDatabases

To view information about all Oracle Databases running from a given database Oracle home, use the dbaascli dbHome getDatabases command. Specify either the Oracle home location or Oracle home name.

Run the command as the root user.

Syntax

```
dbaascli dbHome getDatabases
{ --oracleHomeName value | --oracleHome value }
```

Where:

- --oracleHomeName specifies user-defined Oracle home name
- --oracleHome specifies the location (path) of Oracle home

Example 7-22 dbaascli dbHome getDatabases -- oracleHome

```
dbaascli dbHome getDatabases --oracleHome /u02/app/mar home/
DBAAS CLI version MAIN
Executing command dbHome getDatabases --oracleHome /u02/app/mar home/
Job id: 88f67e73-b58f-4e8c-98ee-f04ab1912b76
  "apr db1" : {
    "id" : "3d780f2f-463f-4143-acf0-ce2821dcf452",
    "dbSyncTime" : 0,
    "createTime" : 1650931200000,
    "updateTime" : 0,
    "dbName" : "apr db1",
    "dbUniqueName" : "apr db1",
    "dbDomain" : "db domain",
    "dbId" : 2144585177,
    "cpuCount": 4,
    "sgaTarget" : "3808MB",
    "pgaAggregateTarget": "2500MB",
    "dbSize" : "68GB",
    "dbUsedSize" : "22GB",
    "totalFraSize" : "300GB",
    "fraSizeUsed" : "20GB",
    "dbKmsKeyOcid" : null,
    "isCDB" : true,
    "dbRole" : "PRIMARY",
    "dbType" : "RAC",
    "dbClass" : "OLTP",
```



```
"dbEdition" : "EE",
"dgEnabled" : false,
"patchVersion" : "19.13.0.0.0",
"resourceOCIDSettings" : null,
"dbCharacterSet" : {
  "characterSet" : "AL32UTF8",
  "nlsCharacterset" : "AL16UTF16",
  "dbTerritory" : "AMERICA",
  "dbLanguage" : "AMERICAN"
},
"dbNodeLevelDetails" : {
  "node1" : {
    "nodeName" : "node1",
    "instanceName" : "apr db11",
   "version" : "19.13.0.0.0",
    "homePath": "/u02/app/mar home/",
    "status" : "OPEN"
  },
  "node2" : {
    "nodeName" : "node2",
    "instanceName" : "apr db12",
    "version" : "19.13.0.0.0",
    "homePath": "/u02/app/mar home/",
    "status" : "OPEN"
  }
},
"pdbs" : {
  "PDB1" : {
    "pdbName" : "PDB1",
    "pdbUID" : "1829689132",
    "cpuCount" : null,
    "storageAllocated" : "UNLIMITED",
    "storageUsed" : "4448MB",
    "guid": "DD8C9D580C2A2645E053FD00000A5150",
    "dbid": "1829689132",
    "conId" : "3",
    "resourceOCIDSettings" : null,
    "pdbNodeLevelDetails" : {
      "node1" : {
        "nodeName" : "node1",
        "openMode" : "READ WRITE"
      "node2" : {
        "nodeName" : "node2",
        "openMode" : "READ WRITE"
      }
    },
    "pdbConnectStrings" : [ {
      "serviceName" : "service name",
      "connectString" : "connect string"
    } ],
    "pdbSize" : "4GB",
    "pdbUsedSize" : "1GB"
  },
},
```

```
"messages" : [ ]
}
dbaascli execution completed
```

dbaascli dbHome getDetails

To view information about a specific Oracle home, use the <code>dbaascli dbHome getDetails</code> command. Specify either the Oracle home location or Oracle home name.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli dbHome getDetails
{ --oracleHomeName value | --oracleHome value }
```

Where:

- --oracleHomeName specifies user-defined Oracle home name
- --oracleHome specifies the location of Oracle home

Example 7-23 dbaascli dbHome getDetails - using Oracle home location

```
dbaascli dbHome getDetails --oracleHome /u02/app/home db19c/
DBAAS CLI version MAIN
Executing command dbHome getDetails --oracleHome /u02/app/home db19c/
Job id: b6cba89f-ffd3-4db8-9f11-2aa82985f0d9
  "homePath" : "/u02/app/home db19c",
  "homeName" : "home db19c",
  "version" : "19.0.0.0.0",
  "createTime" : 1645708761000,
  "updateTime" : 1645708761000,
  "ohNodeLevelDetails" : {
    "node1" : {
      "nodeName" : "node1",
      "version" : "19.13.0.0.0"
    },
    "node2" : {
      "nodeName" : "node2",
      "version" : "19.13.0.0.0"
  },
  "messages" : [ ]
dbaascli execution completed
```



Example 7-24 dbaascli dbHome getDetails - using Oracle home name

```
dbaascli dbHome getDetails --oracleHomeName home db19c
DBAAS CLI version MAIN
Executing command dbHome getDetails --oracleHomeName home db19c
Job id: 8131116c-5299-4b25-b573-1bb92b093501
  "homePath" : "/u02/app/home_db19c",
  "homeName" : "home db19c",
  "version" : "19.0.0.0.",
  "createTime" : 1645708761000,
  "updateTime" : 1645708761000,
  "ohNodeLevelDetails" : {
    "node1" : {
      "nodeName" : "node1",
      "version" : "19.13.0.0.0"
    },
    "node2" : {
      "nodeName" : "node2",
      "version" : "19.13.0.0.0"
    }
  },
  "messages" : [ ]
dbaascli execution completed
```

dbaascli dbHome patch

To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome</code> patch command.

Prerequisite

Run the command as the root user.

Syntax

Where:



- --oracleHome specifies the path of Oracle home
- --oracleHomeName specifies the name of Oracle home
- --targetVersion specifies the target version of Oracle Home specified as five numeric segments separated by periods (e.g. 19.12.0.0.0).
- --resume resumes the previous run
 - --sessionID specifies to resume a specific session ID
- --continueWithDbDowntime continues patching with database downtime. This option can
 be used in environments wherein there is only one active instance up and the patching
 operation can be continued even with a downtime.
- --skipUnreachableNodes skips operation on unreachable nodes
- --nodes specifies a comma-delimited list of nodes if patching has to be performed on a subset of nodes
- --executePrereqs runs prereqs
- --skipDatapatch skips running datapatch on the databases
- --imageLocation specifies custom location for database image
- --skipPDBs skips running the datapatch on a specified comma-delimited list of PDBs. For example: cdb1:pdb1,cdb2:pdb2, and so on
- --skipClosedPdbs skips running datapatch on closed PDBs
- --rollback rolls back patched Oracle home.

Example 7-25 dbaascli dbhome patch

dbaascli dbhome patch --targetVersion 19.10.0.0.0 --oracleHome /u02/app/oracle/product/19.0.0.0/dbhome 2

dbaascli diag collect

To collect diagnostics, use the dbaascli diag collect command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli diag collect
[--destLocation]
[--nodes]
[--components]
[--objectStoreBucketURI]
[--startTime]
[--dbNames]
[--endTime]
```



Where:

- --destLocation specifies the location on domU to collect logs.
 Default: /var/opt/oracle/dbaas acfs
- --nodes specifies a comma-delimited list of nodes to collect logs
- --components specifies a list of components for log collection. Valid values: db, gi, os, dbaastools, all
- --objectStoreBucketURI specifies OSS PAR URL to upload log collections
- --startTime specifies the start time for log collection. Valid date and time format:
 YYYY-MM-DDTHH24:MM:SS
- --dbNames specifies the database name for which to collect logs. You can specify only one database name.
- --endTime specifies the end time for log collection. Valid date and time format:
 YYYY-MM-DDTHH24:MM:SS

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli diag healthCheck

To run diagnostic health checks, use the dbaascli diag healthCheck command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli diag healthCheck
[--destLocation]
[--nodes]
[--objectStoreBucketURI]
```

Where:

- --destLocation specifies the location on domU to collect logs.
 Default: /var/opt/oracle/dbaas acfs
- --nodes specifies a comma-delimited list of nodes to collect logs
- --objectStoreBucketURI specifies OSS PAR URL to upload log collection

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli grid configureTCPS

To configure TCPS for the existing cluster, use the <code>dbaascli grid configureTCPS</code> command.

Prerequisite

Run the command as the root user.

Syntax



By default, TCPS is enabled for databases on Oracle Exadata Database Service on Dedicated Infrastructure systems.

Note:

TCPS is not enabled for databases on Exadata Database Service on Cloud@Customer systems. To enable TCPS for a given database, update the database specific sqlnet.ora file with WALLET_LOCATION = (SOURCE=(METHOD=FILE) (METHOD_DATA=(DIRECTORY=/var/opt/oracle/dbaas_acfs/grid/tcps_wallets))) on all database nodes and then bounce the database. This will enable TCPS usage for the database. However, enabling TCPS will cause ZDLRA connection to fail. On Exadata Database Service on Cloud@Customer systems, you can enable either ZDLRA or TCPS configuration. Enabling both ZDLRA and TCPS simultaneously will not work.

```
dbaascli grid configureTCPS
[--pkcs12WalletPath]
[--caCertChain]
[--precheckOnly]
[--serverCert]
[--privateKey]
[--certType]
[--privateKeyPasswordProtected]
```

- --pkcs12WalletPath specifies the path of the certificate, which is in pkcs12 wallet format
- --caCertChain concatenated list of certs, containing intermediate CA's and root CA certs
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values: yes or no.
- --serverCert specifies the path of PEM certificate to use or rotate for TCPS configuration.
- --privateKey specifies the path of the private key file of the certificate.
- --certType type of the cert to be added to the Grid Infrastructure wallet. Accepted values are: SELF SIGNED CERT, CA SIGNED CERT, or PKCS12 CERT. Default: SELF SIGNED CERT



• --privateKeyPasswordProtected specifies if the private key is password protected or not. Valid values: true or false. Default: true.

Example 7-26 dbaascli grid configureTCPS

To configure grid using self-signed certificate:

```
dbaascli grid configureTCPS
```

To configure grid using CA-signed certificate:

```
dbaascli grid configureTCPS --cert_type CA_SIGNED_CERT --
server_cert /tmp/certs/server_cert.pem --ca_cert_chain /tmp/certs/
ca.pem --private_key /tmp/certs/encrypted_private.key --
private_key_password_protected false
```

dbaascli grid patch

To patch Oracle Grid Infrastructure to the specified minor version, use the <code>dbaascligrid</code> patch command.

Prerequisites

Run the command as the root user.

Syntax

- grid patch patches the Grid Infrastructure to the specified minor version
- --targetVersion specifies the target version of Oracle Home specified as five numeric segments separated by periods (e.g. 19.12.0.0.0)
- --containerURL specifies custom URL for fetching Grid Infrastructure image
- --executePrereqs runs prereqs
- --nodeList specifies a comma-delimited list of nodes if patching has to be performed on a subset of nodes
- --rollback rolls back patched Oracle home
- --resume resumes the previous run



- --sessionID specifies to resume a specific session ID
- --continueWithDbDowntime continues patching with database downtime. This option can be used in environments wherein there is only 1 active instance up and the patching operation can be continued even with a downtime.
- --createImage creates an image from a copy of the active Grid home, patched to the specified target version
- --imageLocation specifies the path of the image to be used

Example 7-27 dbaascli grid patch

```
dbaascli grid patch --targetVersion 19.12.0.0.0
```

dbaascli grid rotateTCPSCert

To rotate TCPS certificates, use the dbaascli grid rotateTCPSCert command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli grid rotateTCPSCert
[--pkcs12WalletPath]
[--caCertChain]
[--precheckOnly]
[--serverCert]
[--privateKey]
[--certType]
[--privateKeyPasswordProtected]
```

- --pkcs12WalletPath specifies the path of the certificate, which is in pkcs12 wallet format
- --caCertChain concatenated list of certs, containing intermediate CA's and root CA certs
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values:
 yes or no.
- --serverCert specifies the path of PEM certificate to use or rotate for TCPS configuration.
- --privateKey specifies the path of the private key file of the certificate.
- --certType type of the cert to be added to the Grid Infrastructure wallet. Accepted values
 are: SELF SIGNED CERT, CA SIGNED CERT, or PKCS12 CERT. Default: SELF SIGNED CERT
- --privateKeyPasswordProtected specifies if the private key is password protected or not. Valid values: true or false. Default: true.



Example 7-28 dbaascli grid rotateTCPSCert

To rotate cert using self-signed certificate (default option):

```
dbaascli grid rotateTCPSCert
```

To rotate cert using CA-signed certificate:

```
dbaascli grid rotateTCPSCert --cert_type CA_SIGNED_CERT --
server_cert /tmp/certs/server_cert.pem --ca_cert_chain /tmp/certs/
ca.pem --private_key /tmp/certs/encrypted_private.key --
privateKeyPasswordProtected true
```

Related Topics

• Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli grid upgrade

To upgrade Oracle Grid Infrastrucure from one major version to another, use the dbaascli grid upgrade command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli grid upgrade --version
[--resume]
[--executePrereqs]
[--containerURL]
[--softwareOnly]
[--targetHome]
[--revert]
```

- --version specifies the target version
- --resume resumes the previous run
- --executePrereqs runs prereqs for Grid Infrastrucure upgrade
- --containerUrl specifies the custom URL for fetching Grid Infrastrucure image
- --softwareOnly installs only the Grid Infrastructure software
- --targetHome specifies the path of existing target Grid home
- --revert reverts failed run



Example 7-29 dbaascli grid upgrade

```
daascli grid upgrade --version 19.11.0.0.0 --executePrereqs
DBAAS CLI version MAIN
Executing command grid upgrade --version 19.11.0.0.0 --executePrereqs
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli job getStatus

To view the status of a specified job, use the dbaascli job getStatus command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli job getStatus --jobID
```

Where:

--jodID specifies the job ID

Example 7-30 dbaascli job getStatus

```
dbaascli job getStatus --jobID 13c82031-f202-41b7-9aef-f4a71df0f551
DBAAS CLI version MAIN
Executing command job getStatus --jobID 13c82031-f202-41b7-9aef-f4a71df0f551
{
    "jobId" : "13c82031-f202-41b7-9aef-f4a71df0f551",
    "status" : "Success",
    "message" : "database create job: Success",
    "createTimestamp" : 1628095442431,
    "updatedTime" : 1628095633660,
    "description" : "Service job report for operation database create",
    "appMessages" : {
        "schema" : [],
        "errorAction" : "SUCCEED_AND_SHOW"
    },
    "resourceList" : [],
    "pct_complete" : "100"
}
```



Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli patch db apply



dbaascli patch db prereq and dbaascli patch db apply commands have been deprecated in dbaascli release 21.2.1.2.0, and replaced with dbaascli grid patch, dbaascli dbhome patch, and dbaascli database move commands.

For more information, see:

- dbaascli grid patch
- dbaascli dbhome patch
- dbaascli database move
- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli

Related Topics

dbaascli grid patch

To patch Oracle Grid Infrastructure to the specified minor version, use the dbaascli grid patch command.

dbaascli dbHome patch

To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome</code> patch command.

- · dbaascli database move
 - To perform out-of-place patching, use the dbaascli database move command.
- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli Learn to use the dbaascli utility to perform patching operations for Oracle Grid Infrastructure and Oracle Database on an Exadata Cloud@Customer system.



dbaascli patch db prereq

Note:

dbaascli patch db prereq and dbaascli patch db apply commands have been deprecated in dbaascli release 21.2.1.2.0, and replaced with dbaascli grid patch, dbaascli dbhome patch, and dbaascli database move commands. For more information, see:

- dbaascli grid patch
- dbaascli dbhome patch
- dbaascli database move
- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli

Related Topics

- dbaascli grid patch
 - To patch Oracle Grid Infrastructure to the specified minor version, use the <code>dbaascli grid patch command</code>.
- dbaascli dbHome patch
 - To patch Oracle home from one patch level to another, use the <code>dbaascli dbHome patch command</code>.
- dbaascli database move
 - To perform out-of-place patching, use the dbaascli database move command.
- Patching Oracle Grid Infrastructure and Oracle Databases Using dbaascli
 Learn to use the dbaascli utility to perform patching operations for Oracle Grid
 Infrastructure and Oracle Database on an Exadata Cloud@Customer system.

dbaascli pdb backup

To backup a pluggable database (PDB), query PDB backups, and delete a PDB backup, use the dbaascli pdb backup command.

Prerequisite

- Run the command as the root user.
- To use the utility, you must connect to an Exadata Cloud@Customer virtual machine. See, Connecting to a Virtual Machine with SSH.

Syntax



```
}
| --delete --backupTag <value>
| --status --uuid <value>
| --getBackupReport --json <value> --tag <value>
| --list [--json <value>]
}
```

Where:

```
--pdbName: PDB name.
--dbname: Oracle Database name.
--start | --delete | --status | --getBackupReport | --list
--start: Begins PDB backup.
      [--level1 | --archival]
     [--level1: Creates a Level-1 (incremental) backup.]
     [--archival: Creates an archival full backup.]
         --tag: Specify backup tag.
--delete: Deletes archival backup.
         --backupTag: Specify backup tag to delete.
--status
          --uuid <value>
-- getBackupReport: Returns backup report.
        -- json: Specify the file name for JSON output.
        --tag: Specify backup tag.
--list: Returns PDB backup information.
        [--json: Specify the file name for JSON output.]
```

Example 7-31 Examples

To take level1 backup for a PDB pdb1 in a CDB myTestDb:

```
dbaascli pdb backup --dbname myTestDb --pdbName pdb1 --start --level1
```

 To query the status of PDB backup request submitted with uuid eef16b26361411ecb13800163e8e4fac:

```
dbaascli pdb backup --dbname myTestDb --pdbName pdb1 --status --uuid eef16b26361411ecb13800163e8e4fac
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb bounce

To bounce a pluggable database (PDB), use the dbaascli pdb bounce command.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.



See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb bounce --dbname --pdbName | --pdbUID
[-openMode]
```

Where:

- --dbname specifies the name of the container database that hosts the PDB
- --pdbName specifies the name of the PDB
- --pdbuid specifies the identifier of the PDB
- --openMode specifies the target OPEN MODE of PDB

Example 7-32 dbaascli pdb bounce

```
dbaascli pdb bounce --dbname cdb\_name --pdbName pdb name associated with the CDB
```

dbaascli pdb bounce --dbname cdb name --pdbUID con uid of that pdb

Optional:

- --openMode READ WRITE
- --openMode READ ONLY

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb close

To close a pluggable database (PDB), use the dbaascli pdb close command.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb close --dbname --pdbName | --pdbUID
```

- --dbname specifies the name of the container database that hosts the PDB.
- --pdbname specifies the name of the PDB that you want to close.



--pdbuid specifies the identifier of the PDB

Upon successful completion of running this command, the PDB is closed on all of the container database instances.

Example 7-33 dbaascli pdb close

```
dbaascli pdb close --dbname \it cdb \it name --pdbName \it pdb \it name \it associated \it with the \it CDB
```

dbaascli pdb close --dbname cdb name --pdbUID con uid of that pdb

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb connectString

To display Oracle Net connect string information for a pluggable database (PDB) run the dbaascli pdb connectString command.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb connectString --dbname --pdbName | --pdbUID
```

Where:

- --dbname specifies the name of the container database that hosts the PDB
- --pdbname specifies the name of the PDB for which you want to display connect string information
- --pdbuid specifies the identifier of the PDB

Example 7-34 dbaascli pdb connectString

dbaascli pdb connectString --dbname dbname --pdbName pdbName

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli pdb create

To create a new pluggable database (PDB), use the dbaascli pdb create command.

Prerequisite

Run the command as the oracle user.

Syntax

```
dbaascli pdb create --pdbName <value> --dbName <value>
[--maxCPU <value>]
[--maxSize <value>]
[--pdbAdminUserName <value>]
[--lockPDBAdminAccount <value>]
[--resume [--sessionID <value>]]
[--executePrereqs <value>]
[--waitForCompletion <value>]
[--standbyBlobFromPrimary <value>]
```

Where:

- --pdbName specifies the name of the new PDB that you want to create
- --dbName specifies the name of the container database that hosts the new PDB
- --maxCPU optionally specifies the maximum number of CPUs that are available to the PDB. Setting this option is effectively the same as setting the CPU_COUNT parameter in the PDB
- --maxSize optionally specifies the maximum total size of data files and temporary files for tablespaces belonging to the PDB. Setting this option is effectively the same as setting the MAXSIZE PDB storage clause in the CREATE PLUGGABLE DATABASE SQL command. You can impose a limit by specifying an integer followed by a size unit (K, M, G, or T), or you can specify UNLIMITED to explicitly enforce no limit
- --pdbAdminUserName specifies the new PDB admin user name
- --lockPDBAdminAccount specifies true or false to lock the PDB admin user account.
 Default value is true.
- --resume resumes the previous run
 - --sessionID specifies to resume a specific session ID
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values:
 yes or no
- --waitForCompletion specifies false to run the operation in the background. Valid values: true or false
- --standbyBlobFromPrimary specifies the location of the standby blob file, which is
 prepared from the primary database. This is required only for standby database PDB
 operations.

During the PDB creation process, you are prompted to specify the administration password for the new PDB.



Example 7-35 dbaascli pdb create

To create a PDB from seed in a standard database in a non-Data Guard environment:

```
dbaascli pdb create --dbName db721 --pdbName new\_pdb1 --maxsize 5G --maxcpu 2
```

To create PDB in Data Guard environment:

```
dbaascli pdb create --dbName db721 --pdbName new_pdb1
dbaascli pdb create --dbName db721 --pdbName new_pdb1 --
standbyBlobFromPrimary /tmp/send db721.tar
```

dbaascli pdb delete

To delete a pluggable database (PDB) run the dbaascli pdb delete command.

Prerequisite

Run the command as the oracle user.

Syntax

```
dbaascli pdb delete --dbName value
{ --pdbName value | --pdbUID value }
[--executePrereqs value]
[--waitForCompletion value]
[--resume [--sessionID value]]
[--allStandbyPrepared]
```

Where:

- --dbName specifies the name of the container database that hosts the PDB
- --pdbName specifies the name of the PDB that you want to delete
- --pdbuid specifies the UID of the PDB that you want to delete
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values: yes or no
- --waitForCompletion specifies false to run the operation in the background.
 Valid values: true or false
- --resume specifies to resume the previous execution
 - --sessionID specifies to resume a specific session ID
- --allStandbyPrepared specifies to confirm that the operation has been successfully run on all the standby databases

Example: dbaascli pdb delete



To delete a PDB from a standard database in a non-Data Guard environment or from Standby database in Data Guard environment.

```
dbaascli pdb delete --dbName db721 --pdbName pdb1
```

To create PDB from Primary database in Data Guard environment:

dbaascli pdb create --dbName db721 --pdbName pdb1 --allStandbyPrepared

dbaascli pdb getDetails

To view details of a pluggable database (PDB), use the dbaascli pdb getDetails command.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb getDetails --dbname --pdbName | --pdbUID
```

Where:

- --dbname specifies the name of the container database that hosts the PDB
- --pdbname specifies the name of the PDB that you want to delete
- --pdbuid specifies the identifier of the PDB

Example 7-36 dbaascli pdb getDetails

```
dbaascli pdb getDetails--dbname \it cdb \it name --pdbName \it pdb \it name \it associated \it with \it the \it CDB
```

dbaascli pdb getDetails--dbname cdb name --pdbUID con uid of that pdb

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb list

To view the list of pluggable databases (PDB) in a container database, use the <code>dbaascli pdb list command</code>.

Prerequisite

Run the command as the oracle user.



To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb list --dbname
```

Where:

--dbname specifies the name of the container database that hosts the PDB

Example 7-37 dbaascli pdb list

```
dbaascli pdb list --dbname cdb name
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb localClone

To create a new pluggable database (PDB) as a clone of an existing PDB in the same container database (CDB), use the dbaascli pdb localClone command.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli pdb localClone --dbName --pdbName
[--resume]
[--maxCPU]
[--waitForCompletion]
[--primaryDBWalletTar]
[--maxSize]
[--targetPDBName]
[--executePrereqs]
[--powerLimit]
```

- --dbName specifies the name of the database
- --pdbName specifies the name of the new PDB that you want to clone
- -- resume resumes the previous run
- --maxCPU specifies the maximum number of CPUs to be allocated for the PDB



- --waitForCompletion specifies false to run the operation in the background. Valid values: true or false
- --primaryDBWalletTar specifies the primary database wallet tar file. This is required only for standby database PDB operations
- --maxSize specifies the maximum storage size in GB for the new PDB
- --targetPDBName specifies the name for the target PDB (new cloned PDB)
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values: yes or no
- --powerLimit specifies the degree of parallelism to be used for the clone operation. Valid value is between 1 and 128

The newly cloned PDB inherits administration passwords from the source PDB.

Example 7-38 dbaascli pdb localClone

```
dbaascli pdb localClone --dbName db35 --pdbName PDB35 --targetPDBName local clone1 --maxCPU 2 --maxSize 15
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb open

To open a pluggable database (PDB), use the dbaascli pdb open command.

Run the command as the root or oracle user.

Syntax

```
dbaascli pdb open --dbname --pdbName | --pdbUID
[--openMode]
```

Where:

- --dbname specifies the name of the container database that hosts the PDB.
- --pdbName specifies the name of the PDB that you want to open
- --pdbUID specifies the identifier of the PDB
- --openMode specifies the target OPEN MODE of PDB

Upon successful completion, the PDB is opened on all of the container database instances.

Example 7-39 dbaascli pdb open

```
dbaascli pdb open --dbname \it cdb \it name --pdbName \it pdb \it name \it associated \it with the \it CDB
```

dbaascli pdb open --dbname cdb name --pdbUID con uid of that pdb



Optional: --openMode READ WRITE/READ ONLY

dbaascli pdb recover

To recover a pluggable database (PDB), use the dbaascli pdb recover command.

Prerequisite

- Run the command as the root user.
- Database must be configured with backup storage destination details where backups are stored.

Syntax

Where:

```
--pdbName: PDB name.
--dbname: Oracle Database name.
--start | --status
--start
--untilTime | --untilSCN | --latest | --tag
--untilTime: Recovers PDB until time. Input format: DD-MON-YYYY
HH24:MI:SS.
--untilSCN: Recovers PDB until SCN.
--latest: Recovers PDB to last known state.
--tag: Recovers PDB to archival tag.
--status
--uuid <value>
```

Example 7-40 Examples

To recover a PDB pdb1 in a CDB myTestDb to latest:

```
dbaascli pdb recover --dbname myTestDb --pdbName pdb1 --start --latest
```

To query the status of PDB recovery request submitted with uuid 81a17352362011ecbc3000163e8e4fac:

```
dbaascli pdb recover --dbname myTestDb --pdbName pdb1 --status -- uuid 81a17352362011ecbc3000163e8e4fac
```



Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli pdb relocate

To relocate the specified PDB from the remote database into local database, use the dbaascli pdb relocate command.

Prerequisite

Run the command as the oracle user. When prompted, you must supply the SYS user password for the source database.

Syntax

```
dbaascli pdb relocate --dbName <value> --sourceDBConnectionString <value> --
pdbName <value>
[--resume [--sessionID <value>]]
[--powerLimit <value>]
[--waitForCompletion <value>]
[--sourcePDBReadOnlyServices <value>]
[--primaryDBWalletTar <value>]
[--executePrereqs <value>]
[--maxCpu <value>]
[--maxCpu <value>]
[--sourcePDBServices <value>]
[--targetPDBName <value>]
[--targetPDBName <value>]
[--maxSize <value>]
```

- --dbName specifies the target database name
- --sourceDBConnectionString specifies the source database connection string in the format <scan name>:<scan port>/<database service name>
- --pdbName specifies the source PDB name to relocate
- --resume specifies to resume the previous execution
 - --sessionID specifies to resume a specific session ID
- --powerLimit specifies the degree of parallelism to be used for the relocate operation
- --waitForCompletion specifies false to run the operation in the background. Valid values: true|false
- --sourcePDBReadOnlyServices specifies a comma-delimited list of source PDB read-only services
- --primaryDBWalletTar specifies the primary database wallet tar file. This is required only for standby database PDB operations
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values:
 yes|no
- --maxCpu specifies the maximum number of CPUs to be allocated for the PDB



- --sourcePDBServices specifies a list of comma-delimited source PDB services
- --targetPDBName specifies a name for the target PDB (new relocated PDB)
- --maxSize specifies the maximum storage size in GB for the new PDB

Example 7-41 dbaascli pdb relocate

```
dbaascli pdb relocate --sourceDBConnectionString test-
scan.dbaastoolslrgsu.dbaastoolslrgvc.oraclevcn.com:1521/
source cdb service name --pdbName source pdb --dbName target db
```

dbaascli pdb remoteClone

To create a new pluggable database (PDB) as a clone of an existing PDB in another container database (CDB), use the dbaascli pdb remoteClone command.

Run the command as the root or oracle user.

Syntax

```
dbaascli pdb remoteClone --sourceDBConnectionString <value> --dbname
<value> --pdbName <value>
[--targetPDBName <value>]
[--powerLimit <value>]
[--maxCPU <value>]
[--maxSize <value>]
[--resume [--sessionID <value>]]
[--executePrereqs < value > ]
[--waitForCompletion < value > ]
[--sourcePDBExportedTDEKeyFile <value>]
[--standbyBlobFromPrimary <value>]
[--excludeUserTablespaces <value>]
[--excludePDBData <value>]
[--pdbAdminUserName <value>]
[--lockPDBAdminAccount <value>]
[--sourcePDBServiceConvertList < value > ]
```

- --sourceDBConnectionString specifies the source database connection string in the format scan name:scan port/database service name
- --dbname specifies the name (DB_NAME) of the CDB that hosts the newly cloned PDB
- --pdbName specifies the name of the source PDB that you want to clone
- --targetPDBName specifies the name for the target PDB (new cloned PDB)
- --powerLimit specifies the degree of parallelism to be used for the clone operation. Valid value is between 1 and 128
- --maxCPU specifies the maximum number of CPUs to be allocated for the PDB
- --maxSize specifies the maximum storage size in GB for the new PDB
- --resume resumes the previous run.



- --sessionID specifies to resume a specific session ID
- --executePrereqs specifies yes to run only the prereqs for this operation. Valid values: yes or no
- --waitForCompletion specifies false to run the operation in the background. Valid values: true or false
- --sourcePDBExportedTDEKeyFile specifies the source PDB exported key file. This variable is applicable to only 12.1 database
- --standbyBlobFromPrimary specify the location of the standby blob file which is prepared from the primary database. This is required only for standby database PDB operations.
- --excludeUserTablespaces option to skip user table spaces, example t1,t2,t3.
- --excludePDBData specify true/yes to skip user data from source pdb.
- --pdbAdminUserName specify new PDB admin user name
- --lockPDBAdminAccount specify true or false to lock the PDB admin user account.
 Default value is true
- --sourcePDBServiceConvertList specify comma separated list of source to target service names which need to be converted. Syntax is source_srv1:new_srv1,source_srv2:new_srv2.

When promoted, you must supply the SYS user password for the source PDB. The newly cloned PDB inherits administration passwords from the source PDB. The cloned PDB is named using the following format: <code>dbname_sourcepdbname</code>. This command is supported only for databases that are not in a Data Guard configuration and use Oracle Database version 12.2.0.1, or later.

Example 7-42 dbaascli pdb remoteClone

```
dbaascli pdb remoteClone --sourceDBConnectionString test-
can.dbaastoolslrgsu.dbaastoolslrgvc.oraclevcn.com:1521 --pdbName source_pdb1
--dbName db9944 --targetPDBName new_pdb1 --maxsize 5 --maxcpu 2

dbaascli pdb remoteClone --sourceDBConnectionString
orcla.dbaastoolslrgsu.dbaastoolslrgvc.oraclevcn.com --pdbName source_pdb1 --
dbName db9944 --targetPDBName new pdb1 --maxsize 5 --maxcpu 2
```

dbaascli system getDBHomes

To view information about all the Oracle homes, use the dbaascli system getDBHomes command.

Prerequisite

Run the command as the root or oracle user.

Syntax

dbaascli system getDBHomes



Example 7-43 dbaascli system getDBHomes

```
dbaascli system getDBHomes
DBAAS CLI version MAIN
Executing command system getDBHomes
Job id: eda3ec9e-55e3-464b-8169-25b79701bdaa
 "feb db19c home" : {
    "homePath" : "/u02/app/feb db19c home",
    "homeName" : "feb db19c home",
    "version": "19.0.0.0.0",
    "createTime" : 1645166784000,
    "updateTime" : 1645166784000,
    "ohNodeLevelDetails" : {
      "node1" : {
         "nodeName" : "node1",
            "version": "19.13.0.0.0"
         "node2" : {
            "nodeName" : "node2",
            "version" : "19.13.0.0.0"
          }
        },
        "messages" : [ ]
      },
 "home db19c" : {
    "homePath" : "/u02/app/home db19c",
    "homeName" : "home db19c",
    "version" : "19.0.0.0.0",
    "createTime" : 1645167664000,
    "updateTime" : 1645167664000,
    "ohNodeLevelDetails" : {
     "node1" : {
            "nodeName" : "node1",
            "version" : "19.13.0.0.0"
         },
        "node2" : {
            "nodeName" : "node2",
            "version" : "19.13.0.0.0"
          }
        },
        "messages" : [ ]
dbaascli execution completed
```



dbaascli tde addSecondaryHsmKey

To add a secondary HSM (KMS) key to the existing HSM (KMS) configuration, use the dbaascli tde addSecondaryHsmKey command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde addSecondaryHsmKey --secondaryKmsKeyOCID
[--dbname]
[--precheckOnly]
```

Where:

- --secondaryKmsKeyOCID specifies the secondary KMS key to add to the existing HSM (KMS) configuration
- --dbname specifies the name of the database
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values:
 yes or no

Example 7-44 dbaascli tde addSecondaryHsmKey

```
dbaascli tde addSecondaryHsmKey --dbname dbname --secondaryKmsKeyOCID

ocid1.key.oc1.eu-

frankfunt 1 bignyalyaafak abtbeliggfya2yeFnyylgdytyggignm2ny2afata54knyy
```

frankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5uxainvvxza

```
\label{thm:condaryHsmKey} \begin{tabular}{ll} $\tt dbaascli tde addSecondaryHsmKey--dbname & dbname & --secondaryKmsKeyOCID \\ ocid1.key.oc1.eu-\\ \end{tabular}
```

frankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5uxainvvxza--precheckOnly yes

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli tde changePassword

To change TDE keystore password as well as DB wallet password for the alias tde_ks_passwd, use the dbaascli tde changePassword command.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli tde changePassword [--dbname <value>] [--pdbName <value>]
```

Where:

- --dbname specifies the name of the database
- --pdbName specifies the name of the PDB for which the TDE Keystore needs to be changed

dbaascli tde enableWalletRoot

To enable wallet_root spfile parameter for the existing database, use the dbaasclitde enableWalletRoot command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde enableWalletRoot
[--dbRestart]
[--dbname]
[--precheckOnly]
```

- --dbrestart specifies the database restart option. Valid values are: rolling or full. Default value: rolling
 If you do not pass the dbrestart argument, then the database restarts in a rolling manner.
- --dbname specifies the name of the Oracle Database.
- --precheckOnly runs only the precheck for this operation. Valid values are: yes or



Example 7-45 dbaascli tde enableWalletRoot

```
dbaascli tde enableWalletRoot --dbname db name --dbrestart rolling|full dbaascli tde enableWalletRoot --dbname orcl dbaascli tde enableWalletRoot --dbname orcl--dbrestart full
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli tde encryptTablespacesInPDB

To encrypt all the tablespaces in the specified PDB, use the dbaascli tde encryptTablespacesInPDB command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde encryptTablespacesInPDB --pdbName
[--dbname]
[--precheckOnly]
[--useSysdbaCredential]
```

- --pdbName specifies the name of the PDB to encrypt all the tablespaces.
- --dbname specifies the name of the Oracle Database.
- --precheckOnly runs only the precheck for this operation. Valid values: yes or no
- --useSysdbaCredential uses SYSDBA credentials for this operation if passed value is true. Valid values: true or false



Example 7-46 dbaascli tde encryptTablespacesInPDB

```
dbaascli tde encryptTablespacesInPDB --dbname dbname --pdbName pdb dbaascli tde encryptTablespacesInPDB --dbname dbname --pdbName pdb --precheckOnly yes

dbaascli tde encryptTablespacesInPDB --dbname dbname --pdbName pdb --useSysdbaCredential true
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli tde fileToHsm

To convert FILE based TDE to HSM (KMS/OKV) based TDE, use the dbaascli tde fileToHsm command.

Prerequisite

Run the command as the root user.

Syntax

```
dbaascli tde fileToHsm --kmsKeyOCID <value>
[--dbname <value>]
[--skipPatchCheck <value>]
[--executePrereqs <value>]
[--primarySuc <value>]
{
      [--resume [--sessionID <value>]] | [--revert [--sessionID <value>]] }
[--waitForCompletion <value>]
```

- --kmsKeyOCID specifies the KMS key OCID to use for TDE. This is applicable only
 if KMS is selected for TDE
- --dbname specifies the name of the database
- --skipPatchCheck skips validation check for required patches if the value passed for this argument is true. Valid values: true or false
- --executePrereqs specifies yes to run only the prechecks for this operation. Valid values: yes or no
- --primarySuc specify this property in the standby database of the Data Guard environment once the command is successfully run on the primary database
- --resume specifies to resume the previous run



- --sessionID specifies to resume a specific session ID
- --revert specifies to rollback the previous run
 - --sessionID specifies to rollback a specific session ID
- --waitForCompletion specify false to run the operation in background. Valid values: true|false.

Example 7-47 dbaascli tde fileToHsm --kmsKeyOCID

```
dbaascli tde fileToHSM --dbname dbname --kmsKeyOCID ocid1.key.oc1.eu-frankfurt-.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5ux ainvvxza
```

```
dbaascli tde fileToHSM --dbname dbname --kmsKeyOCID ocid1.key.oc1.eu-frankfurt-.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5ux ainvvxza --precheckOnly yes
```

```
dbaascli tde fileToHSM --dbname dbname --kmsKeyOCID ocid1.key.oc1.eu-frankfurt-.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5ux ainvvxza --resume
```

dbaascli tde getHsmKeys

To get TDE active key details, use the dbaascli tde getHsmKeys command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde getHsmKeys
[--dbname]
[--infoFile]
```

Where:

- --dbname specifies the name of the database
- --infoFile specifies the file path where the list of OCIDs will be saved. The output is in JSON format

Example 7-48 dbaascli tde getHsmKeys

```
dbaascli tde getHsmkeys --dbname dbname
dbaascli tde getHsmkeys --dbname dbname --infoFile infoFilePath
```



Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli tde getMkidForKeyVersionOCID

To get Master Key ID associated with the KMS key version OCID, use the <code>dbaasclitde getMkidForKeyVersionOCID</code> command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

dbaascli tde getMkidForKeyVersionOCID --kmsKeyVersionOCID
[--dbname]

Where:

- --kmsKeyVersionOCID specifies the KMS key version OCID to set
- --dbname specifies the name of the database

Example 7-49 dbaascli tde getMkidForKeyVersionOCID

dbaascli tde getMkidForKeyVersionOCID --dbname dbname -- kmsKeyVersionOCID ocid1.keyversion.oc1.eu-frankfurt-1.bjqnwclvaafak.bc4hmd3olgaaa.abtheljsyxtgn4vzi2bbpcej6a7abcwvylkd21x561u2s6iwnxwgigu23nha

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli tde getPrimaryHsmKey

To get primary HSM (KMS) key from the existing HSM (KMS) configuration, use the dbaascli tde getPrimaryHsmKey command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.



Syntax

```
dbaascli tde getPrimaryHsmKey
[--dbname]
```

Where:

--dbname specifies the name of the database

Example 7-50 dbaascli tde getPrimaryHsmKey

```
dbaascli tde getPrimaryHsmKey --dbname dbname
```

Related Topics

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.

dbaascli tde hsmToFile

To convert HSM (KMS/OKV) based TDE to FILE based TDE, use the dbaascli tde hsmToFile command.

Run the command as the root user.

Syntax

```
dbaascli tde hsmToFile
[--dbname <value>]
[--standbyBlobFromPrimary <value>]
[--skipPatchCheck <value>]
[--executePrereqs <value>]
[--primarySuc <value>]
{[--resume [--sessionID <value>]]|[--revert]}
[--waitForCompletion <value>]
```

- --dbname specifies the name of the database
- --standbyBlobFromPrimary sspecify the location of the standby blob file which is prepared from the primary database. This is required only for standby operations.
- --skipPatchCheck skips validation check for required patches if the value passed for this argument is true. Valid values: true or false
- --executePrereqs specifies yes to run only the prechecks for this operation. Valid values:
 yes or no
- --primarySuc specify this property in the standby database of the Data Guard environment once the command is successfully run on the primary database
- --resume resumes the previous run
 - --sessionID specifies to resume a specific session ID



- --revert specifies to roll back the previous run
- --waitForCompletion specifies false to run the operation in background. Valid values: true|false

Example 7-51 dbaascli tde hsmToFile

```
dbaascli tde hsmToFile --dbname dbname --executePrereqs yes dbaascli tde hsmToFile --dbname dbname --resume
```

dbaascli tde listKeys

To list TDE master keys, use the dbaascli tde listKeys command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde listKeys
[--file]
[--dbname]
```

Where:

- --file specifies the file path to save the results
- --dbname specifies the name of the database

Example 7-52 dbaascli tde listKeys

```
dbaascli tde listKeys --dbname dbname
dbaascli tde listKeys --dbname dbname --file infoFilePath
```

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli tde removeSecondaryHsmKey

To remove secondary HSM (KMS) key from the existing HSM (KMS) configuration, use the dbaascli tde removeSecondaryHsmKey command.

Prerequisite

Run the command as the root user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.

Syntax

```
dbaascli tde removeSecondaryHsmKey
[--force]
[--secondaryKmsKeyOCID]
[--dbname]
[--precheckOnly]
```

Where:

- --force if not specified, you will be prompted while deleting all of the existing HSM (KMS) keys
- --secondaryKmsKeyOCID specifies the secondary KMS key to add to the existing HSM (KMS) configuration
- --dbname specifies the name of the database
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values:
 yes or no

Example 7-53 dbaascli tde removeSecondaryHsmKey

dbaascli tde removeSecondaryHsmKey --dbname dbname

```
dbaascli tde removeSecondaryHsmKey --dbname dbname --secondaryKmsKeyOCID
```

ocid1.key.oc1.eufrankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5u xainvvxza

```
dbaascli tde remove
Secondary<br/>Hsm
Key --dbname dbname --secondary
Kms
Key<br/>OCID ocid1.key.oc1.eu-
```

frankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5u
xainvvxza --precheckOnly yes

Related Topics

Connecting to a Virtual Machine with SSH

You can connect to the virtual machines in an Exadata Database Service on Cloud@Customer system by using a Secure Shell (SSH) connection.



dbaascli tde setKeyVersion

To set the version of the primary key to be used in DB/CDB or PDB, use the <code>dbaasclitde setKeyVersion</code> command.

Run the command as the root user.

Syntax

```
dbaascli tde setKeyVersion --kmsKeyVersionOCID <value>
[--dbname <value>]
[--pdbName <value>]
[--masterKeyID <value>]
[--standbySuc <value>]
[--executePrereqs <value>]
[--waitForCompletion <value>]
```

Where:

- --kmsKeyVersionOCID specifies the KMS key version OCID to set.
- --dbname specifies the name of the database.
- --pdbName name of the PDB to use the key version OCID.
- --masterKeyID specifies the master key ID of the given key version OCID. This is applicable to the Data Guard environment.
- --standbySuc specify this property in the primary database of the Data Guard environment once the command is successfully run on the standby database
- --executePrereqs specifies yes to run only the prechecks for this operation. Valid values: yes or no
- --waitForCompletion specify false to run the operation in background. Valid values: true|false

Example 7-54 dbaascli tde setKeyVersion

vylkd21x561u2s6iwnxwgigu23nha

```
dbaascli tde setKeyVersion --dbname dbname --kmsKeyVersionOCID

ocidl.keyversion.ocl.eu-
frankfurt-1.bjqnwclvaafak.bc4hmd3olgaaa.abtheljsyxtgn4vzi2bbpcej6a7abcw
vylkd2lx56lu2s6iwnxwgigu23nha

dbaascli tde setKeyVersion --dbname dbname --kmsKeyVersionOCID

ocidl.keyversion.ocl.eu-
frankfurt-1.bjqnwclvaafak.bc4hmd3olgaaa.abtheljsyxtgn4vzi2bbpcej6a7abcw
vylkd2lx56lu2s6iwnxwgigu23nha --precheckOnly yes

dbaascli tde setKeyVersion --dbname dbname --pdbName pdb --
kmsKeyVersionOCID ocidl.keyversion.ocl.eu-
frankfurt-1.bjqnwclvaafak.bc4hmd3olgaaa.abtheljsyxtgn4vzi2bbpcej6a7abcw
```



dbaascli tde setPrimaryHsmKey

To change the primary HSM (KMS) key for the existing HSM (KMS) configuration, use the dbaascli tde setPrimaryHsmKey command.

Run the command as the root user.

Syntax

```
dbaascli tde setPrimaryHsmKey --primaryKmsKeyOCID <value>
[--dbname <value>]
[--standbySuc <value>]
[--precheckOnly]
[--bounceDatabase]
```

Where:

- --primaryKmsKeyOCID specifies the primary KMS key to set
- --dbname specifies the name of the database
- --standbySuc specify this property in the primary database of the Data Guard environment once the command is successfully run on the standby database
- --precheckOnly specifies yes to run only the prechecks for this operation. Valid values: yes or no
- --bounceDatabase specify this flag to do rolling database bounce for this operation

Example 7-55 dbaascli tde setPrimaryHsmKey

```
dbaascli tde setPrimaryHsmKey --dbname dbname --primaryKmsKeyOCID

ocid1.key.oc1.eu-
frankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5u
xainvvxza

dbaascli tde setPrimaryHsmKey --dbname dbname --primaryKmsKeyOCID
ocid1.key.oc1.eu-
frankfurt-1.bjqnwclvaafak.abtheljsgfxa2xe5prvlzdxtygoiqpm2pu2afgta54krxwllk5u
xainvvxza --precheckOnly yes
```

dbaascli tde status

To display information about the keystore for the specified database, use the <code>dbaascli tde status command</code>.

Prerequisite

Run the command as the oracle user.

To use the utility, you must connect to an Exadata Cloud@Customer virtual machine.

See, Connecting to a Virtual Machine with SSH.



Syntax

dbaascli tde status --dbname dbname

Where:

--dbname specifies the name of the database that you want to check.

Output from the command includes the type of keystore, and the status of the keystore.

Example 7-56 dbaascli tde status

dbaascli tde status --dbname dbname

Related Topics

Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

Monitoring and Managing Exadata Storage Servers with ExaCLI

Learn to use the ExaCLI command-line utility to perform monitoring and management functions on Exadata storage servers in the Exadata Cloud Service.

- About the ExaCLI Command
 - The ExaCLI command provides a subset of the commands found in the onpremises Exadata command line utility.
- Exadata Storage Server Username and Password
 You need a username and password to connect to the Exadata Storage Server.
- ExaCLI Command
 - Use ExaCLI (exacli) to configure cell, database node configuration, and objects in the remote node environment, and to monitor your Exadata Database Service on Cloud@Customer services and objects.
- Connecting to a Storage Server with ExaCLI
 To use ExaCLI on storage servers, you will need to know your target storage server's IP address.

About the ExaCLI Command

The ExaCLI command provides a subset of the commands found in the on-premises Exadata command line utility.

ExaCLI offers a subset of the commands found in the on-premises Exadata command line utility. The utility runs on the database compute nodes in the Exadata Cloud Service.

Related Topics

Using the CellCLI Utility



Exadata Storage Server Username and Password

You need a username and password to connect to the Exadata Storage Server.

On Exadata Database Service on Cloud@Customer, the preconfigured user for Exadata Storage Server is <code>cloud_user_clustername</code>, where <code>clustername</code> is the name of the virtual machine (VM) cluster that is being used.

You can determine the name of the VM cluster by running the following <code>crsctl</code> command as the <code>grid</code> user on any cluster node:

```
crsctl get cluster name
```

The password for cloud_user_clustername is initially set to a random value, which you can view by running the following command as the opc user on any cluster node:

```
/opt/exacloud/get cs data.py
```

ExaCLI Command

Use ExaCLI (exacli) to configure cell, database node configuration, and objects in the remote node environment, and to monitor your Exadata Database Service on Cloud@Customer services and objects.

Purpose

ExaCLI (exacli) enables you configure your Exadata Database Service on Cloud@Customer system, and to obtain real-time information about your Exadata Cloud Service. To obtain information about the services and options on your system, run ExaCLI using the monitoring command parameter that you require.

To obtain a list of the system monitoring parameters you can use with ExaCLI, run the ${\tt LIST}$ parameter.

Syntax

```
exacli -c [username@]remotehost[:port]
[-1 username]
[--xml]
[--cookie-jar filename]
[-e {command | 'command; command' | @batchfile}]
```

Options

Option	Description
-c [username@]remotehost orconnect [username@]remotehost[:port]	Specifies the remote node to which you want to connect. ExaCLI prompts for the user name if not specified.
-l username or login-name username	Specifies the user name to log into the remote node. The preconfigured user is cloud_user_clustername.



Option	Description
xml	Displays the output in XML format.
cookie-jar [filename]	Specifies the filename of the cookie jar to use. If you do not specify a filename, then the cookie is stored in a default cookie jar located at <code>HOME/.exacli/cookiejar</code> , where <code>HOME</code> is the home directory of the operating system user running the <code>exaclicommand</code> .
	The presence of a valid cookie allows the ExaCLI user to run commands without requiring the user to log in during subsequent ExaCLI sessions.
<pre>-e command or -e 'command[; command]' or - e @batchFile</pre>	Specifies either the ExaCLI commands to run, or a batch file. After running the commands, ExaCLI quits.
	If you are specifying multiple commands to run, then enclose the commands in single quotes to prevent the shell from interpreting the semicolon.
	To start an interactive ExaCLI session, omit this command.
cert-proxy proxy[:port]	Specifies the proxy server that you want to use when downloading certificates. If port is omitted, then port 80 is used by default.
-n or no-prompt	Suppresses prompting for user input.

Command Parameters

To obtain information about objects and services on your system, use these ExaCLI command parameters.

Table 7-1 Command

Command Parameter	Description
ACTIVEREQUEST	Lists all active requests that are currently being served by the storage servers.
ALERTDEFINITION	Lists all possible alerts and their sources for storage servers.
ALERTHISTORY	Lists all alerts that have been issues for the storage servers.
CELL	Used to list the details of a specific attribute of the storage servers or storage cells. The syntax is as follows: LIST CELL ATTRIBUTES A,B,C, with A, B, and C being attributes. To see all cell attributes, use the LIST CELL ATTRIBUTES ALL command.
CELLDISK	Lists the attributes of the cell disks in the storage servers. Use the following syntax to list the cell disk details: LIST CELLDISK cell_disk_name DETAIL.



Table 7-1 (Cont.) Command

Command Parameter	Description
DATABASE	Lists details of the databases. Uses the regular LIST command syntax: LIST DATABASE and LIST DATABASE DETAIL. You can also use this command to show an individual attribute with the following syntax: LIST DATABASE ATTRIBUTES NAME.
FLASHCACHE	Lists the details of the Exadata system's flash cache. For this object, you can use the following syntax patterns: LIST FLASHCACHE DETAIL or LIST FLASHCACHE ATTRIBUTES attribute_name.
FLASHCACHECONTENT	Lists the details of all objects in the flash cache, or the details of a specified object ID. To list all the details of all objects, use LIST FLASHCACHECONTENT DETAIL.
	To list details for a specific object, use a where clause as follows: LIST FLASHCACHECONTENT WHERE objectNumber=12345 DETAIL.
	Example query: finding the object_id value of an object
	<pre>select object_name, data_object_id from user_objects where object_name = 'BIG_CENSUS'; OBJECT_NAME DATA_OBJECT_ID</pre>
	BIG_CENSUS 29152
FLASHLOG	Lists the attributes for the Oracle Exadata Smart Flash Log.
GRIDDISK	Lists the details of a particular grid disk. The syntax is similar to the CELLDISK command syntax. To view all attributes: LIST GRIDDISK grid_disk_name DETAIL. To view specified attributes of the grid disk: LIST GRIDDISK grid_disk_name ATTRIBUTES size, name.
IBPORT	Lists details of the InfiniBand ports. Syntax is LIST IBPORT DETAIL.
IORMPLAN	Use the ExaCLI CREATE, ALTER, DROP, and LIST commands with IORMPLAN. To see the details of all IORM plans, use LIST IORMPLAN DETAIL. You can also use the command to create and alter IORM plans, and to apply plans to storage servers.



Table 7-1 (Cont.) Command

Command Parameter	Description
IORMPROFILE	Lists any IORM profiles that have been set on the storage servers. You can also refer back to the profile attribute on the DATABASE object if a database has an IORM profile on it. Syntax is LIST IORMPROFILE.
LIST	Lists the command parameter options available with ExaCLI for the Exadata Database Service on Cloud@Customer services and objects.
LUN	The LUN (logical unit number) object returns the number and the detail of the physical disks in the storage servers. List the LUNs of the disks with LIST LUN. List the details of each LUN with LIST LUN lun_number DETAIL.
METRICCURRENT	Lists the current metrics for a particular object type. Syntax is LIST METRICCURRENT WHERE objectType = 'CELLDISK'.
	This command also allows for sorting and results limits as seen in the following example:
	LIST METRICCURRENT attributes name, metricObjectName ORDER BY metricObjectName asc, name desc LIMIT 5
METRICDEFINITION	Lists metric definitions for the object that you can then get details for. With the command LIST metricDefinition WHERE objectType=cell, you can get all the metrics for that object type. You can then use the metric definition object again to get details for one of those specific metrics just listed: LIST metricDefinition WHERE name= IORM_MODE DETAIL



Table 7-1 (Cont.) Command

Command Parameter	Description
METRICHISTORY	List metrics over a specified period of time. For example, with the command LIST METRICHISTORY WHERE ageInMinutes < 30, you can list all the metrics collected over the past 30 minutes. You can also use the predicate collectionTime to set a range from a specific time.
	Use collectionTime as shown in the follow example: LIST METRICHISTORY WHERE collectionTime > '2018-04-01T21:12:00-10:00'. The metric history object can also be used to see a specific metric using the object's name (for example, LIST METRICHISTORY CT_FD_IO_RQ_SM) or with a "where" clause to get objects with similar attributes like name (for example, LIST METRICHISTORY WHERE name like 'CT*').
OFFLOADGROUP	Lists the attributes for the offload group that are running on your storage servers. You can list all details for all groups with LIST OFFLOADGROUP DETAIL, or list the attributes for a specific group, as shown in the following example: LIST OFFLOADGROUP offloadgroup4. List specific attributes with LIST OFFLOADGROUP ATTRIBUTES name.
PHYSICALDISK	Lists all physical disks. Use the results of LIST PHYSICALDISK to identify a specific disk for further investigation, then list the details of that disk using the command as follows: LIST PHYSICALDISK 20:10 DETAIL. To list the details of flash disks, use the command as follows: LIST PHYSICALDISK FLASH_1_0 DETAIL).
PLUGGABLEDATABASE	Lists all PDBs. View the details of a specific PDB with LIST PLUGGABLEDATABASE pdb_name.
QUARANTINE	Lists all SQL statements that you prevented from using Smart Scans. The syntax is LIST QUARANTINE DETAIL. You can also use a "where" clause on any of the available attributes.



Table 7-1 (Cont.) Command

Command Parameter	Description
DIAGPACK	Use the ExaCLI CREATE, ALTER, DROP, and LIST commands with DIAGPACK to list the diagnostic packages and their status in your Exadata system. The syntax is LIST DIAGPACK [DETAIL], with DETAIL being an optional attribute. Use CREATE DIAGPACK with the packStartTime attribute to gather logs and trace files into a single compressed file for downloading, as in the following example: CREATE DIAGPACK packStartTime=2019_12_15T00_00_00. You can also use the value now with packStartTime: CREATE DIAGPACK packStartTime=now.
	To download a diagnostic package, use DOWNLOAD DIAGPACK package_name local_directory. For example, the following command downloads a diagnostic package to the /tmp directory: DOWNLOAD DIAGPACK cfclcx2647_diag_2018_06_03T00_44_24_1 /tmp.

Usage Notes

- Notes for the --cookie-jar option:
 - The user name and password are sent to the remote node for authentication. On successful authentication, the remote node issues a cookie (the login credentials) that is stored in the specified filename on the database node. If filename is not specified, the cookie is stored in a default cookie jar located at HOME/.exacli/cookiejar, where HOME is the home directory of the operating system user running the ExaCLI command. For the opc user, the home is / home/opc.
 - The operating system user running the ExaCLI command is the owner of the cookie jar file.
 - A cookie jar can contain multiple cookies from multiple users on multiple nodes in parallel sessions.
 - Cookies are invalidated after 24 hours.
 - If the cookie is not found or is no longer valid, ExaCLI prompts for the
 password. The new cookie is stored in the cookie jar identified by filename, or
 the default cookie jar if filename is not specified.
 - Even without the --cookie-jar option, ExaCLI still checks for cookies from the default cookie jar. However, if the cookie does not exist or is no longer valid, the new cookie will not be stored in the default cookie jar if the -cookie-jar option is not specified.
- Notes for the -e option:
 - ExaCLI exits after running the commands.



- If specifying multiple commands to run, be sure to enclose the commands in single quotes to prevent the shell from interpreting the semi-colon.
- The batch file is a text file that contains one or more ExaCLI commands to run.
- Notes for the -n (--no-prompt) option:
 - If ExaCLI needs additional information from the user, for example, if ExaCLI needs to prompt the user for a password (possibly because there were no valid cookies in the cookie-jar) or to prompt the user to confirm the remote node's identity, then ExaCLI prints an error message and exits.

Examples

Example 7-57 Starting an Interactive ExaCLI Session on a Storage Server

This example shows the user on an Exadata compute node issuing the command to log in to ExaCLI start an interactive ExaCLI session on a storage server:

```
exacli -l cloud_user_clustername -c 192.168.136.7
```

See "Finding the IP addresses of storage cells using the cellip.ora file" for information about how to determine your storage server IP address.

After you are logged in, run additional commands as follows:

```
exacli cloud_user_clustername@192.168.136.7> LIST DATABASE
ASM
HRCDB
```

Example 7-58 Issuing a Single Command on a Compute Node

This example shows a single command issued on a compute node that does the following:

- Connects to a storage server
- Performs a LIST action
- Exits the session (specified with the -e option)

```
exacli -l cloud_user_clustername -c 192.168.136.7 --xml --cookie-jar -e list griddisk detail
```

Related Topics

Connecting to a Storage Server with ExaCLI
 To use ExaCLI on storage servers, you will need to know your target storage server's IP address.

Connecting to a Storage Server with ExaCLI

To use ExaCLI on storage servers, you will need to know your target storage server's IP address.

If you do not know the IP address of the node you want to connect to, you can find it by viewing the contents of the cellip.ora file.



The following example illustrates how to do so on the UNIX command line for a quarter rack system. (Note that a quarter rack has three storage cells, and each cell has two connections, so a total of six IP addresses are shown.)

```
cat /etc/oracle/cell/
network-config/cellip.oracle
cell="192.168.136.5;cell="192.168.136.6"
cell="192.168.136.7;cell="192.168.136.8"
cell="192.168.136.9;cell="192.168.136.10"
```

If you are connecting to a storage cell for the first time using ExaCLI, you may be prompted to accept an SSL certificate. The ExaCLI output in this case will look like the following:

```
exacli -l cloud_user_clustername -c 192.168.136.7 --cookie-jar
No cookies found for cloud_user_clustername@192.168.136.7
Password: ********

EXA-30016: This connection is not secure. You have asked ExaCLI to connect to cell 192.168.136.7 securely. The identity of 192.168.136.7 cannot be verified.

Got certificate from server:

C=US,ST=California,L=Redwood City,O=Oracle Corporation,OU=Oracle Exadata,CN=ed1c103clu01-priv2.usdc2.oraclecloud.com

Do you want to accept and store this certificate? (Press y/n)
```

Accept the self-signed Oracle certificate by pressing "y" to continue using ExaCLI.

Oracle Exadata Database Service on Cloud@Customer Events

Exadata Cloud@Customer resources emit events, which are structured messages that indicate changes in resources.

- About Event Types on Exadata Cloud@Customer
 Learn about the event types available for Exadata Cloud@Customer resources.
- Exadata Infrastructure Event Types
 Review the list of event types that Exadata Infrastructure instances emit.
- VM Cluster Network Event Types
 Review the list of event types that VM cluster networks emit.
- VM Cluster Event Types
 Review the list of event types that VM clusters emit.
- Backup Destination Event Types
 Review the list of event types that backup destinations emit.
- Database Node Event Types (Cloud@Customer)
 Review the list of event types that database nodes emit.
- Database Home Event Types (Cloud@Customer)
 Review the list of event types that Database Homes emit.
- Database Event Types (Cloud@Customer)
 Review the list of event types that databases emit.



- Database and Grid Infrastructure Patching Event Types
 Review the list of event types that Database and Grid Infrastructure Patching emit.
- Autonomous VM Cluster Event Types
 Review the list of event types that Autonomous VM clusters emit.
- Autonomous Container Database Event Types
 Review the list of event types that Autonomous Container Database emit.
- Autonomous Database Event Types
 Review the list of event types that Autonomous Database emit.
- Data Guard Event Types
 Review the list of event types that Data Guard associations emit.
- Autonomous Data Guard Association Event Types
 Review the list of event types that Autnomous Data Guard associations emit.
- Key Store Event Types
 Review the list of event types that Key Store emits.
- Exadata Cloud@Customer Infrastructure Maintenance Event Types
 Review the list of event types that Exadata Cloud@Customer Infrastructure Maintenance emits.
- Storage Expansion Event Types
 Review the list of event types that storage expansion emits.
- Database Software Images Event Types
 Review the list of event types that Database Software Image emits.
- Database Upgrade Event Types
 Review the list of event types that Database Upgrade emit.
- Pluggable Database Event Types
 Review the list of event types that Pluggable Databases emit.
- VM Node Subsetting Event Types
 Review the list of event types that VM Node Subsetting emits.
- Database Service Events
 The Database Service emits events, which are structured messages that indicate changes in resources.

About Event Types on Exadata Cloud@Customer

Learn about the event types available for Exadata Cloud@Customer resources.

Exadata Cloud@Customer resources emit events, which are structured messages that indicate changes in resources. For more information about Oracle Cloud Infrastructure Events, see *Overview of Events*. You may subscribe to events and be notified when they occur using the Oracle Notification service, see *Notifications Overview*.

Related Topics

- Overview of Events
- Notifications Overview

Exadata Infrastructure Event Types

Review the list of event types that Exadata Infrastructure instances emit.



Table 7-2 Exadata Infrastructure Event Types

Friendly Name	Event Type
Activate Begin	com.oraclecloud.databaseservice.acti vateexadatainfrastructure.begin
Activate End	<pre>com.oraclecloud.databaseservice.acti vateexadatainfrastructure.end</pre>
Change Compartment	<pre>com.oraclecloud.databaseservice.chan geexadatainfrastructurecompartment</pre>
Configuration File Download	<pre>com.oraclecloud.databaseservice.down loadexadatainfrastructureconfigfile</pre>
Create Begin	<pre>com.oraclecloud.databaseservice.crea teexadatainfrastructure.begin</pre>
Create End	<pre>com.oraclecloud.databaseservice.crea teexadatainfrastructure.end</pre>
Delete Begin	<pre>com.oraclecloud.databaseservice.dele teexadatainfrastructure.begin</pre>
Delete End	<pre>com.oraclecloud.databaseservice.dele teexadatainfrastructure.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.upda teexadatainfrastructure.begin</pre>
Update End	<pre>com.oraclecloud.databaseservice.upda teexadatainfrastructure.end</pre>
Exadata Infrastructure - Connectivity Status	<pre>com.oraclecloud.databaseservice.exad atainfrastructureconnectstatus</pre>

Example 7-59 Exadata Infrastructure Example

This is a reference event for Exadata Infrastructure instances:

```
"cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
   "eventType":
"com.oraclecloud.databaseservice.createexadatainfrastructure.begin",
    "source": "databaseservice",
    "eventTypeVersion": "version",
   "eventTime": "2019-08-29T21:16:04Z",
    "contentType": "application/json",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
   },
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique_ID",
      "compartmentName": "example name",
      "resourceName": "my exadata infra",
      "resourceId": "ExadataInfra-unique ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
```



```
"definedTags": {},
"additionalDetails": {
    "id": "ocid1.id..oc1...unique_ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-08-29T12:00:00.000Z",
    "timeUpdated": "2019-08-29T12:30:00.000Z",
    "lifecycleDetails": "detail message",
    "shape": "ExadataCC.Base3.48",
    "timeZone": "US/Pacific",
    "displayName": "testDisplayName"
  }
}
```

This is a reference event for Exadata Infrastructure - Connectivity Status:

```
"eventType" :
"com.oraclecloud.databaseservice.exadatainfrastructureconnectstatus",
  "cloudEventsVersion" : "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventTime": "2020-06-02T06:07:40.141Z",
  "contentType" : "application/json",
  "data" : {
    "compartmentId" :
"ocid1.compartment.oc1..aaaaaaaayryg14guhplo5rtiumx3eh4mk7grrkrqspzaltmvbxecn
bvhkrga",
    "compartmentName": "DBaaSInteg20160918ExaccTest",
    "resourceName" : "MVM_HR",
    "resourceId" : "ocid1.exadatainfrastructure.oc1.ap-
hyderabad-1.abuhsljrp2vzzenmqmctqciwro6euhhsmlrewiiemiktov5xyfsu5hiufjsq",
    "availabilityDomain" : "",
    "additionalDetails" : {
      "timeCreated": "2020-05-28T00:23:18Z",
      "timeUpdated": "2020-06-02T06:07:40Z",
      "lifecycleState" : "DISCONNECTED",
      "lifecycleDetails" : "Exadata Infrastructure is not reachable. Please
lodge a Service Request (SR) with Oracle Support and provide Infrastructure-
id: ocid1.exadatainfrastructure.oc1.ap-
hyderabad-1.abuhsljrp2vzzenmqmctqciwro6euhhsmlrewiiemiktov5xyfsu5hiufjsq.",
      "shape" : "ExadataCC.Half3.200",
      "timeZone" : "UTC"
    },
    "definedTags" : {
      "Oracle-Tags" : {
        "CreatedBy" : "test-user@example.com",
        "CreatedOn": "2020-05-28T00:23:18.291Z"
      }
    }
  },
  "eventID": "cde92d45-a06b-4b69-a125-6005dd8c2f0c",
  "extensions" : {
    "compartmentId" :
```



```
"ocid1.compartment.oc1..aaaaaaaayryg14guhplo5rtiumx3eh4mk7grrkrqspzaltm
vbxecnbvhkrga"
   }
}
```

VM Cluster Network Event Types

Review the list of event types that VM cluster networks emit.

Table 7-3 VM Cluster Network Event Types

Friendly Name	Event Type
Create Begin	com.oraclecloud.databaseservice.crea tevmclusternetwork.begin
Create End	<pre>com.oraclecloud.databaseservice.crea tevmclusternetwork.end</pre>
Network Validation File Download	<pre>com.oraclecloud.databaseservice.down loadvmclusternetworkconfigfile</pre>
Terminate Begin	<pre>com.oraclecloud.databaseservice.dele tevmclusternetwork.begin</pre>
Terminate End	<pre>com.oraclecloud.databaseservice.dele tevmclusternetwork.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.crea tevmclusternetwork.begin</pre>
Update End	<pre>com.oraclecloud.databaseservice.crea tevmclusternetwork.end</pre>
Validate Begin	<pre>com.oraclecloud.databaseservice.vali datevmclusternetwork.begin</pre>
Validate End	<pre>com.oraclecloud.databaseservice.vali datevmclusternetwork.end</pre>

Example 7-60 VM Cluster Network Example

This is a reference event for VM cluster networks:

```
"cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType":
"com.oraclecloud.databaseservice.createvmclusternetwork.begin",
    "source": "databaseservice",
    "eventTypeVersion": "version",
    "eventTime": "2019-08-29T21:16:04Z",
    "contentType": "application/json",
    "extensions": {
        "compartmentId": "ocid1.compartment.oc1..unique_ID"
     },
     "data": {
        "compartmentId": "ocid1.compartment.oc1..unique_ID",
        "compartmentId": "example name",
```



```
"resourceName": "my_vmcluster_network",
    "resourceId": "VmClusterNetwork-unique_ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
        "id": "ocidl.id..ocl...unique_ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-08-29T12:00:00.000Z",
        "timeUpdated": "2019-08-29T12:30:00.000Z",
        "lifecycleDetails": "detail message",
        "exadataInfrastructureId": "ExadataInfra-unique_ID",
        "displayName": "testDisplayName"
    }
}
```

VM Cluster Event Types

Review the list of event types that VM clusters emit.

Table 7-4 VM Cluster Event Types

Friendly Name	Event Type
Change Compartment	com.oraclecloud.databaseservice.changev mclustercompartment
Create Begin	<pre>com.oraclecloud.databaseservice.createv mcluster.begin</pre>
Create End	<pre>com.oraclecloud.databaseservice.createv mcluster.end</pre>
Terminate Begin	<pre>com.oraclecloud.databaseservice.deletev mcluster.begin</pre>
Terminate End	<pre>com.oraclecloud.databaseservice.deletev mcluster.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.updatev mcluster.begin</pre>
Update End	<pre>com.oraclecloud.databaseservice.updatev mcluster.end</pre>

Example 7-61 VM Cluster Example

This is a reference event for VM clusters:

```
"cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType":
"com.oraclecloud.databaseservice.createvmclusternetwork.begin",
    "source": "databaseservice",
    "eventTypeVersion": "version",
    "eventTime": "2019-08-29T21:16:04Z",
```



```
"contentType": "application/json",
  "extensions": {
   "compartmentId": "ocid1.compartment.oc1..unique ID"
  },
  "data": {
    "compartmentId": "ocid1.compartment.oc1..unique ID",
    "compartmentName": "example name",
   "resourceName": "my vmcluster network",
    "resourceId": "VmClusterNetwork-unique ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
      "id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-08-29T12:00:00.000Z",
      "timeUpdated": "2019-08-29T12:30:00.000Z",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExadataInfra-unique ID",
      "displayName": "testDisplayName"
 }
}
```

This is a reference event for VM Cluster Create Begin:

```
{
 "cloudEventsVersion": "0.1",
 "eventId": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
 "eventType": "com.oraclecloud.databaseservice.createvmcluster.begin",
 "source": "databaseservice",
 "eventTypeVersion": "1.0",
 "eventTime": "2019-06-27T21:16:04.000Z",
 "contentType": "application/json",
 "extensions": {
   "compartmentId": "ocid1.compartment.oc1..unique ID"
 },
 "data": {
   "compartmentId": "ocid1.compartment.oc1..unique ID",
   "compartmentName": "example name",
   "resourceName": "my database",
   "resourceId": "Vmcluster-unique ID",
   "availabilityDomain": "all",
   "freeFormTags": {},
   "definedTags": {},
   "additionalDetails": {
      "id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-09-03T12:00:00.000Z",
     "timeUpdated": "2019-09-03T12:30:00.000Z",
      "displayName": "testDisplayName",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExatraInfra-unique ID",
      "vmClusterNetworkId": "VmCluster-unique ID",
```



```
"cpuCoreCount": 2,
   "dataStorageSizeInTBs": 4,
   "dbVersion": "19.0.0.0",
   "licenseType": "BRING_YOUR_OWN_LICENSE",
   "giVersion": "19.0.0.0",
   "dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
   "timeZone": "US/Pacific"
   }
}
```

Backup Destination Event Types

Review the list of event types that backup destinations emit.

Table 7-5 Backup Destination Event Types

Friendly Name	Event Type
Change Compartment	com.oraclecloud.databaseservice.changeb ackupdestinationcompartment
Create	<pre>com.oraclecloud.databaseservice.createb ackupdestination</pre>
Terminate	<pre>com.oraclecloud.databaseservice.deleteb ackupdestination</pre>
Update	${\tt com.oraclecloud.databaseservice.updateb} \\ {\tt ackupdestination}$

Example 7-62 Backup Destination Example

This is a reference event for backup destinations:

```
"cloudEventsVersion": "0.1",
"eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
"eventType": "com.oraclecloud.databaseservice.createbackupdestination",
"source": "databaseservice",
"eventTypeVersion": "version",
"eventTime": "2019-08-29T21:16:04Z",
"contentType": "application/json",
"extensions": {
  "compartmentId": "ocid1.compartment.oc1..unique ID"
"data": {
 "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my backupdestination",
  "resourceId": "BackupDestination-unique_ID",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {}
```



}

Database Node Event Types (Cloud@Customer)

Review the list of event types that database nodes emit.

Table 7-6 Database Node Event Types

Friendly Name	Event Type
Update Begin	com.oraclecloud.databaseservice.dbno deaction.begin
Update End	<pre>com.oraclecloud.databaseservice.dbno deaction.end</pre>

Example 7-63 Database Node Example

This is a reference event for database nodes:

```
"cloudEventsVersion": "0.1",
"eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
"eventType": "com.oraclecloud.databaseservice.dbnodeaction.begin",
"source": "databaseservice",
"eventTypeVersion": "version",
"eventTime": "2019-06-27T21:16:04Z",
"contentType": "application/json",
"extensions": {
  "compartmentId": "ocid1.compartment.oc1..unique ID"
},
"data": {
  "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my dbnode",
  "resourceId": "DbNode-unique ID",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
    "id": "ocid1.id..oc1...unique ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-08-26T12:00:00.000Z",
    "timeUpdated": "2019-08-26T12:30:00.000Z",
    "dbSystemId": "ocid1.dbsystem.oc1.phx.unique ID",
    "lifecycleDetails": "detail message",
    "vmClusterId": "VmCluster-unique ID",
    "dbHostId": "dbHost-unique ID",
    "nodeNumber": 2,
    "powerAction": "HardReset",
    "hostName": "testHostName"
  }
```



```
}
```

Database Home Event Types (Cloud@Customer)

Review the list of event types that Database Homes emit.

Table 7-7 Database Home Event Types

Friendly Name	Event Type
Create Begin	<pre>com.oraclecloud.databaseservice.created bhome.begin</pre>
Create End	${\tt com.oraclecloud.databaseservice.created} \\ {\tt bhome.end}$
Terminate Begin	<pre>com.oraclecloud.databaseservice.deleted bhome.begin</pre>
Terminate End	${\tt com.oraclecloud.databaseservice.deleted} \\ {\tt bhome.end}$
Update Begin	${\tt com.oraclecloud.databaseservice.updated} \\ {\tt bhome.begin}$
Update End	<pre>com.oraclecloud.databaseservice.updated bhome.end</pre>

Example 7-64 Database Home Example

This is a reference event for Database Homes:

```
"cloudEventsVersion": "0.1",
"eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
"eventType": "com.oraclecloud.databaseservice.createdbhome.begin",
"source": "databaseservice",
"eventTypeVersion": "version",
"eventTime": "2019-08-29T21:16:04Z",
"contentType": "application/json",
"extensions": {
  "compartmentId": "ocid1.compartment.oc1..unique ID"
"data": {
  "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my dbhome",
  "resourceId": "DbHome-unique ID",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
   "id": "ocid1.id..oc1...unique ID",
    "lifecycleState": "AVAILABLE",
   "timeCreated": "2019-08-29T12:00:00.000Z",
    "timeUpdated": "2019-08-29T12:30:00.000Z",
```



```
"lifecycleDetails": "detail message",
    "dbSystemId": "DbSystem-unique_ID",
    "dbVersion": "19.0.0.0",
    "recordVersion": 4,
    "displayName": "testDisplayName"
    }
}
```

Database Event Types (Cloud@Customer)

Review the list of event types that databases emit.

Table 7-8 Database Event Types

Friendly Name	Event Type
Create Begin	com.oraclecloud.databaseservice.crea tedatabase.begin
Create End	<pre>com.oraclecloud.databaseservice.crea tedatabase.end</pre>
Delete Backup Begin	<pre>com.oraclecloud.databaseservice.dele tebackup.begin</pre>
Delete Backup End	<pre>com.oraclecloud.databaseservice.dele tebackup.end</pre>
Restore Begin	<pre>com.oraclecloud.databaseservice.rest oredatabase.begin</pre>
Restore End	<pre>com.oraclecloud.databaseservice.rest oredatabase.end</pre>
Terminate Begin	<pre>com.oraclecloud.databaseservice.dele tedatabase.begin</pre>
Terminate End	<pre>com.oraclecloud.databaseservice.dele tedatabase.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.upda tedatabase.begin</pre>
Update End	<pre>com.oraclecloud.databaseservice.upda tedatabase.end</pre>

Example 7-65 Database Example

This is a reference event for databases:

```
"cloudEventsVersion": "0.1",

"eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",

"eventType": "com.oraclecloud.databaseservice.restoredatabase.begin",

"source": "databaseservice",

"eventTypeVersion": "version",

"eventTime": "2019-06-27T21:16:04Z",

"contentType": "application/json",

"extensions": {
```



```
"compartmentId": "ocid1.compartment.oc1..unique ID"
},
"data": {
 "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my database",
  "resourceId": "Database-unique ID",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
   "id": "ocid1.id..oc1...unique ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-08-26T12:00:00.000Z",
    "timeUpdated": "2019-08-26T12:30:00.000Z",
    "dbSystemId": "dbSystem-unique ID",
    "displayName": "testDisplayName",
    "lifecycleDetails": "detail message",
    "vmClusterId": "VmCluster-unique ID",
    "backupType": "FULL",
    "dbHomeId": "dbHome-unique ID",
    "dbVersion": "19.0.0.0",
    "databaseEdition": "ENTERPRISE EDITION EXTREME",
    "autoBackupsEnabled": "true",
    "recoveryWindow": 30,
    "backupDestinationId": "backupDestination-unique ID",
    "backupDestinationType": "OBJECT STORAGE",
    "backupDestinationName": "my backup_destination_name",
    "exadataInfrastructureId": "ExadataInfrastructure-unique ID",
    "dbUniqueName": "akv tgh unqna"
```

Database and Grid Infrastructure Patching Event Types

Review the list of event types that Database and Grid Infrastructure Patching emit.

Table 7-9 Database and Grid Infrastructure Patching Events

Friendly Name	Event Type
VM Cluster - Patch Begin	<pre>com.oraclecloud.databaseservice.patchvm cluster.begin</pre>
VM Cluster - Patch End	<pre>com.oraclecloud.databaseservice.patchvm cluster.end</pre>
DB Home - Patch Begin	<pre>com.oraclecloud.databaseservice.patchdb home.begin</pre>
DB Home - Patch End	${\tt com.oraclecloud.databaseservice.patchdb} \\ {\tt home.end}$
Database - Move Begin	${\tt com.oraclecloud.databaseservice.moved at abase.end}$

Table 7-9 (Cont.) Database and Grid Infrastructure Patching Events

Friendly Name	Event Type
Database - Move End	<pre>com.oraclecloud.databaseservice.movedat abase.end</pre>

Example 7-66 Database Example

This is a reference event for VM Cluster - Patch Begin:

```
{
   "cloudEventsVersion": "0.1",
    "eventId": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
   "eventType":
"com.oraclecloud.databaseservice.patchvmcluster.begin",
    "source": "databaseservice",
    "eventTypeVersion": "1.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
    },
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique_ID",
      "compartmentName": "example name",
      "resourceName": "my database",
      "resourceId": "Vmcluster-unique ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "id": "ocid1.id..oc1...unique ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-09-03T12:00:00.000Z",
        "timeUpdated": "2019-09-03T12:30:00.000Z",
        "displayName": "testDisplayName",
        "lifecycleDetails": "detail message",
        "exadataInfrastructureId": "ExatraInfra-unique ID",
        "vmClusterNetworkId": "VmCluster-unique ID",
        "cpuCoreCount": 2,
        "dataStorageSizeInTBs": 4,
        "dbVersion": "19.0.0.0",
        "licenseType": "BRING YOUR OWN LICENSE",
        "giVersion": "19.0.0.0",
        "dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
        "timeZone": "US/Pacific"
   }
```



This is a reference event for DB Home - Patch Begin:

```
{
    "cloudEventsVersion": "0.1",
    "eventId": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType": "com.oraclecloud.databaseservice.patchdbhome.begin",
    "source": "databaseservice",
    "eventTypeVersion": "1.0",
    "eventTime": "2019-08-29T21:16:04.000Z",
    "contentType": "application/json",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
   },
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique ID",
      "compartmentName": "example name",
      "resourceName": "my dbhome",
      "resourceId": "DbHome-unique ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
       "id": "ocid1.id..oc1...unique_ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-08-29T12:00:00.000Z",
        "timeUpdated": "2019-08-29T12:30:00.000Z",
        "lifecycleDetails": "detail message",
        "dbSystemId": "DbSystem-unique ID",
        "dbVersion": "19.0.0.0",
        "recordVersion": 4,
        "displayName": "testDisplayName"
   }
```

This is a reference event for Database - Move Begin:

```
"cloudEventsVersion": "0.1",
"eventId": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
"eventType": "com.oraclecloud.databaseservice.movedatabase.begin",
"source": "databaseservice",
"eventTypeVersion": "1.0",
"eventTime": "2019-06-27T21:16:04.000Z",
"contentType": "application/json",
"extensions": {
  "compartmentId": "ocid1.compartment.oc1..unique ID"
},
"data": {
  "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my database",
  "resourceId": "Database-unique ID",
  "availabilityDomain": "all",
```



```
"freeFormTags": {},
"definedTags": {},
"additionalDetails": {
 "id": "ocid1.id..oc1...unique ID",
  "lifecycleState": "AVAILABLE",
  "timeCreated": "2019-08-26T12:00:00.000Z",
  "timeUpdated": "2019-08-26T12:30:00.000Z",
  "dbSystemId": "ocid1.dbsystem.oc1.phx.unique ID",
  "displayName": "testDisplayName",
  "lifecycleDetails": "detail message",
  "vmClusterId": "VmCluster-unique ID",
  "dbSystemId": "dbSystem-unique ID",
  "backupType": "FULL",
  "dbHomeId": "dbHome-unique_ID",
  "dbVersion": "19.0.0.0",
  "databaseEdition": "ENTERPRISE EDITION EXTREME",
  "autoBackupsEnabled": "true",
  "recoveryWindow": 30,
  "backupDestinationId": "backupDestination-unique ID",
  "backupDestinationType": "OBJECT STORAGE",
  "backupDestinationName": "my backup destination name",
  "exadataInfrastructureId": "ExadataInfrastructure-unique-ID",
  "dbUniqueName": "akv tgh unqna"
```

Autonomous VM Cluster Event Types

Review the list of event types that Autonomous VM clusters emit.

Table 7-10 Autonomous VM Cluster Events

Friendly Name	Event Type
Autonomous VM Cluster - Change Compartment	com.oraclecloud.databaseservice.chan geautonomousvmclustercompartment
Autonomous VM Cluster - Create Begin	<pre>com.oraclecloud.databaseservice.crea teautonomousvmcluster.begin</pre>
Autonomous VM Cluster - Create End	<pre>com.oraclecloud.databaseservice.crea teautonomousvmcluster.end</pre>
Autonomous VM Cluster - Terminate Begin	<pre>com.oraclecloud.databaseservice.dele teautonomousvmcluster.begin</pre>
Autonomous VM Cluster - Terminate End	<pre>com.oraclecloud.databaseservice.dele teautonomousvmcluster.end</pre>
Autonomous VM Cluster - Update Begin	<pre>com.oraclecloud.databaseservice.upda teautonomousvmcluster.begin</pre>
Autonomous VM Cluster - Update End	<pre>com.oraclecloud.databaseservice.upda teautonomousvmcluster.end</pre>



Example 7-67 Autonomous VM Cluster Examples

This is a reference event for Autonomous VM Cluster - Change Compartment:

```
{
    "cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType":
"com.oraclecloud.databaseservice.changeautonomousvmclustercompartment",
    "source": "databaseservice",
    "eventTypeVersion": "1.0",
    "eventTime": "2019-06-27T21:16:04Z",
    "contentType": "application/json",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
   },
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique ID",
      "compartmentName": "example name",
      "resourceName": "my_database",
      "resourceId": "AutonomousVmCluster-unique ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
       "id": "ocid1.id..oc1...unique ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-09-03T12:00:00.000Z",
        "timeUpdated": "2019-09-03T12:30:00.000Z",
        "displayName": "testDisplayName",
        "lifecycleDetails": "detail message",
        "exadataInfrastructureId": "ExatraInfra-unique ID",
        "vmClusterNetworkId": "VmClusterNetwork-unique ID",
        "cpuCoreCount": "2",
        "availableCpus": "1",
        "dataStorageSizeInTBs": "4",
        "availableDataStorageSizeInTBs": "1",
        "licenseType": "BRING YOUR OWN LICENSE",
        "timeZone": "US/Pacific"
   }
```

This is a reference event for Autonomous VM Cluster - Create Begin

```
{
    "cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType":
"com.oraclecloud.databaseservice.createautonomousvmcluster.begin",
    "source": "databaseservice",
    "eventTypeVersion": "1.0",
    "eventTime": "2019-06-27T21:16:04Z",
    "contentType": "application/json",
    "extensions": {
```



```
"compartmentId": "ocid1.compartment.oc1..unique ID"
},
"data": {
  "compartmentId": "ocid1.compartment.oc1..unique ID",
  "compartmentName": "example name",
  "resourceName": "my database",
  "resourceId": "AutonomousVmCluster-unique ID",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
    "id": "ocid1.id..oc1...unique ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-09-03T12:00:00.000Z",
    "timeUpdated": "2019-09-03T12:30:00.000Z",
    "displayName": "testDisplayName",
    "lifecycleDetails": "detail message",
    "exadataInfrastructureId": "ExatraInfra-unique ID",
    "vmClusterNetworkId": "VmClusterNetwork-unique ID",
    "cpuCoreCount": "2",
    "availableCpus": "1",
    "dataStorageSizeInTBs": "4",
    "availableDataStorageSizeInTBs": "1",
    "licenseType": "BRING YOUR OWN LICENSE",
    "timeZone": "US/Pacific"
}
```

This is a reference event for Autonomous VM Cluster - Terminate Begin

```
{
   "cloudEventsVersion": "0.1",
   "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
   "eventType":
"com.oraclecloud.databaseservice.deleteautonomousvmcluster.begin",
   "source": "databaseservice",
   "eventTypeVersion": "1.0",
   "eventTime": "2019-06-27T21:16:04Z",
   "contentType": "application/json",
   "extensions": {
     "compartmentId": "ocid1.compartment.oc1..unique ID"
   },
   "data": {
     "compartmentId": "ocid1.compartment.oc1..unique ID",
     "compartmentName": "example name",
      "resourceName": "my database",
      "resourceId": "AutonomousVmCluster-unique_ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
     "definedTags": {},
      "additionalDetails": {
       "id": "ocid1.id..oc1...unique ID",
       "lifecycleState": "AVAILABLE",
```



```
"timeCreated": "2019-09-03T12:00:00.000Z",
    "timeUpdated": "2019-09-03T12:30:00.000Z",
    "displayName": "testDisplayName",
    "lifecycleDetails": "detail message",
    "exadataInfrastructureId": "ExatraInfra-unique_ID",
    "vmClusterNetworkId": "VmClusterNetwork-unique_ID",
    "cpuCoreCount": "2",
    "availableCpus": "1",
    "dataStorageSizeInTBs": "4",
    "availableDataStorageSizeInTBs": "1",
    "licenseType": "BRING_YOUR_OWN_LICENSE",
    "timeZone": "US/Pacific"
}
}
```

This is a reference event for Autonomous VM Cluster - Update Begin

```
"cloudEventsVersion": "0.1",
   "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
   "eventType":
"com.oraclecloud.databaseservice.updateautonomousvmcluster.begin",
   "source": "databaseservice",
   "eventTypeVersion": "1.0",
   "eventTime": "2019-06-27T21:16:04Z",
   "contentType": "application/json",
   "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
   },
   "data": {
      "compartmentId": "ocid1.compartment.oc1..unique ID",
      "compartmentName": "example name",
      "resourceName": "my_database",
      "resourceId": "AutonomousVmCluster-unique ID",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
       "id": "ocid1.id..oc1...unique ID",
       "lifecycleState": "AVAILABLE",
       "timeCreated": "2019-09-03T12:00:00.000Z",
       "timeUpdated": "2019-09-03T12:30:00.000Z",
       "displayName": "testDisplayName",
       "lifecycleDetails": "detail message",
       "exadataInfrastructureId": "ExatraInfra-unique ID",
       "vmClusterNetworkId": "VmClusterNetwork-unique ID",
        "cpuCoreCount": "2",
       "availableCpus": "1",
       "dataStorageSizeInTBs": "4",
       "availableDataStorageSizeInTBs": "1",
       "licenseType": "BRING YOUR OWN LICENSE",
       "timeZone": "US/Pacific"
      }
```



}

Autonomous Container Database Event Types

Review the list of event types that Autonomous Container Database emit.

Table 7-11 Autonomous Container Database Events

Friendly Name	Event Type
Change Compartment	<pre>com.oraclecloud.databaseservice.chan geautonomouscontainerdatabasecompart ment</pre>
Create Backup Begin	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.backup.beg in</pre>
Create Backup End	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.backup.end</pre>
Create Begin	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.instance.c reate.begin</pre>
Create End	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.instance.c reate.end</pre>
Maintenance Begin	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.maintenanc e.begin</pre>
Maintenance End	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.maintenanc e.end</pre>
Maintenance Reminder	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.maintenanc e.reminder</pre>
Maintenance Scheduled	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.maintenanc e.scheduled</pre>
Restart Begin	<pre>com.oraclecloud.databaseservice.rest artautonomouscontainerdatabase.begin</pre>
Restart End	<pre>com.oraclecloud.databaseservice.rest artautonomouscontainerdatabase.end</pre>
Restore Begin	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.restore.be gin</pre>
Restore End	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.restore.en d</pre>



Table 7-11 (Cont.) Autonomous Container Database Events

Friendly Name	Event Type
Terminate Begin	<pre>com.oraclecloud.databaseservice.term inateautonomouscontainerdatabase.beg in</pre>
Terminate End	<pre>com.oraclecloud.databaseservice.term inateautonomouscontainerdatabase.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.auto nomous.container.database.instance.u pdate.begin</pre>
Update End	com.oraclecloud.databaseservice.auto nomous.container.database.instance.u pdate.begin

Example 7-68 Autonomous Container Database Examples

This is a reference event for create Autonomous Container Database:

```
{lifecycleState=AVAILABLE,
autonomousVmClusterId=ocid1.autonomousvmcluster.oc1.sea.abzwkljrevsjcfuskw7mg
i6ulzfq2epjjxhbnhwj63q7q3kzvuwq3djqnd2a,
displayName=CDB2-NFS,
dbName=wqxtzzfn,
dbUniqueName=wqxtzzfn sealtd,
freeTags={},
autonomousContainerDatabaseId=ocid1.autonomouscontainerdatabase.oc1.sea.abzwk
ljrxkuruqe3qzgw432adr5ug7ridmwi4ifvjlsahcdqdhbhzbf543xa,
compartmentId=ocid1.compartment.region1..aaaaaaaass5x4witduxzgrs7gmzqk3m5kmog
uve7urwploqef6763w3o42ta,
timeUpdated=2020-06-15 21:52:24.085,
tenantId=ocid1.tenancy.region1..aaaaaaaagyw5okosjg54csr3u5qgaxvtjufz55537h44m
jy2umiqur4z5w3a,
timeCreated=2020-06-15 19:08:03.797,
id=ocid1.autonomouscontainerdatabase.oc1.sea.abzwkljrxkuruqe3qzgw432adr5ug7ri
dmwi4ifvjlsahcdqdhbhzbf543xa,
definedTags={}}
```

Autonomous Database Event Types

Review the list of event types that Autonomous Database emit.

Table 7-12 Autonomous Database Events

Friendly Name	Event Type
Change Compartment Begin	com.oraclecloud.databaseservice.changea utonomousdatabasecompartment.begin
Change Compartment End	<pre>com.oraclecloud.databaseservice.changea utonomousdatabasecompartment.end</pre>



Table 7-12 (Cont.) Autonomous Database Events

Friendly Name	Event Type
Create Backup Begin	com.oraclecloud.databaseservice.autonom ous.database.backup.begin
Create Backup End	<pre>com.oraclecloud.databaseservice.autonom ous.database.backup.end</pre>
Create Begin	<pre>com.oraclecloud.databaseservice.autonom ous.database.instance.create.begin</pre>
Create End	<pre>com.oraclecloud.databaseservice.autonom ous.database.instance.create.end</pre>
Restore Begin	<pre>com.oraclecloud.databaseservice.autonom ous.database.restore.begin</pre>
Restore End	<pre>com.oraclecloud.databaseservice.autonom ous.database.restore.end</pre>
Start Begin	<pre>com.oraclecloud.databaseservice.startau tonomousdatabase.begin</pre>
Start End	<pre>com.oraclecloud.databaseservice.startau tonomousdatabase.end</pre>
Stop Begin	<pre>com.oraclecloud.databaseservice.stopaut onomousdatabase.begin</pre>
Stop End	<pre>com.oraclecloud.databaseservice.stopaut onomousdatabase.end</pre>
Terminate Begin	<pre>com.oraclecloud.databaseservice.deletea utonomousdatabase.begin</pre>
Terminate End	<pre>com.oraclecloud.databaseservice.deletea utonomousdatabase.end</pre>
Update Begin	<pre>com.oraclecloud.databaseservice.updatea utonomousdatabase.begin</pre>
Update End	<pre>com.oraclecloud.databaseservice.updatea utonomousdatabase.end</pre>

Data Guard Event Types

Review the list of event types that Data Guard associations emit.

Table 7-13 Data Guard Association Events

Friendly Name	Event Type
Data Guard Association - Create Begin	com.oraclecloud.databaseservice.crea tedataguardassociation.begin
Data Guard Association - Create End	<pre>com.oraclecloud.databaseservice.crea tedataguardassociation.end</pre>
Switchover Begin	com.oraclecloud.databaseservice.swit choverdataguardassociation.begin



Table 7-13 (Cont.) Data Guard Association Events

Friendly Name	Event Type
Switchover End	com.oraclecloud.databaseservice.swit choverdataguardassociation.end
Failover Begin	<pre>com.oraclecloud.databaseservice.fail overdataguardassociation.begin</pre>
Failover End	<pre>com.oraclecloud.databaseservice.fail overdataguardassociation.end</pre>
Reinstate Begin	<pre>com.oraclecloud.databaseservice.rein statedataguardassociation.begin</pre>
Reinstate End	<pre>com.oraclecloud.databaseservice.rein statedataguardassociation.end</pre>

Example 7-69 Data Guard Associations Examples

This is a reference event for Data Guard Association - Create Begin:

```
{
   "eventId": "022a63a4-ff77-11e9-a0af-f45c89b1cb17",
    "eventTime": "2019-11-05T02:50:21.000Z",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique id"
   },
    "eventType":
"com.oraclecloud.databaseservice.createdataguardassociation.begin",
   "eventTypeVersion": "2.0",
    "cloudEventsVersion": "0.1",
    "source": "databaseservice",
    "contentType": "application/json",
    "definedTags": {},
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique id",
      "compartmentName": "example name",
      "resourceName": "my container database",
      "resourceId": "ocid1.dataguard.oc1.phx.unique id",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "id": "ocid1.dataguard.oc1.phx.unique id",
        "timeCreated": "2019-06-27T21:15:59.000Z",
        "timeUpdated": "2019-06-27T21:16:04.389Z",
        "lifecycleState": "ACTIVE",
        "lifecycleMessage": "",
        "dbSystemId": "ocid1.vmcluster.oc1.phx.unique id",
        "DatabaseId": "ocid1.database.oc1.phx.unique id",
        "DbHomeId": "ocid1.dbhome.oc1.phx.unique id",
        "DGConfigId": "022a67c8-ff77-11e9-af6e-f45c89b1cb17",
        "DGConfigState": "SUCCESS",
        "LastSyncedTime": "2019-06-27T21:16:04.389Z",
        "ApplyLag": "2 hours",
```



```
"dcsDgUpdateTimestamp": "2019-06-27T21:16:04.389Z",
        "lastUpdatedIdentifier": "022a6912-ff77-11e9-9e77-
f45c89b1cb17",
        "displayName": "Data Guard Association - Create Begin",
        "licenseType": "BRING YOUR OWN LICENSE",
        "workloadType": "Transaction Processing"
    }
This is a reference event for Data Guard Association - Create End:
{
    "eventId": "022aa7cc-ff77-11e9-90cd-f45c89b1cb17",
    "eventTime": "2019-11-05T02:50:21.000Z",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique id"
    },
    "eventType":
"com.oraclecloud.databaseservice.createdataguardassociation.end",
    "eventTypeVersion": "2.0",
    "cloudEventsVersion": "0.1",
    "source": "databaseservice",
    "contentType": "application/json",
    "definedTags": {},
    "data": {
      "compartmentId": "ocid1.compartment.oc1..unique id",
      "compartmentName": "example name",
      "resourceName": "my container database",
      "resourceId": "ocid1.dataguard.oc1.phx.unique id",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "id": "ocid1.dataguard.oc1.phx.unique id",
        "timeCreated": "2019-06-27T21:15:59.000Z",
        "timeUpdated": "2019-06-27T21:16:04.389Z",
        "lifecycleState": "ACTIVE",
        "lifecycleMessage": "",
        "dbSystemId": "ocid1.vmcluster.oc1.phx.unique id",
        "DatabaseId": "ocid1.database.oc1.phx.unique id",
        "DbHomeId": "ocid1.dbhome.oc1.phx.unique id",
        "DGConfigId": "022aab34-ff77-11e9-b89c-f45c89b1cb17",
        "DGConfigState": "SUCCESS",
        "LastSyncedTime": "2019-06-27T21:16:04.389Z",
        "ApplyLag": "2 hours",
        "SyncState": "SYNCED",
        "dcsDgUpdateTimestamp": "2019-06-27T21:16:04.389Z",
        "lastUpdatedIdentifier": "022aac10-ff77-11e9-8041-
f45c89b1cb17",
        "displayName": "Data Guard Association - Create End",
        "licenseType": "BRING YOUR OWN LICENSE",
        "workloadType": "Transaction Processing"
```

"SyncState": "SYNCED",



```
}
```

Autonomous Data Guard Association Event Types

Review the list of event types that Autnomous Data Guard associations emit.

Table 7-14 Autonomous Data Guard Association Events

Friendly Name	Event Type
Autonomous Data Guard Association - Create Autonomous Data Guard Begin	com.oraclecloud.DatabaseService.CreateA utonomousDataGuardAssociation.begin
Autonomous Data Guard Association - Create Autonomous Data Guard End	<pre>com.oraclecloud.DatabaseService.CreateA utonomousDataGuardAssociation.end</pre>
Autonomous Data Guard Association - Switchover Begin	com.oraclecloud.DatabaseService.Switcho verAutonomousDataguardAssociation.begin
Autonomous Data Guard Association - Switchover End	<pre>com.oraclecloud.DatabaseService.Switcho verAutonomousDataguardAssociation.end</pre>
Autonomous Data Guard Association - Failover Begin	com.oraclecloud.DatabaseService.Failove rAutonomousDataguardAssociation.begin
Autonomous Data Guard Association - Failover End	<pre>com.oraclecloud.DatabaseService.Failove rAutonomousDataguardAssociation.end</pre>
Autonomous Data Guard Association - Reinstate Begin	com.oraclecloud.DatabaseService.ReinstateAutonomousDataGuardAssociation.begin
Autonomous Data Guard Association - Reinstate End	<pre>com.oraclecloud.DatabaseService.Reinsta teAutonomousDataGuardAssociation.end</pre>

Example 7-70 Autonomous Data Guard Associations Examples

This is a reference event for Autonomous Data Guard Association - Create Autonomous Data Guard Begin:

```
"cloudEventsVersion": "0.1",
 "eventID": "<unique ID>",
 "eventType":
"com.oraclecloud.Database Service.Create Autonomous Data Guard Association.begin",\\
 "source": "databaseservice",
 "eventTypeVersion": "2.0",
 "eventTime": "2019-06-27T21:16:04Z",
 "contentType": "application/json",
 "data": {
    "eventGroupingId": "<unique ID>",
    "eventName"="CreateAutonomousDataGuardAssociation"
    "compartmentId": "ocid1.compartment.oc1..<unique ID>",
    "compartmentName": "example name",
    "resourceVersion":null,
    "resourceName": "my container database",
    "resourceId": "<unique_ID>",
    "availabilityDomain": "all",
```



```
"tagSlug": "<slug ID>",
    "definedTags": {},
    "additionalDetails": {
      "lifecycleState": "PROVISIONING",
      "DGConfigId"="91f298da-b890-42ce-935b-9b841e908756",
      "ApplyLag"=null,
      "LastRoleChangeTime"=null,
      "TransportLag"=null,
"autonomousContainerDatabaseId"="ocid1.autonomouscontainerdatabase.oc1.
sea.<unique ID>",
      "DGConfigState"=null,
      "lifeCycleMessage"=null,
      "lastUpdatedIdentifier"=null,
      "SyncState"=null,
"autonomousExadataInfrastructureId"="ocid1.autonomousvmcluster.oc1.sea.
<unique ID>",
      "timeUpdated"="2020-10-18 23:02:34.864",
      "timeCreated"="2020-10-18 23:02:34.864",
      "dbHomeId"="ocid1.autonomouspodhome.oc1.sea.<unique ID>",
      "LastSyncedTime"=null,
      "dcsDqUpdateTimestamp"=null,
   }
  }
}
```

This is a reference event for Autonomous Data Guard Association - Switchover Begin:

```
"cloudEventsVersion": "0.1",
 "eventID": "<unique ID>",
  "eventType":
"com.oraclecloud.DatabaseService.CreateAutonomousDataGuardAssociation.b
egin",
  "source": "databaseservice",
  "eventTypeVersion": "2.0",
  "eventTime": "2019-06-27T21:16:04Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "<unique ID>",
    "eventName"="SwitchoverAutonomousDataguardAssociation"
    "compartmentId": "ocid1.compartment.oc1..<unique ID>",
    "compartmentName": "example name",
    "resourceVersion":null,
    "resourceName": "my container database",
    "resourceId": "ocid1.autonomousdgassociation.oc1.sea.<unique ID>",
    "availabilityDomain": "all",
    "tagSlug": "<slug ID>",
    "definedTags": {},
    "stateChange": {
        "previous"=null,
        "current: {
            "lifecycleState"="ROLE CHANGE IN PROGRESS
```



```
"additionalDetails": {
      "lifecycleState": "ROLE CHANGE IN PROGRESS",
      "DGConfigId"="<unique ID>",
      "ApplyLag"="0 seconds computed 2 seconds ago",
      "LastRoleChangeTime"=null,
      "TransportLag"="0 seconds computed 2 seconds ago",
"autonomousContainerDatabaseId"="ocid1.autonomouscontainerdatabase.oc1.sea.<u
nique ID>",
      "DGConfigState"="SUCCESS",
      "lifeCycleMessage"=null,
      "lastUpdatedIdentifier"=null,
      "SyncState"="SYNCED",
"autonomousExadataInfrastructureId"="ocid1.autonomousvmcluster.oc1.sea.<uniqu
e ID>",
      "timeUpdated"="2020-10-18 23:02:34.864",
      "timeCreated"="2020-10-18 23:02:34.864",
      "dbHomeId"="ocid1.autonomouspodhome.oc1.sea.<unique ID>",
      "LastSyncedTime"=null,
      "dcsDqUpdateTimestamp"=null,
    }
  }
}
```

This is a reference event for Autonomous Data Guard Association - Failover Begin:

```
{
 "cloudEventsVersion": "0.1",
 "eventID": "<unique ID>",
 "eventType":
"com.oraclecloud.DatabaseService.CreateAutonomousDataGuardAssociation.begin",
 "source": "databaseservice",
 "eventTypeVersion": "2.0",
 "eventTime": "2019-06-27T21:16:04Z",
 "contentType": "application/json",
 "data": {
   "eventGroupingId": "<unique ID>",
   "eventName"="FailoverAutonomousDataguardAssociation"
   "compartmentId": "ocid1.compartment.oc1..<unique ID>",
   "compartmentName": "example name",
   "resourceVersion":null,
   "resourceName": "my container database",
   "resourceId": "ocid1.autonomousdgassociation.oc1.sea.<unique ID>",
   "availabilityDomain": "all",
   "tagSlug": "<slug ID>",
   "definedTags": {},
   "stateChange": {
       "previous"=null,
       "current: {
            "lifecycleState"="ROLE CHANGE IN PROGRESS
```



```
"additionalDetails": {
      "lifecycleState": "ROLE CHANGE IN PROGRESS",
      "DGConfigId"="<unique ID>",
      "ApplyLag"="0 seconds computed 2 seconds ago",
      "LastRoleChangeTime"=null,
      "TransportLag"="0 seconds computed 2 seconds ago",
"autonomousContainerDatabaseId"="ocid1.autonomouscontainerdatabase.oc1.
sea. <unique ID>",
      "DGConfigState"="SUCCESS",
      "lifeCycleMessage"=null,
      "lastUpdatedIdentifier"=null,
      "SyncState"="SYNCED",
"autonomousExadataInfrastructureId"="ocid1.autonomousvmcluster.oc1.sea.
<unique ID>",
      "timeUpdated"="2020-10-18 23:02:34.864",
      "timeCreated"="2020-10-18 23:02:34.864",
      "dbHomeId"="ocid1.autonomouspodhome.oc1.sea.<unique ID>",
      "LastSyncedTime"=null,
      "dcsDgUpdateTimestamp"=null,
    }
  }
}
This is a reference event for Autonomous Data Guard Association - Reinstate Begin:
{
  "cloudEventsVersion": "0.1",
  "eventID": "<unique ID>",
  "eventType":
"com.oraclecloud.DatabaseService.CreateAutonomousDataGuardAssociation.b
egin",
  "source": "databaseservice",
  "eventTypeVersion": "2.0",
  "eventTime": "2019-06-27T21:16:04Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "<unique ID>",
    "eventName"="ReinstateAutonomousDataGuardAssociation"
    "compartmentId": "ocid1.compartment.oc1..<unique ID>",
    "compartmentName": "example name",
    "resourceVersion":null,
    "resourceName": "my container database",
    "resourceId": "ocid1.autonomousdgassociation.oc1.sea.<unique ID>",
    "availabilityDomain": "all",
    "tagSlug": "<slug ID>",
    "definedTags": {},
    "stateChange": {
        "previous"=null,
        "current: {
            "lifecycleState"="ROLE CHANGE IN PROGRESS
```



```
"additionalDetails": {
     "lifecycleState": "ROLE_CHANGE_IN_PROGRESS",
      "DGConfigId"="<unique ID>",
      "ApplyLag"="0 seconds computed 2 seconds ago",
      "LastRoleChangeTime"=null,
      "TransportLag"="0 seconds computed 2 seconds ago",
"autonomousContainerDatabaseId"="ocid1.autonomouscontainerdatabase.oc1.sea.<u
nique ID>",
      "DGConfigState"="SUCCESS",
      "lifeCycleMessage"=null,
      "lastUpdatedIdentifier"=null,
      "SyncState"="SYNCED",
"autonomousExadataInfrastructureId"="ocid1.autonomousvmcluster.oc1.sea.<uniqu
e ID>",
      "timeUpdated"="2020-10-18 23:02:34.864",
      "timeCreated"="2020-10-18 23:02:34.864",
      "dbHomeId"="ocid1.autonomouspodhome.oc1.sea.<unique ID>",
      "LastSyncedTime"=null,
      "dcsDgUpdateTimestamp"=null,
}
```

Key Store Event Types

Review the list of event types that Key Store emits.

Table 7-15 Key Store Events

Friendly Name	Event Type
Key Store - Create	com.oraclecloud.databaseservice.createk eystore
Key Store - Update	<pre>com.oraclecloud.databaseservice.updatek eystore</pre>
Key Store - Terminate	<pre>com.oraclecloud.databaseservice.deletek eystore</pre>
Key Store - Change Compartment	<pre>com.oraclecloud.databaseservice.changek eystorecompartment</pre>
Autonomous Container Database - Rotate Key Begin	<pre>com.oraclecloud.databaseservice.rotatek eyautonomouscontainerdatabase.begin</pre>
Autonomous Container Database - Rotate Key End	<pre>com.oraclecloud.databaseservice.rotatek eyautonomouscontainerdatabase.end</pre>
Autonomous Database - Rotate Key Begin	<pre>com.oraclecloud.databaseservice.rotatek eyautonomousdatabase.begin</pre>
Autonomous Database - Rotate Key End	com.oraclecloud.databaseservice.rotatek eyautonomousdatabase.end

Example 7-71 Key Store Example

This is a reference event for Create Key Store:

```
{
   "cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType": "com.oraclecloud.databaseservice.createkeystore",
   "source": "databaseservice",
   "eventTypeVersion": "version",
    "eventTime": "2020-10-27T21:16:04Z",
    "contentType": "application/json",
    "extensions": {
      "compartmentId": "ocid1.compartment.oc1..unique ID"
    },
    "data": {
     "compartmentId": "ocid1.compartment.oc1..unique ID",
      "compartmentName": "example name",
      "resourceName": "my keystore",
      "resourceId": "KeyStore-unique ID",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "timeUpdated"="2020-10-27 21:16:34.864",
        "timeCreated"="2020-10-27 21:16:34.864",
        "keyStoreType": "all",
        "connectionIps": "ip1, ip2",
        "adminUsername": "username",
  }
```

Exadata Cloud@Customer Infrastructure Maintenance Event Types

Review the list of event types that Exadata Cloud@Customer Infrastructure Maintenance emits.

Table 7-16 Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
Exadata Infrastructure - Virtual Machines Maintenance Begin	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancevm.begi n	This is an Oracle Cloud Operations notice regarding the quarterly maintenance update of the Database Server component of your ExaCC Infrastructure instance <infra- name="">, ocid <infra-ocid> has started. A follow-up notice will be sent when the Database Server maintenance operation has completed.</infra-ocid></infra->



Table 7-16 (Cont.) Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
Exadata Infrastructure - Virtual Machines Maintenance End	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancevm.end	This is an Oracle Cloud Operations notice that quarterly maintenance update of the Database Server component of your ExaCC Infrastructure instance <infra-name>, ocid <infra- ocid="">; Database Server <dbserver name=""> ocid <dbserver ocid=""> has completed.</dbserver></dbserver></infra-></infra-name>
Exadata Infrastructure - Maintenance Scheduled	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenanceschedul ed	Rolling Oracle Cloud Operations is announcing the availability of a new quarterly maintenance update for ExaCC Infrastructure.
		Oracle has scheduled the installation of this new update on your service instance <infra-name>, ocid <infra-ocid> on <time-scheduled>.</time-scheduled></infra-ocid></infra-name>
		The maintenance method for this maintenance is Rolling as selected per the maintenance preferences.
		Non Rolling Oracle Cloud Operations is announcing the availability of a new quarterly maintenance update for ExaCC Infrastructure.
		Oracle has scheduled the installation of this new update on your service instance <infra-name>, ocid <infra-ocid> on <time-scheduled>.</time-scheduled></infra-ocid></infra-name>
		The maintenance method for this maintenance is Non Rolling as selected per the maintenance preferences.
		Non-rolling maintenance minimizes maintenance time but will result in full system downtime.



Table 7-16 (Cont.) Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
- Maintenance Reminder eservice.ex	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancereminde r	Rolling: This is an Oracle Cloud Operations reminder notice. Oracle has scheduled a quarterly maintenance update installation for ExaCC Infrastructure instance <infra-name>, ocid <ocid> in approximately <no-of- days=""> days on <time- scheduled="">. The maintenance method for this maintenance is Rolling as selected per the maintenance preferences.</time-></no-of-></ocid></infra-name>
		Non Rolling:
		This is an Oracle Cloud Operations reminder notice. Oracle has scheduled a quarterly maintenance update installation for ExaCC Infrastructure instance <infra-name>, ocid <ocid> in approximately <no-of-days> days on <time-scheduled>. The maintenance method for this maintenance is Non Rolling as selected per the maintenance preferences. Non-rolling maintenance minimizes maintenance time but will result in full system downtime.</time-scheduled></no-of-days></ocid></infra-name>
Exadata Infrastructure - Maintenance Begin	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenance.begin	This is an Oracle Cloud Operations notice regarding the quarterly maintenance update installation for your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid>. The update installation for the service started at <time scheduled="">. A follow-up notice will be sent when the maintenance update operation has completed.</time></infra-ocid></infra-name>



Table 7-16 (Cont.) Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
Exadata Infrastructure - Maintenance End	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenance.end	Success: This is an Oracle Cloud Operations notice that your ExaCC Infrastructure quarterly maintenance update installation for service instance <infra-name>, ocid <infra-ocid> which started at <maintenance-start-time> is now successfully complete. Failed: This is an Oracle Cloud Operations notice that your ExaCC Infrastructure quarterly maintenance update installation for service instance <infra-name>, ocid <infra-ocid> which started at <maintenance-start-time> has failed to complete due to technical reasons and</maintenance-start-time></infra-ocid></infra-name></maintenance-start-time></infra-ocid></infra-name>
		the operations team are currently looking into the issue. You will receive regular notifications to track the progress of this maintenance.
Exadata Infrastructure - Maintenance Custom action time Begin	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancecustoma ctiontime.begin	This is an Oracle Cloud Operations notice that the custom action timeout for your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid>; Database Server <dbserver name="">, ocid <dbserver ocid=""> has started. A follow-up notice will be sent when the custom action timeout has ended.</dbserver></dbserver></infra-ocid></infra-name>
Exadata Infrastructure - Maintenance Custom action time End	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancecustoma ctiontime.end	This is an Oracle Cloud Operations notice that the custom action timeout for your ExaCC Infrastructure instance <infra-name>, ocid <infra- ocid>; Database Server <dbserver name="">, ocid <dbserver ocid=""> has ended.</dbserver></dbserver></infra- </infra-name>



Table 7-16 (Cont.) Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
Exadata Infrastructure - maintenance Network Switches Begin	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancenetwork switches.begin	This is an Oracle Cloud Operations notice regarding the quarterly maintenance update of the network fabric switches component of your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid> has started. A follow-up notice will be sent when the network fabric switches maintenance operation has completed.</infra-ocid></infra-name>
Exadata Infrastructure - maintenance Network Switches End	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancenetwork switches.end	This is an Oracle Cloud Operations notice that quarterly maintenance update of the network fabric switches component of your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid> has completed.</infra-ocid></infra-name>
Exadata Infrastructure - maintenance Storage servers Start	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancestorage servers.start	This is an Oracle Cloud Operations notice regarding the quarterly maintenance update of Storage servers component of your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid> has started. A follow-up notice will be sent when storage servers maintenance operation has completed.</infra-ocid></infra-name>
Exadata Infrastructure - maintenance Storage servers End	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancestorage servers.end	This is an Oracle Cloud Operations notice that quarterly maintenance update of Storage servers component of your ExaCC Infrastructure instance <infra-name>, ocid <infra-ocid> has completed.</infra-ocid></infra-name>
Exadata Infrastructure - Maintenance Rescheduled	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenanceresched uled	Oracle Cloud Operations is announcing reschedule of a quarterly maintenance update for ExaCC Infrastructure. A maintenance run has been rescheduled on your service instance <infra-name>, ocid <infra-ocid> to <new-schedule-time>.</new-schedule-time></infra-ocid></infra-name>



Table 7-16 (Cont.) Exadata Cloud@Customer Infrastructure Maintenance Events

Friendly Name	Event Type	Event Message
Exadata Infrastructure - Maintenance Method Change	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenancemethodc hange	Oracle Cloud Operations is announcing a change related to quarterly maintenance update for ExaCC Infrastructure. There's a change in maintenance method on your service instance <infra-name>, ocid <infra-ocid> to <new-maintenance-method>.</new-maintenance-method></infra-ocid></infra-name>
Exadata Infrastructure - Maintenance ReScheduled With Reason	com.oraclecloud.databas eservice.exaccinfrastru cturemaintenanceresched uledwithreason	Event message provided is a custom message sent from Oracle Cloud Operations.

Example 7-72 Exadata Cloud@Customer Infrastructure Maintenance Events Examples

This is a reference event for Exadata Infrastructure - Virtual Machines Maintenance Begin:

```
"exampleEvent": {
 "cloudEventsVersion": "0.1",
 "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
 "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenancevm.begin",
 "source": "databaseservice",
 "eventTypeVersion": "2.0",
 "eventTime": "2019-06-27T21:16:04.000Z",
 "contentType": "application/json",
 "data": {
   "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
   "eventName": "ExaccInfrastructureMaintenanceVM",
   "compartmentId": "ocid1.compartment.oc1.....unique id",
   "compartmentName": "example compartment",
   "resourceName": "my exacc infrastructure",
   "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
   "availabilityDomain": "all",
   "freeFormTags": {},
   "definedTags": {},
   "additionalDetails": {
           "id": "ocid1.dbmaintenancerun.oc1...unique ID",
           "lifecycleState": "AVAILABLE",
           "timeCreated": "2019-08-29T12:00:00.000Z",
           "timeScheduled": "2019-08-29T12:30:00.000Z",
           "timeStarted": "2019-08-29T12:30:00.000Z",
           "description": "ExaCC Infrastructure Maintenance Notifications",
           "message": "detailed message",
            "shape": "ExadataCC.Base3.48",
           "displayName": "testDisplayName"
```



```
}
```

This is a reference event for Exadata Infrastructure - Virtual Machines Maintenance End:

```
"exampleEvent": {
  "cloudEventsVersion": "0.1",
  "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
  "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenancevm.end",
  "source": "databaseservice",
  "eventTypeVersion": "2.0",
  "eventTime": "2019-06-27T21:16:04.000Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
    "eventName": "ExaccInfrastructureMaintenanceVM",
    "compartmentId": "ocid1.compartment.oc1.....unique id",
    "compartmentName": "example compartment",
    "resourceName": "my exacc infrastructure",
    "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
       "additionalDetails": {
          "id": "ocid1.dbmaintenancerun.oc1...unique ID",
          "lifecycleState": "AVAILABLE",
          "timeCreated": "2019-08-29T12:00:00.000Z",
          "timeScheduled": "2019-08-29T12:30:00.000Z",
          "timeEnded": "2019-08-29T12:30:00.000Z",
          "description": "ExaCC Infrastructure Maintenance
Notifications",
          "message": "detailed message",
          "shape": "ExadataCC.Base3.48",
          "displayName": "testDisplayName"
       }
  }
}
```

This is a reference event for Exadata Infrastructure - Maintenance Scheduled:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
    "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenanceschedule
d",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
```



```
"eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
    "eventName": "ExaccInfrastructureMaintenanceScheduled",
    "compartmentId": "ocid1.compartment.oc1.....unique id",
    "compartmentName": "example compartment",
    "resourceName": "my exacc infrastructure",
    "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
        "id": "ocid1.dbmaintenancerun.oc1...unique ID",
         "lifecycleState": "AVAILABLE",
         "timeCreated": "2019-08-29T12:00:00.000Z",
         "timeScheduled": "2019-08-29T12:30:00.000Z",
         "description": "ExaCC Infrastructure Maintenance Notifications",
         "message": "detailed message",
         "shape": "ExadataCC.Base3.48",
         "displayName": "testDisplayName"
    }
}
```

This is a reference event for Exadata Infrastructure - Maintenance Reminder:

```
"exampleEvent": {
   "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
   "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenancereminder",
   "source": "databaseservice",
   "eventTypeVersion": "2.0",
   "eventTime": "2019-06-27T21:16:04.000Z",
   "contentType": "application/json",
   "data": {
        "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
        "eventName": "ExaccInfrastructureMaintenanceReminder",
        "compartmentId": "ocid1.compartment.oc1.....unique id",
        "compartmentName": "example compartment",
       "resourceName": "my exacc infrastructure",
       "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
        "availabilityDomain": "all",
        "freeFormTags": {},
         "definedTags": {},
         "additionalDetails": {
             "id": "ocid1.dbmaintenancerun.oc1...unique ID",
             "lifecycleState": "AVAILABLE",
             "timeCreated": "2019-08-29T12:00:00.000Z",
             "timeScheduled": "2019-08-29T12:30:00.000Z",
             "description": "ExaCC Infrastructure Maintenance Notifications",
             "message": "detailed message",
             "shape": "ExadataCC.Base3.48",
             "displayName": "testDisplayName"
```



```
}
```

This is a reference event for Exadata Infrastructure - Maintenance Begin:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
    "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenance.begin",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
        "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
        "eventName": "ExaccInfrastructureMaintenance",
        "compartmentId": "ocid1.compartment.oc1.....unique id",
        "compartmentName": "example compartment",
        "resourceName": "my exacc infrastructure",
        "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
        "availabilityDomain": "all",
        "freeFormTags": {},
        "definedTags": {},
        "additionalDetails": {
            "id": "ocid1.dbmaintenancerun.oc1...unique_ID",
            "lifecycleState": "AVAILABLE",
            "timeCreated": "2019-08-29T12:00:00.000Z",
            "timeScheduled": "2019-08-29T12:30:00.000Z",
            "timeStarted": "2019-08-29T12:30:00.000Z",
            "description": "ExaCC Infrastructure Maintenance
Notifications",
            "message": "detailed message",
            "shape": "ExadataCC.Base3.48",
            "displayName": "testDisplayName"
    }
}
```

This is a reference event for Exadata Infrastructure - Maintenance End:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
    "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenance.end",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
        "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
        "eventName": "ExaccInfrastructureMaintenance",
        "compartmentId": "ocid1.compartment.oc1.....unique_id",
```



```
"compartmentName": "example compartment",
        "resourceName": "my exacc infrastructure",
        "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
        "availabilityDomain": "all",
        "freeFormTags": {},
        "definedTags": {},
        "additionalDetails": {
            "id": "ocid1.dbmaintenancerun.oc1...unique ID",
            "lifecycleState": "AVAILABLE",
            "timeCreated": "2019-08-29T12:00:00.000Z",
             "timeScheduled": "2019-08-29T12:30:00.000Z",
             "timeEnded": "2019-08-29T12:30:00.000Z",
             "description": "ExaCC Infrastructure Maintenance Notifications",
             "message": "detailed message",
             "shape": "ExadataCC.Base3.48",
             "displayName": "testDisplayName"
        }
  }
}
```

This is a reference event for Exadata Infrastructure - Maintenance Custom action time Begin:

```
"exampleEvent": {
   "cloudEventsVersion": "0.1",
   "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
   "eventType":
"com.oraclecloud.databaseservice.exaccinframtncustomactiontime.begin",
   "source": "databaseservice",
   "eventTypeVersion": "2.0",
   "eventTime": "2019-06-27T21:16:04.000Z",
   "contentType": "application/json",
   "data": {
     "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
     "eventName": "ExaccInfraMtnCustomActionTime",
     "compartmentId": "ocid1.compartment.oc1.....unique id",
     "compartmentName": "example compartment",
     "resourceName": "my exacc infrastructure",
     "resourceId": "ocid1.exadatainfrastructure.oc1....unique id",
     "availabilityDomain": "all",
     "freeFormTags": {},
     "definedTags": {},
     "additionalDetails": {
       "id": "ocid1.dbmaintenancerun.oc1...unique ID",
       "lifecycleState": "AVAILABLE",
       "timeCreated": "2019-08-29T12:00:00.000Z",
       "timeScheduled": "2019-08-29T12:30:00.000Z",
       "timeStarted": "2019-08-29T12:30:00.000Z",
       "description": "ExaCC Infrastructure Maintenance Notifications",
       "message": "detail message",
       "shape": "ExadataCC.Base3.48",
       "displayName": "testDisplayName"
   }
 }
```

This is a reference event for Exadata Infrastructure - Maintenance Custom action time End:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b44",
"com.oraclecloud.databaseservice.exaccinframtncustomactiontime.end",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
      "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
      "eventName": "ExaccInfraMtnCustomActionTime",
      "compartmentId": "ocid1.compartment.oc1......unique_id",
      "compartmentName": "example compartment",
      "resourceName": "my exacc infrastructure",
      "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "id": "ocid1.dbmaintenancerun.oc1...unique ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-08-29T12:00:00.000Z",
        "timeScheduled": "2019-08-29T12:30:00.000Z",
        "timeStarted": "2019-08-29T12:30:00.000Z",
        "description": "ExaCC Infrastructure Maintenance
Notifications",
        "message": "detail message",
        "shape": "ExadataCC.Base3.48",
        "displayName": "testDisplayName"
    }
  }
```

This is a reference event for Exadata Infrastructure - maintenance Network Switches Begin:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b98",
    "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenanceibswitch
.begin",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
        "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
        "eventName": "ExaccInfrastructureMaintenanceIBSwitch",
        "compartmentId": "ocid1.compartment.oc1......unique_id",
```



```
"compartmentName": "example compartment",
  "resourceName": "my exacc infrastructure",
  "resourceId": "ocidl.exadatainfrastructure.ocl.....unique id",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
    "id": "ocid1.dbmaintenancerun.oc1...unique ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-08-29T12:00:00.000Z",
    "timeScheduled": "2019-08-29T12:30:00.000Z",
    "timeStarted": "2019-08-29T12:30:00.000Z",
    "description": "ExaCC Infrastructure Maintenance Notifications",
    "message": "detail message",
    "shape": "ExadataCC.Base3.48",
    "displayName": "testDisplayName"
}
```

This is a reference event for Exadata Infrastructure - maintenance Network Switches End:

```
"exampleEvent": {
   "cloudEventsVersion": "0.1",
   "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b98",
   "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenanceibswitch.end",
   "source": "databaseservice",
   "eventTypeVersion": "2.0",
   "eventTime": "2019-06-27T21:16:04.000Z",
   "contentType": "application/json",
   "data": {
     "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
     "eventName": "ExaccInfrastructureMaintenanceIBSwitch",
     "compartmentId": "ocid1.compartment.oc1.....unique id",
     "compartmentName": "example compartment",
     "resourceName": "my exacc infrastructure",
     "resourceId": "ocid1.exadatainfrastructure.oc1....unique id",
     "availabilityDomain": "all",
     "freeFormTags": {},
     "definedTags": {},
     "additionalDetails": {
       "id": "ocid1.dbmaintenancerun.oc1...unique ID",
       "lifecycleState": "AVAILABLE",
       "timeCreated": "2019-08-29T12:00:00.000Z",
       "timeScheduled": "2019-08-29T12:30:00.000Z",
       "timeStarted": "2019-08-29T12:30:00.000Z",
       "description": "ExaCC Infrastructure Maintenance Notifications",
       "message": "detail message",
       "shape": "ExadataCC.Base3.48",
       "displayName": "testDisplayName"
   }
 }
```



This is a reference event for Exadata Infrastructure - maintenance Storage servers Start:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b55",
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenancestorages
ervers.begin",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
      "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
      "eventName": "ExaccInfrastructureMaintenanceStorageServers",
      "compartmentId": "ocid1.compartment.oc1.....unique id",
      "compartmentName": "example compartment",
      "resourceName": "my exacc infrastructure",
      "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
      "availabilityDomain": "all",
      "freeFormTags": {},
      "definedTags": {},
      "additionalDetails": {
        "id": "ocid1.dbmaintenancerun.oc1...unique ID",
        "lifecycleState": "AVAILABLE",
        "timeCreated": "2019-08-29T12:00:00.000Z",
        "timeScheduled": "2019-08-29T12:30:00.000Z",
        "timeStarted": "2019-08-29T12:30:00.000Z",
        "description": "ExaCC Infrastructure Maintenance
Notifications",
        "message": "detail message",
        "shape": "ExadataCC.Base3.48",
        "displayName": "testDisplayName"
      }
    }
  }
```

This is a reference event for Exadata Infrastructure - maintenance Storage servers End:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "b28fcda6-3d7b-4044-aa8e-7c21cde84b55",
    "eventType":
"com.oraclecloud.databaseservice.exaccinfrastructuremaintenancestorages
ervers.end",
    "source": "databaseservice",
    "eventTypeVersion": "2.0",
    "eventTime": "2019-06-27T21:16:04.000Z",
    "contentType": "application/json",
    "data": {
        "eventGroupingId": "4976b940-2c2d-4380-a669-1d70d071b187",
        "eventName": "ExaccInfrastructureMaintenanceStorageServers",
```



```
"compartmentId": "ocid1.compartment.oc1.....unique id",
  "compartmentName": "example compartment",
  "resourceName": "my exacc infrastructure",
  "resourceId": "ocid1.exadatainfrastructure.oc1.....unique id",
  "availabilityDomain": "all",
  "freeFormTags": {},
  "definedTags": {},
  "additionalDetails": {
    "id": "ocid1.dbmaintenancerun.oc1...unique ID",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2019-08-29T12:00:00.000Z",
    "timeScheduled": "2019-08-29T12:30:00.000Z",
    "timeStarted": "2019-08-29T12:30:00.000Z",
    "description": "ExaCC Infrastructure Maintenance Notifications",
    "message": "detail message",
    "shape": "ExadataCC.Base3.48",
    "displayName": "testDisplayName"
}
```

Storage Expansion Event Types

Review the list of event types that storage expansion emits.

Table 7-17 Storage Expansion Events

Friendly Name	Event Type
Exadata Infrastructure - Add Storage Capacity Begin	com.oraclecloud.databaseservice.addstor agecapacityexadatainfrastructure.begin
Exadata Infrastructure - Add Storage Capacity End	<pre>com.oraclecloud.databaseservice.addstor agecapacityexadatainfrastructure.end</pre>

Example 7-73 Storage Expansion Events Examples

This is a reference event for Exadata Infrastructure - Add Storage Capacity Begin:

```
"exampleEvent": {
    "cloudEventsVersion": "0.1",
    "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
    "eventType":
"com.oraclecloud.databaseservice.addstoragecapacityexadatainfrastructure.begin",
    "source": "databaseservice",
    "eventTypeVersion": "1.0",
    "eventTypeVersion": "1.0",
    "eventTime": "2019-08-29T21:16:04.000Z",
    "contentType": "application/json",
    "extensions": {
        "compartmentId": "ocid1.compartment.oc1..unique_ID"
    },
    "data": {
        "compartmentId": "ocid1.compartment.oc1..unique_ID",
        "compartmentId": "example name",
```



```
"resourceName": "my exadata infra",
   "resourceId": "ExadataInfra-unique ID",
   "availabilityDomain": "all",
   "freeFormTags": {},
   "definedTags": {},
   "additionalDetails": {
      "id": "ocid1.id..oc1...unique ID",
     "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-08-29T12:00:00.000Z",
      "timeUpdated": "2019-08-29T12:30:00.000Z",
      "lifecycleDetails": "detail message",
      "shape": "ExadataCC.X8",
      "timeZone": "US/Pacific",
      "displayName": "testDisplayName"
   }
 }
}
```

This is a reference event for Exadata Infrastructure - Add Storage Capacity End:

```
"exampleEvent": {
  "cloudEventsVersion": "0.1",
  "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
  "eventType":
"com.oraclecloud.databaseservice.addstoragecapacityexadatainfrastructur
e.end",
  "source": "databaseservice",
  "eventTypeVersion": "1.0",
  "eventTime": "2019-08-29T21:16:04.000Z",
  "contentType": "application/json",
  "extensions": {
    "compartmentId": "ocid1.compartment.oc1..unique ID"
  },
  "data": {
    "compartmentId": "ocid1.compartment.oc1..unique ID",
    "compartmentName": "example name",
    "resourceName": "my exadata infra",
    "resourceId": "ExadataInfra-unique ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
      "id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-08-29T12:00:00.000Z",
      "timeUpdated": "2019-08-29T12:30:00.000Z",
      "lifecycleDetails": "detail message",
      "shape": "ExadataCC.X8",
      "timeZone": "US/Pacific",
      "displayName": "testDisplayName"
    }
}
```



Database Software Images Event Types

Review the list of event types that Database Software Image emits.

Table 7-18 Database Software Image Events

Action	Event Name	Event Type
Create Database Software Image	CreateDatabaseSoftwareIma ge CreateDatabaseSoftwareIma ge	com.oraclecloud.DatabaseS ervice.CreateDatabaseSoft wareImage.begin
		<pre>com.oraclecloud.DatabaseS ervice.CreateDatabaseSoft wareImage.end</pre>
Delete Database Software Image	DeleteDatabaseSoftwareIma ge DeleteDatabaseSoftwareIma ge	<pre>com.oraclecloud.DatabaseS ervice.DeleteDatabaseSoft wareImage.begin</pre>
		<pre>com.oraclecloud.DatabaseS ervice.DeleteDatabaseSoft wareImage.end</pre>
List Database Software Images	ListDatabaseSoftwareImage s	<pre>com.oraclecloud.DatabaseS ervice.ListDatabaseSoftwa reImages</pre>
Get Database Software Image	GetDatabaseSoftwareImage	<pre>com.oraclecloud.DatabaseS ervice.GetDatabaseSoftwar eImage</pre>
Change compartment of Database Software Image	MoveDatabaseSoftwareImage MoveDatabaseSoftwareImage	com.oraclecloud.DatabaseS ervice.MoveDatabaseSoftwa reImage.begin
		<pre>com.oraclecloud.DatabaseS ervice.MoveDatabaseSoftwa reImage.end</pre>
Update Database Software Image	UpdateDatabaseSoftwareIma ge	<pre>com.oraclecloud.DatabaseS ervice.UpdateDatabaseSoft wareImage</pre>

Example 7-74 Database Software Image Events Examples

This is a reference event for Create Database Software Image - Begin:

```
{
  "eventType":
  "com.oraclecloud.DatabaseService.CreateDatabaseSoftwareImage.begin",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "6dcad2c5-de0a-4e46-9a18-25c66f292dcf",
  "eventTime": "2021-06-18T04:04:35.451Z",
  "contentType": "application/json",
  "data": {
      "eventGroupingId": "csid68e598ea4474b18860cdd476af4a/
```



```
b46a0a70da064d57a149c3c49b7cc588/FB22262C016611EFC401A9292187861D",
    "eventName": "CreateDatabaseSoftwareImage",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaaa34gwbez3dbo7urtcf462wj3mnmanbba5xgincz
qm2z5d64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DBImage 19c",
    "resourceId":
"ocid1.databasesoftwareimage.oc1.sea.abzwkljsbpu3kxb54loym5sgkn2z4briz4
xbokhouxywkir764ht4txx4nya",
    "availabilityDomain": "AD2",
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": "xxxx",
      "principalId":
"ocid1.user.region1..aaaaaaaaedlsln4welqy3upwitxqrss3fnu6potqmds4xo3xld
5sqyzwbveq",
      "authType": "natv",
      "callerName": null,
      "callerId": null,
      "tenantId":
"ocid1.tenancy.region1..aaaaaaaaa34gwbez3dbo7urtcf462wj3mnmanbba5xqincz
gm2z5d64cn15q",
      "ipAddress": "160.34.124.111",
      "credentials": ""
    } ,
    "request": {
      "id": "csid68e598ea4474b18860cdd476af4a/
b46a0a70da064d57a149c3c49b7cc588/FB22262C016611EFC401A9292187861D",
      "path": "/20160918/databaseSoftwareImages",
      "action": "POST",
      "parameters": {},
      "headers": {}
    },
    "response": {
      "status": "200",
      "responseTime": "2021-06-18T04:04:36.457Z",
      "headers": {},
      "payload": null,
      "message": "CreateDatabaseSoftwareImage succeeded"
    "stateChange": {
      "previous": null,
      "current": {
        "displayName": "DBImage 19c",
        "lifecycleState": "PROVISIONING"
      }
    },
    "additionalDetails": {
      "dbVersion": "19.0.0.0",
      "displayName": "DBImage 19c",
      "lifecycleState": "PROVISIONING",
      "timeCreated": "2021-06-18T04:04:35.739Z"
    }
```

```
}
```

This is a reference event for Create Database Software Image – End

```
"eventType":
"com.oraclecloud.DatabaseService.CreateDatabaseSoftwareImage.end",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "7bf14762-1ec7-4230-99d0-6323c5e8b3cb",
  "eventTime": "2021-06-18T04:26:24.119Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csid68e598ea4474b18860cdd476af4a/
b46a0a70da064d57a149c3c49b7cc588/FB22262C016611EFC401A9292187861D",
    "eventName": "CreateDatabaseSoftwareImage",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqinczgm2z5d
64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DBImage_19c",
    "resourceId":
"ocid1.databasesoftwareimage.oc1.sea.abzwkljsbpu3kxb54loym5sgkn2z4briz4xbokho
uxywkir764ht4txx4nya",
    "availabilityDomain": null,
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": null,
      "principalId": null,
      "authType": null,
      "callerName": null,
      "callerId": null,
      "tenantId": null,
      "ipAddress": null,
      "credentials": null,
      "userAgent": null,
      "consoleSessionId": null
    },
    "request": {
      "id": "d2030b31-16aa-4e71-9b06-dabc7545ad65",
      "path": null,
      "action": null,
      "parameters": null,
      "headers": null
    "response": {
      "status": null,
      "responseTime": "2021-06-18T04:26:24.119Z",
      "headers": null,
      "payload": null,
      "message": "CreateDatabaseSoftwareImage"
```



```
},
"stateChange": {
    "previous": null,
    "current": {
        "displayName": "DBImage_19c",
        "lifecycleState": "AVAILABLE"
    }
},
"additionalDetails": {
    "dbVersion": "19.0.0.0",
    "displayName": "DBImage_19c",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2021-06-18T04:04:35.739Z"
}
}
```

This is a reference event for Delete Database Software Image – Start

```
"eventType":
"com.oraclecloud.DatabaseService.DeleteDatabaseSoftwareImage.begin",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "b789f327-ad93-45e1-a739-45fdb97c24d2",
  "eventTime": "2021-06-25T05:06:25.316Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidd793a61a40689138814477fa5c6e/
ffe9b65c8dcf425c9b30ae1a30ae5687/B7CA65C1DDBEDB55052051EF1113DB73",
    "eventName": "DeleteDatabaseSoftwareImage",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaae34qwbez3dbo7urtcf462wj3mnmanbba5xqincz
gm2z5d64cn15g",
    "compartmentName": "sic-dbaas",
    "resourceName": "DBImage 202106152041",
    "resourceId":
"ocid1.databasesoftwareimage.oc1.sea.abzwkljrzqt4tr326jtdmyudcziz6h5uhc
e36jbndxojgeg5kpwjcipxelga",
    "availabilityDomain": "AD2",
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": "xxx",
      "principalId":
"ocid1.user.region1..aaaaaaaaedlsln4welqy3upwitxqrss3fnu6potqmds4xo3xld
5sqyzwbveq",
      "authType": "natv",
      "callerName": null,
      "callerId": null,
      "tenantId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqincz
gm2z5d64cn15g",
```



```
"ipAddress": "160.34.124.245",
      "credentials": ""
    },
    "request": {
      "id": "csidd793a61a40689138814477fa5c6e/
ffe9b65c8dcf425c9b30ae1a30ae5687/B7CA65C1DDBEDB55052051EF1113DB73",
      "path": "/20160918/databaseSoftwareImages/
ocid1.databasesoftwareimage.oc1.sea.abzwkljrzgt4tr326jtdmyudcziz6h5uhce36jbnd
xojgeg5kpwjcipxelga",
      "action": "DELETE",
      "parameters": {},
      "headers": {}
    },
    "response": {
      "status": "204",
      "responseTime": "2021-06-25T05:06:26.074Z",
      "headers": {},
      "payload": null,
      "message": "DeleteDatabaseSoftwareImage succeeded"
    },
    "stateChange": {
      "previous": null,
      "current": {
        "displayName": "DBImage 202106152041",
        "lifecycleState": "AVAILABLE"
    },
    "additionalDetails": {
     "dbVersion": "19.0.0.0",
      "displayName": "DBImage 202106152041",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2021-06-15T15:11:53.672Z"
    }
```

This is a reference event for Delete Database Software Image – End

```
{
"eventType":
"com.oraclecloud.DatabaseService.DeleteDatabaseSoftwareImage.end",
 "cloudEventsVersion": "0.1",
 "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "6a1a808f-f5dd-4fb5-9d77-3bad38591998",
 "eventTime": "2021-06-25T05:07:21.454Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidd793a61a40689138814477fa5c6e/
ffe9b65c8dcf425c9b30ae1a30ae5687/B7CA65C1DDBEDB55052051EF1113DB73",
    "eventName": "DeleteDatabaseSoftwareImage",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqinczgm2z5d
64cn15q",
```

```
"compartmentName": "sic-dbaas",
    "resourceName": "DBImage 202106152041",
    "resourceId":
"ocid1.databasesoftwareimage.oc1.sea.abzwkljrzqt4tr326jtdmyudcziz6h5uhc
e36jbndxojgeg5kpwjcipxelga",
    "availabilityDomain": null,
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": null,
      "principalId": null,
      "authType": null,
      "callerName": null,
      "callerId": null,
      "tenantId": null,
      "ipAddress": null,
      "credentials": null,
      "userAgent": null,
      "consoleSessionId": null
    },
    "request": {
      "id": "676465d5-e066-43e4-bb21-77dc468ce1f9",
      "path": null,
      "action": null,
      "parameters": null,
      "headers": null
    },
    "response": {
      "status": null,
      "responseTime": "2021-06-25T05:07:21.454Z",
      "headers": null,
      "payload": null,
      "message": "DeleteDatabaseSoftwareImage"
    },
    "stateChange": {
      "previous": null,
      "current": {
        "displayName": "DBImage 202106152041",
        "lifecycleState": "TERMINATED"
    },
    "additionalDetails": {
      "dbVersion": "19.0.0.0",
      "displayName": "DBImage 202106152041",
      "lifecycleState": "TERMINATED",
      "timeCreated": "2021-06-15T15:11:53.672Z"
    }
  }
}
This is a reference event for List Database Software Images
```

```
"eventType":
```

```
"com.oraclecloud.DatabaseService.ListDatabaseSoftwareImages",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "762072e3-52a0-437c-9956-334aad767db8",
  "eventTime": "2021-06-24T05:39:41.344Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": null,
    "eventName": "ListDatabaseSoftwareImages",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqinczgm2z5d
64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "",
    "resourceId": null,
    "availabilityDomain": "AD2",
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": "xxx",
      "principalId":
"ocid1.user.region1..aaaaaaaaedlsln4welgy3upwitxqrss3fnu6potqmds4xo3xld5sqyzw
bveq",
      "authType": "natv",
      "callerName": null,
      "callerId": null,
      "tenantId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqinczgm2z5d
64cn15q",
      "ipAddress": "160.34.125.213",
      "credentials": "",
      "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X 10 15 7)
AppleWebKit/537.36 (KHTML, like Gecko) Chrome/91.0.4472.77 Safari/537.36",
      "consoleSessionId": "csidc25d57894f49986ae07157ab5e03"
    },
    "request": {
      "id": "csidc25d57894f49986ae07157ab5e03/
dc74ad5a75d7494bb35408a33a99c0ad/084F718D53FBC66D46B573CF8D5D1A5A",
      "path": "/20160918/databaseSoftwareImages",
      "action": "GET",
      "parameters": {},
      "headers": {}
    },
    "response": {
      "status": "200",
      "responseTime": "2021-06-24T05:39:41.998Z",
      "headers": {},
      "payload": null,
      "message": "ListDatabaseSoftwareImages succeeded"
    },
    "stateChange": {
      "previous": null,
      "current": null
    },
```

```
"additionalDetails": null
}
```

This is a reference event for Get Database Software Image

```
"eventType":
\verb"com.oraclecloud.DatabaseService.GetDatabaseSoftwareImage",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "179471f3-c628-4e55-98d0-959b0913b327",
  "eventTime": "2021-06-24T04:11:10.738Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csid31b4236f4f1ebc4ee66169d17b0a/
1f2e5dbf57ca40c886b111616b02c33f/CA5B5AD4C8678E2C428DA9AF0C62A082",
    "eventName": "GetDatabaseSoftwareImage",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaae34qwbez3dbo7urtcf462wj3mnmanbba5xqincz
gm2z5d64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DBImage 19c",
    "resourceId":
"ocid1.databasesoftwareimage.oc1.sea.abzwkljsbpu3kxb54loym5sgkn2z4briz4
xbokhouxywkir764ht4txx4nya",
    "availabilityDomain": "AD2",
    "freeformTags": null,
    "definedTags": null,
    "identity": {
      "principalName": "xxx",
      "principalId":
"ocid1.user.region1..aaaaaaaalkib75hbawg6xh6rlys5ztumfx3cxf2ktwbon5ryv6
xjev7oectq",
      "authType": "natv",
      "callerName": null,
      "callerId": null,
      "tenantId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqincz
gm2z5d64cn15g",
      "ipAddress": "192.188.170.109",
      "credentials": "",
      "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X 10 15 7)
AppleWebKit/537.36 (KHTML, like Gecko) Chrome/91.0.4472.106 Safari/
537.36",
      "consoleSessionId": "csid31b4236f4f1ebc4ee66169d17b0a"
    "request": {
      "id": "csid31b4236f4f1ebc4ee66169d17b0a/
1f2e5dbf57ca40c886b111616b02c33f/CA5B5AD4C8678E2C428DA9AF0C62A082",
      "path": "/20160918/databaseSoftwareImages/
ocid1.databasesoftwareimage.oc1.sea.abzwkljsbpu3kxb54loym5sgkn2z4briz4x
bokhouxywkir764ht4txx4nya",
```



```
"action": "GET",
      "parameters": {},
      "headers": {}
    "response": {
      "status": "200",
      "responseTime": "2021-06-24T04:11:10.966Z",
      "headers": {},
      "payload": null,
      "message": "GetDatabaseSoftwareImage succeeded"
    "stateChange": {
      "previous": null,
      "current": {
        "displayName": "DBImage 19c",
        "lifecycleState": "AVAILABLE"
    },
    "additionalDetails": {
      "dbVersion": "19.0.0.0",
      "displayName": "DBImage 19c",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2020-09-24T18:06:00.395Z"
  }
}
```

Database Upgrade Event Types

Review the list of event types that Database Upgrade emit.

Table 7-19 Database Upgrade Events

Friendly Name	Event Type
MoveDatabase	<pre>com.oraclecloud.DatabaseService.MoveDat abase.begin</pre>
	<pre>com.oraclecloud.DatabaseService.MoveDat abase.end</pre>
UpgradeDatabase	com.oraclecloud.DatabaseService.Upgrade Database.begin
	<pre>com.oraclecloud.DatabaseService.Upgrade Database.end</pre>

Example 7-75 Database Upgrade Examples

This is a reference event for Move Database Begin:

```
eventType": "com.oraclecloud.DatabaseService.MoveDatabase.begin"
"eventName": "MoveDatabase"
{
    "eventType": "com.oraclecloud.DatabaseService.MoveDatabase.begin",
    "cloudEventsVersion": "0.1",
```



```
"eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "c78fb931-adda-4813-ab75-b9cc51b96847",
  "eventTime": "2021-07-15T11:03:52.582Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidff49902144a1a3c98bd4e5f49c1c/
37d3a7113f1e462fbd5a741dc5d52ef7/57472323A2FFABC31623FB7660F519AB",
    "eventName": "MoveDatabase",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaaa34gwbez3dbo7urtcf462wj3mnmanbba5xqincz
qm2z5d64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DB211507",
    "resourceId":
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcq7at54bpsmdricyq4o
4trsr3pyiqhpq",
   "availabilityDomain": "",
    "freeformTags": {},
    "definedTags": {
      "Operators": {
        "Created By": "testuser@example.com",
        "Created Time": "2021-07-15T11:01:24.085Z"
   },
    "identity": {
      "principalName": null,
      "principalId": null,
      "authType": null,
      "callerName": null,
      "callerId": null,
      "tenantId": null,
      "ipAddress": null,
      "credentials": null,
      "userAgent": null,
      "consoleSessionId": null
    "request": {
     "id": "8f7b5283-4896-4ce0-aefa-a4156971e07b",
     "path": null,
      "action": null,
      "parameters": null,
      "headers": null
   },
    "response": {
      "status": null,
      "responseTime": null,
      "headers": null,
      "payload": null,
      "message": "MoveDatabase"
    },
    "stateChange": {
      "previous": null,
      "current": {
        "definedTags": {
```

```
"Operators": {
            "Created By": "testuser@example.com",
            "Created Time": "2021-07-15T11:01:24.085Z"
          }
        },
        "displayName": "DB211507",
        "freeTags": {},
        "lifecycleState": "UPGRADING"
      }
    },
    "additionalDetails": {
      "databaseEdition": "ENTERPRISE EDITION EXTREME",
      "databaseId":
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcg7at54bpsmdricyg4o4trsr3
pyiqhpq",
      "dbHomeId":
"ocid1.dbhome.oc1.sea.abzwkljskjhqcc4bkzuai6kybx3hp3jznvxcgwlghqjnklpchrktcyn
wnloq",
      "dbUniqueName": "Audit check",
      "dbVersion": "18.14.0.0",
      "exadataInfrastructureId":
"ocidl.exadatainfrastructure.ocl.sea.abzwkljsqtwpumvorlttjuxcx6qtkxhuasvmyu4q
y3bng74sqolpwjunsrqa",
      "lifecycleState": "UPGRADING",
      "timeCreated": "2021-07-15T11:01:24Z",
      "timeUpdated": "2021-07-15T11:02:34Z",
      "vmClusterId":
"ocid1.vmcluster.oc1.sea.abzwkljsghfg7e3q3xh3gzqqxijt72fepczowmk35t554wxbpew7
txnooprq"
```

This is a reference event for Move Database End:

```
eventType": "com.oraclecloud.DatabaseService.MoveDatabase.end"
"eventName": "MoveDatabase"
  "eventType": "com.oraclecloud.DatabaseService.MoveDatabase.end",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "97429610-9b8f-4da7-8f99-2f7cd5455c24",
  "eventTime": "2021-07-15T11:03:56.359Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidff49902144a1a3c98bd4e5f49c1c/
37d3a7113f1e462fbd5a741dc5d52ef7/57472323A2FFABC31623FB7660F519AB",
    "eventName": "MoveDatabase",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xginczgm2z5d
64cn15q",
    "compartmentName": "sic-dbaas",
```

```
"resourceName": "DB211507",
    "resourceId":
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcg7at54bpsmdricyg4o
4trsr3pyiqhpq",
    "availabilityDomain": "",
    "freeformTags": {},
    "definedTags": {
      "Operators": {
        "Created By": "testuser@example.com",
        "Created Time": "2021-07-15T11:01:24.085Z"
    },
    "identity": {
      "principalName": null,
     "principalId": null,
     "authType": null,
      "callerName": null,
      "callerId": null,
      "tenantId": null,
      "ipAddress": null,
      "credentials": null,
      "userAgent": null,
      "consoleSessionId": null
    } ,
    "request": {
     "id": "8f7b5283-4896-4ce0-aefa-a4156971e07b",
      "path": null,
      "action": null,
      "parameters": null,
      "headers": null
    },
    "response": {
     "status": null,
     "responseTime": null,
      "headers": null,
      "payload": null,
      "message": "MoveDatabase"
    } ,
    "stateChange": {
      "previous": null,
      "current": {
        "definedTags": {
          "Operators": {
            "Created By": "testuser@example.com",
            "Created Time": "2021-07-15T11:01:24.085Z"
          }
        },
        "displayName": "DB211507",
        "freeTags": {},
        "lifecycleState": "AVAILABLE"
    },
    "additionalDetails": {
      "databaseEdition": "ENTERPRISE EDITION EXTREME",
      "databaseId":
```

```
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcq7at54bpsmdricyq4o4trsr3
pyiqhpq",
      "dbHomeId":
"ocid1.dbhome.oc1.sea.abzwkljs7obwmwq2kgkjgeko4voudfcd5chu6iuonnew7uuxculsvdr
      "dbUniqueName": "Audit check",
      "dbVersion": "19.10.0.0",
      "exadataInfrastructureId":
"ocidl.exadatainfrastructure.ocl.sea.abzwkljsqtwpumvorlttjuxcx6qtkxhuasvmyu4q
y3bng74sgolpwjunsrga",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2021-07-15T11:01:24Z",
      "timeUpdated": "2021-07-15T11:03:56Z",
      "vmClusterId":
"ocid1.vmcluster.oc1.sea.abzwkljsqhfq7e3q3xh3qzqqxijt72fepczowmk35t554wxbpew7
txnooprq"
    }
  }
}
```

This is a reference event for Upgrade Database Begin:

```
eventType": " com.oraclecloud.DatabaseService.UpgradeDatabase.begin"
"eventName": " UpgradeDatabase"
  "eventType": "com.oraclecloud.DatabaseService.UpgradeDatabase.begin",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "96c66a03-fa53-4008-b86c-619b9f44ef31",
  "eventTime": "2021-07-15T11:02:33.948Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidff49902144a1a3c98bd4e5f49c1c/
37d3a7113f1e462fbd5a741dc5d52ef7/57472323A2FFABC31623FB7660F519AB",
    "eventName": "UpgradeDatabase",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xginczgm2z5d
64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DB211507",
    "resourceId":
"ocid1.database.oc1.sea.abzwkljs5xinda6nuqhtf5tzapxhcq7at54bpsmdricyq4o4trsr3
pyiqhpq",
    "availabilityDomain": "",
    "freeformTags": {},
    "definedTags": {
      "Operators": {
        "Created By": "testuser@example.com",
        "Created Time": "2021-07-15T11:01:24.085Z"
    },
    "identity": {
```

```
"principalName": "testuser@example.com",
      "principalId":
"ocid1.user.region1..aaaaaaaac5dskxmhmemrbyhaeabru4kqpituqmvqxjcm5y22ml
xre26om4zq",
      "authType": "natv",
      "callerName": null,
      "callerId": null,
      "tenantId":
"ocid1.tenancy.region1..aaaaaaaae34gwbez3dbo7urtcf462wj3mnmanbba5xqincz
qm2z5d64cn15q",
      "ipAddress": "160.34.92.141",
      "credentials":
"ST$eyJraWQiOiJhc3dfcmVnaW9uMV8yMDIxLTA1LTE0IiwiYWxnIjoiUlMyNTYifQ.eyJz
dWIiOiJvY21kMS51c2VyLnJ1Z21vbjEuLmFhYWFhYWFhYzVkc2t4bWhtZW1yYnloYWVhYnJ
1NGtncGl0dXFtdmd4amNtNXkyMm1seHJlMjZvbTR6cSIsIm1mYV92ZXJpZml1ZCI6ImZhbH
NlliwiaXNzIjoiYXV0aFNlcnZpY2Uub3JhY2xlLmNvbSIsInB0eXBlIjoidXNlciIsInNlc
3NfZXhwIjoiRnJpLCAxNiBKdWwgMjAyMSAxMDo1OToxNyBVVEMiLCJhdWQiOiJvY2kiLCJw
c3R5cGUiOiJuYXR2IiwidHR5cGUiOiJsb2dpbiIsImV4cCI6MTYyNjM1MDM1OSwiaWF0Ijo
xNjI2MzQ2NzU5LCJqdGki0iJhNWE2YmRhNC02OGJkLTQ0ZjktODFlNS0yZGRiZGMyZWU4MT
QiLCJ0ZW5hbnQiOiJvY21kMS50ZW5hbmN5LnJ1Z21vbjEuLmFhYWFhYWFhZTM0Z3diZXozZ
GJvN3VydGNmNDYyd2ozbW5tYW5iYmE1eHFpbmN6Z20yejVkNjRjbmw1cSIsImp3ayI6Intc
ImtpZFwiOlwicHVia2V5LWU5Y2RmMWY4LTJjNTEtNGEyNi1hZjkyLTN1ZjlkNT1hNWEZN1w
iLFwiblwiOlwicjE1azFxR0s1MXJaVUZzLVdFNDFrU2ZLRWozanlndlZ2bG9pZVM5Y3RLOD
J4QmxZT1F3SkZwX19HUXVGTFktWk45MVZabXdSQkpFeHJYbE1hNHV6aE5VS1BNQ3M5OG9XT
ENpQmo2U1VMekFLZHVtbHZlbHEwTUcwVmtMMjVXb1hONzU2N19wUUx3NDc0T2w2VzNJU19J
d2tBVy1QZnF5QzdpY1NOekI2UXh2aGlVMXRpTUFUZ09RUjQ1Ty1md3NnVn15WW14eVNCbm1
sN1BDUEtoaGpBLT1F0FozeV94cn1PWFBuYj11Q1FrczZ0blqzX08yRkZ1UGxualN5QXd1SE
\verb|ZLSzd6MUJNVVdONUMtLV9Uemw5T0VaOENMeGdKNkpzeUUtRUVMeEZEUkZ0M1VHZGNubUVBY||
2hNQ1qxNEtnWEFELVk5a2dkVS1HczNaUU1VTW5pYmFRXCIsXCJ1XCI6XCJBUUFCXCIsXCJr
dHlcIjpcIlJTQVwiLFwiYWxnXCI6XCJSUzI1NlwiLFwidXNlXCI6bnVsbH0ifQ.GGPB9TMU
CkqOfLNCqO2J6-
QwvHEEaY6jky5T92PBoPOBUkXb ruNOe6C8RwQhs2pmIsIBybTP7Ueene4cJ9nNKzsoTzNA
UrSp9714Be2noQgqJL-ZtFIApThz1vXdfFWZtQQInxx-jALpsvkhvD EVdbfx6FvlwDfm-
ReNDSnrUoFkfx8NpIrkqP8KUFhnX-
TRyOnUvqlaiB9C1L8FZGOJbBnOuiyloZe4DNP3Z39jViy37UntHeuMPnIqOYEsmPrSMTiJU
BAypy4 I5irWuR0PpxfrttP6nlEi80V5YrmO312-
ZJBRDKz8TdMkxclw3IT0qulTzFPqB3cXq45PGQ",
      "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X 10.15;
rv:78.0) Gecko/20100101 Firefox/78.0",
      "consoleSessionId": "csidff49902144a1a3c98bd4e5f49c1c"
    },
    "request": {
      "id": "csidff49902144a1a3c98bd4e5f49c1c/
37d3a7113f1e462fbd5a741dc5d52ef7/57472323A2FFABC31623FB7660F519AB",
      "path": "/20160918/databases/
ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcq7at54bpsmdricyq4o4
trsr3pyiqhpq/actions/upgrade",
      "action": "POST",
      "parameters": {},
      "headers": {}
    },
    "response": {
      "status": "200",
      "responseTime": "2021-07-15T11:02:36.072Z",
      "headers": {},
```

```
"payload": null,
      "message": "UpgradeDatabase succeeded"
    },
    "stateChange": {
      "previous": null,
      "current": {
        "definedTags": {
          "Operators": {
            "Created By": "testuser@example.com",
            "Created Time": "2021-07-15T11:01:24.085Z"
          }
        },
        "displayName": "DB211507",
        "freeTags": {},
        "lifecycleState": "UPGRADING"
      }
    },
    "additionalDetails": {
      "action": "UPGRADE",
      "currentDbVersion": "18.14.0.0",
      "lifecycleState": "IN PROGRESS",
      "source": "DATABASE HOME",
      "targetDbVersion": "19.10.0.0",
      "timeStarted": "2021-07-15T11:02:34Z",
      "upgradeHistoryEntryId":
"ocid1.dbupgradehistory.oc1.sea.abzwkljstw7dymj6mfnaotkxpuie2bdxmlizgr5ie46de
wcuzdh35md7fuhq"
}
```

This is a reference event for Upgrade Database End:

```
eventType": " com.oraclecloud.DatabaseService.UpgradeDatabase.end"
"eventName": " UpgradeDatabase"
  "eventType": "com.oraclecloud.DatabaseService.UpgradeDatabase.end",
  "cloudEventsVersion": "0.1",
  "eventTypeVersion": "2.0",
  "source": "DatabaseService",
  "eventId": "e6c8a9e4-53b0-4bb8-be65-a39d157f04b2",
  "eventTime": "2021-07-15T11:03:56.028Z",
  "contentType": "application/json",
  "data": {
    "eventGroupingId": "csidff49902144a1a3c98bd4e5f49c1c/
37d3a7113f1e462fbd5a741dc5d52ef7/57472323A2FFABC31623FB7660F519AB",
    "eventName": "UpgradeDatabase",
    "compartmentId":
"ocid1.tenancy.region1..aaaaaaaaa34qwbez3dbo7urtcf462wj3mnmanbba5xqinczgm2z5d
64cn15q",
    "compartmentName": "sic-dbaas",
    "resourceName": "DB211507",
    "resourceId":
```



```
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcq7at54bpsmdricyq4o
4trsr3pyiqhpq",
    "availabilityDomain": "",
    "freeformTags": {},
    "definedTags": {
      "Operators": {
        "Created By": "testuser@example.com",
        "Created Time": "2021-07-15T11:01:24.085Z"
      }
    },
    "identity": {
      "principalName": null,
      "principalId": null,
      "authType": null,
      "callerName": null,
      "callerId": null,
      "tenantId": null,
      "ipAddress": null,
      "credentials": null,
      "userAgent": null,
      "consoleSessionId": null
    },
    "request": {
      "id": "8f7b5283-4896-4ce0-aefa-a4156971e07b",
      "path": null,
      "action": null,
      "parameters": null,
      "headers": null
    },
    "response": {
      "status": null,
      "responseTime": null,
      "headers": null,
      "payload": null,
      "message": "UpgradeDatabase"
    },
    "stateChange": {
      "previous": null,
      "current": {
        "definedTags": {
          "Operators": {
            "Created By": "testuser@example.com",
            "Created Time": "2021-07-15T11:01:24.085Z"
        },
        "displayName": "DB211507",
        "freeTags": {},
        "lifecycleState": "AVAILABLE"
    },
    "additionalDetails": {
      "databaseEdition": "ENTERPRISE EDITION EXTREME",
      "databaseId":
"ocid1.database.oc1.sea.abzwkljs5xinda6nughtf5tzapxhcq7at54bpsmdricyq4o
4trsr3pyiqhpq",
```

```
"dbHomeId":
"ocidl.dbhome.oc1.sea.abzwkljs7obwmwq2kgkjgeko4voudfcd5chu6iuonnew7uuxculsvdr
alzda",
    "dbUniqueName": "Audit_check",
    "dbVersion": "19.10.0.0",
    "exadataInfrastructureId":
"ocidl.exadatainfrastructure.oc1.sea.abzwkljsqtwpumvorlttjuxcx6qtkxhuasvmyu4q
y3bng74sqolpwjunsrqa",
    "lifecycleState": "AVAILABLE",
    "timeCreated": "2021-07-15T11:01:24Z",
    "timeUpdated": "2021-07-15T11:03:56Z",
    "vmClusterId":
"ocidl.vmcluster.oc1.sea.abzwkljsghfg7e3q3xh3gzqqxijt72fepczowmk35t554wxbpew7
txnooprq"
    }
}
```

Pluggable Database Event Types

Review the list of event types that Pluggable Databases emit.

Table 7-20 Pluggable Database Events

Friendly Name	Event Type
Pluggable Database - Create Begin	com.oraclecloud.databaseservice.createp luggabledatabase.begin
Pluggable Database - Create End	<pre>com.oraclecloud.databaseservice.createp luggabledatabase.end</pre>
Pluggable Database - Delete Begin	<pre>com.oraclecloud.databaseservice.deletep luggabledatabase.begin</pre>
Pluggable Database - Delete End	<pre>com.oraclecloud.databaseservice.deletep luggabledatabase.end</pre>
Pluggable Database - Local Clone Begin	<pre>com.oraclecloud.databaseservice.localcl onepluggabledatabase.begin</pre>
Pluggable Database - Local Clone End	<pre>com.oraclecloud.databaseservice.localcl onepluggabledatabase.end</pre>
Pluggable Database - Remote Clone Begin	<pre>com.oraclecloud.databaseservice.remotec lonepluggabledatabase.begin</pre>
Pluggable Database - Remote Clone End	<pre>com.oraclecloud.databaseservice.remotec lonepluggabledatabase.end</pre>
Start Pluggable Database - Begin	<pre>com.oraclecloud.databaseservice.startpl uggabledatabase.begin</pre>
Start Pluggable Database - End	<pre>com.oraclecloud.databaseservice.startpl uggabledatabase.end</pre>
Stop Pluggable Database - Start	<pre>com.oraclecloud.databaseservice.stopplu ggabledatabase.begin</pre>
Stop Pluggable Database - End	<pre>com.oraclecloud.databaseservice.stopplu ggabledatabase.end</pre>

Example 7-76 Pluggable Database Examples

This is a reference event for Pluggable Database - Create Begin:

```
"eventID": "aflcdf4e-4001-11eb-9fb6-f45c89b1cb17",
  "eventTime": "2020-12-17T00:49:14.123Z",
  "extensions": {
    "compartmentId": "ocid1.compartment.oc1..unique id"
  },
  "eventType":
"com.oraclecloud.databaseservice.createexternalpluggabledatabase",
 "eventTypeVersion": "2.0",
 "cloudEventsVersion": "0.1",
  "source": "databaseservice",
  "contentType": "application/json",
  "definedTags": {},
  "data": {
    "compartmentId": "ocid1.compartment.oc1.....unique id",
    "compartmentName": "MyCompartment",
    "resourceName": "11092020 PKS PDB1",
    "resourceId": "ocid1.externalpluggabledatabases.oc1.phx.unique id",
    "availabilityDomain": "XXIT:PHX-AD-1",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
     "id": "ocid1.externalpluggabledatabases.oc1.phx.unique id",
      "timeCreated": "2020-11-13T21:15:59.000Z",
      "timeUpdated": "2020-11-13T21:15:59.000Z",
      "externalCDBId":
"ocid1.externalcontainerdatabase.oc1....unique id",
     "lifecycleState": "AVAILABLE",
      "lifecycleDetails": "External Pluggable Database is available",
      "dbUniqueName": "CDB122 phx16q",
      "dbId": "3455094890",
      "dbVersion": "12.2.0.1.0",
      "dbEdition": "ENTERPRISE EDITION EXTREME PERFORMANCE",
      "timeZone": "US/Pacific",
      "databaseManagementServiceStatus": "ENABLED",
      "databaseManagementServiceConnectorId":
"ocid1.externaldatabaseconnector.oc1....unique id",
      "displayName": "External Pluggable Database - Create"
    }
}
```

VM Node Subsetting Event Types

Review the list of event types that VM Node Subsetting emits.



Table 7-21 VM Node Subsetting Events

Friendly Name	Event Type
VM Cluster - Add Virtual Machine Begin	com.oraclecloud.databaseservice.vmclust eraddvirtualmachine.begin
VM Cluster - Add Virtual Machine End	<pre>com.oraclecloud.databaseservice.vmclust eraddvirtualmachine.end</pre>
VM Cluster - Terminate Virtual Machine Begin	<pre>com.oraclecloud.databaseservice.vmclust erterminatevirtualmachine.begin</pre>
VM Cluster - Terminate Virtual Machine End	<pre>com.oraclecloud.databaseservice.vmclust erterminatevirtualmachine.end</pre>

Example 7-77 VM Node Subsetting Examples

This is a reference event for VM Cluster - Add Virtual Machine Begin:

```
"exampleEvent": {
"cloudEventsVersion": "0.1",
  "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
  "eventType":
"com.oraclecloud.databaseservice.vmclusteraddvirtualmachine.begin",
 "source": "databaseservice",
 "eventTypeVersion": "1.0",
  "eventTime": "2019-06-27T21:16:04.000Z",
  "contentType": "application/json",
 "extensions": {
"compartmentId": "ocid1.compartment.oc1..unique ID"
  "data": {
"compartmentId": "ocid1.compartment.oc1..unique ID",
    "compartmentName": "example name",
    "resourceName": "my database",
    "resourceId": "Vmcluster-unique ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
"id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-09-03T12:00:00.000Z",
      "timeUpdated": "2019-09-03T12:30:00.000Z",
      "displayName": "testDisplayName",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExatraInfra-unique ID",
      "vmClusterNetworkId": "VmCluster-unique ID",
      "cpuCoreCount": 2,
      "dataStorageSizeInTBs": 4,
      "memorySizeInGBs": 30,
      "dbNodeStorageSizeInGBs": 60,
      "dbVersion": "19.0.0.0",
      "licenseType": "BRING YOUR OWN LICENSE",
      "giVersion": "19.0.0.0",
```



```
"dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
   "dbServerIds": "[ocid1.dbserver.1, ocid1.dbserver.2,...]",
   "timeZone": "US/Pacific"
   }
}
```

This is a reference event for VM Cluster - Add Virtual Machine End:

```
"exampleEvent": {
"cloudEventsVersion": "0.1",
  "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
  "eventType":
"com.oraclecloud.databaseservice.vmclusteraddvirtualmachine.end",
  "source": "databaseservice",
  "eventTypeVersion": "1.0",
  "eventTime": "2019-06-27T21:16:04.000Z",
  "contentType": "application/json",
  "extensions": {
"compartmentId": "ocid1.compartment.oc1..unique ID"
 },
  "data": {
"compartmentId": "ocid1.compartment.oc1..unique ID",
    "compartmentName": "example name",
    "resourceName": "my database",
    "resourceId": "Vmcluster-unique ID",
    "availabilityDomain": "all",
   "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
"id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-09-03T12:00:00.000Z",
      "timeUpdated": "2019-09-03T12:30:00.000Z",
      "displayName": "testDisplayName",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExatraInfra-unique ID",
      "vmClusterNetworkId": "VmCluster-unique ID",
      "cpuCoreCount": 2,
      "dataStorageSizeInTBs": 4,
      "memorySizeInGBs": 30,
      "dbNodeStorageSizeInGBs": 60,
      "dbVersion": "19.0.0.0",
      "licenseType": "BRING YOUR OWN LICENSE",
      "giVersion": "19.0.0.0",
      "dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
      "dbServerIds": "[ocid1.dbserver.1, ocid1.dbserver.2,...]",
      "timeZone": "US/Pacific"
   }
  }
}
```



This is a reference event for VM Cluster - Terminate Virtual Machine Begin:

```
"exampleEvent": {
"cloudEventsVersion": "0.1",
  "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
  "eventType":
"com.oraclecloud.databaseservice.vmclusterterminatevirtualmachine.begin",
  "source": "databaseservice",
  "eventTypeVersion": "1.0",
  "eventTime": "2019-06-27T21:16:04.000Z",
  "contentType": "application/json",
  "extensions": {
"compartmentId": "ocid1.compartment.oc1..unique ID"
  },
  "data": {
"compartmentId": "ocid1.compartment.oc1..unique_ID",
    "compartmentName": "example name",
    "resourceName": "my database",
    "resourceId": "Vmcluster-unique ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
"id": "ocid1.id..oc1...unique ID",
     "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-09-03T12:00:00.000Z",
      "timeUpdated": "2019-09-03T12:30:00.000Z",
      "displayName": "testDisplayName",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExatraInfra-unique ID",
      "vmClusterNetworkId": "VmCluster-unique ID",
      "cpuCoreCount": 2,
      "dataStorageSizeInTBs": 4,
      "memorySizeInGBs": 30,
      "dbNodeStorageSizeInGBs": 60,
      "dbVersion": "19.0.0.0",
      "licenseType": "BRING YOUR OWN LICENSE",
      "giVersion": "19.0.0.\overline{0}",
      "dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
      "dbServerIds": "[ocid1.dbserver.1, ocid1.dbserver.2,...]",
      "timeZone": "US/Pacific"
}
```

This is a reference event for VM Cluster - Terminate Virtual Machine End:

```
"exampleEvent": {
"cloudEventsVersion": "0.1",
   "eventID": "60600c06-d6a7-4e85-b56a-1de3e6042f57",
   "eventType":
"com.oraclecloud.databaseservice.vmclusterterminatevirtualmachine.end",
   "source": "databaseservice",
   "eventTypeVersion": "1.0",
```



```
"eventTime": "2019-06-27T21:16:04.000Z",
  "contentType": "application/json",
  "extensions": {
"compartmentId": "ocid1.compartment.oc1..unique ID"
  "data": {
"compartmentId": "ocid1.compartment.oc1..unique ID",
    "compartmentName": "example name",
    "resourceName": "my database",
    "resourceId": "Vmcluster-unique_ID",
    "availabilityDomain": "all",
    "freeFormTags": {},
    "definedTags": {},
    "additionalDetails": {
"id": "ocid1.id..oc1...unique ID",
      "lifecycleState": "AVAILABLE",
      "timeCreated": "2019-09-03T12:00:00.000Z",
      "timeUpdated": "2019-09-03T12:30:00.000Z",
      "displayName": "testDisplayName",
      "lifecycleDetails": "detail message",
      "exadataInfrastructureId": "ExatraInfra-unique ID",
      "vmClusterNetworkId": "VmCluster-unique ID",
      "cpuCoreCount": 2,
      "dataStorageSizeInTBs": 4,
      "memorySizeInGBs": 30,
      "dbNodeStorageSizeInGBs": 60,
      "dbVersion": "19.0.0.0",
      "licenseType": "BRING YOUR OWN LICENSE",
      "giVersion": "19.0.0.0",
      "dbNodeIds": "[ocid1.dbnode.1, ocid1.dbnode.2,...]",
      "dbServerIds": "[ocid1.dbserver.1, ocid1.dbserver.2,...]",
      "timeZone": "US/Pacific"
    }
}
```

Database Service Events

The Database Service emits events, which are structured messages that indicate changes in resources.

- Overview of Database Service Events
- Receive Notifications about Database Service Events
 Subscribe to the Database Service Events and get notified.
- Database Service Event Types
 Review the list of event types that the Database Service emits.
- Temporarily Restrict Automatic Diagnostic Collections for Specific Events
 Use the tfact1 blackout command to temporarily suppress automatic diagnostic
 collections.
- Remediation

These topics cover some common issues you might run into and how to address them.

Overview of Database Service Events

Database Service Events feature implementation enables you to get notified about health issues with your Oracle Databases or other components on the Guest VM.

It is possible that Oracle Database or Clusterware may not be healthy or various system components may be running out of space in the Guest VM. Customers are not notified of this situation.

Database Service Events feature implementation generates events for Data Plane operations and conditions, as well as Notifications for customers by leveraging the existing OCI Events service and Notification mechanisms in their tenancy. Customers can then create topics and subscribe to these topics through email, functions, or streams.



Events flow on ExaDB-C@C depends on the following components: Oracle Trace File Analyzer (TFA), sysLens, and Oracle Database Cloud Service (DBCS) agent. Ensure that these components are up and running.

Manage Oracle Trace File Analyzer

• To check the run status of Oracle Trace File Analyzer, run the tfactl status command as root or a non-root user:

 To start the Oracle Trace File Analyzer daemon on the local node, run the tfactl start command as root:

```
# tfactl start
Starting TFA..
Waiting up to 100 seconds for TFA to be started..
. . . . .
. . . . .
. . . . .
```



```
. . . . . . Successfully started TFA Process.. . . . . . TFA Started and listening for commands
```

• To stop the Oracle Trace File Analyzer daemon on the local node, run the tfact1 stop command as root:

```
# tfactl stop
Stopping TFA from the Command Line
Nothing to do !
Please wait while TFA stops
Please wait while TFA stops
TFA-00002 Oracle Trace File Analyzer (TFA) is not running
TFA Stopped Successfully
Successfully stopped TFA..
```

Manage sysLens

• If sysLens is running, then once every 15 minutes data is collected in the local domU to discover the events to be reported. To check if sysLens is running, run the systemctl status syslens command as root in the domU:

```
# systemctl status syslens
\u25cf syslens.service
Loaded: loaded (/etc/systemd/system/syslens.service; disabled;
vendor preset: disabled)
Active: active (running) since Wed 2022-03-16 18:08:59 UTC; 34s ago
Main PID: 358039 (python3)
Memory: 31.6M
CGroup: /system.slice/syslens.service
\u2514\u2500358039 /usr/bin/python3 /var/opt/oracle/syslens/bin/
syslens_main.py --archive /var/opt/oracle/log/...
Mar 16 18:08:59 node1 systemd[1]: Started syslens.service.
Mar 16 18:09:09 node1 su[360495]: (to oracle) root on none
Mar 16 18:09:10 node1 su[360611]: (to grid) root on none
Mar 16 18:09:11 node1 su[360653]: (to oracle) root on none
```

• If the sysLens is enabled, when there is a reboot of the domU, then sysLens starts automatically. To validate if sysLens is enabled to collect telemetry, run the systemctl is-enabled syslens command as root in the domU:

```
# systemctl is-enabled syslens
enabled
```

To validate if sysLens is configured to notify events, run the /usr/bin/syslens -config /var/opt/oracle/syslens/data/exacc.syslens.config --get-key
enable_telemetry command as root in the domU:

```
# /usr/bin/syslens --config /var/opt/oracle/syslens/data/
exacc.syslens.config --get-key enable telemetry
```



```
syslens Collection 2.3.3 on
```

Manage Database Service Agent

View the /opt/oracle/dcs/log/dcs-agent.log file to identify issues with the agent.

To check the status of the Database Service Agent, run the systematl status command:

```
# systemctl status dbcsagent.service
dbcsagent.service
Loaded: loaded (/usr/lib/systemd/system/dbcsagent.service; enabled;
vendor preset: disabled)
Active: active (running) since Fri 2022-04-01 13:40:19 UTC; 6min ago
Process: 9603 ExecStopPost=/bin/bash -c kill `ps -fu opc |grep
"java.*dbcs-agent.*jar" |awk '{print $2}' ` (code=exited, status=0/
SUCCESS)
Main PID: 10055 (sudo)
CGroup: /system.slice/dbcsagent.service

□ 10055 sudo -u opc /bin/bash -c umask 077; /bin/java -
Doracle.security.jps.config=/opt/oracle/...
```

• To start the agent if it is not running, run the systematl start command as the root user:

```
systemctl start dbcsagent.service
```

Related Topics

- Using the Console to Create a VM Cluster
 To create your VM cluster, be prepared to provide values for the fields required for configuring the infrastructure.
- Using the Console to Enable or Disable Diagnostics Notification
 You can enable or disable diagnostics collection for your Guest VMs after provisioning the VM cluster.
- Overview of Events
- Notifications Overview

Receive Notifications about Database Service Events

Subscribe to the Database Service Events and get notified.

To receive notifications, subscribe to Database Service Events and get notified using the Oracle Notification service, see *Notifications Overview*. For more information about Oracle Cloud Infrastructure Events, see *Overview of Events*.

Events Service - Event Types:

- Database Critical
- DB Node Critical
- DB Node Error
- DB Node Warning



- DB Node Info
- DB System Critical

Related Topics

- Overview of Events
- Notifications Overview

Database Service Event Types

Review the list of event types that the Database Service emits.

Note:

- Critical events are triggered due to several types of critical conditions and errors that cause disruption to the database and other critical components. For example, database hang errors, and availability errors for databases, database nodes, and database systems to let you know if a resource becomes unavailable.
- Information events are triggered when the database and other critical components work as expected. For example, a clean shutdown of CRS, CDB, client, or scan listener, or a startup of these components will create an event with the severity of INFO.
- Threshold limits reduce the number of notifications customers will receive for similar incident events whilst at the same time ensuring they receive the incident events and are reminded in a timely fashion.



Table 7-22 Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
Resource Utilization - Disk Usage	HEALTH.DB_GUEST .FILESYSTEM.FRE E_SPACE This event is reported when VM guest file system free space falls below 10% free, as determined by the operating system	HEALTH.DB_GUE ST.FILESYSTEM.F REE_SPACE	com.oraclecloud .databaseservic e.dbnode.critic al	
	df (1) command, for the following file systems:			
Disk Issues	HEALTH.DB_GUEST .FILESYSTEM.COR RUPTION A Write-then-Read operation with a dummy file has failed for a file system, typically indicating the operating system had detected an I/O error or inconsistency (i.e. corruption) with the file system and changed the file system mount mode from read- write to read-only. The following file systems are tested: /u01 /u02	HEALTH.DB_GUE ST.FILESYSTEM. CORRUPTION	com.oraclecloud .databaseservic e.dbnode.critic al	N/A



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
В	CONFIGURATION.D B_GUEST.MEMORY. HUGEPAGES_TOO_L ARGE	CONFIGURATION. DB_GUEST.MEM ORY.HUGEPAGES _TOO_LARGE	com.oraclecloud .databaseservic e.dbnode.critic al	90%
	An event of type CRITICAL is created when the amount of memory in the VM configured for HugePages is 90% or more of the total VM memory.			
sshd Configuration		CONFIGURATION. DB_GUEST.SSHD. INVALID	com.oraclecloud .databaseservic e.dbnode.critic	N/A
	An event of type CRITICAL is created if unexpected values are set in the /etc/ssh/ sshd_config file.		al	



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
Oracle EXAchk Reported Issues	HEALTH.DB_CLUST ER.EXACHK.CRITI CAL_ALERT Oracle EXAchk is Exadata database platform's holistic health check that includes software, infrastructure and database configuration checks. CRITICAL check alerts should	HEALTH.DB_CLU	com.oraclecloud .databaseservic e.dbnode.critic al	
	be addressed in 24 hours to maintain the maximum stability and availability of your system. This database service event alerts every 24 hours whenever there are any CRITICAL checks that are flagged in the most recent Oracle EXAchk report. The event will point to the latest Oracle EXAchk zip report.			
CRS status Up/ Down		AVAILABILITY.DB_ GUEST.CRS_INST ANCE.DOWN	com.oraclecloud .databaseservic e.dbnode.critic al (if .DOWN and NOT "user_action")	N/A
	AVAILABILITY.DB _GUEST.CRS_INST ANCE.DOWN_CLEAR ED An event of type INFORMATION is created once it is determined that the event for CRS down has cleared.		com.oraclecloud .databaseservic e.dbnode.inform ation (if.DOWN_CLEAR ED)	



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
SCAN Listener Up/ Down	AVAILABILITY.DB _CLUSTER.SCAN_L ISTENER.DOWN A DOWN event is created when a SCAN listener goes down. The event is of type INFORMATION when a SCAN listener is shutdown due to user action, such as with the Server Control Utility (srvctl) or Listener Control (lsnrctl) commands, or any Oracle Cloud maintenance action that uses those commands, such as performing a grid infrastructure software update. The event is of type CRITICAL when a SCAN listener goes down unexpectedly. A corresponding DOWN_CLEARED event is created when a SCAN listener is started. There are three SCAN listeners per cluster called LISTENER_SCAN[1,2,3].		com.oraclecloud .databaseservic e.dbnode.critic al (if.DOWN and NOT "user_action")	N/A
	AVAILABILITY.DB _CLUSTER.SCAN_L ISTENER.DOWN_CL EARED An event of type INFORMATION is created once it is determined that the event for SCAN Listener down has cleared.	N/A	com.oraclecloud .databaseservic e.dbnode.inform ation (if.DOWN_CLEAR ED)	



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
Net Listener Up/ Down	GUEST.CLIENT_L ISTENER.DOWN A DOWN event is created when a client listener goes down. The event is of type INFORMATION when a client listener is shutdown due to user action, such as with the Server Control Utility (srvctl) or Listener Control (lsnrctl) commands, or any Oracle Cloud maintenance action that uses those commands, such as performing a grid infrastructure software update. The event is of type CRITICAL when a client listener goes down unexpectedly. A corresponding DOWN_CLEARED event is created when a client listener is started. There is one client listener per node, each called	AVAILABILITY.DB_ GUEST.CLIENT_LI STENER.DOWN	Event Type com.oraclecloud .databaseservic e.database.crit ical (if .DOWN and NOT "user_action")	Threshold N/A
	AVAILABILITY.DB _GUEST.CLIENT_L ISTENER.DOWN_CL EARED An event of type INFORMATION is created once it is determined that the event for Client Listener down has cleared.	N/A	com.oraclecloud .databaseservic e.database.info rmation (if.DOWN_CLEAR ED)	



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
CDB Up/Down		GUEST.CDB_INST ANCE.DOWN	com.oraclecloud .databaseservic e.database.crit	N/A
	A DOWN event is created when a database instance goes down. The event is of type INFORMATION when a database instance is shutdown due to user action, such as with the SQL*Plus (sqlplus) or Server Control Utility (srvctl) commands, or any Oracle Cloud maintenance action that uses those commands, such as performing a database home software update. The event is of type CRITICAL when a database instance goes down unexpectedly. A corresponding DOWN_CLEARED event is created when a database instance is started.		ical (if .DOWN and NOT "user_action")	
	AVAILABILITY.DB _GUEST.CDB_INST ANCE.DOWN_CLEAR ED An event of type INFORMATION is created once it is determined that the	N/A	com.oraclecloud .databaseservic e.database.info rmation (if.DOWN_CLEAR ED)	



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
Critical DB Errors	HEALTH.DB_CLUST ER.CDB.CORRUPTI ON Database corruption has been detected on your primary or standby database. The database alert.log is parsed for any specific errors that are indicative of physical block corruptions, logical block corruptions, or logical block corruptions caused by lost writes.		com.oraclecloud .databaseservic e.database.crit ical	N/A
Other DB Errors	HEALTH.DB_CLUST ER.CDB.ARCHIVER _HANG An event of type CRITICAL is created if a CDB is either unable to archive the active online redo log or unable to archive the active online redo log fast enough to the log archive destinations.	HEALTH.DB_CLU STER.CDB.ARCHI VER_HANG	com.oraclecloud .databaseservic e.database.crit ical	N/A
	HEALTH.DB_CLUST ER.CDB.DATABASE _HANG An event of type CRITICAL is created when a process/session hang is detected in the CDB.	HEALTH.DB_CLU STER.CDB.DATAB ASE_HANG		



Table 7-22 (Cont.) Database Service Events

Friendly Name	Event Name	Remediation	Event Type	Threshold
Backup Failures	HEALTH.DB_CLUST ER.CDB.BACKUP_F AILURE	HEALTH.DB_CLU STER.CDB.BACK UP_FAILURE	com.oraclecloud .databaseservic e.database.crit	N/A
An event of type CRITICAL is created if there is a CDB backup with a FAILED status reported in the v\$rman_status view.	ical			
Disk Group Usage	HEALTH.DB_CLUST ER.DISK_GROUP.F REE SPACE		com.oraclecloud .databaseservic e.dbsystem.crit	sent when the usage hits 70%,
	An event of type CRITICAL is created when an ASM disk group reaches space usage of 90% or higher. An event of type INFORMATION is created when the ASM disk group space usage drops below 90%.		ical com.oraclecloud .databaseservic e.dbsystem.info rmation (if < 90%)	80%, 90%, and 100% with a corresponding severity of 4, 3, 2, and 1.

Example 7-78 Database Service DB Node Critical Events Examples

DB node critical reference events:

```
"eventType" : "com.oraclecloud.databaseservice.dbnode.critical",
 "cloudEventsVersion" : "0.1",
 "eventTypeVersion" : "2.0",
 "source" : "SYSLENS/host Name/DomU",
 "eventTime": "2022-03-07T23:17:47Z",
 "contentType" : "application/json",
 "data" : {
   "compartmentId" : "compartment ID",
   "compartmentName" : "compartment Name",
   "resourceName" : "resource Name",
   "resourceId" : "resource ID",
   "additionalDetails" : {
     "serviceType" : "EXACC",
     "hostName" : "host Name",
     "description" : "EXACHK is reporting 6 checks in critical status.
Results in: /u02/oracle.ahf/data/host Name/exachk/user root/output/
exachk host Name v1c2 030722 150746.zip",
     "eventName" : "HEALTH.DB CLUSTER.EXACHK.CRITICAL ALERT",
```



```
"status" : "online"
  }
},
"eventID": "cce55ca2-9e6c-11ec-90e6-00163e9b4de8",
 "extensions" : {
  "compartmentId" : "compartment ID"
}
"eventType" : "com.oraclecloud.databaseservice.dbnode.critical",
 "cloudEventsVersion" : "0.1",
 "eventTypeVersion": "2.0",
"source": "SYSLENS/host Name/DomU",
"eventTime": "2022-03-06T18:14:57Z",
 "contentType" : "application/json",
 "data" : {
  "compartmentId": "compartment ID",
  "compartmentName" : "compartment Name",
  "resourceName" : "resource Name",
  "resourceId" : "resource ID",
  "additionalDetails" : {
    "serviceType" : "EXACC",
    "hostName" : "host Name",
    "description": "Parameter ClientAliveCountMax has incorrect value.",
    "eventName" : "CONFIGURATION.DB GUEST.SSHD.INVALID",
    "status" : "online"
  }
},
 "eventID": "5453554e-9d79-11ec-8096-00163eb980bb",
"extensions" : {
  "compartmentId" : "compartment ID"
}
"eventType" : "com.oraclecloud.databaseservice.dbnode.critical",
"cloudEventsVersion" : "0.1",
"eventTypeVersion": "2.0",
"source": "SYSLENS/host Name/DomU",
 "eventTime": "2022-03-04T18:19:42Z",
"contentType" : "application/json",
 "data" : {
  "compartmentId" : "compartment ID",
   "compartmentName" : "compartment Name",
  "resourceName" : "resource Name",
  "resourceId" : "resource ID",
  "additionalDetails" : {
    "serviceType" : "EXACC",
    "hostName" : "host Name",
    "description" : "The '/' filesystem is over 90% used.",
    "eventName" : "HEALTH.DB GUEST.FILESYSTEM.FREE SPACE",
    "status" : "online"
```

```
}
 "eventID": "a9752630-9be7-11ec-a203-00163eb980bb",
 "extensions" : {
   "compartmentId" : "compartment_ID"
}
 "eventType" : "com.oraclecloud.databaseservice.dbnode.critical",
 "cloudEventsVersion" : "0.1",
 "eventTypeVersion" : "2.0",
 "source" : "SYSLENS/host Name/DomU",
 "eventTime": "2022-03-04T18:49:25Z",
 "contentType" : "application/json",
 "data" : {
   "compartmentId" : "compartment ID",
   "compartmentName" : "compartment Name",
   "resourceName" : "resource Name",
   "resourceId" : "resource ID",
   "additionalDetails" : {
    "serviceType" : "EXACC",
    "hostName" : "host Name",
    "description" : "Huge Pages is configured more than 90% of total
memory amount.",
     "eventName" : "CONFIGURATION.DB GUEST.MEMORY.HUGEPAGES TOO LARGE",
     "status" : "online"
  }
 },
 "eventID": "d0724fac-9beb-11ec-a203-00163eb980bb",
 "extensions" : {
  "compartmentId" : "compartment ID"
}
```

Temporarily Restrict Automatic Diagnostic Collections for Specific Events

Use the tfactl blackout command to temporarily suppress automatic diagnostic collections.

If you set blackout for a target, then Oracle Trace File Analyzer stops automatic diagnostic collections if it finds events in the alert logs for that target while scanning. By default, blackout will be in effect for 24 hours.

You can also restrict automatic diagnostic collection at a granular level, for example, only for **ORA-00600** or even only **ORA-00600** with specific arguments.

Syntax

```
tfactl blackout add|remove|print
-targettype host|crs|asm|asmdg|database|dbbackup|db_dataguard|
db_tablespace|pdb_tablespace|pdb|listener|service|os
-target all|name
[-container name]
```



```
[-pdb pdb_name]
-event all|"event_str1, event_str2"|availability
[-timeout nm|nh|nd|none]
[-c|-local|-nodes "node1, node2"]
[-reason "reason for blackout"]
[-docollection]
```

Parameters

Table 7-23 tfactl blackout Command Parameters

Parameter	Description
add remove print	Adds, removes, or prints blackout conditions.
-targettype <i>type</i>	Limits blackout only to the specified target type.
Target type: host crs asm asmdg database dbbackup db dataguard	host: The whole node is under blackout. If there is host blackout, then every blackout element that's shown true in the Telemetry JSON will have the reason for the blackout.
db_tablespace pdb_tablespace pdb	crs: Blackout the availability of the Oracle Clusterware resource or events in the Oracle Clusterware logs.
listener service os	asm: Blackout the availability of Oracle Automatic Storage Management (Oracle ASM) on this machine or events in the Oracle ASM alert logs.
	asmdg: Blackout an Oracle ASM disk group.
	database: Blackout the availability of an Oracle Database, Oracle Database backup, tablespace, and so on, or events in the Oracle Database alert logs.
	dbbackup: Blackout Oracle Database backup events (such as CDB or archive backups).
	db_dataguard: Blackout Oracle Data Guard events.
	db_tablespace: Blackout Oracle Database tablespace events (container database).
	pdb_tablespace: Blackout Oracle Pluggable Database tablespace events (Pluggable database).
	pdb: Blackout Oracle Pluggable Database events.
	listener: Blackout the availability of a listener.
	service: Blackout the availability of a service.
	os: Blackout one or more operating system records.
-target all <i>name</i>	Specify the target for blackout. You can specify a comma-delimited list of targets.
	By default, the target is set to all.
-container name	Specify the database container name (db_unique_name) where the blackout will take effect (for PDB, DB_TABLESPACE, and PDB_TABLESPACE).
-pdb <i>pdb_name</i>	Specify the PDB where the blackout will take effect (for PDB_TABLESPACE only).



Table 7-23 (Cont.) tfactl blackout Command Parameters

Parameter	Description
-events all "str1,str2"	Limits blackout only to the availability events, or event strings, which should not trigger auto collections, or be marked as blacked out in telemetry JSON.
	all: Blackout everything for the target specified.
	string: Blackout for incidents where any part of the line contains the strings specified.
	Specify a comma-delimited list of strings.
-timeout $nh \mid nd \mid$ none	Specify the duration for blackout in number of hours or days before timing out. By default, the timeout is set to 24 hours (24h).
-c -local	Specify if blackout should be set to cluster-wide or local. By default, blackout is set to local.
-reason comment	Specify a descriptive reason for the blackout.
-docollection	Use this option to do an automatic diagnostic collection even if a blackout is set for this target.

Example 7-79 tfactl blackout

To blackout event: ORA-00600 on targettype: database, target: mydb

tfactl blackout add -targettype database -target mydb -event "ORA-00600"

To blackout event: ORA-04031 on targettype: database, target: all

tfactl blackout add -targettype database -target all -event "ORA-04031" -timeout 1h

To blackout db backup events on targettype: dbbackup, target: mydb

tfactl blackout add -targettype dbbackup -target mydb

To blackout db dataguard events on targettype: db_dataguard, target: mydb

tfactl blackout add -targettype db_dataguard -target mydb -timeout 30m

To blackout db tablespace events on targettype: db_tablespace, target: system,
 container: mydb

tfactl blackout add -targettype db_tablespace -target system - container mydb -timeout 30m

To blackout ALL events on targettype: host, target: all

tfactl blackout add -targettype host -event all -target all -timeout 1h -reason "Disabling all events during patching"



To print blackout details

tfact1 blackout print	
T.	
myhostname	
++	
+	ı
Target Type Target	
Time End Time	
Collection Reason	
++	
+	•
HOST ALL	
UTC 2022 Thu Mar 24 17:48:39 UTC 2022	
Disabling all events during patching	Melivii Taise
DATABASE MYDB	ORA-00600 Thu Mar 24 16:39:03
UTC 2022 Fri Mar 25 16:39:03 UTC 2022	
NA	
DATABASE ALL	
UTC 2022 Thu Mar 24 17:39:54 UTC 2022	ACTIVE false
NA DB DATAGUARD MYDB	AII Thu Mar 2/ 16./1.20
UTC 2022 Thu Mar 24 17:11:38 UTC 2022	
NA	MOTIVE Talbe
DBBACKUP MYDB	ALL Thu Mar 24 16:40:47
UTC 2022 Fri Mar 25 16:40:47 UTC 2022	ACTIVE false
NA	
DB_TABLESPACE SYSTEM_CDBNAME_MYDB	
UTC 2022 Thu Mar 24 17:15:56 UTC 2022	ACTIVE false
NA	
+	
+	

To remove blackout for event: ORA-00600 on targettype: database, target: mydb

tfactl blackout remove -targettype database -event "ORA-00600" -target ${\tt mydb}$

To remove blackout for db backup events on targettype: dbbackup, target: mydb

tfactl blackout remove -targettype dbbackup -target mydb



 To remove blackout for db tablespace events on targettype: db_tablespace, target: system, container: mydb

tfactl blackout remove -targettype db_tablespace -target system - container mydb

To remove blackout for host events on targettype: all, target: all

tfactl blackout remove -targettype host -event all -target all

Remediation

These topics cover some common issues you might run into and how to address them.

- HEALTH.DB GUEST.FILESYSTEM.FREE SPACE
- HEALTH.DB GUEST.FILESYSTEM.CORRUPTION
- CONFIGURATION.DB_GUEST.MEMORY.HUGEPAGES_TOO_LARGE
- CONFIGURATION.DB_GUEST.SSHD.INVALID
- HEALTH.DB_CLUSTER.EXACHK.CRITICAL_ALERT
- AVAILABILITY.DB GUEST.CRS INSTANCE.DOWN
- AVAILABILITY.DB CLUSTER.SCAN LISTENER.DOWN
- AVAILABILITY.DB_GUEST.CLIENT_LISTENER.DOWN
- AVAILABILITY.DB GUEST.CDB INSTANCE.DOWN
- HEALTH.DB CLUSTER.CDB.CORRUPTION
- HEALTH.DB_CLUSTER.CDB.ARCHIVER_HANG
- HEALTH.DB CLUSTER.CDB.DATABASE HANG
- HEALTH.DB_CLUSTER.CDB.BACKUP_FAILURE
- HEALTH.DB CLUSTER.DISK GROUP.FREE SPACE
- Managing the Log and Diagnostic Files on Oracle Exadata Database Service on Cloud@Customer

HEALTH.DB GUEST.FILESYSTEM.FREE SPACE

Problem Statement: One or more VM guest file systems has free space below 10% free

Risk: Insufficient VM guest file system free space can cause disk space allocation failure, which can result in wide-ranging errors and failures in Oracle software (Database, Clusterware, Cloud, Exadata).

Action:

Oracle Cloud and Exadata utilities run automatically to purge old log files and trace files created by Oracle software to reclaim file system space.

If the automatic file system space reclamation utilities cannot sufficiently purge old files to clear this event, then perform the following actions:



1. Remove unneeded files and/or directories created manually or by customer-installed applications or utilities. Files created by customer-installed software are outside the scope of Oracle's automatic file system space reclamation utilities. The following operating system command, run as the opc user, is useful for identifying directories consuming excessive disk space:

```
$ sudo du -hx file-system-mount-point | sort -hr
```

Only remove files or directories you are certain can be safely removed.

- 2. Reclaim /u02 file system disk space by removing Database Homes that have no databases. For more information about managing Database Homes, see Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems.
- 3. (Exadata Cloud@Customer only) Increase /u02 file system size. For more information about scaling up local storage, see *Introduction to Scale Up or Scale Down Operations*.
- **4.** Open service request to receive additional guidance about reducing file system space use.

Related Topics

- Manage Oracle Database Homes on Exadata Database Service on Cloud@Customer Systems
 - Learn to manage Oracle Database homes on Exadata Database Service on Cloud@Customer.
- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can scale up or
 scale down your VM cluster resources.

HEALTH.DB_GUEST.FILESYSTEM.CORRUPTION

Problem Statement: A file system that is expected to be read-write can no longer be written to.

Risk: Oracle software (Linux, Database, Clusterware, Cloud, Exadata) requires write access to file systems to operate correctly.

Action:

/u01 and /u02 file systems:

- 1. Stop running services, if any, that are using the file system, such as Oracle Clusterware, Trace File Analyzer (TFA), and Enterprise Manager (EM) agent.
- 2. Unmount the file system.
- 3. Run file system check and repair.
 - **ext4:** Refer to Checking and Repairing a File System.
 - xfs: Refer to Checking and Repairing an XFS File System.
 - If the file system cannot be repaired then open a service request with Oracle Support for assistance.
- 4. Mount the file system.
- 5. Start the services.



/ (root) file system:

Open a service request with Oracle Support for assistance.

- If there is VM access, then collect full dmesg(1) command output and provide it to Oracle Support.
- Note that / (root) file system repair is possible only with console access.

Related Topics

- Checking and Repairing a File System
- Checking and Repairing an XFS File System

CONFIGURATION.DB GUEST.MEMORY.HUGEPAGES TOO LARGE

Problem Statement: Too much VM memory is allocated for HugePages use.

Risk: Excessive memory allocated to HugePages may result in poor database performance, or the system running out of memory, experiencing excessive swapping, or having crucial system services fail, causing system crash or node eviction.

Action:

- 1. Reduce HugePages memory use. To determine the proper setting for operating system parameter vm.nr_hugepages, see My Oracle Support document 361323.1.
- 2. Scale up VM memory. For more information about scaling VM memory, see *Introduction to Scale Up or Scale Down Operations*.

Related Topics

- https://support.oracle.com/rs?type=doc&id=361323.1
- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can scale up or scale down your VM cluster resources.

CONFIGURATION.DB_GUEST.SSHD.INVALID

Problem Statement: SSHD configuration is unexpected.

SSHD Configuration Setting	Expected Value
PubkeyAuthentication	yes
AuthorizedKeysFile	.ssh/authorized_keys
	This file must exist in root user home directory.
HostbasedAuthentication	no
IgnoreUserKnownHosts	yes
IgnoreRhosts	yes
PermitEmptyPasswords	no
PasswordAuthentication	no
ChallengeResponseAuthentication	no



SSHD Configuration Setting	Expected Value	
GSSAPIAuthentication	no	
UsePAM	yes	
PrintMotd	no	
UsePrivilegeSeparation	yes	
PermitUserEnvironment	no	
Compression	delayed	
MaxStartups	100	
AcceptEnv	Must contain one of the following: LANG LC_CTYPE LC_NUMERIC LC_TIME LC_COLLATE LC_MONETARY LC_MESSAGES LC_PAPER LC_NAME LC_ADDRESS LC_TELEPHONE LC_MEASUREMENT LC_IDENTIFICATION	
Subsystem	LC_ALLLANGUAGEXMODIFIERS sftp /usr/libexec/openssh/sftp-	
-	server	
Protocol	2	

Risk: SSHD configuration is unexpected which may cause Oracle Cloud automation failure or prevent customer SSH access to the VM.

Action: Change SSHD to match expected configuration.

1. Verify SSHD service is active.

 $\$ sudo systemctl is-active sshd.service active

If SSHD service is inactive, then start it.

\$ sudo systemctl start sshd.service



2. Verify SSHD service is enabled.

```
$ sudo /opt/oracle.cellos/host_access_control ssh-service --status
[INFO] [IMG-SEC-1201] Service sshd is enabled {1}
```

If SSHD service is disabled, then enable it.

\$ sudo /opt/oracle.cellos/host access control ssh-service --enable

3. Change SSHD configuration to match the expected values according to the table shown in the Problem Statement section above.

SSHD Configuration Setting	How to Change Current setting	
Ciphers	/opt/oracle.cellos/ host_access_control sshciphers help	
MACs	<pre>/opt/oracle.cellos/ host_access_control ssh-macs help</pre>	
PermitRootLogin	<pre>/opt/oracle.cellos/ host_access_control rootsshhelp</pre>	
ClientAliveInterval	/opt/oracle.cellos/ host_access_control idle-timeouthelp	
ClientAliveCountMax	/opt/oracle.cellos/ host_access_control idle-timeout help	
ListenAddress	<pre>/opt/oracle.cellos/ host_access_control ssh-listen help</pre>	
ALL OTHER PARAMETERS	 Edit /etc/ssh/sshd_config. Restart sshd.service.\$ sudo systemctl restart sshd.service 	

HEALTH.DB_CLUSTER.EXACHK.CRITICAL_ALERT

Problem Statement: A CRITICAL Exachk check failed and should be reviewed and addressed as soon as possible.

Risk: A CRITICAL check is expected to impact a large number of customers AND should be addressed immediately (for example, within 24 hours) AND meets one or more of the following criteria:

- 1. On-disk corruption or data loss
- 2. Intermittent wrong results with Exadata feature usage (e.g. smart scan)
- 3. System wide availability impact
- 4. Severe system wide performance impact seriously affecting application service Service Level Agreements (SLAs)
- 5. Compromised redundancy and inability to restore redundancy



- 6. Inability to update software in a rolling manner
- 7. Configuration error that could lead to an unexpected or unknown impact

Action:

Recommend that you bring up the EXAchk HTML report from the latest EXAchk zip file and click "view" on each CRITICAL check and follow the recommendation guidance that contains: Benefit/Impact, Risk, and Action/Repair guidance. Once the CRITICAL check is addressed, the next EXAchk run will pass that check. For more information about Oracle EXAchk, see *Oracle Exadata Database Machine Exachk (Doc ID 1070954.1)*.

As the root user, you can re-run EXAchk command by issuing:

```
/usr/bin/exachk -profile exatier1 -noupgrade -dball
```

If the check results are returning false data, then log a Service Request.

If there is a CRITICAL check that needs to be temporarily excluded, then follow the "Skipping Specific Best Practice Checks in Exadata Cloud" section of *Oracle Exadata Database Machine Exachk (Doc ID 1070954.1)*.

Related Topics

Oracle Exadata Database Machine Exachk (Doc ID 1070954.1)

AVAILABILITY.DB GUEST.CRS INSTANCE.DOWN

Problem Statement: The Cluster Ready Stack is in an offline state or has failed.

Risk: If the Cluster Ready Service is offline on a node, then the node cannot provide database services for the application.

Action:

- 1. Check if CRS was stopped by your administrator, as part of a planned maintenance event, or a scale up or down of local storage.
 - a. The following patching events will stop CRS:
 - i. GRID Patching
 - ii. Exadata VM patching of Guest
 - iii. Exadata VM Patching of Host
- 2. If CRS has stopped unexpectedly, then the current status can be checked by issuing the crsctl check crs command.
 - a. If the node is not responding, then the VM node may be rebooting. Wait for the node reboot to finish, CRS will normally be started through the init process.
- 3. If CRS is still down, then investigate the cause of the failure by referring to the alert.log found in /u01/app/grid/diag/crs/<node_name>/crs/trace. Review the log entries corresponding to the date/time of the down event. Act on any potential remediation.
- 4. Restart the CRS, by issuing the crsctl start crs command.
- 5. A successful restart of CRS will generate the clearing event: AVAILABILITY.DB GUEST.CRS INSTANCE.DOWN CLEARED.



AVAILABILITY.DB CLUSTER.SCAN LISTENER.DOWN

Problem Statement: A SCAN listener is down and unable to accept application connections.

Risk: If all SCAN listeners are down, then application connections to the database through the SCAN listener will fail.

Action:

Start the SCAN listener to receive the DOWN CLEARED event.

DOWN event of type INFORMATION

- 1. If the event was caused by an Oracle Cloud maintenance action, such as performing a Grid Infrastructure software update, then no action is required. The affected SCAN listener will automatically failover to an available instance.
- 2. If the event was caused by user action, then start the SCAN listener at the next opportunity.

DOWN event of type CRITICAL

Check SCAN status and restart the SCAN listener.

1. Login to the VM as opc user and sudo to the grid user:

```
[opc@vm ~] sudo su - grid
```

2. Check the SCAN listener status on any node:

```
[grid@vm ~] srvctl status scan listener
```

3. Start the SCAN listener:

```
[grid@vm ~] srvctl start scan listener
```

- 4. Recheck the SCAN listeners status on any node: If the scan_listener is still down, then investigate the cause of the scan listener failure:
 - a. Collect both the CRS and operating system logs 30 minutes prior and 10 minutes for the <hostName>indicated in the log. Note the time in the event payload is always provided in UTC. For tfactl collection, adjust the time to the timezone of the VM Cluster.

```
[grid@vm ~] tfactl diagcollect -crs -os -node <hostName> -from "<eventTime adjusted for local vm timezone> - 30 minute " -to "<eventTime adjusted for local vm timezone> + 10 minutes"
```

b. Review the SCAN listener log located under /u01/app/grid/diag/ tnslsnr/<hostName>/<listenerName>/trace

AVAILABILITY.DB GUEST.CLIENT LISTENER.DOWN



Problem Statement: A client listener is down and unable to accept application connections.

Risk:

- If the node's client listener is down, then the database instances on the node cannot provide services for the application.
- If the client listener is down on all nodes, then any application that connects to any database using the SCAN or VIP will fail.

Action:

Start the client listener to receive the DOWN CLEARED event.

DOWN event of type INFORMATION

- 1. If the event was caused by an Oracle Cloud maintenance action, such as performing a Grid Infrastructure software update, then no action is required. The affected client listener will automatically restart when maintenance affecting the grid instance is complete.
- 2. If the event was caused by user action, then start the client listener at the next opportunity.

DOWN event of type CRITICAL

Check the client listener status and then restart the client listener.

1. Login to the VM as opc user and sudo to the grid user:

```
[opc@vm ~] sudo su - grid
```

2. Check the client listener status on any node:

```
[grid@vm ~] srvctl status listener
```

3. Start the client listener:

```
[grid@vm ~] srvctl start listener
```

- 4. Recheck the client listener status on any node:
 If the client listener is still down, then investigate the cause of the client listener failure:
 - a. Use tfactl to collect both the CRS and operating system logs 30 minutes prior and 10 minutes for the <hostName> indicated in the log. Note the time in the event payload is always provided in UTC. For tfactl collection, adjust the time to the timezone of the VM Cluster.

```
[grid@vm ~] tfactl diagcollect -crs -os -node <hostName> -from "<eventTime adjusted for local vm timezone> - 30 minute " -to "<eventTime adjusted for local vm timezone> + 10 minutes"
```

b. Review the listener log located under /u01/app/grid/diag/tnslsnr/ <hostName>/<listenerName>/trace

AVAILABILITY.DB GUEST.CDB INSTANCE.DOWN

Problem Statement: A database instance has gone down.



Risk: A database instance has gone down, which may result in reduced performance if database instances are available on other nodes in the cluster, or complete downtime if database instances on all nodes are down.

Action:

Start the database instance to receive the DOWN CLEARED event.

DOWN event of type INFORMATION

- If the event was caused by an Oracle Cloud maintenance action, such as
 performing a Database Home software update, then no action is required. The
 affected database instance will automatically restart when maintenance affecting
 the instance is complete.
- 2. If the event was caused by user action, then start the affected database instance at the next opportunity.

DOWN event of type CRITICAL

- 1. Check database status and restart the down database instance.
 - a. Login to the VM as oracle user:
 - **b.** Set the environment:

```
[oracle@vm ~] . <dbName>.env
```

c. Check the database status:

```
[oracle@vm ~] srvctl status database -db <dbName>
```

d. Start the database instance:

```
[oracle@vm ~] srvctl start instance -db <dbName> -instance
<instanceName>
```

- 2. Investigate the cause of the database instance failure.
 - a. Review Trace File Analyzer (TFA) events for the database:

```
[oracle@vm ~] tfactl events -database <dbName> -instance
<instanceName>
```

b. Review the database alert log located at \$ORACLE_BASE/diag/rdbms/ <dbName>/<instanceName>.log

HEALTH.DB_CLUSTER.CDB.CORRUPTION

Problem Statement: Corruptions can lead to application or database errors and in worse case result in significant data loss if not addressed promptly.

A corrupt block is a block that was changed so that it differs from what Oracle Database expects to find. Block corruptions can be categorized as physical or logical:

 In a physical block corruption, which is also called a media corruption, the database does not recognize the block at all; the checksum is invalid or the block



contains all zeros. An example of a more sophisticated block corruption is when the block header and footer do not match.

In a logical block corruption, the contents of the block are physically sound and pass the
physical block checks; however, the block can be logically inconsistent. Examples of
logical block corruption include incorrect block type, incorrect data or redo block
sequence number, corruption of a row piece or index entry, or data dictionary corruptions.

For more information, see *Physical and Logical Block Corruptions*. All you wanted to know about it. (Doc ID 840978.1).

Block corruptions can also be divided into interblock corruption and intrablock corruption:

- In an intrablock corruption, the corruption occurs in the block itself and can be either a physical or a logical block corruption.
- In an interblock corruption, the corruption occurs between blocks and can only be a logical block corruption.

Oracle checks for the following errors in the alert.log:

- ORA-01578
- ORA-00752
- ORA-00753
- ORA-00600 [3020]
- ORA-00600 [kdsgrp1]
- ORA-00600 [kclchkblk_3]
- ORA-00600 [13013]
- ORA-00600 [5463]

Risk: A data corruption outage occurs when a hardware, software, or network component causes corrupt data to be read or written. The service-level impact of a data corruption outage may vary, from a small portion of the application or database (down to a single database block) to a large portion of the application or database (making it essentially unusable). If remediation action is not taken promptly, then potential downtime and data loss can increase.

Action:

The current event notification currently triggers on physical block corruptions (ORA-01578), lost writes (ORA-00752, ORA-00753 and ORA-00600 with first argument 3020), and logical corruptions (typical detected from ORA-00600 with first argument of kdsgrp1, kdsgrp1, kclchkblk 3, 13013 OR 5463).

Oracle recommends the following steps:

- 1. Confirm that these corruptions were reported in the alert.log trace file. Log a Service Request (SR) with latest EXAchk report, excerpt of the alert.log and trace file containing the corruption errors, any history of recent application, database or software changes and any system, clusterware and database logs for the same time period. For all these cases, a TFA collection should be available and should be attached to the SR.
- 2. For repair recommendations, refer to Handling Oracle Database Corruption Issues (Doc ID 1088018.1).

For physical corruptions or ORA-1578 errors, the following notes will be helpful:



- Doc ID 1578.1 : OERR: ORA-1578 "ORACLE data block corrupted (file # %s, block # %s)" Primary Note
- Doc ID 472231.1: How to identify all the Corrupted Objects in the Database reported by RMAN
- Doc ID 819533.1: How to identify the corrupt Object reported by ORA-1578 / RMAN / DBVERIFY
- Depending on the object that has the corruption, follow the guidance in Doc ID 1088018.1. Note RMAN can be used to recover one or many data block that are physically corrupted. Also using Active Data Guard with real time apply, auto block repair of physical data corruptions would have occurred automatically.

For logical corruptions caused by lost writes (ORA-00752, ORA-00753 and ORA-00600 with first argument 3020) on the primary or standby databases, they will be detected on the primary or with standby's redo apply process. The following notes will be helpful:

- Follow the guidance, follow Doc ID 1088018.1.
- If you have a standby and lost write corruption on the primary or standby, refer to Resolving ORA-00752 or ORA-00600 [3020] During Standby Recovery (Doc ID 1265884.1)

For logical corruptions (typical detected from ORA-00600 with arguments of kdsgrp1, kclchkblk 3, 13013 OR 5463):

- Follow the guidance, follow Doc ID 1088018.1 for specific guidance on the error that was detected.
- If you have a standby and logical corruption on the primary, refer to Resolving Logical Block Corruption Errors in a Physical Standby Database (Doc ID 2821699.1)

Related Topics

- Physical and Logical Block Corruptions. All you wanted to know about it. (Doc ID 840978.1)
- OERR: ORA-1578 "ORACLE data block corrupted (file # %s, block # %s)" Primary Note (Doc ID 1578.1)
- How to identify all the Corrupted Objects in the Database with RMAN (Doc ID 472231.1)
- How to identify the corrupt Object reported by ORA-1578 / RMAN / DBVERIFY (Doc ID 819533.1)
- Resolving ORA-00752 or ORA-600 [3020] During Standby Recovery (Doc ID 1265884.1)
- Resolving Logical Block Corruption Errors in a Physical Standby Database (Doc ID 2821699.1)

HEALTH.DB CLUSTER.CDB.ARCHIVER HANG

Problem Statement: CDB RAC Instance may temporarily or permanently stall due to the log writer's (LGWR) inability to write the log buffers to an online redo log. This occurs because all online logs need archiving. Once the archiver (ARC) can archive at least one online redo log, LGWR will be able to resume writing the log buffers to online redo logs and the application impact will be alleviated.



Risk: If the archiver hang is temporary, then this can result in a small application brown out or stall for application processes attempting to commit their database changes. If the archiver is not unblocked, applications can experience extended delay in processing.

Action:

- See, Script To Find Redo log Switch History And Find Archivelog Size For Each instance In RAC (Doc ID 2373477.1) to determine the hourly frequency for each thread/instance.
- If any hourly bucket is greater than 12, then consider resizing the online redo logs. See item 2 below for resizing steps.
- If the database hangs are temporary, then the archiver may be unable to keep up with the redo log generated. Check the alert.log, \$ORACLE_BASE/diag/rdbms/
 <dbName>/<instanceName>/trace/alert_<instanceName>.log, for "All online logs need archiving", multiple events in a short period can indicate 2 possible solutions.
 - If the number of redo logs groups per thread is less than 4, then consider adding additional logs groups to reach 4, see item 1 below for add redo log steps.
 - The other possible solution is to resize the redo logs, see item 2 below for resizing steps.
- For Data Guard and Non Data Guard review the Configure Online Redo Logs
 Appropriately of section Oracle Database High Availability Overview and Best Practices for sizing guidelines.
- 1. Add a redo log group for each thread. The additional redo log should equal the current log size.
 - **a.** Use the following query:

```
select max(group#) Ending_group_number, thread#, count(*)
number_of_groups_per_thread, bytes redo_size_in_bytes from v$log
group by thread#,bytes
```

b. Add one new group per thread using the same size as the current redo logs.

```
alter database add logfile thread <thread_number> Group <max group +
1> ('<DATA DISKGROUP>') size <redo_size_in_bytes>
```

- 2. Resize the online redo logs by adding larger redo logs and dropping the current smaller redo logs.
 - **a.** Use the following query:

```
select max(group#) Ending_group_number, thread#, count(*)
number_of_groups_per_thread, bytes redo_size_in_bytes from v$log
group by thread#,bytes
```

- b. Add the same number of redo logs for each thread <number_of_groups_per_thread> that currently exist. The <new_redo_size_in_bytes> should be based on Configure Online Redo Logs Appropriately of section Oracle Database High Availability Overview and Best Practices.
 - i. alter database add logfile thread <thread_number> Group <max group
 + 1> ('<DATA_DISKGROUP>') size <new_redo_size_in_bytes>



ii. The original smaller redo logs should be deleted. A redo log can only be deleted if its status is inactive.

To determine the status of a redo logs issue:

```
select group#, thread#, status, bytes from v$log order by
bytes, group#, thread#;
```

To delete the original smaller redo logs:

```
alter database drop logfile <group#>
```

 If the database is hung, the primary log archive destination and alternate may be full. Review the HEALTH.DB_CLUSTER.DISK_GROUP.FREE_SPACE for details on freeing space in RECO and DATA disk groups.

Related Topics

- Script To Find Redolog Switch History And Find Archivelog Size For Each Instances In RAC (Doc ID 2373477.1)
- Configure Online Redo Logs Appropriately
- HEALTH.DB_CLUSTER.DISK_GROUP.FREE_SPACE

HEALTH.DB CLUSTER.CDB.DATABASE HANG

Problem Statement: Hang management detected a process hang and generated a ORA-32701 error message. Additionally, this event may be raised if Diagnostic Process (DIA0) process detects a hang in a critical database process.

Risk: A hang can indicate resource, operating system, or application coding related issues.

Action:

Investigate the cause of the session hang.

 Review TFA events for the database for the following message patterns corresponding to the date/time of the event: ORA-32701, "DIA0 Critical Database Process Blocked" or "DIA0 Critical Database Process As Root".

```
[oracle@vm ~] tfactl events -database <dbName> -instance <instanceName>
```

2. Review the alert.log file.

```
$ORACLE_BASE/diag/rdbms/<dbName>/<instanceName>/trace/
alert <instanceName>.log
```

- **3. For ora-32701:** An overloaded system can cause slow progress, which can be interpreted as a hang.
 - The hang manager may attempt to resolve the hang by terminating the final blocker process.
- **4. For DIA0 Critical Database Process messages:** Review the related diagnostic lines indicating the process and the reason for the hang.



HEALTH.DB_CLUSTER.CDB.BACKUP_FAILURE

Problem Statement: A daily incremental BACKUP of the CDB failed.

Risk: A failure of the backup can compromise the ability to use the backups for restore/ recoverability of the database. Recoverability Point Object (RPO) and the Recoverability Time Object (RTO) can be impacted.

Action:

Review the RMAN logs corresponding to the date/time of the event. Note the event time stamp <*eventTime*> is in UTC, adjust as necessary for the VM's timezone.

- For Exadata Database Service on Cloud@Customer Oracle Managed Backups or User Configured Backups under dbaascli:
 - RMAN output can be found at /var/opt/oracle/log/<DB_NAME>/obkup.

 Daily incremental logs have the following format obkup_yyyy-mm
 dd_24hh:mm:ss.zzzzzzzzzzzlog within the obkup directory. The logs are located on the lowest active node/instance of the database when the backup was initiated.
 - Review the log for any failures:
 - * If the failure is due to an external event outside of RMAN, for example the backup location was full or a networking issue, resolve the external issue.
 - * For other RMAN script errors, collect the diagnostic logs and open a Service Request. See DBAAS Tooling: Using dbaascli to Collect Cloud Tooling Logs and Perform a Cloud Tooling Health Check.
 - If the issue is transient or is resolved, take a new incremental backup: See dbaascli database backup.
- For Customer owned and managed backup taken through RMAN:
 - Review the RMAN logs for the backup.

Related Topics

- DBAAS Tooling: Using dbaascli to Collect Cloud Tooling Logs and Perform a Cloud Tooling Health Check
- dbaascli database backup
 To configure Oracle Database with a backup storage destination, take database backups,
 query backups, and delete a backup, use the dbaascli database backup command.

HEALTH.DB_CLUSTER.DISK_GROUP.FREE_SPACE

Problem Statement: ASM disk group space usage is at or exceeds 90%.

Risk: Insufficient ASM disk group space can cause database creation failure, tablespace and data file creation failure, automatic data file extension failure, or ASM rebalance failure.

Action:



ASM disk group used space is determined by the running the following query while connected to the ASM instance.

```
[opc@node ~] sudo su - grid
[grid@node ~] sqlplus / as sysasm
```

SQL> select 'ora.'||name||'.dg', total_mb, free_mb, round ((1-(free_mb/total_mb))*100,2) pct_used from v\$asm_diskgroup;

NAME	TOTAL_MB	FREE_MB	PCT_USED
ora.DATAC1.dg	75497472	7408292	90.19
ora.RECOC1.dg	18874368	17720208	6.11

ASM disk group capacity can be increased in the following ways:

- 1. Scale Exadata VM Cluster storage to add more ASM disk group capacity. See *Introduction to Scale Up or Scale Down Operations*.
- 2. Scale Exadata Infrastructure storage to add more ASM disk group capacity. See *Overview of Elastic Storage Expansion*.

DATA disk group space use can be reduced in the following ways:

- 1. Drop unused data files and temp files from databases. See *Dropping Data Files*.
- 2. Terminate unused databases (e.g. test databases). See *Using the Console to Terminate a Database*.

RECO disk group space use can be reduced in the following ways:

- Drop unnecessary Guaranteed Restore Points. See Using Normal and Guaranteed Restore Points.
- 2. Delete archived redo logs or database backups already backed up outside the Flash Recovery Area (FRA). See *Maintaining the Fast Recovery Area*.

SPARSE disk group space use can be reduced in the following ways:

- 1. Move full copy test master databases to another disk group (e.g. DATA).
- 2. Drop unused snapshot databases or test master databases. See *Managing Exadata Snapshots*.

For more information about managing the log and diagnostic files, see Managing the Log and Diagnostic Files on Oracle Exadata Database Service on Cloud@Customer.

Related Topics

- Introduction to Scale Up or Scale Down Operations
 With the Multiple VMs per Exadata system (MultiVM) feature release, you can
 scale up or scale down your VM cluster resources.
- Overview of Elastic Storage Expansion
 With elastic storage expansion, you can dynamically increase your storage
 capacity to meet your growing workload requirements.
- Dropping Data Files
- Using the Console to Terminate a Database
 You can terminate a database and thereby remove the terminated database from the Cloud Control Plane.



- Using Normal and Guaranteed Restore Points
- Maintaining the Fast Recovery Area
- Managing Exadata Snapshots
- Managing the Log and Diagnostic Files on Oracle Exadata Database Service on Cloud@Customer

Managing the Log and Diagnostic Files on Oracle Exadata Database Service on Cloud@Customer

The software components in Oracle Exadata Database Service on Cloud@Customer generate a variety of log and diagnostic files, and not all these files are automatically archived and purged. Thus, managing the identification and removal of these files to avoid running out of file storage space is an important administrative task.

Database deployments on ExaDB-C@C include the cleandblogs script to simplify this administrative task. The script runs daily as a cron job on each compute node to archive key files and remove old log and diagnostic files.

The cleandblogs script operates by using the adrci (Automatic Diagnostic Repository [ADR] Command Interpreter) tool to identify and purge target diagnostic folders and files for each Oracle Home listed in /etc/oratab. It also targets Oracle Net Listener logs, audit files, and core dumps.

On ExaDB-C@C, the script is run separately as the oracle user to clean log and diagnostic files that are associated with Oracle Database, and as the grid user to clean log and diagnostic files that are associated with Oracle Grid Infrastructure.

The cleandblogs script uses a configuration file to determine how long to retain each type of log or diagnostic file. You can edit the file to change the default retention periods. The file is located at /var/opt/oracle/cleandb/cleandblogs.cfg on each compute node.



Configure an optimal retention period for each type of log or diagnostic file. An insufficient retention period will hinder root cause analysis and problem investigation.

Parameter	Description and Default Value
AlertRetention	Alert log (alert_instance.log) retention value in days.
	Default value: 14
ListenerRetention	Listener log (listener.log) retention value in days. Default value: 14
AuditRetentionDB	Database audit (* . aud) retention value in days. Default value: 1
CoreRetention	Core dump/files (* . cmdp*) retention value in days. Default value: 7



Parameter	Description and Default Value	
TraceRetention	Trace file (*.tr* and *.prf) retention value in days.	
	Default value: 7	
longpRetention	Data designated in the Automatic Diagnostic Repository (ADR) as having a long life (the LONGP_POLICY attribute). For information about ADR, see Automatic Diagnostic Repository (ADR) in the Oracle Database Administrator's Guide. Default value: 14	
shortpRetention	Data designated in the Automatic Diagnostic Repository (ADR) as having a short life (the SHORTP_POLICY attribute). For information about ADR, see Automatic Diagnostic Repository (ADR) in the Oracle Database Administrator's Guide.	
	Default value: 7	
LogRetention	Log file retention in days for files under /var/opt/oracle/log and log files in ACFS under /var/opt/oracle/dbaas acfs/log.	
	Default value: 14	
LogDirRetention	cleandblogs logfile retention in days.	
	Default value: 14	
ScratchRetention	Temporary file retention in days for files under / scratch.	
	Default value: 7	

Archiving Alert Logs and Listener Logs

When cleaning up alert and listener logs, cleandblogs first archives and compresses the logs, operating as follows:

- 1. The current log file is copied to an archive file that ends with a date stamp.
- 2. The current log file is emptied.
- 3. The archive file is compressed using gzip.
- 4. Any existing compressed archive files older than the retention period are deleted.

Running the cleandblogs Script Manually

The cleandblogs script automatically runs daily on each compute node, but you can also run the script manually if the need arises.

Connect to the compute node as the oracle user to clean log and diagnostic files
that are associated with Oracle Database, or connect as the grid user to clean log
and diagnostic files that are associated with Oracle Grid Infrastructure.
For detailed instructions, see Connecting to a Virtual Machine with SSH.

Change to the directory containing the cleandblogs script:

\$ cd /var/opt/oracle/cleandb



2. Run the cleandblogs script:

```
$ ./cleandblogs.pl
```

When running the script manually, you can specify an alternate configuration file to use instead of cleandblogs.cfg by using the --pfile option:

```
$ ./cleandblogs.pl --pfile config-file-name
```

3. Close your connection to the compute node:

\$ exit

Related Topics

- Automatic Diagnostic Repository (ADR)
- Connecting to a Virtual Machine with SSH
 You can connect to the virtual machines in an Exadata Database Service on
 Cloud@Customer system by using a Secure Shell (SSH) connection.

Policy Details for Exadata Database Service on Cloud@Customer

Learn to write policies to control access to Exadata Database Service on Cloud@Customer resources.



For more information on Policies, see "How Policies Work".

For a sample policy, see "Let database admins manage Exadata Database Service on Cloud@Customer instances".

- About Resource-Types
 - Learn about resource-types you can use in your policies.
- Resource-Types for Exadata Database Service on Cloud@Customer Review the list of resource-types specific to Exadata Database Service on Cloud@Customer.
- Supported Variables
 - Use variables when adding conditions to a policy.
- Details for Verb + Resource-Type Combinations
 Review the list of permissions and API operations covered by each verb.
- Permissions Required for Each API Operation
 Review the list of API operations for Exadata Database Service on Cloud@Customer resources in a logical order, grouped by resource type.

Related Topics

How Policies Work



Let database admins manage Exadata Database Service on Cloud@Customer instances

About Resource-Types

Learn about resource-types you can use in your policies.

An aggregate resource-type covers the list of individual resource-types that directly follow. For example, writing one policy to allow a group to have access to the database-family is equivalent to writing eight separate policies for the group that would grant access to the exadata-infrastructures, vmcluster-networks, vmclusters, backup-destinations, db-nodes, and the rest of the individual resource-types. For more information, see Resource-Types.

Resource-Types for Exadata Database Service on Cloud@Customer

Review the list of resource-types specific to Exadata Database Service on Cloud@Customer.

Aggregate Resource-Type

database-family



Individual Resource-Types

exadata-infrastructures vmclusters backup-destinations db-nodes db-homes databases backups database-software-images autonomous-vmclusters autonomous-container-databases autonomous-databases key-stores $\verb"autonomousContainerData" base \texttt{DataguardAssociations}$

Supported Variables

Use variables when adding conditions to a policy.

 ${\tt AutonomousDatabaseDataguardAssociation}$

Exadata Database Service on Cloud@Customer supports only the general variables. For more information, see "General Variables for All Requests".

Related Topics

General Variables for All Requests



Details for Verb + Resource-Type Combinations

Review the list of permissions and API operations covered by each verb.

For more information, see "Permissions", "Verbs", and "Resource-Types".

Database-Family Resource Types Understand the level of access of each verb.

exadata-infrastructures

Review the list of permissions and API operations for exadata-infrastructures resource-type.

vmcluster-networks

Review the list of permissions and API operations for vmcluster-networks resource-type.

vmclusters

Review the list of permissions and API operations for vmclusters resource-type.

backup-destinations

Review the list of permissions and API operations for backup-destinations resource-type.

db-nodes

Review the list of permissions and API operations for db-nodes resource-type.

db-homes

Review the list of permissions and API operations for db-homes resource-type.

databases

Review the list of permissions and API operations for databases resource-type.

backups

Review the list of permissions and API operations for backups resource-type.

database-software-image

Review the list of permissions and API operations for database-software-image resource-type.

autonomous-vmclusters

Review the list of permissions and API operations for autonomous-vmclusters resource-type.

autonomous-container-databases

Review the list of permissions and API operations for autonomous-container-databases resource-type.

autonomous-databases

Review the list of permissions and API operations for autonomous-databases resource-type.

key-stores

Review the list of permissions and API operations for key-store resource-type.

pluggable-databases (PDBs)

Review the list of permissions and API operations for pluggable-databases resource-type.

dbServers

Review the list of permissions and API operations for dbServers resource-type.



Related Topics

- Permissions
- Verbs
- Resource-Types

Database-Family Resource Types

Understand the level of access of each verb.

The level of access is cumulative as you go from inspect > read > use > manage. A plus sign (+) in a table cell indicates incremental access compared to the cell directly above it, whereas "no extra" indicates no incremental access.

For example, the read verb for the vmclusters resource-type covers no extra permissions or API operations compared to the inspect verb. However, the use verb includes one more permission, fully covers one more operation, and partially covers another additional operation.

exadata-infrastructures

Review the list of permissions and API operations for exadata-infrastructures resource-type.

Granting permissions on exadata-infrastructure resources grants permissions on associated vmcluster-network resources.

Table 7-24 INSPECT

Permission	APIs Fully Covered	APIs Partially Covered
EXADATA_INFRASTRUCTURE_IN SPECT	ListExadataInfrastructure s GetExadataInfrastructure	ChangeExadataInfrastructu reCompartment
	GenerateRecommendedNetworkDetails	
	ListVmClusterNetworks	
	GetVmClusterNetwork	
	ValidateVmClusterNetwork	
	<pre>DownloadExadataInfrastruc tureConfigFile</pre>	
	DownloadVmClusterNetworkC onfigFile	

Table 7-25 READ

Permissions	APIs Fully Covered	APIs Partially Covered
INSPECT+	none	none
EXADATA_INFRASTRUCTURE_CO NTENT_READ		



Table 7-26 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + EXADATA INFRASTRUCTURE	ActivateExadataInfrastr ucture	CreateVmCluster (also needs manage vmclusters)
UPDATE	<pre>UpdateExadataInfrastruc ture</pre>	UpdateVmCluster (also needs use vmclusters)
	ChangeExadataInfrastruc tureCompartment	ChangeExadataInfrastruc tureCompartment
	AddStorageCapacityExada taInfrastructure	
	CreateVmClusterNetwork	
	UpdateVmClusterNetwork	
	DeleteVmClusterNetwork	

Table 7-27 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + EXADATA INFRASTRUCTURE	CreateExadataInfrastruc ture	none
CREATE EXADATA INFRASTRUCTURE	DeleteExadataInfrastruc ture	
DELETE	<pre>downloadExadataInfrastr uctureConfigFile</pre>	

vmcluster-networks

Review the list of permissions and API operations for <code>vmcluster-networks</code> resource-type.

 ${\tt vmcluster-network} \ resources \ inherit \ permissions \ from \ the \ exadata-infrastructure \ resources \ with \ which \ they \ are \ associated. \ You \ cannot \ grant \ permissions \ to \ vmcluster-network \ resources \ explicitly.$

Table 7-28 INSPECT

Permission	APIs Fully Covered	APIs Partially Covered
EXADATA_INFRASTRUCTURE_INSPECT	ListVmClusterNetworks GetVmClusterNetwork ValidateVmClusterNetwork	none



Table 7-29 READ

Permissions	APIs Fully Covered	APIs Partially Covered
INSPECT+	DownloadVmClusterNetworkC	none
EXADATA_INFRASTRUCTURE_CO NTENT_READ	onfigFile	

Table 7-30 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ+	CreateVmClusterNetwork	none
EXADATA_INFRASTRUCTURE_UP	UpdateVmClusterNetwork	
DATE	DeleteVmClusterNetwork	

Table 7-31 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	none	none
EXADATA_INFRASTRUCTURE_CR EATE		
EXADATA_INFRASTRUCTURE_DE LETE		

vmclusters

Review the list of permissions and API operations for vmclusters resource-type.

Table 7-32 INSPECT

Permission	APIs Fully Covered	APIs Partially Covered
VM_CLUSTER_INSPECT	ListVmClusters	none
	GetVmCluster	
	ListVmClusterPatches	
	ListVmClusterPatchHistory Entries	
	GetVmClusterPatch	
	GetVmClusterPatchHistoryE ntry	
	ListVmClusterUpdates	
	ListVmClusterUpdateHistor yEntries	
	GetVmClusterUpdate	
	GetVmClusterUpdateHistory Entry	



Table 7-33 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-34 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + VM_CLUSTER_UPDATE	ChangeVmClusterCompartm ent	UpdateVmCluster (also needs use exadata-infrastructures)
		CreateDbHome, (also needs manage db-homes and manage databases). If automatic backups are enabled on the default database, also needs manage backups
		DeleteDbHome, (also needs manage db-homes and manage databases. If automatic backups are enabled on the default database, also needs manage backups

Table 7-35 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + VM_CLUSTER_CREATE VM_CLUSTER_DELETE	No extra	CreateVmCluster (also needs use exadata-infrastructures)
		DeleteVmCluster (also needs use exadata-infrastructures)

backup-destinations

Review the list of permissions and API operations for ${\tt backup-destinations}$ resource-type.

Table 7-36 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
BACKUP_DESTINATION_INSP ECT	ListBackupDestinations GetBackupDestination	none



Table 7-37 READ

Permissions	APIs Fully Covered	APIs Partially Covered
no extra	no extra	none

Table 7-38 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ+	UpdateBackupDestination	none
BACKUP_DESTINATION_UPDATE	ChangeBackupDestinationCo mpartment	

Table 7-39 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	CreateBackupDestination	none
BACKUP_DESTINATION_CREATE	DeleteBackupDestination	
BACKUP_DESTINATION_DELETE		

db-nodes

Review the list of permissions and API operations for db-nodes resource-type.

Table 7-40 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
DB_NODE_INSPECT	GetDbNode	none
DB_NODE_QUERY		

Table 7-41 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-42 USE

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none



Table 7-43 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	DbNodeAction	none
DB_NODE_POWER_ACTIONS		

db-homes

Review the list of permissions and API operations for db-homes resource-type.

Table 7-44 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
DB_HOME_INSPECT	ListDBHome	none
	GetDBHome	
	ListDbHomePatches	
	ListDbHomePatchHistoryE ntries	
	GetDbHomePatch	
	<pre>GetDbHomePatchHistoryEn try</pre>	

Table 7-45 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-46 USE

Permissions	APIs Fully Covered	APIs Partially Covered
DB_HOME_UPDATE	UpdateDBHome	none



Table 7-47 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	No extra	CreateDbHome, (also needs
DB_HOME_CREATE		manage db-homes, manage
DB_HOME_DELETE		backups, manage db-nodes, read vmclusters, read work-requests, and inspect exadata-infrastructures). If automatic backups are enabled on the default database, also needs manage backups.
		DeleteDbHome, (also needs manage db-homes, manage backups, manage db-nodes, read vmclusters, read work-requests, and inspect exadata-infrastructures). If automatic backups are enabled on the default database, also needs manage backups.

databases

Review the list of permissions and API operations for databases resource-type.

Table 7-48 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
DATABASE_INSPECT	ListDatabases	ListDatabaseUpgradeHistor
	GetDatabase	yEntries
	getDatabaseUpgradeHistory Entry	UpgradeDatabase
	ListDataGuardAssociations	
	GetDataGuardAssociation	

Table 7-49 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none



Table 7-50 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ+	UpdateDatabase	If enabling automatic backups,
DATABASE_UPDATE DB HOME UPDATE	SwitchoverDataGuardAsso ciation	also needs manage backups.
	FailoverDataGuardAssoci ation	
	ReinstateDataGuardAssoc iation	

Table 7-51 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + DATABASE_CREATE DATABASE_DELETE	No extra	CreateDbHome, (also needs use vmclusters and manage db-homes). If automatic backups are enabled on the default database, also needs manage backups
		DeleteDbHome, (also needs use vmclusters and manage db-homes). If automatic backups are enabled on the default database, also needs manage backups

backups

Review the list of permissions and API operations for backups resource-type.

Table 7-52 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
DB_BACKUP_INSPECT	GetBackup	none
	ListBackups	

Table 7-53 READ

Permissions	APIs Fully Covered	APIs Partially Covered
INSPECT+	none	RestoreDatabase (also
DB_BACKUP_CONTENT_READ		needs use databases)



Table 7-54 USE

Permissions	APIs Fully Covered	APIs Partially Covered
no extra	no extra	none

Table 7-55 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	no extra	none
DB_BACKUP_CREATE		
DB_BACKUP_DELETE		

database-software-image

Review the list of permissions and API operations for database-software-image resource-type.

Table 7-56 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
DB_SOFTWARE_IMG_INSPECT	ListDatabaseSoftwareImage s	none
	GetDatabaseSoftwareImage	

Table 7-57 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-58 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + DB_SOFTWARE_IMG_UPDATE	UpdateDatabaseSoftwareIma ge	none
	ChangeDatabaseSoftwareIma geCompartment	

Table 7-59 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + DB_SOFTWARE_IMG_CREATE +	CreateDatabaseSoftwareIma ge DeleteDatabaseSoftwareIma	none
DB_SOFTWARE_IMG_DELETE	ge	



autonomous-vmclusters

Review the list of permissions and API operations for ${\tt autonomous-vmclusters}$ resource-type.

Table 7-60 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
AUTONOMOUS_VM_CLUSTER_I NSPECT	ListAutonomousVmCluster s	ChangeAutonomousVmClust erCompartment
	GetAutonomousVmCluster	

Table 7-61 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-62 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + AUTONOMOUS VM CLUSTER U	ChangeAutonomousVmClust erCompartment	UpdateAutonomousVmClust er
PDATE		CreateAutonomousContain erDatabase
		TerminateAutonomousCont ainerDatabase

Table 7-63 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	DeleteAutonomousVmClust	CreateAutonomousVmClust
AUTONOMOUS_VM_CLUSTER_C REATE +	er	er
AUTONOMOUS_VM_CLUSTER_D ELETE		

autonomous-container-databases

Review the list of permissions and API operations for autonomous-container-databases resource-type.



Table 7-64 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
AUTONOMOUS_CONTAINER_DATA BASE_INSPECT	ListAutonomousContainerDa tabases, GetAutonomousContainerDat abase	none

Table 7-65 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	No extra	none

Table 7-66 USE

Permissions	APIs Fully Covered	APIs Partially Covered	
AUTONOMOUS_CONTAINER_DATA BASE_UPDATE	UpdateAutonomousContainer Database	(also needs manage	
	ChangeAutonomousContainer DatabaseCompartment	autonomous-databases)	

Table 7-67 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + AUTONOMOUS_CONTAINER_DATA BASE_CREATE AUTONOMOUS_CONTAINER_DATA BASE_DELETE	No extra	CreateAutonomousContainer Database, TerminateAutonomousContai nerDatabase (both also need use autonomous-VmCluster)

autonomous-databases

Review the list of permissions and API operations for autonomous-databases resource-type.

Table 7-68 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
AUTONOMOUS_DATABASE_INSPECT	GetAutonomousDatabase, ListAutonomousDatabases	no extra



Table 7-69 READ

Permissions	APIs Fully Covered	APIs Partially Covered
<pre>INSPECT + AUTONOMOUS_DATABASE_CON TENT_READ</pre>	no extra	CreateAutonomousDatabas eBackup (also needs manage autonomous-backups)

Table 7-70 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + AUTONOMOUS_DATABASE_CON TENT_WRITE +	UpdateAutonomousDatabas e	RestoreAutonomousDataba se (also needs read autonomous-backups)
AUTONOMOUS_DATABASE_UPD ATE		ChangeAutonomousDatabas eCompartment (also needs read autonomous-backups)

Table 7-71 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE+	CreateAutonomousDatabas	none
AUTONOMOUS_DATABASE_CRE ATE	е	
AUTONOMOUS_DATABASE_DEL ETE		

key-stores

Review the list of permissions and API operations for key-store resource-type.

Table 7-72 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
KEY_STORE_INPSECT	GetKeyStore	ChangeKeyStoreCompartme
AUTONOMOUS_CONTAINER_DA	GetAutonomousContainerD	nt
TABASE_INSPECT	atabase	RotateAutonomousContain
AUTONOMOUS_DATABASE_INS	GetAutonomousDatabase	erDatabaseKey
PECT	GetAutonomousDatabaseBa	
AUTONOMOUS_DB_BACKUP_IN	ckup	
SPECT		

Table 7-73 READ

Permissions	APIs Fully Covered	APIs Partially Covered	
no extra	no extra	no extra	



Table 7-74 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + KEY_STORE_UPDATE +	UpdateKeyStore	ChangeKeyStoreCompartment
AUTONOMOUS_VM_CLUSTER_UPD ATE +	none none	CreateAutonomousContainer Database
AUTONOMOUS_CONTAINER_DATA BASE_UPDATE AUTONOMOUS_DATABASE_UPDAT E	<pre>none RotateAutonomousDatabaseK ey</pre>	RotateAutonomousContainer DatabaseKey none

Table 7-75 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
USE + KEY_STORE_CREATE +	CreateKeyStore	none
KEY_STORE_DELETE +	DeleteKeyStore	none
AUTONOMOUS_CONTAINER_DATA BASE_CREATE	CreateAutonomousContainer Database	none

pluggable-databases (PDBs)

Review the list of permissions and API operations for pluggable-databases resource-type.

Verbs	Permissions	APIs Fully Covered	APIs Partially Covered
inspect	PLUGGABLE_DATABA SE_INSPECT	ListPluggableDataba ses	none
		GetPluggableDatabas e	
read	INSPECT + PLUGGABLE_DATABA	no extra	none
use	SE_CONTENT_READ READ + PLUGGABLE_DATABA	UpdatePluggableData base	none
	SE_CONTENT_WRITE PLUGGABLE_DATABA SE_UPDATE	StartPluggableDatab ase	
		StopPluggableDataba se	
manage	USE + PLUGGABLE_DATABA SE_CREATE PLUGGABLE_DATABA SE_DELETE	no extra	CreatePluggableData base, DeletePluggableData base, LocalClonePluggable Database, RemoteClonePluggabl eDatabase (all also need use databases)



dbServers

Review the list of permissions and API operations for dbServers resource-type.

Table 7-76 INSPECT

Permissions	APIs Fully Covered	APIs Partially Covered
EXADATA INFRASTRUCTURE	none	GetDbServer
INSPECT		ListDbServers

Table 7-77 READ

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	none	none

Table 7-78 USE

Permissions	APIs Fully Covered	APIs Partially Covered
READ + VM_CLUSTER_UPDATE EXADATA_INFRASTRUCTURE_ UPDATE	none	AddVirtualMachineToVmCl uster, RemoveVirtualMachineFro mVmCluster

Table 7-79 MANAGE

Permissions	APIs Fully Covered	APIs Partially Covered
No extra	none	none

Permissions Required for Each API Operation

Review the list of API operations for Exadata Database Service on Cloud@Customer resources in a logical order, grouped by resource type.

For information about permissions, see *Permissions*.

Table 7-80 Database API Operations

API Operation	Permissions Required to Use the Operation
ListExadataInfrastructures	EXADATA_INFRASTRUCTURE_INSPECT
GetExadataInfrastructure	EXADATA_INFRASTRUCTURE_INSPECT
CreateExadataInfrastructure	EXADATA_INFRASTRUCTURE_CREATE
UpdateExadataInfrastructure	EXADATA_INFRASTRUCTURE_UPDATE
ChangeExadataInfrastructureCompartme nt	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation
DeleteExadataInfrastructure	EXADATA_INFRASTRUCTURE_DELETE
DownloadExadataInfrastructureConfigF ile	EXADATA_INFRASTRUCTURE_CONTENT_READ
AddStorageCapacityExadataInfrastruct ure	EXADATA_INFRASTRUCTURE_UPDATE
ActivateExadataInfrastructure	EXADATA_INFRASTRUCTURE_UPDATE
GenerateRecommendedNetworkDetails	EXADATA_INFRASTRUCTURE_INSPECT
ListVmClusterNetworks	EXADATA_INFRASTRUCTURE_INSPECT
GetVmClusterNetwork	EXADATA_INFRASTRUCTURE_INSPECT
CreateVmClusterNetwork	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE
UpdateVmClusterNetwork	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE
DeleteVmClusterNetwork	EXADATA_INFRASTRUCTURE_UPDATE
DownloadVmClusterNetworkConfigFile	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_CONTENT_READ
ValidateVmClusterNetwork	EXADATA_INFRASTRUCTURE_INSPECT
ListVmClusters	VM_CLUSTER_INSPECT
GetVmCluster	VM_CLUSTER_INSPECT
CreateVmCluster	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE and VM_CLUSTER_CREATE
UpdateVmCluster	EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE and VM_CLUSTER_UPDATE
ChangeVmClusterCompartment	VM_CLUSTER_INSPECT and VM_CLUSTER_UPDATE
DeleteVmCluster	VM_CLUSTER_DELETE
ListVmClusterPatches	VM_CLUSTER_INSPECT
ListVmClusterPatchHistoryEntries	VM_CLUSTER_INSPECT
GetVmClusterPatch	VM_CLUSTER_INSPECT
GetVmClusterPatchHistoryEntry	VM_CLUSTER_INSPECT
ListVmClusterUpdates	VM_CLUSTER_INSPECT
ListVmClusterUpdateHistoryEntries	VM_CLUSTER_INSPECT
GetVmClusterUpdate	VM_CLUSTER_INSPECT
GetVmClusterUpdateHistoryEntry	VM_CLUSTER_INSPECT
ListBackupDestination	BACKUP DESTINATION INSPECT



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation	
GetBackupDestination	BACKUP_DESTINATION_INSPECT	
CreateBackupDestination	BACKUP_DESTINATION_CREATE	
UpdateBackupDestination	BACKUP_DESTINATION_UPDATE	
DeleteBackupDestination	BACKUP_DESTINATION_DELETE	
ChangeBackupDestinationCompartment	BACKUP_DESTINATION_INSPECT and BACKUP_DESTINATION_UPDATE	
GetDbNode	DB_NODE_INSPECT	
DbNodeAction	DB_NODE_POWER_ACTIONS	
ListDbHomes	DB_HOME_INSPECT	
GetDbHome	DB_HOME_INSPECT	
CreateDbHome	VM_CLUSTER_INSPECT and VM_CLUSTER_UPDATE and DB_HOME_CREATE and DATABASE_CREATE	
	To enable automatic backups for the database, also need DB_BACKUP_CREATE and DATABASE_CONTENT_READ.	
UpdateDbHome	DB_HOME_UPDATE	
DeleteDbHome	VM_CLUSTER_UPDATE and DB_HOME_UPDATE and DATABASE_DELETE	
ListDbHomePatches	DB_HOME_INSPECT	
ListDbHomePatchHistoryEntries	DB_HOME_INSPECT	
GetDbHomePatch	DB_HOME_INSPECT	
GetDbHomePatchHistoryEntry	DB_HOME_INSPECT	
CreateDatabase	VM_CLUSTER_INSPECT, VM_CLUSTER_UPDATE, DB_HOME_INSPECT, DB_HOME_UPDATE, DATABASE_CREATE	
	DB_BACKUP_CREATE and DATABASE_CONTENT_READ	
	DB_BACKUP_INSPECT, DB_BACKUP_CONTENT_READ	
ListDatabases	DATABASE_INSPECT	
GetDatabase	DATABASE_INSPECT	
UpdateDatabase	DATABASE_UPDATE	
	To enable automatic backups, also need DB_BACKUP_CREATE and DATABASE_CONTENT_READ	



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation
DeleteDatabase	VM_CLUSTER_UPDATE, DB_HOME_UPDATE, DATABASE_DELETE
	DB_BACKUP_INSPECT, DB_BACKUP_DELETE
	DB_BACKUP_CREATE and DATABASE_CONTENT_READ
UpgradeDatabase	DATABASE_INSPECT
	DATABASE_UPDATE
	DB_HOME_INSPECT
	DB_HOME_UPDATE
getDatabaseUpgradeHistoryEntry	DATABASE_INSPECT
getDatabaseUpgradeHistoryEntry	DATABASE_INSPECT
ListDbVersions	(no permissions required; available to anyone)
GetBackup	DB_BACKUP_INSPECT
ListBackups	DB_BACKUP_INSPECT
CreateBackup	DB_BACKUP_CREATE and DATABASE_CONTENT_READ
DeleteBackup	DB_BACKUP_DELETE and DB_BACKUP_INSPECT
RestoreDatabase	DB_BACKUP_INSPECT and DB_BACKUP_CONTENT_READ and DATABASE_CONTENT_WRITE
CreateAutonomousVmCluster	AUTONOMOUS_VM_CLUSTER_CREATE and EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE
ListAutonomousVmClusters	AUTONOMOUS_VM_CLUSTER_INSPECT
GetAutonomousVmCluster	AUTONOMOUS_VM_CLUSTER_INSPECT
UpdateAutonomousVmCluster	AUTONOMOUS_VM_CLUSTER_UPDATE and EXADATA_INFRASTRUCTURE_INSPECT and EXADATA_INFRASTRUCTURE_UPDATE
ChangeAutonomousVmClusterCompartment	AUTONOMOUS_VM_CLUSTER_INSPECT and AUTONOMOUS_VM_CLUSTER_UPDATE
DeleteAutonomousVmCluster	AUTONOMOUS_VM_CLUSTER_DELETE
ListAutonomousContainerDatabases	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
GetAutonomousContainerDatabase	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
CreateAutonomousContainerDatabase	AUTONOMOUS_VM_CLUSTER_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_CREATE
TerminateAutonomousContainerDatabase	AUTONOMOUS_VM_CLUSTER_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_DELETE



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation	
UpdateAutonomousContainerDatabase	AUTONOMOUS_CONTAINER_DATABASE_UPDATE	
ChangeAutonomousContainerDatabaseCom partment	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T and AUTONOMOUS_CONTAINER_DATABASE_UPDATE	
GetAutonomousDatabase	AUTONOMOUS DATABASE INSPECT	
ListAutonomousDatabases	AUTONOMOUS DATABASE INSPECT	
CreateAutonomousDatabase	AUTONOMOUS_DATABASE_CREATE and AUTONOMOUS_CONTAINER_DATABASE_INSPEC T	
UpdateAutonomousDatabase	AUTONOMOUS_DATABASE_UPDATE	
ChangeAutonomousDatabaseCompartment	AUTONOMOUS_DATABASE_UPDATE and AUTONOMOUS_DB_BACKUP_INSPECT and AUTONOMOUS_DB_BACKUP_CONTENT_READ and AUTONOMOUS_DATABASE_CONTENT_WRITE and AUTONOMOUS_DB_BACKUP_CREATE	
DeleteAutonomousDatabase	AUTONOMOUS_DATABASE_DELETE	
StartAutonomousDatabase	AUTONOMOUS_DATABASE_UPDATE	
StopAutonomousDatabase	AUTONOMOUS_DATABASE_UPDATE	
RestoreAutonomousDatabase	AUTONOMOUS_DB_BACKUP_CONTENT_READ and AUTONOMOUS_DATABASE_CONTENT_WRITE	
CreateAutonomousDatabaseBackup	AUTONOMOUS_DB_BACKUP_CREATE and AUTONOMOUS_DATABASE_CONTENT_READ	
DeleteAutonomousDatabaseBackup	AUTONOMOUS_DB_BACKUP_DELETE	
ListAutonomousDatabaseBackups	AUTONOMOUS_DB_BACKUP_DELETE	
GetAutonomousDatabaseBackup	AUTONOMOUS_DB_BACKUP_DELETE	
CreateDataGuardAssociation	VM_CLUSTER_INSPECT and DATABASE_INSPECT and DATABASE_UPDATE	
GetDataGuardAssociation	DATABASE_INSPECT	
ListDataGuardAssociations	DATABASE_INSPECT	
SwitchoverDataGuardAssociation	DATABASE_UPDATE	
FailoverDataGuardAssociation	DATABASE_UPDATE	
ReinstateDataGuardAssociation	DATABASE_UPDATE	
DeleteDatabase	VM_CLUSTER_UPDATE and DB_HOME_UPDATE and DATABASE_DELETE	
CreateKeyStore	KEY_STORE_CREATE	
GetKeyStore	KEY_STORE_INSPECT	
UpdateKeyStore	KEY_STORE_UPDATE	



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation
DeleteKeyStore	KEY_STORE_DELETE
ChangeKeyStoreCompartment	KEY_STORE_INPSECT and KEY_STORE_UPDATE
CreateAutonomousContainerDatabase	AUTONOMOUS_VM_CLUSTER_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_CREATE
GetAutonomousContainerDatabase	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
RotateAutonomousContainerDatabaseKey	AUTONOMOUS_CONTAINER_DATABASE_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
GetAutonomousDatabase	AUTONOMOUS_DATABASE_INSPECT
RotateAutonomousDatabaseKey	AUTONOMOUS_DATABASE_UPDATE
GetAutonomousDatabaseBackup	AUTONOMOUS_DB_BACKUP_INSPECT
CreateAutonomousContainerDatabase	No changes for Primary. AUTONOMOUS_VM_CLUSTER_INSPECT, AUTONOMOUS_VM_CLUSTER_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_CREATE Standby: AUTONOMOUS_CONTAINER_DATABASE_CREATE
GetAutonomousContainerDatabase	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
deleteAutonomouContainerDatabase	AUTONOMOUS_VM_CLUSTER_UPDATE and AUTONOMOUS_CONTAINER_DATABASE_DELETE
ListAutonomousContainerDatabaseDatag uardAssociations	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
GetAutonomousContainerDatabaseDatagu ardAssociation	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
FailoverAutonomousContainerDatabaseD ataguardAssociation	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T and AUTONOMOUS_CONTAINER_DATABASE_UPDATE
SwitchoverAutonomousContainerDatabas eDataguardAssociation	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T and AUTONOMOUS_CONTAINER_DATABASE_UPDATE
ReinstateAutonomousContainerDatabase DataguardAssociation	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T and AUTONOMOUS_CONTAINER_DATABASE_UPDATE
ListAutonomousDatabaseDataguardAssoc iations	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T
GetAutonomousDatabaseDataguardAssoci ation	AUTONOMOUS_CONTAINER_DATABASE_INSPEC T



Table 7-80 (Cont.) Database API Operations

API Operation	Permissions Required to Use the Operation	
GetAutonomousDatabase	AUTONOMOUS_DATABASE_INSPECT	
ListDatabaseSoftwareImages	DB_SOFTWARE_IMG_INSPECT	
GetDatabaseSoftwareImage	DB_SOFTWARE_IMG_INSPECT	
UpdateDatabaseSoftwareImage	DB_SOFTWARE_IMG_INSPECT and DB_SOFTWARE_IMG_UPDATE	
ChangeDatabaseSoftwareImageCompartment	DB_SOFTWARE_IMG_INSPECT and DB_SOFTWARE_IMG_UPDATE	
CreateDatabaseSoftwareImage	DB_SOFTWARE_IMG_INSPECT and DB_SOFTWARE_IMG_CREATE	
DeleteDatabaseSoftwareImage	DB_SOFTWARE_IMG_INSPECT and DB_SOFTWARE_IMG_DELETE	
ListPluggableDatabase	PLUGGABLE_DATABASE_INSPECT	
GetPluggableDatabase	PLUGGABLE_DATABASE_INSPECT	
CreatePluggableDatabase	PLUGGABLE_DATABASE_CREATE, DATABASE_INSPECT and DATABASE_UPDATE.	
UpdatePluggableDatabase	PLUGGABLE_DATABASE_INSPECT and PLUGGABLE_DATABASE_UPDATE	
StartPluggableDatabase	PLUGGABLE_DATABASE_INSPECT and PLUGGABLE_DATABASE_UPDATE	
StopPluggableDatabase	PLUGGABLE_DATABASE_INSPECT and PLUGGABLE_DATABASE_UPDATE	
DeletePluggableDatabase	PLUGGABLE_DATABASE_DELETE, DATABASE_INSPECT, and DATABASE_UPDATE	
LocalClonePluggableDatabase	PLUGGABLE_DATABASE_INSPECT, PLUGGABLE_DATABASE_UPDATE, PLUGGABLE_DATABASE_CONTENT_READ, PLUGGABLE_DATABASE_CONTENT_WRITE, PLUGGABLE_DATABASE_CREATE, DATABASE_INSPECT, and DATABASE_UPDATE	
RemoteClonePluggableDatabase	PLUGGABLE_DATABASE_INSPECT, PLUGGABLE_DATABASE_UPDATE, PLUGGABLE_DATABASE_CONTENT_READ, PLUGGABLE_DATABASE_CONTENT_WRITE, PLUGGABLE_DATABASE_CREATE, DATABASE_INSPECT, and DATABASE_UPDATE	
GetDbServer	DB_SERVER_INSPECT	
ListDbServers	DB_SERVER_INSPECT	
AddVirtualMachineToVmCluster	VM_CLUSTER_UPDATE EXADATA_INFRASTRUCTURE_UPDATE	
RemoveVirtualMachineFromVmCluster	VM_CLUSTER_UPDATE EXADATA_INFRASTRUCTURE_UPDATE	



Related Topics

Permissions

Managing Exadata Resources with Oracle Enterprise Manager Cloud Control

To manage and monitor Exadata Cloud and Exadata Cloud@Customer resources, use Oracle Enterprise Manager Cloud Control.

For complete documentation and Oracle By Example tutorials, see the following documentation resources: *Oracle Enterprise Manager Cloud Control for Oracle Exadata Cloud* and *Setting Up Oracle Enterprise Manager 13.4 on Oracle Cloud Infrastructure*.

- Overview of Oracle Enterprise Manager Cloud Control
 Oracle Enterprise Manager Cloud Control provides a complete lifecycle management
 solution for Oracle Cloud Infrastructure's Exadata Cloud and Exadata Cloud@Customer
 services.
- Features of Enterprise Manager Cloud Control
 Familiarize yourself with the features of Enterprise Manager Cloud Control to manage and monitor Exadata Cloud and Exadata Cloud@Customer resources.

Related Topics

- Oracle Enterprise Manager Cloud Control for Oracle Exadata Cloud
- Setting Up Oracle Enterprise Manager 13.4 on Oracle Cloud Infrastructure

Overview of Oracle Enterprise Manager Cloud Control

Oracle Enterprise Manager Cloud Control provides a complete lifecycle management solution for Oracle Cloud Infrastructure's Exadata Cloud and Exadata Cloud@Customer services.

Enterprise Manager Cloud Control discovers Exadata Cloud and Exadata Cloud@Customer services as a single target and automatically identifies and organizes all dependent components. Using Enterprise Manager Cloud Control you can then:

- Monitor and manage all Exadata, Exadata Cloud and Exadata Cloud@Customer systems, along with any other targets, from a single interface
- Visualize storage and compute data
- View performance metrics of your Exadata components

Features of Enterprise Manager Cloud Control

Familiarize yourself with the features of Enterprise Manager Cloud Control to manage and monitor Exadata Cloud and Exadata Cloud@Customer resources.

Enterprise Manager Target for Exadata Cloud

The target for Oracle Cloud Infrastructure Exadata resources, which covers both Exadata Cloud and Exadata Cloud@Customer does the following:

Automatically identifies and organizes related targets.



• Provides a high-level integration point for Enterprise Manager framework features such as incident rules, groups, notifications, and monitoring templates.

Improved Performance Monitoring

Enterprise Manager Cloud Control enhances performance monitoring in the following ways:

- Adds Exadata Storage Server and Exadata Storage Grid targets.
- Offers visualization of storage and compute performance for your Exadata Cloud and Exadata Cloud@Customer resources.
- Enables use of the same Maximum Availability Architecture (MAA) key performance indicators (KPI) developed for Oracle Exadata Database Machine.

Scripted CLI-based Discovery

Enterprise Manager Cloud Control uses scripts to discover Oracle Cloud Infrastructure Exadata resources. Scripts comb the existing hosts, clusters, ASM, databases and related targets, as well as adding the storage server targets.

"Single Pane of Glass" View of On-Premises and Oracle Cloud Infrastructure Exadata Resources

Enterprise Manager Cloud Control 's use of a single Exadata target type provides a consistent Enterprise Manager experience across on-premises, Exadata Cloud, and Exadata Cloud@Customer resources. The common Exadata target menu allows you to easily navigate to, monitor and manage all of your Exadata systems.

Visualization

Enterprise Manager Cloud Control allows you to visualize the database and related targets associated with each Exadata Cloud and Exadata Cloud@Customer system.

Security Guide for Exadata Database Service on Cloud@Customer Systems

This guide describes security for an Oracle Exadata Cloud@Customer System. It includes information about the best practices for securing the Oracle Exadata Cloud@Customer System.

- Security Configurations and Default Enabled Features
- Additional Procedures for Updating Security Posture

Security Configurations and Default Enabled Features

- Responsibilities
- Guiding Principles Followed for Security Configuration Defaults
- Security Features
- Guest VM Default Fixed Users
- Guest VM Default Security Settings



- Guest VM Default Processes
- Guest VM Network Security

Responsibilities

Exadata Cloud@Customer is jointly managed by the customer and Oracle. The Exadata Cloud@Customer deployment is divided into two major areas of responsibilities:

- Customer accessible services:
 Components that the customer can access as part of their subscription to Exadata Cloud@Customer:
 - Customer accessible virtual machines (VM)
 - Customer accessible database services
- Oracle-managed infrastructure:
 - Power Distribution Units (PDUs)
 - Out-of-band (OOB) management switches » InfiniBand switches
 - Exadata Storage Servers
 - Physical Exadata database servers

Customers control and monitor access to customer services, including network access to their VMs (through layer 2 VLANs and firewalls implemented in the customer VM), authentication to access the VM, and authentication to access databases running in the VMs. Oracle controls and monitors access to Oracle-managed infrastructure components. Oracle staff are not authorized to access customer services, including customer VMs and databases.

Customers access Oracle Databases running on Exadata Cloud@Customer through a layer 2 (tagged VLAN) connection from customer equipment to the databases running in the customer VM using standard Oracle Database connection methods, such as Oracle Net on port 1521. Customers access the VM running the Oracle Databases through standard Oracle Linux methods, such as token based SSH on port 22.

Guiding Principles Followed for Security Configuration Defaults

Defense in Depth

Exadata Cloud@Customer offers a number of controls to ensure confidentiality, integrity, and accountability throughout the service.

First, Exadata Cloud@Customer is built from the hardened operating system image provided by Exadata Database Machine. For more information, see *Overview of Oracle Exadata Database Machine Security*. This secures the core operating environment by restricting the installation image to only the required software packages, disabling unnecessary services, and implementing secure configuration parameters throughout the system.

In addition to inheriting all the strength of Exadata Database Machine's mature platform, because Exadata Cloud@Customer provisions systems for customers, additional secure default configuration choices are implemented in the service instances. For example, all database tablespaces require transparent data encryption (TDE), strong password enforcement for initial database users and superusers, and enhanced audit and event rules.



Exadata Cloud@Customer also constitutes a complete deployment and service, so it is subjected to industry-standard external audits such as PCI, HIPPA and ISO27001. These external audit requirements impose additional value-added service features such as antivirus scanning, automated alerting for unexpected changes to the system, and daily vulnerability scans for all Oracle-managed infrastructure systems in the fleet.

Least Privilege

To ensure that processes only have access to the privileges they require, Oracle Secure Coding Standards require the paradigm of least privilege.

Each process and daemon, must run as a normal, unprivileged user unless it can prove a requirement for a higher level of privilege. This helps contain any unforeseen issues or vulnerabilities to unprivileged user space and not compromise an entire system.

This principle also applies to Oracle operations team members who use individual named accounts to access the Oracle Exadata Cloud@Customer infrastructure for maintenance or troubleshooting. Only when necessary will they use the audited access to higher levels of privilege to solve or resolve an issue. Most issues are resolved through automation, so we also employ least privilege by not permitting human operators to access a system unless the automation is unable to resolve the issue.

Auditing and Accountability

When required, access to the system is allowed, but all access and actions are logged and tracked for accountability.

This ensures that both Oracle and customers know what was done on the system and when that occurred. These facts not only ensure we remain compliant with reporting needs for external audits, but also can help match up some change with a change in perceived behavior in the application.

Auditing capabilities are provided at all infrastructure components to ensure all actions are captured. Customers also have ability to configure auditing for their database and Guest VM configuration and may choose to integrate those with other enterprise auditing systems.

Automating Cloud Operations

By eliminating manual operations required to provision, patch, maintain, troubleshoot, and configure systems, the opportunity for error is reduced and a secure configuration is ensured.

The service is designed to be secure and by automating all provisioning, configuration, and most other operational tasks, it is possible to avoid missed configurations and ensure all necessary paths into the system are closed tightly.

Related Topics

Overview of Oracle Exadata Database Machine Security

Security Features

Hardened Operating System Image

Minimal package installation:
 Only the necessary packages required to run an efficient system are installed.
 By installing a smaller set of packages, the attack surface of the operating system is reduced and the system remains more secure.



Secure configuration:

Many non-default configuration parameters are set during installation to enhance the security posture of the system and its content. For example, SSH is configured to only listen on certain network interfaces, sendmail is configured to only accept localhost connections, and many other similar restrictions are implemented during installation.

Run only necessary services:

Any services that may be installed on the system, but not required for normal operation are disabled by default. For example, while NFS is a service often configured by customers for various application purposes, it is disabled by default as it is not required for normal database operations. Customers may choose to optionally configure services per their requirements.

Minimized Attack Surface

As part of the hardened image, attack surface is reduced by disabling services.

Additional Security Features Enabled (grub passwords, secure boot)

- Leveraging Exadata image capabilities, Exadata Cloud@Customer enjoys the features integrated into the base image such as grub passwords and secure boot in addition to many others.
- Through customization, customers may wish to further enhance their security posture with additional configurations detailed later in this chapter.

Secure Access Methods

- Accessing database servers through SSH using strong cryptographic ciphers. Weak ciphers are disabled by default.
- Accessing databases via encrypted Oracle Net connections. By default, our services are available using encrypted channels and a default configured Oracle Net client will use encrypted sessions.
- Accessing diagnostics through Exadata MS web interface (https).

Auditing and Logging

By default, auditing is enabled for administrative operations and those audit records are communicated to OCI internal systems for automated review and alerting when required.

Deployment-Time Considerations

- Wallet file download contents and sensitivity: The wallet file download that is obtained
 by a customer to enable the deployment to occur contains sensitive information and
 should be handled appropriately to ensure the contents are protected. The content of
 the wallet file download is not needed after deployment is completed, so it should be
 destroyed to ensure no information leakage occurs.
- Control Plane Server (CPS):
 - * Deployment requirements for the CPS include permitting outbound HTTPS access so the CPS can connect to Oracle and enable remote administration, monitoring, and maintenance. Find more details in the *Deployment Guide*.
 - * Customer responsibilities include providing physical security to the Exadata Cloud@Customer equipment in their data center. While Exadata Cloud@Customer employs many software security features, physical server compromise must be addressed by customer physical security to ensure the safety of the servers' contents.



Guest VM Default Fixed Users

Several user accounts regularly manage the components of Oracle Exadata Cloud@Customer. In all Exadata Cloud@Customer machines, Oracle uses and recommends SSH based login only. No Oracle user or processes use password based authentication system.

Below described are the different kind of users created by default.

Default Users: No Logon Privileges

This user list consists of default operating system users along with some specialized users like <code>exawatch</code> and <code>dbmsvc</code>. These users should not be altered. These users cannot login to the system as all are set to <code>/bin/false</code>.

- exawatch:

The exawatch user is responsible for collecting and archiving system statistics on both the database servers and the storage servers.

dbmsvc.

User is used for Management Server on the database node service in Oracle Exadata System.

NOLOGIN Users

```
bin:x:1:1:bin:/bin:/bin/false
daemon:x:2:2:daemon:/sbin:/bin/false
adm:x:3:4:adm:/dev/null:/bin/false
mail:x:8:12:mail:/var/spool/mail:/bin/false
nobody:x:99:99:Nobody:/:/bin/false
systemd-network:x:192:192:systemd Network Management:/:/bin/false
dbus:x:81:81:System message bus:/:/bin/false
rpm:x:37:37::/var/lib/rpm:/bin/false
sshd:x:74:74:Privilege-separated SSH:/var/empty/sshd:/bin/false
rpc:x:32:32:Rpcbind Daemon:/var/lib/rpcbind:/bin/false
nscd:x:28:28:NSCD Daemon:/:/bin/false
saslauth:x:999:76:Saslauthd user:/run/saslauthd:/bin/false
mailnull:x:47:47::/var/spool/mqueue:/bin/false
smmsp:x:51:51::/var/spool/mqueue:/bin/false
chrony:x:998:997::/var/lib/chrony:/bin/false
rpcuser:x:29:29:RPC Service User:/var/lib/nfs:/bin/false
uucp:x:10:14:Uucp user:/var/spool/uucp:/bin/false
nslcd:x:65:55:LDAP Client User:/:/bin/false
tcpdump:x:72:72::/:/bin/false
exawatch:x:1010:510::/:/bin/false
sssd:x:997:508:User for sssd:/:/bin/false
tss:x:59:59:Account used by the trousers package to sandbox the
tcsd daemon:/dev/null:/bin/false
dbmsvc:x:12137:11137::/home/dbmsvc:/bin/false
```

Default Users With Restricted Shell Access

These users are used for accomplishing a defined task with a restricted shell login. These users should not be altered as the defined task will fail in case these users are altered or deleted.



dbmmonitor: The dbmmonitor user is used for DBMCLI Utility. For more information, see Using the DBMCLI Utility.

Restricted Shell Users

dbmmonitor:x:2003:2003::/home/dbmmonitor:/bin/rbash

Default Users with Login permissions

These privileged users are used for accomplishing most of the tasks in the system. These users should never be altered or deleted as it would have significant impact on the running system.

SSH keys are used for login by customer staff and cloud automation.

Customer-added SSH keys may be added by the <code>UpdateVmCluster</code> method, or by customers directly accessing the customer VM and managing SSH keys inside of the customer VM. Customers are responsible for adding comments to keys to make them identifiable. When a customer adds the SSH key by the <code>UpdateVmCluster</code> method, the key is only added to the <code>authorized</code> keys file of the <code>opc</code> user.

Cloud automation keys are temporary, specific to a given cloud automation task, for example, VM Cluster Memory resize, and unique. Cloud automation access keys can be identified by the following comments: OEDA_PUB, EXACLOUD_KEY, ControlPlane. Cloud automation keys are removed after the cloud automation task completes so the authorized_keys files of the root, opc, oracle, and grid accounts should only contain cloud automation keys while the cloud automation actions are running.

Privileged Users

```
root:x:0:0:root:/root:/bin/bash
oracle:x:1001:1001::/home/oracle:/bin/bash
grid:x:1000:1001::/home/grid:/bin/bash
opc:x:2000:2000::/home/opc:/bin/bash
dbmadmin:x:2002:2002::/home/dbmadmin:/bin/bash
```

- root: Linux requirement, used sparingly to run local privileged commands. root is also used for some processes like Oracle Trace File Analyzer Agent and ExaWatcher.
- grid: Owns Oracle Grid Infrastructure software installation and runs Grid Infastructure processes.
- oracle: Owns Oracle database software installation and runs Oracle Database processes.
- opc:
 - Used by Oracle Cloud automation for automation tasks.
 - * Has the ability to run certain privileged commands without further authentication (to support automation functions).
 - * Runs the local agent, also known as "DCS Agent" that performs lifecycle operations for Oracle Database and Oracle Grid Infastructure software (patching, create database, and so on).
- dbmadmin:
 - * The dbmadmin user is used for Oracle Exadata Database Machine Command-Line Interface (DBMCLI) utility.



* The dbmadmin user should be used to run all services on the database server. For more information, see *Using the DBMCLI Utility*.

Related Topics

Using the DBMCLI Utility

Guest VM Default Security Settings

In addition to all of the Exadata features explained in *Security Features of Oracle Exadata Database Machine*, the following security settings are also applicable.

- Custom database deployment with non-default parameters.
 The command host access control is to configure Exadata security settings:
 - Implementing password aging and complexity policies.
 - Defining account lockout and session timeout policies.
 - Restricting remote root access.
 - Restricting network access to certain accounts.
 - Implementing login warning banner.
- account-disable: Disables a user account when certain configured conditions are met.
- pam-auth: Various PAM settings for password changes and password authentication.
- rootssh: Adjusts the PermitRootLogin value in /etc/ssh/sshd_config, which permits or denies the root user to login through SSH..
 - By default, PermitRootLogin is set to without-password.
 - It is recommended to leave this setting to permit the subset of cloud automation that uses this access path (for example, customer VM OS patching) to function. Setting PermitRootLogin to no will disable this subset of cloud automation functionality.
- session-limit: Sets the * hard maxlogins parameter in /etc/security/limits.conf, which is the maximum number of logins for all users. This limit does not apply to a user with uid=0.
 - Defaults to \star hard maxlogins 10 and it is the recommended secure value.
- ssh-macs: Specifies the available Message Authentication Code (MAC) algorithms.
 - The MAC algorithm is used in protocol version 2 for data integrity protection.
 - Defaults to hmac-sha1, hmac-sha2-256, hmac-sha2-512 for both server and client.
 - Secure recommended values: hmac-sha2-256, hmac-sha2-512 for both server and client.
- password-aging: Sets or displays the current password aging for interactive user accounts.
 - M: Maximum number of days a password may be used.
 - m: Minimum number of days allowed between password changes.
 - W: Number of days warning given before a password expires.



- Defaults to -M 99999, -m 0, -W 7
- --strict compliance only -M 60, -m 1, -W 7
- Secure recommended values: -M 60, -m 1, -W 7

Related Topics

Security Features of Oracle Exadata Database Machine

Guest VM Default Processes

- Exadata Cloud@Customer Guest VM agent: Cloud agent for handling database lifecycle operations
 - Runs as opc user.
 - Process table shows it running as a Java process with jar names, dbcs-agent-VersionNumber-SNAPSHOT.jar and dbcs-admin-VersionNumver-SNAPSHOT.jar.
- Oracle Trace File Analyzer agent: Oracle Trace File Analyzer (TFA) provides a number of diagnostic tools in a single bundle, making it easy to gather diagnostic information about the Oracle Database and Oracle Clusterware, which in turn helps with problem resolution when dealing with Oracle Support.
 - Runs as root user.
 - Runs as initd demon, /etc/init.d/init.tfa.
 - Process tables show a Java application, oracle.rat.tfa.TFAMain.
- ExaWatcher:
 - Runs as root and exawatch users.
 - Runs as backgroud script, ExaWatcher.sh and all its child process run as a Perl process.
 - Process table shows as multiple Perl applications.
- Oracle Database and Oracle Grid Infrastructure (Oracle Clusterware):
 - Runs as dbmsvc and grid users.
 - Process table shows following applications:
 - * orangent.bin, apx *, and ams * as grid user.
 - * dbrsMain, and Java applications, derbyclient.jar and weblogic.Server as oracle user.
- Management Server (MS): Part of Exadata image software for managing and monitoring the image functions.
 - Runs as dbmadmin user.
 - Process table shows it running as a Java process.

Guest VM Network Security



Table 7-81 Default Port Matrix for Guest VM Services

Type of interface	Name of interface	Port	Process running
Bridge on client VLAN	bondeth0	22	sshd
		1521	Oracle TNS listener
		Optionally, customers can assign a SCAN listener port (TCP/IP) in the range between 1024 and 8999. Default is 1521.	
		5000	Oracle Trace File Analyzer Collector
		7879	Jetty Management Server
	bondeth0:1	1521	Oracle TNS listener
		Optionally, customers can assign a SCAN listener port (TCP/IP) in the range between 1024 and 8999. Default is 1521.	
	bondeth0:2	1521	Oracle TNS listener
		Optionally, customers can assign a SCAN listener port (TCP/IP) in the range between 1024 and 8999. Default is 1521.	
Bridge on backup VLAN	bondeth1	7879	Jetty Management Server
Oracle Clusterware	clib0/clre0	1525	Oracle TNS listener
running on each cluster node		3260	Synology DSM iSCSI
communicates through these interfaces.		5054	Oracle Grid Interprocess Communication
		7879	Jetty Management Server
		Dynamic Port: 9000-65500	System Monitor service (osysmond)
		Ports are controlled by the configured ephemeral range in the operating system and are dynamic.	



Table 7-81 (Cont.) Default Port Matrix for Guest VM Services

Type of interface	Name of interface	Port	Process running
		Dynamic Port: 9000-65500	Cluster Logger service (ologgerd)
		Ports are controlled by the configured ephemeral range in the operating system and are dynamic.	
	clib1/clre1	5054	Oracle Grid Interprocess communication
		7879	Jetty Management Server
Cluster nodes use	stib0/stre0	7060	dbcs-admin
these interfaces to access storage cells		7070	dbcs-agent
(ASM disks).	stib1/stre1	7060	dbcs-admin
However, the IP/ports 7060/7070 attached to the storage interfaces are used to access DBCS agent from the Control Plane server.		7070	dbcs-agent
Control Plane server to domU	eth0	22	sshd
Loopback	lo	22	sshd
		2016	Oracle Grid Infrastructure
		6100	Oracle Notification Service (ONS), part of Oracle Grid Infrastructure
		7879	Jetty Management Server
		Dynamic Port 9000-65500	Oracle Trace File Analyzer



TNS listener opens dynamic ports after initial contact to well known ports (1521, 1525).

Default iptables rules for Guest VM:



The default iptables are setup to ACCEPT connections on input, forward, and output chains.

Additional Procedures for Updating Security Posture

- Customer Responsibilities
- Enabling Additional Security Capabilities

Customer Responsibilities

Table 7-82 Resposibilities

	Oracle Cloud Platform		Customer/Tenant Instances	
Monitoring	Oracle Cloud Ops	Customer	Oracle Cloud Ops	Customer
	Infrastructure, Control Plane, hardware faults, availability, capacity	Provide network access to support Oracle infrastructure log collection and monitoring	Infrastructure availability to support customer monitoring of customer services	Monitoring of customer operating system, databases, apps
Incident Management and Resolution	Incident Management and Remediation Spare parts and	Onsite diagnostic assistance, for example, network troubleshooting	Support for any incidents related to the underlying platform	Incident Management and resolution for Customer's apps
	field dispatch			
Patch Management	Proactive patching of hardware, laaS/ PaaS control stack	Provide network access to support patch delivery	Staging of available patches, for example, Oracle Database patch set	Patching of tenant instances Testing



Table 7-82 (Cont.) Resposibilities

	Oracle Cloud Platform		Customer/Tenant Instances	
Backup and Restoration	Infrastructure and Control Plane backup and recovery, receate customer VMs	Provide network access to support cloud automation delivery		Snapshots / backup and recovey of customer's laaS and PaaS data using Oracle native or third- party capability
Cloud Support	Response and resolution of SR related to infrastructure or subscription issues	Submit SR through MOS	Response and resolution of SR	Submit SR through Suppot portal

Enabling Additional Security Capabilities

Using Oracle Key Vault as an External TDE Key Store for Databases on Exadata Cloud@Customer

Oracle supports customers using Oracle Key Vault (OKV) as an external key store for databases running on Exadata Cloud@Customer. Instructions for migrating TDE Master Keys to OKV are published in My Oracle Support Document 2823650.1 (*Migration of File based TDE to OKV for Exadata Database Service on Cloud at Customer Gen2*). Oracle does not support third-party hardware security modules (HSM) with Exadata Cloud@Customer.

Modifying Password Complexity Requirements Using host_access_control

Table 7-83 host_access_control password-aging

Option	Description
-s,status	Displays current user password aging.
-u USER,user=USER	A valid interactive user's username.
defaults	Sets all password-aging values to *Exadata factory defaults for all interactive users.
secdefaults	Sets all password-aging values to **Exadata secure defaults for all interactive users.
policy	Sets all password-aging values to the aging policy as defind by the password-policy command (or /etc/login.defs) for all interactive users.
-M int,maxdays=int	Maximum number of days a password may be used. Input limited to from 1 to 99999.
-m int,mindays=int	Minimum number of days allowed between password changes. Input limited to from 0 to 99999, 0 for anytime.
-W int,warndays=int	Number of days warning given before a password expires. Input limited to from 0 to 99999.



Table 7-83 (Cont.) host_access_control password-aging

Option	Description
host_access_control password-policy	PASS_MAX_DAYS integer (60)*
	PASS_MIN_DAYS integer (1)*
	PASS_MIN_LEN integer (8)*
	PASS_WARN_AGE integer (7)*
	defaults
	status

Table 7-84 host_access_control pam-auth

Options	Description
-h,help	Shows this help message and exits.
-d DENY,deny=DENY	Number of failed login attempts before an account will be locked. Input is limited to from 1 to 10. (*Exadata factory default is 5)
-1 LOCK_TIME,lock=LOCK_TIME	Number of seconds (integer) an account will be locked due to a single failed login attempt. Input is limited to from 0 to 31557600 (one year) (*Exadata factory default is 600 (10m))
-p list,passwdqc=list	FOR SYSTEMS RUNNING ON LESS THAN OL7
	Comma-separated set of 5 values: N0,N1,N2,N3,N4 defining the minimum allowed length for different types of password/ passphrases. Each subsequent number is required to be no larger than the preceding one. The keyword "disabled" can be used to disallow passwords of a given kind regardless of their length. (Refer to the pam_passwdqc manpage for an explanation).
	Passwords must use three character classes. Character classes for passwords are digits, lowercase letters, uppercase letters, and other characters. Minimum password length is 12 characters when using three character classes.
	Minimum password length is 8 characters when using four character classes. (*Exadata factory default is 5,5,5,5,5) (**Exadata secure default is disabled,disabled,16,12,8)



Table 7-84 (Cont.) host_access_control pam-auth

Description
FOR SYSTEMS RUNNING ON OL7 AND GREATER
Integer, ranging from 6 to 40, defining the minimum allowed password length. defined by the Exadata secure defaults. All classes will be required for password changes as well as other checks enforced for lengths >7. For lengths <8, class requirements are not used.
(*Exadata factory default is: minlen=8 dcredit=-1 ucredit=-1 lcredit=-1 ocredit=-1 difok=8 maxrepeat=3 maxclassrepeat=4)
(**Exadata secure default is: minlen=15 dcredit=-1 ucredit=-1 lcredit=-1 ocredit=-1 difok=8 maxrepeat=3 maxclassrepeat=4)
(Refer to the pam_pwquality manpage for details)
The last <i>n</i> passwords to remember for password change history. Valid range is an integer from 0 to 1000.
(*Exadata factory default is 10)
Sets all pam-auth values to *Exadata factory defaults.
Sets all pam-auth values to **Exadata secure defaults.
Displays current PAM authentication settings.

Implementing or Updating the iptables firewall Configuration in Guest VM

iptables configuration and firewall rules are stored in /etc/sysconfig/iptables.

man iptables: To get iptables help. Various websites online have many tutorials as well.

iptables --list: To get current iptables rules.

Refer to earlier section "Guest VM Network Security" for details on what ports may be required on Guest VM. To configure the firewall manually, create commands like the following example. Note that it is possible to lock yourself out of the system by blocking the ports over which you connect, so it's recommended to consult a test system and engage an experienced iptables administrator if possible.

1. At the command prompt, enter the appropriate command for each port to be opened, for example:

```
# iptables -A INPUT -m state --state NEW -m tcp -p tcp --dport 7002 -j
ACCEPT
# iptables -A INPUT -m state --state NEW -m udp -p udp --dport 123 -j
ACCEPT
```



2. Save the iptables configuration.

service iptables save

Changing passwords and Updating Authorized Keys

To change a user password the password command is used. Passwords must be changed 7 days prior expiration date. Password policies are described above in the default security settings section.

Default Oracle Exadata Users and Passwords - See My Oracle Support note https://support.oracle.com/epmos/faces/DocContentDisplay?id=1291766.1. Other accounts not included in that note are listed below.

Table 7-85 User Accounts

User Name and Password	User Type	Component
opc - key-based login only	Operating system user	Oracle Exadata Database Servers
exawatch (release 19.1.0 and later) - no logon privileges	Operating system user	Oracle Exadata Database Servers
		Oracle Exadata Storage Servers
SYS/Welcome\$	Oracle Database user	Oracle Exadata Database Servers
SYSTEM/Welcome\$	Oracle Database user	Oracle Exadata Database Servers
MSUser	ILOM user	Database server ILOMs
Management Server (MS) uses this account to manage ILOM and reset it if it detects a hang.		Oracle Exadata Storage Server ILOMs
The MSUser password is not persisted anywhere. Each time MS starts up, it deletes the previous MSUser account and re-creates the account with a randomly generated password.		
Do not modify this account. This account is to be used by MS only.		

Pay Attention to What Actions May Impact Service-Related Logins for Cloud Automation

For example, procedures will include ensuring that authorized keys used for cloud automation actions remain intact.

For more information about Physical Network access controls including guidelines for Oracle Cloud Automation, see *Oracle Gen2 Exadata Cloud@Customer Security Controls*.



Oracle Cloud Automation access to the customer VM is controlled through token based SSH. Public keys for Oracle Cloud Automation access are stored in the authorized keys files of the oracle, opc, and root users of the customer VM. The private keys used by the automation are stored and protected by the Oracle Cloud Automation software running in the Exadata Cloud@Customer hardware in the customer's data center. The customer's OCI Identity and Access Management (IAM) controls govern if and how a customer can execute Oracle Cloud Automation functionality against the customer VM and databases. The customer may further control access through the management network and Oracle Cloud Automation keys by blocking network access (firewall rules, disabling network interface), and by revoking the credentials used by the Oracle Cloud Automation (remove the public keys from the authorized keys files). Oracle Cloud Automation Access may be temporarily restored by the customer to permit the subset of functionality required to access the customer VM and customer databases, such as customer VM operating system patching. Oracle Cloud Automation does not need network access the customer VM to perform OCPU scaling, and OCPU scaling functionality will function normally when customers block Oracle Cloud Automation network access to the customer VM.

Configure Encrypted Channels for Database Listener (Oracle Net) Connectivity

For more information, see Configuring Oracle Database Native Network Encryption and Data Integrity.

Related Topics

- Managing the Keystore and the Master Encryption Key
- https://support.oracle.com/rs?type=doc&id=1291766.1
- https://support.oracle.com/rs?type=doc&id=2823650.1
- Oracle Gen2 Exadata Cloud@Customer Security Controls
- Configuring Oracle Database Native Network Encryption and Data Integrity

Troubleshooting Exadata Database Service on Cloud@Customer Systems

These topics cover some common issues you might run into and how to address them.

- Patching Failures on Exadata Database Service on Cloud@Customer Systems
- Obtaining Further Assistance
- VM Operating System Update Hangs During Database Connection Drain
- Adding a VM to a VM Cluster Fails
- CPU Offline Scaling Fails

Patching Failures on Exadata Database Service on Cloud@Customer Systems

Patching operations can fail for various reasons. Typically, an operation fails because a database node is down, there is insufficient space on the file system, or the virtual machine cannot access the object store.



Determining the Problem

In the Console, you can identify a failed patching operation by viewing the patch history of an Exadata Database Service on Cloud@Customer system or an individual database.

Troubleshooting and Diagnosis

Diagnose the most common issues that can occur during the patching process of any of the Exadata Database Service on Cloud@Customer components.

Determining the Problem

In the Console, you can identify a failed patching operation by viewing the patch history of an Exadata Database Service on Cloud@Customer system or an individual database.

A patch that was not successfully applied displays a status of Failed and includes a brief description of the error that caused the failure. If the error message does not contain enough information to point you to a solution, you can use the database CLI and log files to gather more data. Then, refer to the applicable section in this topic for a solution.

Troubleshooting and Diagnosis

Diagnose the most common issues that can occur during the patching process of any of the Exadata Database Service on Cloud@Customer components.

Database Server VM Issues

One or more of the following conditions on the database server VM can cause patching operations to fail.

Oracle Grid Infrastructure Issues

One or more of the following conditions on Oracle Grid Infrastructure can cause patching operations to fail.

Oracle Databases Issues

An improper database state can lead to patching failures.

Database Server VM Issues

One or more of the following conditions on the database server VM can cause patching operations to fail.

Database Server VM Connectivity Problems

Cloud tooling relies on the proper networking and connectivity configuration between virtual machines of a given VM cluster. If the configuration is not set properly, this may incur in failures on all the operations that require cross-node processing. One example can be not being able to download the required files to apply a given patch.

Given the case, you can perform the following actions:

- Verify that your DNS configuration is correct so that the relevant virtual machine addresses are resolvable within the VM cluster.
- Refer to the relevant Cloud Tooling logs as instructed in the *Obtaining Further Assistance* section and contact Oracle Support for further assistance.



Oracle Grid Infrastructure Issues

One or more of the following conditions on Oracle Grid Infrastructure can cause patching operations to fail.

Oracle Grid Infrastructure is Down

Oracle Clusterware enables servers to communicate with each other so that they can function as a collective unit. The cluster software program must be up and running on the VM Cluster for patching operations to complete. Occasionally you might need to restart the Oracle Clusterware to resolve a patching failure.

In such cases, verify the status of the Oracle Grid Infrastructure as follows:

```
./crsctl check cluster

CRS-4537: Cluster Ready Services is online

CRS-4529: Cluster Synchronization Services is online

CRS-4533: Event Manager is online
```

If Oracle Grid Infrastructure is down, then restart by running the following commands:

```
crsctl start cluster -all
crsctl check cluster
```

Oracle Databases Issues

An improper database state can lead to patching failures.

Oracle Database is Down

The database must be active and running on all the active nodes so the patching operations can be completed successfully across the cluster.

Use the following command to check the state of your database, and ensure that any problems that might have put the database in an improper state are resolved:

```
\verb|srvctl| status database -d | \textit{db}\_unique\_name - \verb|verbose||
```

The system returns a message including the database instance status. The instance status must be **Open** for the patching operation to succeed.

If the database is not running, use the following command to start it:

```
srvctl start database -d db_unique_name -o open
```

Obtaining Further Assistance

If you were unable to resolve the problem using the information in this topic, follow the procedures below to collect relevant database and diagnostic information. After you have collected this information, contact Oracle Support.



- Collecting Cloud Tooling Logs
 Use the relevant log files that could assist Oracle Support for further investigation and resolution of a given issue.
- Collecting Oracle Diagnostics

Related Topics

Oracle Support

Collecting Cloud Tooling Logs

Use the relevant log files that could assist Oracle Support for further investigation and resolution of a given issue.

DBAASCLI Logs

/var/opt/oracle/log/dbaascli

dbaascli.log

Collecting Oracle Diagnostics

To collect the relevant Oracle diagnostic information and logs, run the dbaascli diag collect command.

For more information about the usage of this utility, see DBAAS Tooling: Using dbaascli to Collect Cloud Tooling Logs and Perform a Cloud Tooling Health Check.

Related Topics

 DBAAS Tooling: Using dbaascli to Collect Cloud Tooling Logs and Perform a Cloud Tooling Health Check

VM Operating System Update Hangs During Database Connection Drain

Description: This is an intermittent issue. During virtual machine operating system update with 19c Grid Infrastructure and running databases, <code>dbnodeupdate.sh</code> waits for <code>RHPhelper</code> to drain the connections, which will not progress because of a known bug "DBNODEUPDATE.SH HANGS IN RHPHELPER TO DRAIN SESSIONS AND SHUTDOWN INSTANCE".

Symptoms: There are two possible outcomes due to this bug:

- 1. VM operating system update hangs in rhphelper
 - Hangs the automation
 - Some or none of the database connections will have drained, and some or all of the database instances will remain running.
- 2. VM operating system update does not drain database connections because rhphelper crashed
 - Does not hang automation
 - Some or none of the database connection draining completes



/var/log/cellos/dbnodeupdate.trc will show this as the last line:

(ACTION:) Executing RHPhelper to drain sessions and shutdown instances. (trace:/u01/app/grid/crsdata/scaqak04dv0201/rhp//executeRHPDrain.150721125206.trc)

Action:

 Upgrade Grid Infrastructure version to 19.11 or above. (OR)

Disable rhphelper before updating and enable it back after updating.

To disable before updating is started:

```
/u01/app/19.0.0.0/grid/srvm/admin/rhphelper /u01/app/19.0.0.0/grid 19.10.0.0.0 -setDrainAttributes ENABLE=false
```

To enable after updating is completed:

/u01/app/19.0.0.0/grid/srvm/admin/rhphelper /u01/app/19.0.0.0/grid oracle-home-current-version -setDrainAttributes ENABLE=true

If you disable rhphelper, then there will be no database connection draining before database services and instances are shutdown on a node before the operating system is updated.

- 2. If you missed disabling RHPhelper and upgrade is not progressing and hung, then it is observed that the draining of services is taking time:
 - a. Inspect the /var/log/cellos/dbnodeupdate.trc trace file, which contains a paragraph similar to the following:

```
(ACTION:) Executing RHPhelper to drain sessions and shutdown instances. (trace: /u01/app/grid/crsdata/<nodename>/rhp//executeRHPDrain.150721125206.trc)
```

b. Open the /var/log/cellos/dbnodeupdate.trc trace file.If rhphelper fails, then the trace file contains the message as follows:

```
"Failed execution of RHPhelper"
```

If rhphelper hangs, then the trace file contains the message as follows:

```
(ACTION:) Executing RHPhelper to drain sessions and shutdown instances.
```

c. Identify the rhphelper processes running at the operating system level and kill them. There are two commands that will have the string "rhphelper" in the name – a Bash shell, and the underlying Java program, which is really rhphelper executing.

rhphelper runs as root, so must be killed as root (sudo from opc).

For example:

```
[opc@<HOST> ~] pgrep -lf rhphelper
191032 rhphelper
191038 java
[opc@<HOST> ~] sudo kill -KILL 191032 191038
```



d. Verify that the <code>dbnodeupdate.trc</code> file moves and the Grid Infrastructure stack on the node is shutdown.

For more information about RHPhelper, see *Using RHPhelper to Minimize Downtime During Planned Maintenance on Exadata (Doc ID 2385790.1).*

Related Topics

 Using RHPhelper to Minimize Downtime During Planned Maintenance on Exadata (Doc ID 2385790.1)

Adding a VM to a VM Cluster Fails

Description: When adding a VM to a VM cluster, you might encounter the following issue:

[FATAL] [INS-32156] Installer has detected that there are non-readable files in oracle home.

CAUSE: Following files are non-readable, due to insufficient permission oracle.ahf/data/scaqak03dv0104/diag/tfa/tfactl/user_root/tfa_client.trc ACTION: Ensure the above files are readable by grid.

Cause: Installer has detected a non-readable trace file, oracle.ahf/data/scaqak03dv0104/diag/tfa/tfactl/user_root/tfa_client.trc created by Autonomous Health Framework (AHF) in Oracle home that causes adding a cluster VM to fail.

AHF ran as root created a trc file with root ownership, which the grid user is not able to read.

Action: Ensure that the AHF trace files are readable by the grid user before you add VMs to a VM cluster. To fix the permission issue, run the following commands as root on all the existing VM cluster VMs:

chown grid:oinstall /u01/app/19.0.0.0/grid/srvm/admin/logging.properties

chown -R grid:oinstall /u01/app/19.0.0.0/grid/oracle.ahf*

chown -R grid:oinstall /u01/app/grid/oracle.ahf*

CPU Offline Scaling Fails

Description: CPU offline scaling fails with the following error:

 ** CPU Scale Update $^{\star\star} \text{An}$ error occurred during module execution. Please refer to the log file for more information

Cause: After provisioning a VM cluster, the <code>/var/opt/oracle/cprops/cprops.ini</code> file, which is automatically generated by the database as a service (DBaaS) is not updated with the <code>common_dcs_agent_bindHost</code> and <code>common_dcs_agent_port</code> parameters and this causes CPU offline scaling to fail.



Action: As the root user, manually add the following entries in the $\protect{var/opt/oracle/cprops.ini}$ file.

```
common_dcs_agent_bindHost=<IP_Address>
common dcs agent port=7070
```



The common dcs agent port value is 7070 always.

Run the following command to get the IP address:

```
netstat -tunlp | grep 7070
```

For example:

```
netstat -tunlp | grep 7070
tcp 0 0 <IP address 1>:7070 0.0.0.0:* LISTEN 42092/java
tcp 0 0 <IP address 2>:7070 0.0.0.0:* LISTEN 42092/java
```

You can specify either of the two IP addresses, <IP address 1> or <IP address 2> for the common_dcs_agent_bindHost parameter.

