Memory Management

Management of a limited resource:

(Memory hunger of applications increases with capacity!)

⇒ Sophisticated algorithms needed, together with support from HW and from compiler and loader.

Key point: program's view memory is set of memory cells starting at addresss 0x0 and finishing at some value (logical address)

Hardware: have set of memory cells starting at address 0x0 and finishing at some value (physical address)


Want to be able to store memory of several programs in main memory at the same time

need suitable mapping from logical addresses to physical addresses:

- at compile time: absolute references are generated (eg MS-DOS .com-files)
- at load time: can be done by special program
- at execution time: needs HW support

Address mapping can be taken one step further: dynamic linking: use only one copy of system library

 \Rightarrow OS has to help: same code accessible to more than one process



If memory demand is too high, memory of some processes is transferred to disk

Usually combined with scheduling: low priority processes are swapped out

Problems:

- Big transfer time
- What to do with pending I/O?

First point reason why swapping is not principal memory management technique

exception: systems without hardware support by memory management unit (some embedded systems)

⇒ user decides which process is swapped out possible only at few pre-defined moments Swapping raises two problems:

- over time, many small holes appear in memory (external fragmentation)
- programs only a little smaller than hole ⇒ leftover too small to qualify as hole (internal fragmentation)

Strategies for choosing holes:

- First-fit: Start from beginning and use first available hole
- Rotating first fit: start after last assigned part of memory
- Best fit: find smallest usable space
- Buddy system: Free holes are administered according to tree structure; smallest possible chunk used

4□ ト ← □ ト ← 亘 ト ← 亘 り へ ○

Paging

Alternative approach: Assign memory of a fixed size (page) ⇒ avoids external fragmentation

Translation of logical address to physical address done via page table


Hardware support mandatory for paging:

If page table small, use fast registers

Store large page tables in main memory, but cache most recently used entries

Instance of a general principle:

Whenever large lookup tables are required, use cache (small but fast storage) to store most recently used entries



Eike Ritter

◆□ > ◆□ > ◆□ > ◆□ > ◆□



Operating Systems with C/C++

Operating Systems with C/C++

Eike Ritter

Operating Systems with C/C++

Segmentation

Idea: Divide memory according to its usage by programs:


- Data: mutable, different for each instance
- Program Code: immutable, same for each instance
- Symbol Table: immutable, same for each instance, only necessary for debugging


Requires again HW support

can use same principle as for paging, but have to do overflow check

Paging motivated by ease of allocation, segmentation by use of memory

⇒ combination of both works well (eg 80386)





Virtual memory

Idea: complete separation of logical and physical memory

⇒ Program can have extremely large amount of virtual memory

Generalisation of paging and segmentation works because most programs use only small fraction of memory intensively.

Efficient implementation tricky

Reason: Enormous difference between

- memory access speed (ca. 60ns)
- disk access speed (ca. 6ms)

Factor 100,000 !!



Virtual memory implemented as demand paging:

memory divided into units of same length (pages), together with valid/invalid bit

Two strategic decisions to be made:

Demand Paging

- Which process to "swap out" (move whole memory to disk and block process): done by swapper
- which pages to move to disk when additional page is required: done by pager

Minimisation of rate of page faults (page has to be fetched from memory) crucial

1.) FIFO:

easy to implement, but does not take locality into account Further problem: Increase in number of frames can cause increase in number of page faults (Belady's anomaly)

2.) Optimal algorithm: select page which will be re-used at the latest time (or not at all) ⇒ not implementable, but good for comparisons

3.) Least-recently used:

use past as guide for future and replace page which has been unused for the longest time

Problem: Requires a lot of HW support

Possibilities:

- -Stack in microcode
- -Approximation using reference bit: HW sets bit to 1 when page is referenced.

Now use FIFO algorithm, but skip pages with reference bit 1, resetting it to 0

Eike Ritter

 \Rightarrow Second-chance algorithm



Thrashing

If process lacks frames it uses constantly, page-fault rate very high.

- ⇒ CPU-throughput decreases dramatically.
- ⇒ Disastrous effect on performance.

Two solutions:

1.) Working-set model (based on locality):

Define working set as set of pages used in the most recent Δ page references

keep only working set in main memory

⇒ Achieves high CPU-utilisation and prevents thrashing

Difficulty: Determine the working set!

Approximation: use reference bits; copy them each 10,000

references and define working set as pages with reference bit set. > > <

Eike Ritter

Operating Systems with C/C++

Memory Management in the Linux Kernel

2.) Page-Fault Frequency: takes direct approach:

- give process additional frames if page frequency rate high
- remove frame from process if page fault rate low

Have only four segments in total:

- Kernel Code
- Kernel Data
- User Code
- User Data

Paging used as described earlier

Have elaborate permission system for pages

Operating Systems with C/C++

Kernel memory and user memory

Page caches

Memory usage in linux influenced by HW limitations of earlier architecture

Result: When using 32 bit architecture, division of logical address space in

- 3GB for user processes (so-called high memory)
- 1GB for kernel (so-called low memory)

If kernel requires more memory, pages in high memory may be temporarily mapped into low memory Division not present in 64 bit architecture Experience shows: have repeated cycles of allocation and freeing same kind of objects (eg inodes, dentries)

can have pool of pages used as cache for these objects (so-called slab cache)

cache maintained by application (eg file system) kmalloc uses slab caches for commonly used sizes



