Memory Management

Management of a limited resource: (Memory hunger of applications increases with capacity!)

⇒ Sophisticated algorithms needed, together with support from HW and from compiler and loader.

Start by looking at mapping from logical addresses to physical addresses:

- at compile time: absolute references are generated (e.g., MS-DOS .com-files)
- at load time: can be done by special program
- at execution time: needs HW support

Address mapping can be taken one step further:

dynamic linking: use only one copy of system library

 \Rightarrow OS has to help: same code accessible to more than one process

27

Paging

Alternative approach: Assign memory of a fixed size (page)

 \Rightarrow avoids external fragmentation

Translation of logical address to physical address done via page table

Hardware support mandatory for paging:

If page table small, use fast registers

Store large page tables in main memory, but cache most recently used entries

Instance of a general principle:

Whenever large lookup tables are required, use cache (small but fast storage) to store most recently used entries

Memory protection easily added to paging: protection information stored in page table

Fragmentation

Swapping raises two problems:

- over time, many small holes appear in memory (external fragmentation)
- programs only a little smaller than hole
 ⇒ leftover too small to qualify as hole (internal fragmentation)

Strategies for choosing holes:

- First-fit: Start from beginning and use first available hole
- Rotating first fit: start after last assigned part of memory
- Best fit: find smallest usable space
- Buddy system: Free holes are administered according to tree structure; smallest possible chunk used

Swapping

If memory demand is too high, memory of some processes is transferred to disk Usually combined with scheduling: low priority processes are swapped out

Problems:

- Big transfer time
- What to do with pending I/O?

First point reason why swapping is not principal memory management technique


exception: MS-Windows 3.1: based on MS-DOS for 8086, which is not sophisticated enough (no MMU).

 \Rightarrow user decides which process is swapped out possible only at few pre-defined moments

⇒ multi-processing severely limited

DOS-mode in Windows 9.x has same limitations!

28



Logical Address Offset Pagenumber Control bits Page Table Memory address Main Memory

31

Idea: Divide memory according to its usage by programs:

- Data: mutable, different for each instance
- Program Code: immutable, same for each instance
- Symbol Table: immutable, same for each instance, only necessary for debugging


Requires again HW support


can use same principle as for paging, but have to do overflow check

Paging motivated by ease of allocation, segmentation by use of memory

 \Rightarrow combination of both works well (e.g., 80386)

32





Virtual memory

Demand Paging

Virtual memory implemented as demand pag-

Idea: complete separation of logical and physical memory

⇒ Program can have extremely large amount of virtual memory

Generalisation of paging and segmentation works because most programs use only small fraction of memory intensively.

Efficient implementation tricky

Reason: Enormous difference between

- memory access speed (ca. 60ns)
- disk access speed (ca. 6ms)

Factor 100,000 !!

35

Page replacement algorithms

1.) FIFO:

easy to implement, but does not take locality into account

Further problem: Increase in number of frames can cause increase in number of page faults (Belady's anomaly)

2) Optimal algorithm:

select page which will be re-used at the latest time (or not at all)

⇒ not implementable, but good for comparisons

memory divided into units of same length (pages), together with valid/invalid bit

Two strategic decisions to be made:

- Which process to "swap out" (move whole memory to disk and block process): done by swapper
- which pages to move to disk when additional page is required: done by pager

Minimisation of rate of page faults (page has to be fetched from memory) crucial

If we want 10% slowdown due to page fault, require fault rate $p < 10^{-6}$!!

36

3) Least-recently used:

use past as guide for future and replace page which has been unused for the longest time

Problem: Requires a lot of HW support Possibilities:

- -Stack in microcode
- -Approximation using reference bit: HW sets bit to 1 when page is referenced. Now use FIFO algorithm, but skip pages with reference bit 1, resetting it to 0

⇒ Second-chance algorithm

37

38

Thrashing

If process lacks frames it uses constantly, page-fault rate very high.

- ⇒ CPU-throughput decreases dramatically.
- ⇒ Disastrous effect on performance.

Two solutions:

1.) Working-set model (based on locality): Define working set as set of pages used in the most recent Δ page references keep only working set in main memory \Rightarrow Achieves high CPU-utilisation and prevents thrashing

Difficulty: Determine the working set! Approximation: use reference bits; copy them each 10,000 references and define working set as pages with reference bit set.

2.) Page-Fault Frequency: takes direct approach:

- give process additional frames if page frequency rate high
- remove frame from process if page fault rate low