LAB:: SNORT (IDS)

- In this example we are using apnictraining.net as domain name.
- # super user command.
- \$ normal user command.
- X replace with your group no.
- Username apnic and password training

Topology

```
[group1.apnictraining.net] [192.168.30.1] [group2.apnictraining.net] [192.168.30 .2] [group8.apnictraining.net] [192.168.30.8] [group9.apnictraining.net] [192.168.30.9] [group10.apnictraining.net] [192.168.3 .30.10] [group20.apnictraining.net] [192.168.3 .20] [group21.apnictraining.net] [192.168.3 .30.21] [group22.apnictraining.net] [192.168.3 .30.22] [group30.apnictraining.net] [192.1 .48.3 .30.3 .30]
```

Install SNORT

```
sudo apt-get install snort
```

It will ask for your HOME_NET. For this lab define it as your host IP. For group1 it will 192.168.30.11/32. If required we can change it from snort.conf file also.

After installation check the installation location of SNORT

whereis snort

Few important location

- 1. SNORT configuration: /etc/snort/snort.conf
- 2. SNORT debian configuration: /etc/snort/snort.debian.conf
- 3. SNORT rules : /etc/snort/rules
- 4. SNORT exuecuble: /usr/sbin/snort

Configure SNORT

Check HOME_NET and Interface related configuration from <code>/etc/snort.debian.conf</code>. During installation process if you define your HOME_NET properly; no need to edit it. Or you can edit this file.

The main configuration file for SNORT is /etc/snort/snort.conf file.

```
sudo vi /etc/snort/snort.conf
```

This is a big configuration file; for lab purpose we will disable all predefined rules. Disable (put #) all the line having include \$RULE\ PATH (in Step 7 of configuration file) except

```
include $RULE\_PATH/local.rules . We will pur all our local rules in
include $RULE\_PATH/local.rules
```

To enable alert log; comment (adding # before the line) the following line:

```
output unified2: filename snort.log, limit 128, nostamp, mpls_event_types, vlan_ev
ent_types
```

```
Save and quit from snort.conf file :wq

Start SNORT sudo /etc/init.d/snort start

Check whether SNORT is running # ps -ef|grep snort
```

SNORT Rules

Snort rules are divided into two logical sections:

- 1. Rule Header: The rule header contains the rule's action, protocol, source and destination IP addresses and netmasks, and the source and destination ports information.
- 2. Rule Options: The rule option section contains alert messages and information on which parts of the packet should be inspected to determine if the rule action should be taken.

The First Bad Rule

Add the following rules in /etc/snort/rules/local.rules

```
alert ip any any -> any any (msg: "IP Packet detected"; sid: 10000;)
```

Save and exit. Restart snort service

sudo /etc/init.d/snort restart

This rules will generate alert for every packet. Try to ping any destination and check alert log file:

sudo su
tail -f /var/log/snort/alert

SNORT Exercise

Excercise 1: Write a rules to check XMAS scan on your server from external network

Exercise 2: Write a rules to check any external network access your webserver /admin pages

Exercise 3: Write a rules to check SSH brute force attack and log IP trying to connect more than 3 times in

60 seconds

END OF EXERCISE