The Definitive Physics Definition List

Engineers of Dubious Quality Yudong, Yicheng, Samuel, and Walter

September 14, 2016

1 Measurements

Express errors/uncertainties to 1 s.f. and write the measured value to the same decimal place as its error/uncertainty

Systematic Error	An error that occurs consistently more or consistently less than the actual reading.
Random Error	An error that occurs as a scattering (or spreading) of readings about the average or mean value of the measurements.
Precision	The reproducibility of a measurement. Repeated measurements which are very close to one another are precise measurements. Thus an experiment which has small random errors (i.e. small spread of readings) is said to have high precision .
Accuracy	The agreement between the measured value and the true or accepted value of a quantity. An experiment which has small systematic errors is said to have high accuracy . The average value is close to the true value.
Vector Quantity	A quantity that has a magnitude and direction .
Scalar Quantity	A quantity that has a magnitude only .

2 Kinematics

We define a coordinate system with defined reference positive directions, and we assume constant acceleration when we apply the kinematics equations.

Displacement	s	The distance travelled in a stated direction from a reference point.
Velocity	$\mathbf{v} = \frac{d\mathbf{s}}{dt}$	The rate of change of displacement with respect to time.
Speed	$v = \mathbf{v} = \left \frac{d\mathbf{s}}{dt} \right $	The rate of change of distance travelled with respect to time.
Acceleration	$\mathbf{a} = \frac{d\mathbf{v}}{dt} = \frac{d^2\mathbf{s}}{dt^2}$	The rate of change of velocity with respect to time.

3 Dynamics

3.1 Newton's Laws of Motion

1 st Law	A body will continue in its state of rest , or move at constant speed in a straight line unless an external resultant force acts on it.		
\rightarrow Inertia	The resistance to change in the state of motion of an object		
$\rightarrow Mass$	A property of that determines the objects inertia.		
2 nd Law	The rate of change of linear momentum of a body is directly proportional to the resultant force acting on it, and its direction is in the same direction as this resultant force.		
	The force acting on an object is defined as the rate of change of linear momentum of an object.		
	$\mathbf{F} \propto rac{d\mathbf{p}}{dt}, \ \mathbf{F} = m\mathbf{a}$ (if constant mass)		
3 rd Law	If body A exerts a force on body B, then body B will exert an equal and opposite force on body A.		
	<i>Note:</i> Action-Reaction Pairs act on different bodies and are of the same nature.		
Weight	The gravitational force acting on the object.		
Weightlessness	There is no contact force acting on the object. A body experiences apparent weightlessness when the resultant force acting on it is its weight, or it is undergoing freefall.		

3.2 Momentum

Linear Momen- tum	$\mathbf{p} = m\mathbf{v}$	The product of an object's mass and its velocity.
Impulse	$\mathbf{J} = \int_{t1}^{t2} \mathbf{F} dt = \mathbf{p}_f - \mathbf{p}_i$	The product of the average force acting on an object and the time interval that the force is being applied.
-	The total momentum of the system is a constant when no external resultant force acts on it.	

4 Forces

Pressure due to Fluid	$\Delta P = h\rho g$	The force acting per unit area by the fluid on a body submerged at a depth in the fluid.
Upthrust	$U = m_f g = \rho V_{dis} g$	The net upward force exerted by a fluid on a body partially or fully submerged in the fluid.
Principle of Floatation	$mg = U = \rho V_{dis}g$	This holds true for an object floating in equilibrium in a fluid.
Drag	$\mathbf{F_D} = k\mathbf{v}$ (Laminar Flow)	It is the force resisting an object moving relative to a fluid. It always opposes motion, and its magnitude is dependent on the velocity of the object.
Moment of a force (Torque)	$ au = \mathbf{r} imes \mathbf{F}$	Moment of a force about a point (the pivot) is the product of the magnitude of the force and the perpendicular distance of the line of action of the force to the point.
Couple	A couple always consists of 2 parallel forces which are equal in magnitude and opposite in direction (their lines of action do not coincide)	
Torque of a couple	The product of the magnitude of one of the forces of the couple and the perpendicular distance between the forces .	
Center of gravity of a body	It is the point at which	ch the weight of the body appears to act.

4.1 Equilibrium of Forces

For a rigid body to be in static equilibrium, 2 conditions must be satisfied:

- 1. **Translational equilibrium**The **net external** force acting on the body is zero.
- 2. **Rotational Equilibrium**The **net torque** on the body about <u>ANY</u> **point** is zero.

$$\sum F = 0$$

$$\sum \tau = 0$$

Principle of Moments The principle of moments states that when in (rotational) equilibrium the total sum of the anti-clockwise moment is equal to the total sum of the clockwise moment.

For a 3-forces system in static equilibrium, the 3 forces form *a closed vector triangle*. For 3 forces acting on an *extended body* in static equilibrium, the lines of action of the 3 forces *must intersect at a common point* unless the 3 forces are parallel.

5 Work, Energy, and Power

Principle of Conservation of Energy	Energy can be converted from one form to another, but it cannot be created or destroyed . The total energy of an isolated system is constant	
Work done by a Force	$W = \int_C \mathbf{F} \cdot d\mathbf{s}$	The product of the magnitude of the force F and the displacement s in the direction of the force.
Total Mechanical Energy	$\sum KE + \sum PE$	The total mechnical energy of a system is the sum of all types of kinetic energy and potential energy.
Kinetic Energy	$E_k = \frac{1}{2}mv^2$	Kinetic energy of a body is a measure of the energy possessed by the body by virtue of its motion.
Potential Energy	_	The amount of work that was done on a body to give it that position.
	ш	It is a measure of the energy possessed by the body by virtue of its position or the arrangement of the system that it is part of. [There are 3 types: Elastic, Gravitational and Electrical]
Power	$P = \frac{dW}{dt} = Fv$	Power is the rate at which work is done.
		When a force acts on a body that is moving with velocity v , in the direction of the force, it delivers power to the body at the rate given by $P=Fv$.

6 Circular Motion

Always write "The forces provide the centripetal force".		
Angular Displacement	θ	Angle swept from a reference point.
Angular Velocity	$\omega = \frac{d\theta}{dt} = \frac{2\pi}{T} = 2\pi f$	Rate of change of angular displacement with respect to time.
Period	$T = \frac{1}{f}$	Time taken for one complete revolution.
Linear/Tangential Speed	$v = \frac{2\pi r}{T} = r\omega$	(No need to know definition)

6.1 Uniform Circular Motion

Conditions: ω constant, r constant

Uniform Circular Motion It is the motion of an object travelling at constant (uniform) speed in a circular path.

Centripetal Acceleration/ Centripetal Force The centripetal acceleration/force is directed **radially inward** towards the centre of the circular path. The direction of the centripetal acceleration/force is continuously changing.

$$\sum a = a_{net} = a_c = \frac{v^2}{r} = r\omega^2 = v\omega$$

No acceleration/force in the tangential direction. \Rightarrow No work done.

7 Gravitation

The 'G's in the following left column stands for 'Gravitation', or 'Gravitational'.

Newton's Law of G	,	Gravitational force between 2 objects is directly proportional to the product of their masses, and inversely proportional to the square of the distances between them.
G Field Strength	$g = \frac{F_g}{m} = G\frac{M}{r^2}$	The GFS g at a point in a gravitational field is the gravitational force per unit mass acting on a small mass placed at that point.
G Field	_	A region of space surrounding a body possessing mass, in which any other body that has mass will experience a force of attraction.
G Potential	$\phi = \frac{U}{m} = -G\frac{M}{r}$ $g = -\frac{d\phi}{dr}$	experience a force of attraction. Work done per unit mass by an external force in bringing a small mass from infinity to that point in a gravitational field without a change in kinetic energy.
G Potential Energy	$U = -G\frac{m_1 m_2}{r}$ $F_g = -\frac{dU}{dr}$	Work done by an external force in bringing a mass from infinity to that point in a gravitational field without a change in kinetic energy.
Geostationary Orbit		A satellite in orbit that appears stationary to an observer on Earth. It has a period of 24 h, orbits the Earth along the plane containing the equator, and moves from the West to the East.

8 Oscillations

Simple Harmonic Motion	$a = -\omega^2 x$	A body oscillating with SHM has acceleration
		that is directly proportional to the displacement
		from equilibrium and the acceleration is in a
		direction opposite to that of displacement from
		equilibrium.

8.1 Types of Oscillations

Damped Oscillation	Oscillation in which the amplitude of the oscillations decreases with time.
\rightarrow Light	
\rightarrow Critical	
\rightarrow Heavy	
Forced Oscillation	
Resonance	Phenomenon where the maximum amplitude of an object driven to oscillate is achieved when the driver frequency is equal to the natural frequency due to efficient transfer of energy.

9 Waves and Superposition

Progressive Waves	Disturbance/Vibration which propagates , carrying energy without physically transferring the wave particle.	
\rightarrow Transverse Waves	Progressive wave in which particles or fields oscillate perpendicular to direction of wave propagation.	
\rightarrow Longitudinal Waves	Progressive wave in which particles oscillate parallel to direction of wave propagation.	
Intensity	Power per unit area	
	$E \propto A^2 \Rightarrow I \propto A^2$	
Polarisation	Vibrations in a transverse waves are restricted to only 1 direction in a plane normal to the direction of energy transfer.	
Principle of Superposition	When 2 or more waves of the same type superimpose, the displacement of a resultant wave at any point at any instant is the vector sum of the displacements of the individual waves at that point at that instant.	
Stationary/Standing Waves	Formed when 2 similar waves of same speed, frequency and amplitude travelling towards each other in opposite directions superimpose.	
Interference	The overlap of 2 or more waves to give a resultant wave whose displacement at every point at any time is given by the Principle of Superposition.	
	⇒ Conditions: (i) Same kind of waves; (ii) overlap	
ightarrow Observable Interference	Same type, overlapCoherenceRoughly same AmplitudeUnpolarised or polarised in the same plane	
	<u>Constructive</u> : Oscillation at that point has maximum resultant amplitude and maximum intensity. <u>Destructive</u> : Oscillation at that point has minimum resultant amplitude and minimum intensity.	
Diffraction	Spreading of waves into "geometrical" shadow after passing through an aperture or around an obstacle as a result of a redistribution of energy.	

10 Thermal Physics

Temperature	T	Measure of the average kinetic energy the molecules in a system possess.
Heat	Q	Thermal energy that naturally flows from regions of higher to lower temperature.
Thermal Equilibrium		2 objects in thermal contact with no net exchange of heat.
Kelvin Scale		Absolute temperature scale independent of thermometric properties.
Absolute Zero	0K	All molecules possess minimal internal energy.
Specific Heat Capacity	C	Amount of thermal energy per unit mass to increase the temperature of the unit mass of substance by one unit of temperature.
Specific latent heat of fusion	L_f	Amount of thermal energy per unit mass to convert the substance from solid to liquid without any change in temperature.
Specific latent heat of vaporisation	L_v	Amount of thermal energy per unit mass to convert the substance from liquid to gas without any change in temperature.
Internal Energy	U	Sum of microscopic random kinetic energy and microscopic potential energy of molecules in system. For ideal gases: $U=\frac{3}{2}\ nRT$

10.1 Laws of Thermodynamics

$$\Delta U = Q + W_{on}$$

We need not know the 3rd and 4th laws.

 $^{0^{}th}$ If two systems are in thermal equilibrium with a third system, they are in thermal equilibrium with each other.

¹st Increase in internal energy of system is sum of heat absorbed by system and work done on system.

10.2 PV Graphs

We assume, for the following, that the arrow points towards the positive- $\!V$ direction.

Isobaric	Constant Pressure	$W_{on} < 0 \; , \; \Delta U > 0$
Isochoric	Constant Volume	$W_{on} = 0 \; , \; \Delta U > 0$
Isothermal	Constant Temperature	$W_{on} < 0 \; , \; \Delta U = 0$
Adiabatic	Thermally Insulated	$W_{on} < 0 , \ Q = 0$
Cyclic	Start and end at the same state	$\Delta U = 0$

11 Electric Fields

Electric Field	$E = \frac{Q}{4\pi\varepsilon_0 r^2}$	Electric force per unit charge acting on small positive test charge at that point.
Coulomb's Law	$F_E = \frac{ Q_1 Q_2 }{4\pi\varepsilon_0 r^2}$	Magnitude of the electric force between 2 point charges is directly proportional to the product of the magnitude of their charges and inversely proportional to square of their distance.
		$F_E = qE$
Electric Potential	$V = \frac{Q}{4\pi\varepsilon_0 r}$	Work done per unit charge by external force to bring small positive test charge from infinity to that point in an electric field without change in kinetic energy.
Electric Potential Energy	$U = \frac{Q_1 Q_2}{4\pi\varepsilon_0 r}$	Work done by external force to bring small positive test charge from infinity to that point in an electric field without change in kinetic energy.
		U = qV

12 Current of Electricity

Potential Difference The potential difference between 2 points in a circuit is the electrical

energy converted to non-electrical energy per unit electric charge

between the 2 points.

Current Rate of flow of charge.

$$I_{\text{instantaneous}} = \frac{dQ}{dt}$$

Electromotive Force EMF of a source is the amount of non-electrical energy converted to

electrical energy per unit electric charge in driving a charge round a

complete circuit

Resistance Ratio of potential difference across device to the current flowing through

it

 $R = \frac{\rho L}{A}$

Charge The charge passing through a given point is the product of current and

time during which the current flows.

Q = It

Coulomb 1 C is the quantity of electric charge that pass a given point in a circuit

when a steady current of 1 A passes through that point for 1 s.

Ohm 1Ω is the resistance of a device through which a current of 1 A flows


when a potential difference of 1 V exists across it.

13 DC Circuits

The potential divider rule is summarised by the equation:

$$V_{\rm R1} = \frac{R_{\rm R1}}{R_{\rm total}} \times V_{\rm total}$$

A potentiometer can be used to find the electromotive force of an unknown cell as well as its internal resistance. The simplest and most common potentiometer setup is shown in the following figure.



When the galvanometer shows zero deflection, i.e. no current passes through G, the emf of E_1 can be found by:

$$V_{E_1} = \frac{L_{\text{AC}_1}}{L_{\text{AB}}} \times V_{E_0}$$

To find the internal resistance of E_1 , a resistor of known resistance is added across E_1 , and the position of C_1 adjusted such that the galvanometer again shows no deflection. This effectively creates two separate circuits, one around E_0AB and one from E_1 to the resistor. The terminal potential difference of E_1 can be found using the same equation as above. Using this value, the previously found electromotive force of E_1 , and the potential divider rule, the internal resistance can be found accordingly.

14 EM and EMI

14.1 Concepts

Magnetic Flux Density	В	The force per unit length per unit current acting on an infinitely long current carrying conductor placed perpendicular to the magnetic field. The SI unit is the tesla, T.
\rightarrow Tesla	Т	The magnetic flux density of a magnetic field is said to be $1\mathrm{T}$ if the force acting per unit length on an infinitely long conductor carrying a current of $1\mathrm{A}$ and placed perpendicular to the magnetic field is $1\mathrm{N}\mathrm{m}^{-1}$.
Magnetic Flux	$\varphi = \mathbf{B} \cdot \mathbf{A}$	The magnetic flux through a surface is the product of the magnetic flux density normal to the surface and the area of the surface. The SI unit is the weber, Wb.
\rightarrow Weber	Wb	The weber is defined as the magnetic flux through a surface of $1~\mathrm{m}^2$ if a magnetic field of flux density $1~\mathrm{T}$ exists perpendicular to the surface.
Flux Linkage	$\Phi = N\mathbf{B} \cdot \mathbf{A}$	The product of the magnetic flux through a coil and the number of turns of the coil. The SI unit is also the weber, Wb .
Lenz's Law	that creates a lit is a statement energy is convenient.	f the induced EMF is such that it tends to produce a current magnetic field so as to oppose the change in magnetic flux. ent of the conservation of energy where the mechanical verted to electrical energy. This law allows us to determine f the induced EMF and predict the direction of the induced

14.2 Equations

Force on Current Carrying Conductor	$\mathbf{F} = \mathbf{I}L \times \mathbf{B}$
Force on Moving Charge	$\mathbf{F} = q\mathbf{v} \times \mathbf{B}$
Torque in DC Motor	$\tau = NBIA\sin\theta$
Faraday's Law	$\varepsilon \propto rac{d\Phi}{dt}$
Induced EMF in AC Generator	$\varepsilon = NBA\omega\sin\left(\omega t\right)$
Induced EMF in a Rod Cutting Flux	$\varepsilon = B_{\perp} L v$
Induced EMF in a Faraday's Disc	$\varepsilon = BAf$

15 Alternating Current

Alternating Current

Occurs when charge carriers periodically reverse their direction of motion.

Root-Mean-Square

To find the RMS value for any AC graph:

- 1. Square the I/t or V/t graph.
- 2. Find area under graph in 1 period.
- 3. Divide the area by 1 period.
- 4. Square root the above result.

$$\sqrt{\frac{f(t)^2}{T}}$$

If the graph is sinusoidal, the RMS value can be found by simply dividing the peak value by $\sqrt{2}$. The RMS value of an alternating current is the equivalent constant DC that will dissipate the same power in a given resistive load.

AC to DC Conversion

Called rectification. Can be accomplished by placing a diode next to the AC source.

Non-Ideality in Transformers

Caused by:

- 1. Energy dissipated as heat due to resistance of windings in coils. Can be minimised by using thick coils.
- 2. Alternating magnetic flux induces eddy currents in iron core and causes heating. Can be minimised by using a laminated core.
- 3. Hysteresis loss whenever direction of magnetic flux is reversed causing some energy wastage. Can be minimised by using a soft iron core.
- 4. Flux leakage if core is badly designed.

16 Quantum Physics

16.1 Photoelectric Effect

$hf = \Phi + KE_{max}$	The <i>Photoelectric Effect</i> is the liberation of electrons from a metal surface when EM radiation of sufficiently high frequency is incident on it. This provides evidence of the particulate nature of EM radiation. $KE_{max} = \frac{1}{2} m v_{max}^2 = eV_s$
Work Function Energy Φ	The minimum amount of energy needed to remove an electron from a metal surface. This varies with the metal.
Stopping Potential V_s	The minimum pd between the emitter and the collecter that will prevent even the most energetic photoelectrons from reaching the collector.

16.2 Line Spectra

Line Spectra provides the evidence for the existence of **discrete** energy levels in the atom (interactions with the outermost electrons).

Conditions of the experiment:

- Atoms sufficiently isolated so that they do not interact with one another and the energy level remain discrete.
- Low-pressure gas is needed.

Emission Spectrum	Bright coloured lines on dark background. This is due to the photons produced when de-excitation takes place from a higher to a lower energy state.
Absorption Spectrum	Dark lines on bright coloured (rainbow) background. Only frequencies corresponding to the difference between energy intervals can be absorbed.

16.3 X-Ray Spectra

X-Ray Spectra is produced due to energy changes in electrons close to the nucleus of metal atoms.

Characteristic Lines Peaks resulting as a result of photons emitted from outer shell electrons falling into vacancies in the inner shells (e.g. $L \to K$). The positions of the peaks depend solely on the type of metal. \Rightarrow Energy differences in the inner shells are large \Rightarrow shorter λ

Continuous Radiation (Bremsstrahlung) Result of the loss in KE when the energetic bombarding electrons decelerate as they hit the metal target. The photon has λ_{min} when all the KE of the electron is converted to energy in the form of a photon.

$$hf_{max} = \frac{hc}{\lambda_{min}} = eV$$

16.4 Wave-Particle Duality

Waves can exhibit particle-like characteristics and particles can exhibit wave-like characteristics.

de Broglie wavelength
$$\lambda = \frac{h}{p} = \frac{h}{mv}$$

16.5 Heisenberg's Uncertainty Principle

Position-Momentum $\Delta x \Delta p \geq \frac{h}{4\pi} \quad \text{If a measurement of position of a particle is made with uncertainty } \Delta x \text{ and a simultaneous measurement of linear momentum is made with uncertainty } \Delta p \text{, then the product of the 2 uncertainties can never be smaller than } \frac{h}{4\pi}.$ Energy-Time Uncertainty $\Delta E \Delta t \geq \frac{h}{4\pi}$ $\Delta E \text{ is the uncertainty in the energy of the system, and } \Delta t \text{ is the time during which the system exists unperturbed. Definition is similar to that of the one above.}$ Linewidth is a result of this uncertainty principle.

16.6 Schrödinger Model and Wave Function

The wave function Ψ is obtained when one solves the Schrödinger equation.

Significance of the wave function Ψ

 $|\Psi|^2$ is the probability density function (of finding the particle). Hence, the probability of find the particle between x=a and x=b is given by

$$\int_a^b |\Psi|^2 dx$$

Quantum Tunnelling

Classically, a particple of total energy E indicent on potential energy barrier U, where U>E, will not be able to cross the barrier, since that would mean that the particle has negative KE when it is crossing the barrier.

However, when one solves the Schrödinger equation to obtain the particle's wave function Ψ , one realizes that there is a probability of finding the particle on the other side of the barrier.

$$T \propto e^{-2kd}$$
, where $k = \sqrt{\frac{8\pi^2 m(U-e)}{h^2}}$

17 Lasers and Semiconductors

Spontaneous Emission	Emission of photons through random de-excitation of excited atoms. These photons are of random phase, direction and plane of polarisation.
Stimulated Emission	Emission of photons from excited atoms as triggered by an incident photon with energy exactly equal to the difference between the excited state and the lower energy state. Emitted photon has exactly the same phase, energy, polarisation and direction of travel as incident photon.
Population Inversion	Condition where there are more atoms in the upper energy state/level than in the lower energy state/level.
Metastable State	Excited state with longer life-time than other excited states.
Conduction Band	Empty or partially filled band just above the valence band.
Valence Band	Highest fully-filled energy band at $0\mathrm{K}$.
Metals	Metals have a partially filled conduction band at $0\mathrm{K}.$
Insulators	Insulators have a fully-filled valence band and empty conduction band at 0K, and also a large bandgap. There are very few electrons in the conduction band even at room temperature due to the large bandgap.
Intrinsic Semiconductor	Intrinsic semiconductors have a full valence band and empty conduction band at 0K, but a smaller bandgap than that of insulators. An appreciable number of electrons are promoted to the conduction band at room temperature due to the smaller bandgap.

18 Nuclear Physics

Nucleon	A constituent of a nucleus, i.e. a proton or neutron.
---------	---

of neutrons and protons).

Isotope Atoms with the same number of protons but different number of

neutrons.

Unified Atomic Mass Unit 1 u is defined as $\frac{1}{12}$ of the mass of a Carbon-12 atom.

Binding Energy of Nucleus/Atom The energy required to separate the nucleus/atom into its con-

stituents

Binding Energy per Nucleon The average energy required to remove a nucleon from its nu-

cleus.

Radioactive Decay A **spontaneous** and **random** process where an **unstable** nu-

cleus changes into a different nuclide by emitting radiation. Spontaneous means that it is not triggered by external factors or influences, and random means that it is impossible to predict **which** nucleus will decay and **when** a **particular** nucleus will

decay.

Activity The rate of decay, or number of disintegrations per unit time. SI

unit is s^{-1} or the becquerel, Bq.

$$A = -\frac{dN}{dt} = \lambda N$$

Decay Constant **Probability per unit time** that a nucleus will decay. SI unit is

 s^{-1} .

 $\lambda = \frac{A}{N}$

Half-Life The average time taken for a number of radioactive nuclei to

decay to **half** its original value.

 $t_{\frac{1}{2}} = \frac{\ln 2}{\lambda}$

That's all folks!
Good luck! Don't panic, all is well.