


# (فرآبندها) Processes

Hamid R. Zarandi h\_zarandi@aut.ac.ir

### Definition


- **Process** 
  - A program in execution; process execution must progress in sequential fashion
    - In time-sharing sys: unit of work
  - All processes are executed concurrently
- Process vs. Job?
  - Passive: program
  - Active: process
    - Program becomes process when executable file loaded into memory
    - One program can be several processes
  - Ouestion?
    - java program

# Process in memory



### Process state

- >As a process executes, it changes state
  - onew: The process is being created
  - orunning: Instructions are being executed
  - waiting: The process is waiting for some event to occur
  - oready: The process is waiting to be assigned to a processor
  - o terminated: The process has finished execution



# Process Control Block (PCB)


- ► How to manage processes?
- ➤ Information associated with each process

(also task control block)

- o Process state
- Program counter
- CPU registers contents of all process-centric registers
- CPU scheduling info. priorities, scheduling queue pointers
- Memory-management info. memory allocated to the process
- Accounting info. CPU used, clock time elapsed since start, time limits
- o I/O status info. − I/O devices allocated to process, list of open files

process state process number program counter registers memory limits list of open files


# CPU switch from process to process



# Process representation in Linux


### Represented by the C structure task\_struct

```
pid t_pid; /* process identifier */
long state; /* state of the process */
unsigned int time_slice /* scheduling information */
struct task_struct *parent; /* this process's parent */
struct list_head children; /* this process's children */
struct files_struct *files; /* list of open files */
struct mm_struct *mm; /* address space of this process */
```




# Process scheduling

Process scheduler selects among available processes for next execution on CPU



# Diagram representation of process scheduling

Queueing diagram represents queues, resources, flows




### Schedulers

- ➤ Short-term scheduler (or CPU scheduler)
  - o selects which process should be executed next and allocates CPU
    - Sometimes the only scheduler in a system
    - Short-term scheduler is invoked frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler (or job scheduler)
  - o selects which processes should be brought into the ready queue
    - Long-term scheduler is invoked infrequently (seconds, minutes) ⇒ (may be slow)
    - The long-term scheduler controls the degree of multiprogramming
- Processes:
  - I/O-bound
    - spends more time doing I/O than computations, many short CPU bursts
  - o CPU-bound
    - spends more time doing computations; few very long CPU bursts
- Long-term scheduler strives for good process mix

# Example of standard API

#### > Medium-term scheduler

- Can be added if degree of multiple programming needs to decrease
- Remove process from memory, store on disk, bring back in from disk to continue execution:
   swapping



# (تعویض متن) Context switch


- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- ➤ Context-switch time is overhead; the system does no useful work while switching
  - The more complex the OS and the PCB → the longer the context switch
- >Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU → multiple contexts loaded at once

2015/09/12

### Process creation


- > Parent vs. Child
- ➤ Generally, process identified and managed via a process identifier (pid)
- **▶** Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- > Execution options
  - Parent and children execute concurrently
  - o Parent waits until children terminate

# A tree of processes in Linux



### Process creation

- ► Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- >UNIX examples
  - o fork() system call creates new process
  - o exec() system call used after a fork() to replace the process' memory space
    with a new program



### Process creation with C

```
#include <sys/types.h>
#include <stdio.h>
                                          POSIX
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
     fprintf(stderr, "Fork Failed");
     return 1:
   else if (pid == 0) { /* child process */
     execlp("/bin/ls","ls",NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
      printf("Child Complete");
   return 0;
```

```
#include <stdio.h>
#include <windows.h>
                                              Windows
int main(VOID)
STARTUPINFO si:
PROCESS_INFORMATION pi;
   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));
   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
     "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
    &si,
    &pi))
      fprintf(stderr, "Create Process Failed");
      return -1;
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");
   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
```

### Process termination

- Child → Parent
  - o Process' resources are deallocated when:
    - exit(n)
    - return() in main()
  - Catch exit status → wait()
    - pid = wait(&status);
- ▶Parent → Child
  - o abort()
  - o Why?
    - Child has exceeded allocated resources
    - Task assigned to child is no longer required
    - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates


# Problems of process termination

- >zombie process
  - No parent waiting
- >orphan process
  - Parent termination without wait
- ➤ Multi process example: Chrome Browser
  - o Browser, Renderer, Plugins, etc



# Interprocess communication (IPC)

- Process:
  - o independent vs. cooperating
- **≻**Cooperating process:
  - Shared memory
  - Message passing



# Circular buffer & producer-consumer problem

```
item next_consumed;
while (true) {
    while (in == out) ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;

    /* consume the item in next consumed */
}
```

### Message passing

- Direct communication (unidirectional)
  - o send (P, message) send a message to process P
  - oreceive(Q, message) receive a message from process Q
- **►Indirect** communication (uni & bidirectional)
  - Messages are directed and received from mailboxes (or ports)
  - Can be used by multiple processes
  - o Primitives are defined as:
    - send(A, message) send a message to mailbox A
    - receive(A, message) receive a message from mailbox A

# Synchronization

- Blocking vs. non-blocking
- Blocking is considered synchronous
  - Blocking send
  - Blocking receive
- Non-blocking is considered asynchronous
  - Non-blocking send
  - Non-blocking receive
    - The receiver receives
      - ☐ A valid message
      - □ Null message
- Different combinations possible
  - o If both send and receive are blocking, we have a rendezvous

22


2015/09/12

# POSIX examples of **shared memory**: (sender->receiver)

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";
/* shared memory file descriptor */
int shm_fd:
/* pointer to shared memory obect */
void *ptr;
   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);
   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);
   /* write to the shared memory object */
   sprintf(ptr,"%s",message_0);
   ptr += strlen(message_0);
   sprintf(ptr, "%s", message_1);
   ptr += strlen(message_1);
   return 0;
```

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm_fd:
/* pointer to shared memory obect */
void *ptr;
   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);
   /* read from the shared memory object */
   printf("%s",(char *)ptr);
   /* remove the shared memory object */
   shm_unlink(name);
   return 0;
```

# Local procedure calls in Windows




# Communications in client-server systems

- **≻**Sockets
- **▶** Remote Procedure Calls (windows)
- **Pipes**
- ➤ Remote Method Invocation (Java)

### Sockets

- ➤ A socket is defined as an endpoint for communication
- Concatenation of IP address and port a number included at start of message packet to differentiate network services on a host
- > The socket 161.25.19.8:1625 refers to port 1625 on host 161.25.19.8
- Communication consists between a pair of sockets
- > All ports below 1024 are well known, used for standard services
- > Special IP address 127.0.0.1 (loopback) to refer to system on which process is running

### Socket communication




### Sockets in Java

- ➤ Three types of sockets
  - Connection-oriented (TCP)
  - Connectionless (UDP)
  - MulticastSocket class– data can be sent to multiple recipients
- Consider this "Date" server:

```
import java.net.*;
import java.io.*;
public class DateServer
  public static void main(String[] args) {
     try
       ServerSocket sock = new ServerSocket(6013);
       /* now listen for connections */
       while (true) {
          Socket client = sock.accept();
          PrintWriter pout = new
           PrintWriter(client.getOutputStream(), true);
          /* write the Date to the socket */
          pout.println(new java.util.Date().toString());
          /* close the socket and resume */
          /* listening for connections */
          client.close();
     catch (IOException ioe) {
       System.err.println(ioe);
```

# Execution of RPC (Remote Procedure Call)



# Pipes

- > Acts as a conduit allowing two processes to communicate
- > Issues:
  - o Is communication unidirectional or bidirectional?
  - o In the case of two-way communication, is it half or full-duplex?
  - Must there exist a relationship (i.e., parent-child) between the communicating processes?
  - o Can the pipes be used over a network?

#### Ordinary pipes


o cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created.

#### ➤ Named pipes

o can be accessed without a parent-child relationship.

# Ordinary Pipes

- > Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe)
- Ordinary pipes are therefore unidirectional
- > Require parent-child relationship between communicating processes



- ➤ Windows calls these anonymous pipes
- See Unix and Windows code samples in textbook

# Ordinary pipe (POSIX), parent-child

```
#include <sys/types.h>
#include <stdio.h>
#include <string.h>
#include <unistd.h>
#define BUFFER_SIZE 25
#define READ_END 0
#define WRITE_END 1
int main(void)
char write_msg[BUFFER_SIZE] = "Greetings";
char read_msg[BUFFER_SIZE];
int fd[2];
pid_t pid;
   /* create the pipe */
   if (pipe(fd) == -1) {
      fprintf(stderr, "Pipe failed");
      return 1;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1:
```

```
if (pid > 0) { /* parent process */
  /* close the unused end of the pipe */
  close(fd[READ_END]);
  /* write to the pipe */
  write(fd[WRITE_END], write_msg, strlen(write_msg)+1);
  /* close the write end of the pipe */
  close(fd[WRITE_END]);
else { /* child process */
  /* close the unused end of the pipe */
  close(fd[WRITE_END]);
  /* read from the pipe */
  read(fd[READ_END], read_msg, BUFFER_SIZE);
  printf("read %s",read_msg);
  /* close the write end of the pipe */
  close(fd[READ_END]);
return 0;
```

# Ordinary pipe (windows), parent

```
#include <stdio.h>
#include <stdlib.h>
#include <windows.h>
#define BUFFER SIZE 25
int main(VOID)
HANDLE ReadHandle, WriteHandle;
STARTUPINFO si;
PROCESS_INFORMATION pi;
char message[BUFFER_SIZE] = "Greetings";
DWORD written:
  /* set up security attributes allowing pipes to be inherited */
  SECURITY_ATTRIBUTES sa = {sizeof(SECURITY_ATTRIBUTES), NULL, TRUE};
  /* allocate memory */
  ZeroMemory(&pi, sizeof(pi));
  /* create the pipe */
  if (!CreatePipe(&ReadHandle, &WriteHandle, &sa, 0))
     fprintf(stderr, "Create Pipe Failed");
     return 1:
  /* establish the START_INFO structure for the child process */
  GetStartupInfo(&si):
  si.hStdOutput = GetStdHandle(STD_OUTPUT_HANDLE);
  /* redirect standard input to the read end of the pipe */
  si.hStdInput = ReadHandle;
  si.dwFlags = STARTF_USESTDHANDLES;
```

```
/* don't allow the child to inherit the write end of pipe */
SetHandleInformation(WriteHandle, HANDLE_FLAG_INHERIT, 0);
/* create the child process */
CreateProcess(NULL, "child.exe", NULL, NULL,
 TRUE, /* inherit handles */
 0, NULL, NULL, &si, &pi);
/* close the unused end of the pipe */
CloseHandle (ReadHandle):
/* the parent writes to the pipe */
if (!WriteFile(WriteHandle, message, BUFFER_SIZE, &written, NULL))
  fprintf(stderr, "Error writing to pipe.");
/* close the write end of the pipe */
CloseHandle(WriteHandle);
/* wait for the child to exit */
WaitForSingleObject(pi.hProcess, INFINITE);
CloseHandle(pi.hProcess);
CloseHandle(pi.hThread);
return 0;
```

# Ordinary pipe (windows), child

```
#include <stdio.h>
#include <windows.h>
#define BUFFER_SIZE 25
int main(VOID)
HANDLE Readhandle;
CHAR buffer[BUFFER_SIZE];
DWORD read;
   /* get the read handle of the pipe */
   ReadHandle = GetStdHandle(STD_INPUT_HANDLE);
   /* the child reads from the pipe */
   if (ReadFile(ReadHandle, buffer, BUFFER_SIZE, &read, NULL))
     printf("child read %s", buffer);
   else
     fprintf(stderr, "Error reading from pipe");
   return 0;
```

# Named pipes

- **►Named Pipes** are more powerful than ordinary pipes (?)
- > Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- >Several processes can use the named pipe for communication
- ➤ Provided on both UNIX and Windows systems

# Questions?

