

Operating Systems

Synchronization Tools-Part2

Seyyed Ahmad Javadi

sajavadi@aut.ac.ir

Fall 2022

Peterson's Solution

```
//P<sub>0</sub>
                                       //P_1
while (true) {
                                       while (true) {
   flag[0] = true;
                                           flag[1] = true;
   turn = 1;
                                           turn = 0;
                                            while (flag[0] \&\& turn == 0);
    while (flag[1] \&\& turn == 1);
    /* critical section */
                                            /* critical section */
    flag[0] = false;
                                            flag[1] = false;
    /* remainder section */
                                            /* remainder section */
```

Peterson's Solution and Modern Architecture

 Although useful for demonstrating an algorithm, Peterson's solution is not guaranteed to work on modern architectures.


 To improve performance, processors and/or compilers may reorder operations that have no dependencies.

 Understanding why it will not work is useful for better understanding race conditions.

Peterson's Solution and Modern Architecture

For single-threaded this is ok as the result will always be the same.

For multithreaded the reordering may produce inconsistent or unexpected results!





Modern Architecture Example

Two threads share the data:

```
boolean flag = false; int x = 0;
```

Thread 1 performs

```
while (!flag);
   print x
```

Thread 2 performs

$$x = 100;$$
 flag = true

What is the expected output?

100



Modern Architecture Example (cont.)

However, since the variables flag and x are independent of each other, the instructions:

flag = true;
$$x = 100;$$


for Thread 2 may be reordered

If this occurs, the output may be 0!



Peterson's Solution Revisited

The effects of instruction reordering in Peterson's Solution




- This allows both processes to be in their critical section at the same time!
- To ensure that Peterson's solution will work correctly on modern computer architecture we must use Memory Barrier.

Hardware Support for Synchronization

Memory Barrier

 Memory model are the memory guarantees a computer architecture makes to application programs.



https://www.researchgate.net/figure/Shared-memory-architecture_fig1_272377248



Memory Barrier (cont.)

Memory models may be either:

Strongly ordered


Memory modification of one processor is immediately visible to all other processors.


Weakly ordered

 Memory modification of one processor may not be immediately visible to all other processors.

Memory Barrier (cont.)

 A memory barrier is an instruction that forces any change in memory to be propagated (made visible) to all other processors.





Memory Barrier Instructions

• When a memory barrier instruction is performed, the system ensures that all loads and stores are completed before any subsequent load or store operations are performed.

Therefore, even if instructions were reordered, the memory barrier ensures that the store operations are completed in memory and visible to other *processors* before future load or store operations are performed.

Memory Barrier Example

Returning to the example of slides 5-6

 We could add a memory barrier (as follows) to ensure Thread 1 outputs 100.

Memory Barrier Example (cont.)

Thread 1 now performs

```
while (!flag)
memory_barrier();
print x
```

Thread 2 now performs

```
x = 100;
memory_barrier();
flag = true
```

- For Thread 1 \rightarrow the value of flag is loaded before the value of x.
- For Thread 2 \rightarrow the assignment to x occurs **before the assignment flag**.



Memory Barrier for Peterson's solution

Where should we add memory barrier?

```
//P_0
                                      //P_1
                                      1. while (true) {
1. while (true) {
2.
   flag[0] = true;
                                      2. flag[1] = true;
3.
                                      3. turn = 0;
  turn = 1;
  while (flag[1] \&\& turn == 1);
                                      4. while (flag[0] && turn == 0);
4.
    /* critical section */
                                          /* critical section */
5.
     flag[0] = false;
                                            flag[1] = false;
    /* remainder section */
                                          /* remainder section */
                                      }
```

Memory Barrier for Peterson's solution (Cont.)

We could place a memory barrier between the first two assignment statements in the entry section to avoid the reordering of operations shown in the previous slide.

Note that memory barriers are considered very low-level operations and are typically only used by kernel developers when writing specialized code that ensures mutual exclusion.

Synchronization Hardware Support

- Many systems provide hardware support for implementing the critical section code.
- Uniprocessors could disable interrupts
 - Currently running code would execute without preemption
 - Generally, too inefficient on multiprocessor systems
 - Operating systems using this not broadly scalable.
- We will look at two forms of hardware support:
 - 1. Hardware instructions
 - 2. Atomic variables



Hardware Instructions

- Special hardware instructions that allow us to either test-and-modify the content of a word, or two swap the contents of two words atomically (uninterruptedly.)
 - Test-and-Set instruction
 - Compare-and-Swap instruction

The test_and_set Instruction

Definition

```
boolean test_and_set (boolean *target)
{
    boolean rv = *target;
    *target = true;
    return rv:
}
```

- Properties
 - Executed atomically
 - Returns the original value of passed parameter
 - Set the new value of passed parameter to true



Solution Using test_and_set()

Shared boolean variable lock, initialized to false

Does it solve the critical-section problem?

Requirement	Yes/No
Mutual Exclusion	
Progress	
Bounded waiting	

The compare_and_swap Instruction

Definition

```
Int compare_and_swap(int *value, int expected, int new_value)
{
  int temp = *value;
  if (*value == expected)
     *value = new_value;
  return temp;
}
```

Properties

- Executed atomically
- Returns the original value of passed parameter value
- Set the variable value the value of the passed parameter new_value but only if *value == expected is true.



Solution using compare_and_swap

Shared integer lock initialized to 0;

```
while (true) {
  while (compare_and_swap(&lock, 0, 1)!= 0);/*do nothing*/
  /* critical section */
  lock = 0;
  /* remainder section */
}
```

Does it solve the critical-section problem?

Requirement	Yes/No
Mutual Exclusion	
Progress	
Bounded waiting	



Second solution using compare-and-swap

The common data structures are:

```
boolean waiting[n];
int lock;
```

- The elements in the waiting array are initialized to false
- Variable *lock* is initialized to 0.

Second solution using compare-and-swap

```
while (true) {
   waiting[i] = true;
   key = 1;
   while (waiting[i] && key == 1)
      key = compare and swap(\&lock, 0, 1);
   waiting[i] = false;
   /* critical section */
```



Second solution using compare-and-swap

```
while (true) {
   j = (i + 1) % n;
   while ((j != i) \&\& !waiting[j])
       j = (j + 1) % n;
                                              Yes/No?
                                Requirement
   if (j == i)
                             Mutual Exclusion
       lock = 0;
                             Progress
                             Bounded waiting
   else
      waiting[j] = false;
   /* remainder section */
```

Synchronization Hardware Support

Hardware instructions

- test_and_set()
- Compare_and_swap()

Atomic variables

- We unfortunately do not have enough time to cover this
- Please read the related section in the reference book