Squirrel 0.5 alpha

Reference manual

 $^{\circ}$ 2003.Alberto Demichelis. All rights reserved. You are allowed to copy and to print this document as long as you don't exploit the information commercially.

The author of this document makes no warranty of any kind, expressed or implied, with regard to the programs or the documentation contained in this document.

1 Contents

1	CONTENTS	. 2
_		
<u>2</u>	INTRODUCTION	<u>. 5</u>
•	THE LANGUAGE	_
<u>3</u>	THE LANGUAGE	<u>. 5</u>
3.1	LEXICAL STRUCTURE	
3.1.		
3.1.		
3.1.	1	
3.1. 3.1.		
3.1. 3.2	VALUES AND DATA TYPES	
3.2.		
3.2.		
3.2.		
3.2.		
3.2.		
3.2.	6 Array	. 6
3.2.	7 Function	. 7
3.2.	8 GENERATOR	. 7
3.2.	9 Userdata	. 7
3.3	EXECUTION CONTEXT	. 7
3.3.		
3.4	STATEMENTS	
3.4.		
3.4.		
3.4. 3.4.		
3.4. 3.4.		• -
3.4.		
3.4.		
3.4.		
3.4.		
3.4.		
3.4.	5 CONTINUE	11
3.4.	6 RETURN	11
3.4.	7 YIELD	11
3.4.		
3.4.		
3.4.		
3.4.		
3.4.		
3.5	EXPRESSIONS	
3.5. 3.5.		
3.5.		
3.5.	1	
3.5.		
3.5.		
3.5.		
	*	

3.5.2.6		
3.5.2.7	1	
3.5.2.8	Bitwise Operators	14
3.5.2.9	Operators precedence	14
3.5.3	TABLE CONSTRUCTOR	
3.5.4	DELEGATE	
3.5.5	CLONE	
3.5.6	ARRAY CONSTRUCTOR	
	TABLES	
3.6.1	CONSTRUCTION	
3.6.2	SLOT CREATION	
3.6.3	SLOT DELETION	
	ARRAYS	
	FUNCTIONS	
3.8.1	FUNCTION DECLARATION	
3.8.2	FUNCTION CALLS	
3.8.3	FREE VARIABLES	
3.8.4	TAIL RECURSION	
	GENERATORS	
	DELEGATION	
3.11	METAMETHODS	
3.11.1	_SET	20
3.11.2	_GET	21
3.11.3	_NEWSLOT	21
3.11.4	ADD	21
3.11.5	SUB	21
3.11.6		21
3.11.7	DIV	
3.11.8	 _MODULO	
3.11.9	_UNM	
3.11.10		
3.11.11		
3.11.12		
3.11.12	_	
3.11.14	-	
	BUILT-IN FUNCTIONS	
3.12.1	GLOBAL FUNCTIONS	
3.12.2	DEFAULT DELEGATES	
3.12.2.	\mathcal{C}	
3.12.2.		
3.12.2.		
3.12.2.		
3.12.2.	·	
3.12.2.	6 Function	24
3.12.2.	7 Generator	24
4 500		•
<u>4</u> <u>EN</u>	MBEDDING SQUIRREL	24
4.1 N	MEMORY MANAGEMENT	25
	JNICODE	
	ERROR CONVENTIONS	
	NITIALIZING SQUIRREL	
	FTA CIV. INDEXES	
4.5.1	STACK INDEXES	
4.5.2	STACK MANIPULATION	
	RUNTIME ERRORS HANDLING	
	COMPILING A SCRIPT	
	CALLING A FUNCTION	28
10 (In many and a fill many a company	20

4.10		
4.11		
4.12		
4.13		
<u>5</u>	API REFERENCE MANUAL	33
5.1		33
5.2		34
5.3	STACK OPERATIONS	
5.4		
5.5		
5.6		
5.7		45
5.8		46
<u>6</u>	<u>INDEX</u>	48

2 Introduction

Squirrel is a high level imperative/OO programming language, designed to be a powerful scripting tool that fits in the size, memory bandwidth, and real-time requirements of applications like games.

Although Squirrel offers a wide range of features like dynamic typing, delegation, higher order functions, generators, tail recursion, exception handling, automatic memory management, both compiler and virtual machine fit together in about 6k lines of C++ code.

3 The language

This part of the document describes the syntax and semantics of the language.

3.1 Lexical structure

3.1.1 Identifiers

Identifiers start with a alphabetic character or '_' followed by any number of alphabetic characters, '_' or digits ([0-9]). Squirrel is a case sensitive language, this means that the lowercase and uppercase representation of the same alphabetic character are considered different characters. For instance "foo", "Foo" and "fOo" will be treated as 3 distinct identifiers.

$$id: = [a-zA-Z_]+[a-zA-Z_0-9]*$$

3.1.2 Keywords

The following words are reserved words by the language and cannot be used as identifiers:

break	case	catch	Clone	continue	default	delegate	delete
else	for	if	in	local	long	null	resume
return	switch	this	throw	try	typeof	while	yield

Keywords are covered in detail later in this document.

3.1.2.1 Operators

Squirrel recognizes the following operators:

```
! != <- % & && * + +=
-= - < <= == => > ^ |
```

3.1.3 Other tokens

3.1.4 Literals

Squirrel accepts integer numbers, floating point numbers and stings literals.

34	Integer number
0xFF00A120	Integer number
'a' or 'FORM'	Integer number

```
1.52 Floating point number
"I'm a string" String

IntegerLiteral := [0-9]+ | '0x' [0-9A-Fa-f]+ | ''' [.]+ '''

FloatLiteral := [0-9]+ '.' [0-9]+

StringLiteral:= '"'[.]* '"'
```

3.2 Values and Data types

Squirrel is a dynamically typed language so variables do not have a type, although they refer to a value that does have a type.

Squirrel basic types are integer, float, string, null, table, array, function, generator and userdata.

3.2.1 Integers

An Integer represents a 32 bits (or better) signed number.

```
local a = 123 //decimal
local b = 0x0012 //hexadecimal
```

3.2.2 Float

A float represents a 32 bits (or better) floating point number.

```
local a=1.0
local b=0.234
```

3.2.3 String

Strings are an immutable sequence of characters to modify a string is necessary create a new one.

```
local a="I'm a wonderful string"
```

3.2.4 Null

The *null value* is a primitive value that represents the null, empty, or non-existent reference. The type **Null** has exactly one value, called **null**. In squirrel it is also used to represent a false Boolean value.

```
local a=null
```

3.2.5 Table

Tables are associative containers implemented as pairs of key/value (called a slot)

```
local t={}
local test=
{
   a=10
   b=function(a) { return a+1; }
}
```

3.2.6 Array

Arrays are simple sequence of objects, their size is dynamic and their index starts always from 0.

```
local a=["I'm", "an", "array"]
```

```
local b=[null]
b[0]=a[2];
```

3.2.7 Function

Functions are similar to those in other C-like languages and to most programming languages in general, however there are a few key differences (see below).

3.2.8 Generator

Generators are functions that can be suspended with the statement 'yield' and resumed later (see Generators).

3.2.9 Userdata

Userdata objects are blobs of memory(or pointers) defined by the host application but stored into Squirrel variables (See <u>Userdata and UserPointers</u>).

3.3 Execution Context

The execution context is the union of the function stack frame and the function environment object(this).

The stack frame is the portion of stack where the local variables declared in is body are stored.

The environment object is an implicit parameter that is automatically passed by the function caller (see <u>Functions</u>).

During the execution, the body of a function can only transparently refer to his execution context. This mean that a single identifier can refer either to a local variable or to an environment object slot; Global variables require a special syntax (see Variables). The environment object can be explicitly accessed by the keyword this.

3.3.1 Variables

There are two types of variables in Squirrel, local variables and tables/arrays slots. Because global variables are stored in a table, they are table slots.

A single identifier refers to a local variable or a slot in the environment object.

```
derefexp := id;
quad brackets are used to index tables or arrays
derefexp:= exp '[' exp ']'
_table["foo"]
_array[10]
with tables we can also use the '.' syntax
derefexp := exp '.' id
```

Squirrel first checks if an identifier is a local variable (function arguments are local variables) if not it checks if it is a member of the environment object (this).

For instance

table.foo

```
function testy(arg)
{
  local a=10;
  print(a);
  return arg;
}

will access to local variable 'a' and prints 10.
function testy(arg)
{
  local a=10;
```

in this case 'foo' will be equivalent to 'this.foo' or this["foo"]

Global variables are stored in a table called the root table. Usually in the global scope the environment object is the root table, but to explicitly access the global table from another scope, the slot name must be prefixed with '::' (::foo).

```
exp:= '::' id
For instance
function testy(arg)
{
  local a=10;
  return arg+::foo;
}
```

return arg+foo;

accesses the global variable 'foo'.

3.4 Statements

A squirrel program is a simple sequence of statements.

```
stats := stat [';'/'\n'] stats
```

Statements in squirrel are comparable to the C-Family languages (C/C++, Java, C# etc...): assignment, function calls, program flow control structures etc.. plus some custom statement like yield, table & array constructors (All those will be covered in detail later in this document).

Statements can be separated with a new line or ';' (or with the keywords case or default if inside a switch/case statement), both symbols are not required if the statement is followed by '}'.

3.4.1 Blocks

```
stat := '{' stats '}'
```

A sequence of statements delimited by curly brackets ({ }) is called block; a block is a statement itself.

3.4.2 Control Flow Statements

3.4.2.1 if/else

```
stat:= 'if' '(' exp ')' stat ['else' stat]
```

Conditionally execute a statement depending on the result of an expression. exp is considered 'false' when is value is **null** and true for any other value.

NOTE: In Squirrel also the number 0 is considered 'true'.

```
if(a>b)
    a=b;
else
    b=a;

////
if(a==10)
{
    b=a+b;
    return a;
}
```

3.4.2.2 while

```
stat:= 'while' '(' exp ')' stat
```

Executes a statement until the condition is false(null).

```
function testy(n)
{
    local a=0;
    while(a<n) a+=1;
    while(1)
    {
        if(a<0) break;
        a-=1;
    }
}</pre>
```

3.4.2.3 do/while

```
stat:= 'do' stat 'while' '(' expression ')'
```

Executes a statement once, and then repeats execution of the statement until a condition expression evaluates to null.

```
local a=0;

do
{
    print(a+"\n");
    a+=1;
} while(a>100)
```

3.4.2.4 switch

Is a control statement allows multiple selections of code by passing control to one of the **case** statements within its body.

The control is transferred to the case label whose case_exp matches with exp if none of the case match will jump to the default label (if present).

A switch statement can contain any number if case instances, if 2 case have the same expression result the first one will be taken in account first. The **default** label is only allowed once and must be the last one.

A break statement will jump outside the switch block.

3.4.3 Loops

3.4.3.1 for

```
stat:= 'for' '(' [initexp] ';' [condexp] ';' [incexp] ')' statement
```

Executes a statement as long as a condition is different than null.

```
for(local a=0;a<10;a+=1)
    print(a+"\n");

//or

glob <- null
for(glob=0;glob<10;glob+=1){
    print(glob+"\n");
}

//or

for(;;){
    print(loops forever+"\n");
}</pre>
```

3.4.3.2 foreach

```
'foreach' '(' [index_id','] value_id 'in' exp ')' stat
```

Executes a statement for every element contained in an array, table or generator. If exp is a generator it will be resumed every iteration as long as it is alive; the value will be the result of 'resume' and the index the sequence number of the iteration starting from 0.

```
local a=[10,23,33,41,589,56]
foreach(idx,val in a)
        print("index="+idx+" value="+val+"\n");

//or
foreach(val in a)
        print("value="+val+"\n");
```

3.4.4 break

```
stat := 'break'
```

The break statement terminates the execution of a loop (for, foreach, while or do/while) or jumps out of switch statement;

3.4.5 continue

```
stat := \continue'
```

The continue operator jumps to the next iteration of the loop skipping the execution of the following statements.

3.4.6 return

```
stat:= return [exp]
```

The return statement terminates the execution of the current function/generator and optionally returns the result of an expression. If the expression is omitted the function will return null. If the return statement is used inside a generator, the generator will not be resumable anymore.

3.4.7 yield

```
stat := yield [exp]
(see Generators).
```

3.4.8 Local variable declaration

```
initz := id [= exp][',' initz]
stat := 'local' initz
```

Local variables can be declared at any point in the program; they exist between their declaration to the end of the block where they have been declared.

EXCEPTION: a local declaration statement is allowed as first expression in a for loop.

```
for(local a=0;a<10;a+=1)
    print(a);</pre>
```

3.4.9 Function declaration

```
funcname := id ['::' id]
stat:= 'function' id ['::' id]+ '(' args ')'[':' '(' args ')'] stat
```

creates a new function.

3.4.10 try/catch

```
stat:= 'try' stat 'catch' '(' id ')' stat
```

The try statement encloses a block of code in which an exceptional condition can occur, such as a runtime error or a throw statement. The **catch** clause provides the exception-handling code. When a catch clause catches an exception, its *id* is bound to that exception.

3.4.11 throw

```
stat:= 'throw' exp
```

Throws an exception. Any value can be thrown.

3.4.12 expression statement

```
stat := exp
```

In Squirrel every expression is also allowed as statement, if so, the result of the expression is thrown away.

3.5 Expressions

3.5.1 Assignment(=) & new slot(<-)

```
exp := derefexp '=' exp

exp:= derefexp '<-' exp

squirrel implements 2 kind of assignment:
the normal assignment(=)

a=10;

and the "new slot" assignment.

a <- 10;</pre>
```

The new slot expression allows to add a new slot into a table(see <u>Tables</u>). If the slot already exists in the table it behaves like a normal assignment.

3.5.2 Operators

3.5.2.1 ?: Operator

```
exp := exp_cond '?' exp1 ':' exp2
```

conditionally evaluate an expression depending on the result of an expression.

3.5.2.2 Arithmetic

```
exp:= 'exp' op 'exp'
```

Squirrel supports the standard arithmetic operators +, -, * and /. Other than that is also supports 2 compact operators (+ = and -=) and increment and decrement operators(+ + and --);

```
a+=2;
//is the same as write
a=a+2;

x++
//is the same as write
x=x+1
```

All operators work normally with integers and floats; if one operand is an integer and one is a float the result of the expression will be float.

The + operator has a special behavior with strings; if one of the operands is a string the operator + will try to convert the other operand to string as well and concatenate both together.

3.5.2.3 Relational

```
exp:= 'exp' op 'exp'
```

Relational operators in Squirrel are : == < <= > >= !=

These operators return null if the expression is false and a value different than null if the expression is true. Internally the VM uses the integer 1 as true but this could change in the future.

3.5.2.4 Logical

```
exp := exp op exp
exp := '!' exp
```

Logical operators in Squirrel are: && ||!

The operator && (logical and) returns null if its first argument is null, otherwise returns its second argument.

The operator || (logical or) returns its first argument if is different than null, otherwise returns the second argument.

The '!' operator will return null if the given value to negate was different than null, or a value different than null if the given value was null.

3.5.2.5 in operator

```
exp:= keyexp 'in' tableexp
```

Tests the existence of a slot in a table.

Returns a value different than null if keyexp is a valid key in tableexp

```
Eg.
local t=
{
    foo="I'm foo",
       [123]="I'm not foo"
```

```
}
if("foo" in t) dostuff("yep");
if(123 in t) dostuff();
```

3.5.2.6 typeof operator

```
exp:= 'typeof' exp
```

returns the type name of a value as string.

```
local a={},b="squirrel"
print(typeof a); //will print "table"
print(typeof b); //will print "string"
```

3.5.2.7 comma operator

```
exp:= exp ',' exp
```

The comma operator evaluates two expression left to right, the result of the operator is the result of the expression on the right; the result of the left expression is discarded.


```
local j=0,k=0;
for(local i=0; i<10; i++ , j++)
{
        k = i + j;
}
local a,k;
a = (k=1,k+2); //a becomes 3</pre>
```

3.5.2.8 Bitwise Operators

```
exp:= 'exp' op 'exp'
exp := '~' exp
```

Squirrel supports the standard c-like bit wise operators &, |, $^{\wedge}$, $_{\sim}$, <, >. Those operators only work on integers values, passing of any other operand type to these operators will cause an exception.

3.5.2.9 Operators precedence



3.5.3 Table constructor

```
tslots := ( 'id' '=' exp | '[' exp ']' '=' exp ) [',']
exp := '{' [tslots] '}'
Creates a new table.
local a={} //create an empty table
A table constructor can also contain slots declaration;
With the syntax
id = exp [',']
a new slot with id as key and exp as value is created
local a=
    slot1="I'm the slot value"
An alternative syntax can be
'[' exp1 ']' = exp2 [',']
A new slot with exp1 as key and exp2 as value is created
local a=
    [1]="I'm the value"
both syntaxes can be mixed
local table=
    a = 10,
    b="string",
    [10]={},
    bau=function(a,b)
      return a+b;
    }
}
```

The comma between slots is optional.

3.5.4 delegate

```
exp:= 'delegate' parentexp : exp
```

Sets the parent of a table.

The result of *parentexp* is set as parent of the result of exp, the result of the expression is exp (see <u>Delegation</u>).

3.5.5 clone

```
exp:= 'clone' exp
```

Clone performs shallow copy of a table, (copies all slots in the new table without recursion). If the source table has a delegate, the same delegate will be assigned as delegate (not copied) to the new table (see <u>Delegation</u>).

After the new table is ready the "_clone" meta method is called (see Metamethods).

3.5.6 Array constructor

```
exp := '[' [explist] ']'

Creates a new array.

eg.
a <- [] //creates an empty array

arrays can be initialized with values during the construction

eg.
a <- [1, "string!",[],{}] //creates an array with 4 elements</pre>
```

3.6 Tables

Tables are associative containers implemented as pairs of key/value (called slot); values can be any possible type and keys any type except 'null'.

Tables are squirrel's skeleton, delegation and many other features are all implemented through this type; even the environment, where global variables are stored, is a table (known as root table).

3.6.1 Construction

Tables are created through the table constructor (see <u>Table constructor</u>)

3.6.2 Slot creation

Adding a new slot in a existing table is done through the "new slot" operator '<-'; this operator behaves like a normal assignment except that if the slot does not exists it will be created.

```
eg.
local a={}
```

The following line will cause an exception because the slot named 'newslot' does not exist in the table 'a'

```
a.newslot = 1234
this will succeed:
a.newslot <- 1234;
or</pre>
```

```
a[1] <- "I'm the value of the new slot";</pre>
```

3.6.3 Slot deletion

```
exp:= delete derefexp
```

Deletion of a slot is done through the keyword delete; the result of this expression will be the value of the deleted slot.

```
a <-
{
    test1=1234
    deleteme="now"
}

delete a.test1
print(delete a.deleteme); //this will print the string "now"</pre>
```

3.7 Arrays

An array is a sequence of values indexed by a integer number from 0 to the size of the array minus 1. Arrays elements can be obtained through their index.

```
eg.
local a=["I'm a string", 123]
print(typeof a[1]) //prints "string"
print(typeof a[0]) //prints "integer"
```

Resizing, insertion, deletion of arrays and arrays elements is done through a set of standard functions (see <u>built-in functions</u>).

3.8 Functions

Functions are first class values like integer or strings and can be stored in table slots, local variables, arrays and passed as function parameters.

Functions can be implemented in Squirrel or in a native language with calling conventions compatible with ANSI C.

3.8.1 Function declaration

Functions are declared through the function expression

```
local a= function(a,b,c) {return a+b-c;}

or with the syntactic sugar

function ciao(a,b,c)
{
    return a+b-c;
}

that is equivalent to

this.ciao=function(a,b)
{
```

```
return a+b-c;
}
is also possible to declare something like
T <- {}
function T::ciao(a,b,c)
{
  return a+b-c;
}
that is equivalent to write
T.ciao <- function(a,b,c)
{
  return a+b-c;
}</pre>
```

3.8.2 Function calls

```
exp:= derefexp '(' explist ')'
```

The expression is evaluated in this order: derefexp after the explist (arguments) and at the end the call.

Every function call in Squirrel passes the environment object 'this' as hidden parameter to the called function. The 'this' parameter is the object where the function was indexed from.

If we call a function with this syntax

```
table.foo(a)
```

the environment object passed to foo will be 'table'

```
foo(x,y) // equivalent to this.foo(x,y)
```

The environment object will be 'this' (the same of the caller function).

3.8.3 Free Variables

Free variables are variables referenced by a function that are not visible in the function scope. In the following example the function foo() declares x, y and testy as free variables.

```
local x=10,y=20
testy <- "I'm testy"

function foo(a,b):(x,y,testy)
{
    ::print(testy);
    return a+b+x+y;
}</pre>
```

The value of a free variable is frozen and bound to the function when the function is created; the value is passed to the function as implicit parameter every time is called.

3.8.4 Tail recursion

Tail recursion is a method for partially transforming a recursion in a program into an iteration: it applies when the recursive calls in a function are the last executed statements in that function (just before the return).

If this happenes the squirrel interpreter collapses the caller stack frame before the recursive call; because of that very deep recursions are possible without risk of a stack overflow.

```
function loopy(n)
{
     if(n>0){
         ::print("n="+n+"\n");
               return loopy(n-1);
     }
}
loopy(1000);
```

3.9 Generators

A function that contains a yield statement is called 'generator function'.

When a generator function is called, it does not execute the function body, instead it returns a new suspended generator.

The returned generator can be resumed through the resume statement while it is alive. The yield keyword, suspends the execution of a generator and optionally returns the result of an expression to the function that resumed the generator.

The generator dies when it returns, this can happen through an explicit return statement or by exiting the function body; If an unhandled exception (or runtime error) occurs while a generator is running, the generator will automatically die. A dead generator cannot be resumed anymore.

```
function geny(n)
{
    for(local i=0;i<n;i+=1)
        yield i;
    return null;
}

local gtor=geny(10);
local x;
while(x=resume gtor) print(x+"\n");</pre>
```

the output of this program will be

9

3.10 Delegation

Squirrel supports *implicit delegation*. Every table or userdata can have a parent table (delegate). A parent table is a normal table that allows the definition of special behaviors for his child.

When a table (or userdata) is indexed with a key that doesn't correspond to one of its slots, the interpreter automatically delegates the get (or set) operation to its parent.

3.11 Metamethods

Metamethods are a mechanism that allows the customization of certain aspects of the language semantics. Those methods are normal functions placed in a table parent(delegate); Is possible to change many aspect of a table behavior by just defining a metamethod for this parent.

For instance when we use relational operators other than '==' on 2 tables, the VM will check if the table has a method in his parent called $'_cmp'$ if so it will call it to determine the relation between the tables.

```
local comparable={
    _cmp = function (other)
    {
        if(name<other.name)return -1;
        if(name>other.name)return 1;
        return 0;
    }
}
local a=delegate comparable : { name="Alberto" };
local b=delegate comparable : { name="Wouter" };
if(a>b)
        print("a>b")
else
    print("b<=a");</pre>
```

3.11.1 set

invoked when the index idx is not present in the table or in its delegate chain

function _set(idx,val) //returns val

3.11.2 _get

invoked when the index idx is not present in the table or in its delegate chain

function _get(idx) //return the fetched values

3.11.3 _newslot

invoked when a script tries to add a new slot in a table.

function _newslot(key,value) //returns val

if the slot already exists in the target table the method will not be invoked also if the "new slot" operator is used.

3.11.4 _add

the + operator

function _add(op) //returns this+op

3.11.5 sub

the - operator (like _add)

3.11.6 mul

the * operator (like _add)

3.11.7 _div

the / operator (like _add)

3.11.8 _modulo

the % operator (like _add)

3.11.9 _unm

the unary minus operator

function _unm()

3.11.10 _typeof

invoked by the typeof operator on tables and userdata

function _typeof() //returns the type of this as string

3.11.11 _cmp

invoked to emulate the < > <= >= operators

function _cmp(other)

returns an integer

>0 if this>other

==0 if this==other

<0 if this<other

3.11.12 _call

invoked when a tables or userdatas are called

function call(original_this,params...)

3.11.13 _clone

invoked when a table is cloned(in the cloned table)
function clone()

3.11.14 _nexti

invoked when a userdata is iterated by a foreach loop function nexti(previdx)

if previdx==null it means that it is the first iteration.
The function has to return the index of the 'next' value.

3.12 Built-in functions

The squirrel virtual machine has a set of built utility functions.

3.12.1 Global functions

```
seterrorhandler(func)
sets the runtime error handler
setdebughook(hook_func)
sets the debug hook
getroottable()
returns the root table of the VM.
setroottable(table)
sets the root table of the VM and returns the previous one
assert(exp)
throws an exception if exp is null
print(x)
prints x in the standard output
chcode2string(code)
converts an integer representing a character code to a string
collect_garbage()
calls the garbage collector and returns the number of reference cycles found(and
deleted)
```

3.12.2 Default delegates

//<<FIXME>>

Except null and userdata every squirrel object has a default delegate containing a set of functions to manipulate and retrieve information from the object itself.

3.12.2.1 Integer

tofloat()

convert the number to float and returns it

tostring()

converts the number to string and returns it

3.12.2.2 Float

tointeger()

converts the number to integer and returns it

tostring()

converts the number to string and returns it

3.12.2.3 String

len()

returns the string length

tointeger()

converts the string to integer and returns it

tofloat()

converts the string to float and returns it

slice(start,[end])

returns a section of the string as new string. Copies from start to the end (not included). If start is negative the index is calculated as length + start, if end is negative the index is calculated as length + start. If end is omitted end is equal to the string length.

find(substr,[startidx])

search a sub string(substr) starting from the index startidx and returns the index of its first occurrence. If startidx is omitted the search operation starts from the beginning of the string. The function returns null if substr is not found.

3.12.2.4 Table

len()

returns the number of slots contained in a table

rawget(key)

tries to get a value from the slot 'key' without employ delegation

rawset(key,val)

sets the slot 'key' with the value 'val' without employing delegation.

If the slot do not exists, it will be created.

getdelegate()

returns the table delegate or null if no delegate is assigned.

3.12.2.5 Array

len()

returns the length of the array

append(val)

appends the value 'val' at the end of the array

extend(array)

Extends the array by appending all the items in the given array.

pop()

removes a value from the back of the array and returns it

top()

returns the value of the array with the higher index

insert(idx,val)

inserst the value 'val' at the position 'idx' in the array

remove(idx)

removes the value at the position 'idx' in the array

resize(size)

resizes the array

sort()

sorts the array

reverse()

reverse the elements of the array in place

slice(start,[end])

returns a section of the array as new array. Copies from start to the end (not included). If start is negative the index is calculated as length + start, if end is negative the index is calculated as length + start. If end is omitted end is equal to the array length.

3.12.2.6 Function

call(_this,args...)

calls the function with the specified environment object ('this') and parameters

acall(array_args)

calls the function with the specified environment object ('this') and parameters. The function accepts an array containing the parameters that will be passed to the called function.

3.12.2.7 Generator

getstatus()

returns the status of the generator as string: "running", "dead" or "suspended".

4 Embedding Squirrel

This section describes how to embed Squirrel in a host application, C language knowledge is required to understand this part of the manual.

Because of his nature of extension language, Squirrel's compiler and virtual machine are implemented as C library.

The library exposes a set of functions to compile scripts, call functions, manipulate data and extend the virtual machine.

All declarations needed for embedding the language in an application are in the header file 'squirrel.h'.

4.1 Memory Management

Squirrel uses reference counting (RC) as primary system for memory management; however, is possible to conditionally compile the virtual machine (VM) with an auxiliary mark and sweep garbage collector.

There are 3 possible compile time options:

First a situation where Squirrel is compiled with RC only; in this case it is impossible for the VM to detect reference cycles, so is the programmer that has to remove the links to avoid memory leaks (no special define is needed).

The second option is compiling with 'CYCLIC_REF_SAFE' defined; in this situation the VM keeps a linked list of all objects that can cause a reference cycle (tables, arrays etc..) and ensures that, when the VM is deleted, all cycles are detected and removed.

The third configuration consists in a mark and sweep garbage collector (option 'GARBAGE_COLLECTOR'). This option behaves like CYCLIC_REF_SAFE but in addition the host program can call the function sq_collectgarbage() and perform a garbage collection during the program execution. The garbage collector isn't invoked by the VM and has to be explicitly called by the host program.

The only disadvantage introduced by the second and third option is that 2 additional pointers have to be stored for each object (8 bytes for 32 bits systems). The types involved are: tables, arrays, functions, userdata and generators; all other types are untouched. These options do not affect execution speed.

4.2 Unicode

By default Squirrel strings are plain 8-bits ASCII characters; however if the symbol '_UNICODE' is defined the VM, compiler and API will use 16-bits characters.

4.3 Error conventions

Most of the functions in the API return a SQRESULT value; SQRESULT indicates if a function completed successfully or not.

The macros SQ_SUCCEEDED() and SQ_FAILED() are used to test the result of a function.

```
if(SQ_FAILED(sq_getstring(v,-1,&s)))
    printf("getstring failed");
```

4.4 Initializing Squirrel

The first thing that a host application has to do, is create a virtual machine. The host application can create any number of virtual machines through the function sq newvm().

Every single VM has to be released with the function $sq_releasevm()$ when it is not needed anymore.

```
int main(int argc, char* argv[])
{
    HSQUIRRELVM v;
    v=sq_newvm(NULL,1024); //creates a VM with initial stack size 1024
    //do some stuff with squirrel here
    sq_releasevm(v);
}
```

4.5 The Stack

Squirrel exchanges values with the virtual machine through a stack. This mechanism has been inherited from the language LUA.

For instance to call a Squirrel function from C it is necessary to push the function and the arguments in the stack and then invoke the function; also when Squirrel calls a C function the parameters will be in the stack as well.

4.5.1 Stack Indexes

Many API functions can arbitrarily refer to any element in the stack through an index. The stack indexes follow those conventions:

- 1 is the stack base
- Negative indexes are considered an offset from top of the stack. For instance –1 is the top of the stack.
- 0 is an invalid index

Here an example (let's pretend that this table is the VM stack)

"test"
1
0.5
"foo"

Positive	Negative
index	index
4	-1(top)
3	-2
2	-3
1(base)	-4

In this case, the function sq_gettop would return 4;

4.5.2 Stack manipulation

The API offers several functions to push and retrieve data from the Squirrel stack.

To push a value that is already present in the stack in the top position void sq_push(HSQUIRRELVM v,int idx);

```
To pop an arbitrary number of elements
```

void sq_pop(HSQUIRRELVM v,int nelemstopop);

To remove an element from the stack

void sq_remove(HSQUIRRELVM v,int idx);

To retrieve the top index (and size) of the current virtual stack you must call sq_gettop

```
int sq_gettop(HSQUIRRELVM v);
```

To force the stack to a certain size you can call sq_settop

```
void sq_settop(HSQUIRRELVM v,int newtop);
```

If the newtop is bigger than the previous one, the new posistions in the stack will be filled with null values.

The following function pushes a C value into the stack

```
void sq_pushstring(HSQUIRRELVM v,const SQChar *s,int len);
void sq_pushfloat(HSQUIRRELVM v,SQFloat f);
void sq_pushinteger(HSQUIRRELVM v,SQInteger n);
void sq_pushuserpointer(HSQUIRRELVM v,SQUserPointer p);
```

```
this function pushes a null into the stack
void sq_pushnull(HSQUIRRELVM v);
```

returns the type of the value in a arbitrary position in the stack

```
SQObjectType sq_gettype(HSQUIRRELVM v,int idx);
```

the result can be one of the following values:

```
OT_NULL,OT_INTEGER,OT_FLOAT,OT_STRING,OT_TABLE,OT_ARRAY,OT_USERDATA,OT_CLOSURE,OT_NATIVECLOSURE,OT_GENERATOR,OT_USERPOINTER
```

The following functions convert a squirrel value in the stack to a C value

```
SQRESULT sq_getstring(HSQUIRRELVM v,int idx,const SQChar **c);
SQRESULT sq_getinteger(HSQUIRRELVM v,int idx,SQInteger *i);
SQRESULT sq_getfloat(HSQUIRRELVM v,int idx,SQFloat *f);
SQRESULT sq_getuserpointer(HSQUIRRELVM v,int idx,SQUserPointer *p);
SQRESULT sq_getuserdata(HSQUIRRELVM v,int idx,SQUserPointer *p);
```

The function sq_cmp pops 2 values from the stack and returns their relation (like strcmp() in ANSI C).

```
int sq_cmp(HSQUIRRELVM v);
```

4.6 Runtime errors handling

When an exception is not handled by Squirrel code with a try/catch statement, a runtime error is raised and the execution of the current program is interrupted. It is possible to set a call back function to intercept the runtime error from the host program; this is useful to show meaningful errors to the script writer and for implementing visual debuggers.

The following API call pops a Squirrel function from the stack and sets it as error handler.

```
SQUIRREL_API void sq_seterrorhandler(HSQUIRRELVM v);
```

The error handler is called with 2 parameters, an environment object (this) and a object. The object can be any squirrel type.

4.7 Compiling a script

```
You can compile a Squirrel script with the function sq_compile. typedef SQChar (*SQLEXREADFUNC)(SQUserPointer userdata);
```

```
SQRESULT sq_compile(HSQUIRRELVM v,SQREADFUNC read,SQUserPointer p,const SQChar *sourcename,int raiseerror,int lineinfo);
```

In order to compile a script is necessary for the host application to implement a reader function (SQLEXREADFUNC); this function is used to feed the compiler with the script data.

The function is called every time the compiler needs a character; It has to return a character code if succeed or 0 if the source is finished.

If sq_compile succeeds, the compiled script will be pushed as Squirrel function in the stack.

Here an example of a 'read' function that read from a file:

```
SQChar file_lexfeedASCII(SQUserPointer file)
{
    int ret;
    char c;
    if( ( ret=fread(&c,sizeof(c),1,(FILE *)file )>0) )
        return c;
    return 0;
}
int compile_file(HSQUIRRELVM v,const char *filename)
{
FILE *f=fopen(filename,"rb");
    if(f)
{
        sq_compile(v,file_lexfeedASCII,file,filename,1,0);
        fclose(f);
        return 1;
}
return 0;
}
```

When the compiler fails for a syntax error it will try to call the 'compiler error handler'; this function is must be declared as follow

```
typedef void (*SQCOMPILERERROR)(const SQChar * /*desc*/,const SQChar *
/*source*/,int /*line*/,int /*column*/);
```

and can be set with the following API call

void sq_setcompilererrorhandler(HSQUIRRELVM v,SQCOMPILERERROR f);

4.8 Calling a function

To call a squirrel function it is necessary to push the function in the stack followed by the parameters and then call the function sq_call.

The function will pop the parameters and push the return value if the last sq_call parameter is >0.

```
sq_pushroottable(v); sq_pushstring(v, "foo",-1); sq_get(v,-2); //get the function from the root table sq_pushroottable(v); //'this' (function environment object) sq_pushinteger(v,1); sq_pushfloat(v,2.0); sq_pushstring(v,"three",-1); sq_call(v,4,0); sq_pop(v,2); //pops the roottable and the function
```

this is equivalent to the following Squirrel code

```
foo(1,2.0,"three");
```

If a runtime error occurs (or a exception is thrown) during the squirrel code execution the sq call will fail.

4.9 Create a C function

A native C function must have the following prototype:

```
typedef int (*SQFUNCTION)(HSQUIRRELVM);
```

The parameters is an handle to the calling VM and the return value is an integer respecting the following rules:

- Bigger than 0 if the function returns a value
- 0 if the function does not return a value
- Less than 0 to a runtime error is thrown

In order to obtain a new callable squirrel function from a C function pointer, is necessary to call sq_newclosure() passing the C function to it; the new Squirrel function will be pushed in the stack.

When the function is called, the stackbase is the first parameter of the function and the top is the last. In order to return a value the function has to push it in the stack and return a value bigger than 0.

Here an example, the following function print the value of each argument and return the number of arguments.

```
int print_args(HSQUIRRELVM v)
{
      int nargs = sq_gettop(v); //number of arguments
      for(int n=1;n<=nargs;n++)</pre>
            printf("arg %d is ",n);
            switch(sq_gettype(v,n))
            {
                  case OT_NULL:
                        printf("null");
                        break;
                  case OT INTEGER:
                        printf("integer");
                        break;
                  case OT FLOAT:
                        printf("float");
                        break;
                  case OT_STRING:
                        printf("string");
                        break;
                  case OT TABLE:
                        printf("table");
                        break;
                  case OT ARRAY:
                        printf("array");
                        break;
                  case OT_USERDATA:
                        printf("userdata");
                        break;
                  case OT_CLOSURE:
                        printf("closure(function)");
                        break;
                  case OT NATIVECLOSURE:
                        printf("native closure(C function)");
                        break;
                  case OT_GENERATOR:
                        printf("generator");
                        break;
                  case OT_USERPOINTER:
                        printf("userpointer");
                        break;
```

```
defaut:
                         return sq_throwerror(v,"invalid param"); //throw an
exception
             }
      }
      printf("\n");
      sq_pushinteger(v,nargs); //push the number of arguments as return
value
      return 1; //1 because 1 value is returned
}
Here an example of how to register a function
int register_global_func(HSQUIRRELVM v,SQFUNCTION f,const char *fname)
      sq_pushroottable(v);
      sq_pushstring(v,fname,-1);
      sq_newclosure(v,f,0); //create a new function
      sq_set(v,-3);
      sq_pop(v,1); //pops the root table
}
4.10 Tables and arrays manipulation
A new table is created calling sq_newtable, this function pushes a new table in the stack.
void sq_newtable (HSQUIRRELVM v);
To create a new slot
SQRESULT sq_createslot(HSQUIRRELVM v,int idx);
To set or get the table delegate
SQRESULT sq_setdelegate(HSQUIRRELVM v,int idx);
SQRESULT sq_getdelegate(HSQUIRRELVM v,int idx);
A new array is created calling sq_newarray, the function pushes a new array in the
stack; if the parameters size is bigger than 0 the elements are initialized to null.
void sq_newarray (HSQUIRRELVM v,int size);
To append a value to the back of the array
SQRESULT sq_arrayappend(HSQUIRRELVM v,int idx);
To remove a value from the back of the array
SQRESULT sq_arraypop(HSQUIRRELVM v,int idx,int pushval);
To resize the array
SQRESULT sq_arrayresize(HSQUIRRELVM v,int idx,int newsize);
To retrieve the size of a table or an array you must use sq_getsize()
SQInteger sq_getsize(HSQUIRRELVM v,int idx);
To set a value in an array or table
SQRESULT sq set(HSQUIRRELVM v,int idx);
```

To get a value from an array or table

```
SQRESULT sq_get(HSQUIRRELVM v,int idx);

To get or set a value from a table without employ delegation

SQRESULT sq_rawget(HSQUIRRELVM v,int idx);

SQRESULT sq_rawset(HSQUIRRELVM v,int idx);

To iterate a table or an array

SQRESULT sq_next(HSQUIRRELVM v,int idx);

Here an example of how to perform an iteration:

//push your table/array here
sq_pushnull(v) //null iterator
while(SQ_SUCCEEDED(sq_next(v,-2)))

{
    //here -1 is the value and -2 is the key
```

4.11 Userdata and UserPointers

sq_pop(v,1); //pops the null iterator

}

Squirrel allows the host application put arbitrary data chunks into a Squirrel value, this is possible through the data type userdata.

 $sq_pop(v,2)$; //pops key and val before the nex iteration

```
SQUserPointer sq_newuserdata (HSQUIRRELVM v,unsigned int size);
```

When the function sq_newuserdata is called, Squirrel allocates a new userdata with the specified size, returns a pointer to his payload buffer and push the object in the stack; at this point the application can do whatever it want with this memory chunk, the VM will automatically take cake of the memory deallocation like for every other built-in type. A userdata can be passed to a function or stored in a table slot. By default Squirrel cannot manipulate directly userdata; however is possible to assign a delegate to it and define a behavior like it would be a table.

Because the application would want to do something with the data stored in a userdata object when it get deleted, is possible to assign a callback that will be called by the VM just before deleting a certain userdata.

This is done through the API call sq_setreleasehook.

```
typedef int (*SQUSERDATARELEASE)(SQUSerPointer);
void sq_setreleasehook(HSQUIRRELVM v,int idx,SQUSERDATARELEASE hook);
```

Another kind of userdata is the userpointer; this type is not a memory chunk like the normal userdata, but just a 'void*' pointer. It cannot have a delegate and is passed by value, so pushing a userpointer doesn't cause any memory allocation.

```
void sq_pushuserpointer(HSQUIRRELVM v,SQUserPointer p);
```

4.12 Keeping object references from C

Squirrel allows to keep objects references from C; the function sq_getstackobject() gets a handle to a squirrel object(any type), this object can be pushed later in the stack.

```
HSQOBJECT obj;
sq_resetobject(v,&obj) //initialize the handle
sq_geststackobject(v,-2,&obj); //retrieve an object handle from the pos -2
sq_addref(v,&obj); //adds a reference to the object
... //do stuff
sq_pushobject(v,&obj); //push the object in the stack
sq_release(v,&obj); //relese the object
```

4.13 Debug Interface

The squirrel VM exposes a very simple debug interface that allows to easily built a full featured debugger.

Through the function sq_setdebughook is possible in fact to set a callback function that will be called every time the VM executes an new line of a script or if a function get called. The callback will pass as argument the current line the current source and the current function name (if any).

```
SQUIRREL_API void sq_setdebughook(HSQUIRRELVM v);
```

The following code shows how a debug hook could look like(obviously is possible to implement this function in C as well).

The parameter event_type can be 'l' or 'c'; the first if a new line was executed the second if a function call occurred.

A full-featured debugger always allows displaying local variables and calls stack. The call stack information are retrieved through $sq_getstackinfos()$

```
int sq_stackinfos(HSQUIRRELVM v,int level,SQStackInfos *si);
While the local variables info through sq_getlocal()
int sq_getlocal(HSQUIRRELVM v,unsigned int level,unsigned int nseq);
```

5 API Reference Manual

5.1 Virtual Machine

sq_newvm

HSQUIRRELVM sq_newvm(HSQUIRRELVM friendvm,int initialstacksize)

creates a new instance of a squirrel VM that consists in a new stack, new root table etc..

parameters:

HSQUIRRELVM friendvm

A vm that can share objects with the newone, this parameter can be NULL.

int initialstacksize

the size of the stack in slots(number of objects)

return:

an handle to a squirrel vm

remarks:

the returned VM has to be released with sq_releasevm

sq_releasevm

void sq_releasevm(HSQUIRRELVM v)

release a squirrel VM

parameters:

HSQUIRRELVM v

a handle to a squirrel VM

sq_seterrorhandler

void sq_seterrorhandler(HSQUIRRELVM v)

pops from the stack a closure or native closure an sets it as runtime-error handler.

parameters:

HSQUIRRELVM v the target VM

sq_setforeignptr

void sq_setforeignptr(HSQUIRRELVM v, SQUserPointer p)

Sets the foreign pointer of a certain VM instance. The foreign pointer is an arbitrary user defined pointer associated to a VM (by default is value id 0). This pointer is ignored by the VM.

parameters:

HSQUIRRELVM v the target VM SQUserPointer p The pointer that has to be set

sq_getforeignptr

SQUserPointer sq_getforeignptr(HSQUIRRELVM v)

Returns the foreign pointer of a VM instance.

parameters:

HSQUIRRELVM v the target VM

return:

the current VM's foreign pointer.

5.2 Compiler

sq_setcompilererrorhandler

$void \ sq_setcompilererror handler (\textit{HSQUIRRELVM} \ v, \textit{SQCOMPILERERROR} \ f);$

sets the compiler error handler function

parameters:

HSQUIRRELVM v the target VM SQCOMPILERERROR f

A pointer to the error handler function

remarks:

if the parameter f is NULL no function will be called when a compiler error occurs

sq_compile

 $SQRESULT \ sq_compile(HSQUIRRELVM \ v, HSQLEXREADFUNC \ read, SQUserPointer \ p, const \ SQChar \ *sourcename, int \ raiseerror, int \ line info)$

compiles a squirrel program; if it succeeds, push the compiled script as function in the stack.

parameters:

HSQUIRRELVM v

the target VM

HSQLEXREADFUNC read

a pointer to a read function that will feed the compiler with the program.

SQUserPointer p

a user defined pointer that will be passed by the compiler to the read function at each invocation.

const SQChar *sourcename

the symbolic name of the program (used only for more meaningful runtime errors)

int raiseerror

if this value is different than 0 the compiler error handler will be called in case of an error

int lineinfo

if this value is different than 0 the compiled code will contain debug information (to use with the runtime debug interface)

return:

a SQRESULT. If the sq_compile fails nothing is pushed in the stack.

remarks:

in case of an error the function will call the function set by sq_setcompilererrorhandler().

5.3 Stack Operations

sq_push

void sq_push(HSQUIRRELVM v,int idx)

pushes in the stack the value at the index idx

parameters:

HSQUIRRELVM v the target VM int idx

the index in the stack of the value that has to be pushed

sq_pop

void sq_pop(HSQUIRRELVM v,int nelemstopop)

pops n elements from the stack

parameters:

HSQUIRRELVM v the target VM int nelementstopop the number of elements to pop

sq_remove

void sq_remove(HSQUIRRELVM v,int idx)

removes an element from an arbitrary position in the stack

parameters:

HSQUIRRELVM v the target VM int idx

index of the element that has to be removed

sq_gettop

int sq_gettop(HSQUIRRELVM v)

returns the index of the top of the stack

parameters:

HSQUIRRELVM v the target VM

return:

an integer representing the index of the top of the stack

sq_settop

void sq_settop(HSQUIRRELVM v,int newtop)

resize the stack, if new top is bigger then the current top the function will push nulls.

parameters:

HSQUIRRELVM v the target VM int newtop the new top index

sq_cmp

int sq_cmp(HSQUIRRELVM v)

pops 2 object from the stack and compares them.

parameters:

HSQUIRRELVM v the target VM

return:

> 0 if obj1>obj2 0 if obj1=obj2 < 0 if obj1<obj2

5.4 Object creation and handling

sq_newuserdata

SQUserPointer sq_newuserdata (HSQUIRRELVM v,unsigned int size); creates a new userdata and pushes it in the stack

parameters:

HSQUIRRELVM v the target VM unsigned int size

the size of the userdata that as to be created in bytes

return:

a pointer to the userdata buffer

sq_newtable

void sq_newtable (HSQUIRRELVM v);

creates a new table and pushes it in the stack

parameters:

HSQUIRRELVM v the target VM

sq_newarray

void sq_newarray (HSQUIRRELVM v,int size);

creates a new array and pushes it in the stack

parameters:

HSQUIRRELVM v the target VM int size

the size of the array that as to be created

sq_newclosure

void sq_newclosure(HSQUIRRELVM v, HSQFUNCTION func, unsigned int nfreevars);

create a new native closure, pops n values set those as free variables of the new closure, and push the new closure in the stack

parameters:

HSQUIRRELVM v
the target VM
HSQFUNCTION func
a pointer to a native-function
int nfreevars
number of free variables(can be 0)

sq_pushstring

```
void sq_pushstring(HSQUIRRELVM v,const SQChar *s,int len);
pushes a string in the stack
```

parameters:

HSQFUNCTION v the target VM

```
const SQChar * s
pointer to the string that has to be pushed
int len
lenght of the string pointed by s
```

remarks:

if the parameter len is less than 0 the VM will calculate the length using strlen(s)

sq_pushfloat

the target VM SQFloat f the float that has to be pushed

sq_pushinteger

```
void sq_pushinteger(HSQUIRRELVM v,SQInteger n);
  pushes a integer into the stack

parameters:
    HSQUIRRELVM v
    the target VM
    SQInteger n
```

the integer that has to be pushed

sq_pushuserpointer

HSQUIRRELVM v the target VM SQUserPointer p the pointer that as to be pushed

sq_pushnull

sq_gettype

an index in the stack

return:

the type of the value at the position idx in the stack

sq_getsize

SQInteger sq_getsize(HSQUIRRELVM v,int idx);

returns the size of a value at the idx position in the stack

parameters:

HSQUIRRELVM v the target VM int idx an index in the stack

return:

the size of the value at the position idx in the stack

remarks:

this function only works with strings, arrays and tables if the value is not one of those types the function will return -1

sq_getstring

```
SQRESULT sq_getstring(HSQUIRRELVM v,int idx,const SQChar **c)
```

gets a pointer to the string at the idx position in the stack.

parameters:

HSQUIRRELVM v
the target VM
int idx
an index in the stack
const SQChar **c
a pointer to the pointer that will point to the string

return:

a SQRESULT

sq_getinteger

```
SQRESULT sq_getinteger(HSQUIRRELVM v,int idx,SQInteger *i)
```

gets the value of the integer at the idx position in the stack.

parameters:

HSQUIRRELVM v
the target VM
int idx
an index in the stack
SQInteger *i
A pointer to the integer that will store the value
return:
a SQRESULT

sq_getfloat

```
SQRESULT sq_getfloat(HSQUIRRELVM v,int idx,SQFloat *f)
```

gets the value of the float at the idx position in the stack.

parameters:

HSQUIRRELVM v the target VM

sq_getuserpointer

```
gets the value of the userpointer at the idx position in the stack.

parameters:

HSQUIRRELVM v

the target VM

int idx
an index in the stack
SQUserPointer *p
A pointer to the userpointer that will store the value

return:
a SQRESULT
```

SQRESULT sq_getuserpointer(HSQUIRRELVM v,int idx,SQUserPointer *p)

sq_getuserdata

```
SQRESULT sq\_getuserdata(HSQUIRRELVM\ v,int\ idx,SQUserPointer\ *p) gets a pointer to the value of the userdata at the idx position in the stack.
```

parameters:

```
HSQUIRRELVM v
the target VM
int idx
an index in the stack
SQUserPointer *p
A pointer to the userpointer that will store the value
return:
a SQRESULT
```

sq_setreleasehook

```
void sq\_setreleasehook(\textit{HSQUIRRELVM } v,int idx,\textit{HSQUSERDATARELEASE } hook) sets the release hook of the userdata at position idx in the stack.
```

```
parameters:
```

```
HSQUIRRELVM v
the target VM
int idx
an index in the stack
HSQUSERDATARELEASE hook
a function pointer(see HSQUSERDATARELEASE)
```

remarks:

the function hook is called by the VM before the userdata memory is deleted.

sq_getscratchpad

```
SQChar *sq_getscratchpad(HSQUIRRELVM v,int minsize);
returns a pointer to a memory buffer that is at least as big as minsize.

parameters:
HSQUIRRELVM v
the target VM
int minsize
```

the requested size for the scratchpad buffer

remarks.

the buffer is valid until the next call to sq_getscratchpad

5.5 Calls

sq_call

SQRESULT sq_call(HSQUIRRELVM v,int params,int retval)

calls a closure or a native closure.

parameters:

HSQUIRRELVM v
the target VM
int params
number of parameters of the function
int retval

if >0 the function will push the return value in the stack

return:

a SQRESULT

remarks:

pops n values(params) and a closure and calls it; if retval != 0 the return value of the closure is pushed.

sq_resume

SQRESULT sq_resume(HSQUIRRELVM v, int retval)

resumes the generator at the top position of the stack.

parameters:

HSQUIRRELVM v
the target VM
int retval
if >0 the function will push the return value in the stack

return:

a SQRESULT

remarks:

if retval != 0 the return value of the generator is pushed

sq_getlocal

const SQChar *sq_getlocal(HSQUIRRELVM v,unsigned int level,unsigned int nseq)

returns the name of a local variable given stackframe and sequence in the stack and pushes is current value.

parameters:

```
HSQUIRRELVM v
the target VM
unsigned int level
the function index in the calls stack, 0 is the current function
unsigned int nseq
the index of the local variable in the stack frame (0 is 'this')
```

return.

the name of the local variable if a variable exists at the given level/seq otherwise NULL.

sq_throwerror

SQRESULT sq_throwerror(HSQUIRRELVM v,const SQChar *err)

sets the last error in the virtual machine and returns the value that has to be returned by a native closure in order to trigger an exception in the virtual machine.

parameters:

HSQUIRRELVM v
the target VM
const SQChar * err
the description of the error that has to be thrown

return:

the value that has to be returned by a native closure in order to throw an exception in the virtual machine.

sq_getlasterror

$SQRESULT \ sq_getlasterror(HSQUIRRELVM \ v)$

pushes the last error in the stack.

parameters:

HSQUIRRELVM v the target VM

return:

a SQRESULT

remarks:

the pushed error descriptor can be any valid squirrel type.

5.6 Object manipulation

sq_pushroottable

void sq_pushroottable(HSQUIRRELVM v);

pushes the current root table in the stack

parameters:

HSQUIRRELVM v the target VM

sq_setroottable

void sq_setroottable(HSQUIRRELVM v);

pops a table from the stack and set it as root table

parameters:

HSQUIRRELVM v the target VM

sq_createslot

$\textit{SQRESULT sq_createslot(HSQUIRRELVM } v, \textit{int } idx)$

pops a key and a value from the stack and performs a set operation on the table at position idx in the stack, if the slot does not exits it will be created.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack

return:

a SQRESULT

remarks:

no delegation is involved in the operation. it only works on tables.

sq_set

SQRESULT sq_set(HSQUIRRELVM v,int idx);

pops a key and a value from the stack and performs a set operation on the object at position idx in the stack

parameters:

HSQUIRRELVM v the target VM int idx

index of the target object in the stack

return:

a SORESULT

remarks:

this call will invoke the delegation system like a normal assignment, it only works on tables, arrays and userdata.

sq_get

SQRESULT sq_get(HSQUIRRELVM v,int idx)

pops a key from the stack and performs a get operation on the object at the position idx in the stack, and pushes the result in the stack.

parameters:

HSQUIRRELVM v the target VM index of the target object in the stack

return:

a SQRESULT

remarks:

this call will invoke the delegation system like a normal dereference it only works on tables, arrays and userdata. if the function fails nothing will be pushed in the stack.

sq_rawget

SQRESULT sq_rawget(HSQUIRRELVM v,int idx);

pops a key from the stack and performs a get operation on the object at position idx in the stack, without employing delegation or metamethods.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack return: a SQRESULT remarks:

Only works on tables, arrays and userdata.

sq_rawset

SQRESULT sq rawset(HSQUIRRELVM v,int idx);

pops a key and a value from the stack and performs a set operation on the object at position idx in the stack, without employing delegation or metamethods.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack return: a SQRESULT

remarks:

it only works on tables, arrays. if the function fails nothing will be pushed in the

sq_arrayappend

SQRESULT sq_arrayappend(HSQUIRRELVM v,int idx);

pops a value from the stack and pushes it in the back of the array at the position idx in the stack.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack return: a SQRESULT remarks: Only works on arrays.

sq_arraypop

SQRESULT sq_arraypop(HSQUIRRELVM v,int idx);

pops a value the back of the array at the position idx in the stack.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack return: a SQRESULT remarks: it only works on arrays.

sq_arrayresize

```
SQRESULT sq_arrayresize(HSQUIRRELVM v,int idx,int newsize);
```

resizes the array at the position idx in the stack.

parameters:

HSQUIRRELVM v the target VM int idx index of the target object in the stack int newsize requested size of the array return: a SQRESULT remarks: it only works on arrays.

sq_setdelegate

SQRESULT sq_setdelegate(HSQUIRRELVM v,int idx);

pops a table from the stack and sets it as delegate of the object at the position idx in the stack.

parameters:

HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack

return:

a SQRESULT

sq_getdelegate

SQRESULT sq_getdelegate(HSQUIRRELVM v,int idx)

pushes the current delegate of the object at the position idx in the stack.

parameters:

```
HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
return:
a SQRESULT
```

sq_clone

SQRESULT sq_clone(HSQUIRRELVM v,int idx)

Clones the table or array at the position idx, clones it and pushes the new object in the stack.

parameters:

```
HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
return:
a SQRESULT
```

sq_setfreevariable

SQRESULT sq setfreevariable(HSQUIRRELVM v, int idx, unsigned int nval)

pops a value from the stack and sets it as free variable of the closure at the position idx in the stack.

parameters:

```
HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
int nval
0 based index of the free variable(relative to the closure).

return:
a SQRESULT
```

sq_next

```
SQRESULT sq_next(HSQUIRRELVM v,int idx)
```

Pushes in the stack the next key and value of an array or table slot.

To start the iteration this function expects a null value on top of the stack; at every call the function will substitute the null value with an iterator and push key and value of the container slot. Every iteration the application has to pop the previous key and value but leave the iterator(that is used as reference point for the next iteration). The function will fail when all slots have been iterated(see <u>Tables and arrays</u> manipulation).

parameters:

return:

HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
urn:
a SQRESULT

5.7 Raw object handling

sq_getstackobj

```
SQRESULT sq_getstackobj(HSQUIRRELVM v,int idx,HSQOBJECT *po) gets an object from the stack and stores it in a object handler.
```

parameters:

return:

HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
HSQOBJECT *po
pointer to an object handler
urn:
a SQRESULT

sq_pushobject

```
void sq_pushobject(HSQUIRRELVM v, HSQOBJECT obj)
```

push an object referenced by an object handler into the stack.

parameters:

HSQUIRRELVM v
the target VM
int idx
index of the target object in the stack
HSQOBJECT obj
object handler

sq_addref

```
void sq_addref(HSQUIRRELVM v,HSQOBJECT *po);
  add a reference to an object handler.

parameters:
    HSQUIRRELVM v
        the target VM
    HSQOBJECT *po
    pointer to an object handler
```

sq_release

void sq_release(HSQUIRRELVM v, HSQOBJECT *po);

remove a reference to an object handler.

parameters:

HSQUIRRELVM v the target VM HSQOBJECT *po pointer to an object handler

sq_resetobject

```
void sq_resetobject(HSQUIRRELVM v, HSQOBJECT *obj);
```

reset(initialize) an object handler.

parameters:

HSQUIRRELVM v the target VM HSQOBJECT *po pointer to an object handler

remarks:

Every object handler has to be initialized with this function.

5.8 Function prototypes

SQFUNCTION

typedef int (*SQFUNCTION)(HSQUIRRELVM);

SQUSERDATARELEASE

typedef int (*SQUSERDATARELEASE)(SQUserPointer);

SQCOMPILERERROR

typedef void (*SQCOMPILERERROR)(HSQUIRRELVM,const SQChar * /*desc*/,const SQChar * /*source*/,int /*line*/,int /*column*/);

SQWRITEFUNC

typedef int (*SQWRITEFUNC)(SQUserPointer,SQUserPointer,int);

SQREADFUNC

typedef int (*SQREADFUNC)(SQUserPointer,SQUserPointer,int);

SQLEXREADFUNC

typedef SQChar (*SQLEXREADFUNC)(SQUserPointer);

SQUIRREL_MALLOC

typedef void *(*SQUIRREL_MALLOC)(unsigned int);

SQUIRREL_REALLOC

typedef void *(*SQUIRREL_REALLOC)(void*,unsigned int,unsigned int);

SQUIRREL_FREE

typedef void (*SQUIRREL_FREE)(void*,unsigned int);

6 Index

 $sq_addref,\,45$ sq_arrayappend, 43 sq_arraypop, 43 sq_arrayresize, 43 sq_call, 40 sq clone, 44 sq_cmp, 35 sq_compile, 34 sq_createslot, 41 sq_get, 42 sq_getdelegate, 44 sq_getfloat, 38 sq_getforeignptr, 33 sq_getinteger, 38 sq_getlasterror, 41 sq_getlocal, 40 sq_getscratchpad, 39 sq_getsize, 38 sq_getstackobj, 45 sq_getstring, 38 sq_gettop, 35 sq_gettype, 37 sq_getuserdata, 39 sq_getuserpointer, 39 sq_newarray, 36 sq_newclosure, 36 sq_newtable, 36 sq_newuserdata, 36 sq_newvm, 33 sq_next, 44 sq_pop, 35 sq_push, 34 sq_pushfloat, 37 sq_pushinteger, 37 sq_pushnull, 37

sq_pushroottable, 41 sq_pushstring, 36 sq_pushuserpointer, 37 sq_rawget, 42 sq_rawset, 42 sq_release, 45 sq_releasevm, 33 sq_remove, 35 sq_resetobject, 46 sq_resume, 40 sq_set, 42 sq_setcompilererrorhandler, 34 sq_setdelegate, 44 sq_seterrorhandler, 33 sq_setforeignptr, 33 sq_setfreevariable, 44 sq_setreleasehook, 39 sq_setroottable, 41 sq_settop, 35 sq_throwerror, 40 SQCOMPILERERROR, 46 SQFUNCTION, 46 SQLEXREADFUNC, 46 SOREADFUNC, 46 SQUIRREL_FREE, 47 SQUIRREL_MALLOC, 46 SQUIRREL_REALLOC, 47 SQUSERDATARELEASE, 46 SQWRITEFUNC, 46 Table, 6, 15, 16, 23 delegation, 15, 16, 20 Userdata userdata, 7

sq_pushobject, 45