Address Translation and Virtual Memory


CENG331 - Computer Organization

Instructor:

Murat Manguoglu (Sections 1-2)

Adapted from: http://inst.eecs.berkeley.edu/~cs152

Bare Machine



In a bare machine, the only kind of address is a physical address, corresponding to address lines of actual hardware memory.


Dynamic Address Translation

Motivation

- In early machines, I/O was slow and each I/O transfer involved the CPU (programmed I/O)
- Higher throughput possible if CPU and I/O of 2 or more programs were overlapped, how?
- → multiprogramming with DMA I/O devices, interrupts
- Location-independent programs
 - Programming and storage management ease
 - → need for a *base* register
- Protection
 - Independent programs should not affect each other inadvertently
 - → need for a **bound** register
- Multiprogramming drives requirement for resident supervisor software to manage context switches between multiple programs

Program 1 Physical Memory **Program 2** OS


Simple Base and Bound Translation



Base and bounds registers are visible/accessible only when processor is running in the *supervisor mode*


Separate Areas for Program and Data

(Scheme used on all Cray vector supercomputers prior to X1, 2002)




What is an advantage of this separation? What about more base/bound pairs?

Base and Bound Machine



Can fold addition of base register into (register+immediate) address calculation using a carry-save adder (sums three numbers with only a few gate delays more than adding two numbers)

External Fragmentation with Segments




Paged Memory Systems

Program-generated (virtual or logical) address split into:


Page Number	Offset
-------------	--------

 Page Table contains physical address of start of each fixed-sized page in virtual address space



 Paging makes it possible to store a large contiguous virtual memory space using non-contiguous physical memory pages

Private Address Space per User




Virtual Address Space Pages for Job 1

0	
1	
2	
3	

Virtual Address Space Pages for Job 2

0	
1	
2	
3	

Virtual Address Space Pages for Job 3




Physical Memory Pages

Paging Simplifies Allocation

- Fixed-size pages can be kept on OS free list and allocated as needed to any process
- Process memory usage can easily grow and shrink dynamically
- Paging suffers from internal fragmentation where not all bytes on a page are used
 - Much less of an issue than external fragmentation or compaction for common page sizes (4-8KB)
 - But one reason that many oppose move to larger page sizes

Page Tables Live in Memory



Coping with Limited Primary Storage

- Paging reduces fragmentation, but still many problems would not fit into primary memory, have to copy data to and from secondary storage (drum, disk)
- Two early approaches:
 - Manual overlays, programmer explicitly copies code and data in and out of primary memory
 - Tedious coding, error-prone (jumping to non-resident code?)
 - Software interpretive coding (Brooker 1960). Dynamic interpreter detects variables that are swapped out to drum and brings them back in
 - Simple for programmer, but inefficient

Not just ancient black art, e.g., IBM Cell microprocessor using in Playstation-3 had explicitly managed local store!

Many new "deep learning" accelerators have similar structure.


Demand Paging in Atlas (1962)

"A page from secondary storage is brought into the primary storage whenever it is (implicitly) demanded by the processor."


Tom Kilburn

Primary memory as a *cache* for secondary memory

User sees 32 x 6 x 512 words of storage



Hardware Organization of Atlas



Compare the effective page address against all 32 PARs

match \Rightarrow normal access

no match \Rightarrow page fault

save the state of the partially executed instruction


Atlas Demand-Paging Scheme

On a page fault:

- Input transfer into a free page is initiated
- The Page Address Register (PAR) is updated
- If no free page is left, a page is selected to be replaced (based on usage)
- The replaced page is written on the drum
 - to minimize drum latency effect, the first empty page on the drum was selected
- The page table is updated to point to the new location of the page on the drum


Size of Linear Page Table

- With 32-bit addresses, 4-KB pages & 4-byte PTEs:
 - 220 PTEs, i.e, 4 MB page table per user
 - 4 GB of swap needed to back up full virtual address space
- Larger pages?
 - Internal fragmentation (Not all memory in page is used)
 - Larger page fault penalty (more time to read from disk)
- What about 64-bit virtual address space???
 - Even 1MB pages would require 244 8-byte PTEs (35 TB!)




RISC-V Sv32 Virtual Memory Scheme

Two-Level Page Tables in Physical Memory



Address Translation & Protection



 Every instruction and data access needs address translation and protection checks

A good VM design needs to be fast (~ one cycle) and space efficient

Translation-Lookaside Buffers (TLB)


Address translation is very expensive!

In a two-level page table, each reference becomes several memory accesses

Solution: Cache translations in TLB

TLB hit \Rightarrow Single-Cycle Translation

TLB miss \Rightarrow Page-Table Walk to refill



TLB Designs

- Typically 32-128 entries, usually fully associative
 - Each entry maps a large page, hence less spatial locality across pages → more likely that two entries conflict
 - Sometimes larger TLBs (256-512 entries) are 4-8 way setassociative
 - Larger systems sometimes have multi-level (L1 and L2) TLBs
- Random or FIFO replacement policy
- TLB Reach: Size of largest virtual address space that can be simultaneously mapped by TLB
 - Example: 64 TLB entries, 4KB pages, one page per entry
 - TLB Reach =


64 entries * 4 KB = 256 KB (if contiguous)

Handling a TLB Miss

■ Software (MIPS, Alpha)


- TLB miss causes an exception and the operating system walks the page tables and reloads TLB. A privileged "untranslated" addressing mode used for walk.
- Software TLB miss can be very expensive on out-of-order superscalar processor as requires a flush of pipeline to jump to trap handler.
- Hardware (SPARC v8, x86, PowerPC, RISC-V)
 - A memory management unit (MMU) walks the page tables and reloads the TLB.
 - If a missing (data or PT) page is encountered during the TLB reloading, MMU gives up and signals a Page Fault exception for the original instruction.
- NOTE: A given ISA can use either TLB miss strategy

Hierarchical Page Table Walk: SPARC v8



MMU does this table walk in hardware on a TLB miss

Page-Based Virtual-Memory Machine (Hardware Page-Table Walk)




Assumes page tables held in untranslated physical memory

Page-Fault Handler


- When the referenced page is not in DRAM:
 - The missing page is located (or created)
 - It is brought in from disk, and page table is updated
 - Another job may be run on the CPU while the first job waits for the requested page to be read from disk
 - If no free pages are left, a page is swapped out
 - Pseudo-LRU replacement policy, implemented in software
- Since it takes a long time to transfer a page (msecs), page faults are handled completely in software by OS
 - Untranslated addressing mode is essential to allow kernel to access page tables
- Keeping TLBs coherent with page table changes might require expensive "TLB shootdown"
 - Interrupt other processors to invalidate stale TLB entries
 - Some mainframes had hardware TLB coherence

Handling VM-related exceptions




- Handling a TLB miss needs a hardware or software mechanism to refill TLB
- Handling page fault (e.g., page is on disk) needs restartable exception so software handler can resume after retrieving page
 - Precise exceptions are easy to restart
 - Can be imprecise but restartable, but this complicates OS software
- A protection violation may abort process
 - But often handled the same as a page fault

Address Translation: putting it all together




Address Translation in CPU Pipeline




- Need to cope with additional latency of TLB:
 - slow down the clock?
 - pipeline the TLB and cache access?
 - virtual address caches
 - parallel TLB/cache access

Virtual-Address Caches




Alternative: place the cache before the TLB



- one-step process in case of a hit (+)
- cache needs to be flushed on a context switch unless address space identifiers (ASIDs) included in tags (-)
- aliasing problems due to the sharing of pages (-)
- maintaining cache coherence (-)

Virtually Addressed Cache (Virtual Index/Virtual Tag)




Modern Virtual Memory Systems

Illusion of a large, private, uniform store

Protection & Privacy

several users, each with their private address space and one or more shared address spaces page table = name space




Demand Paging

Provides the ability to run programs larger than the primary memory

Hides differences in machine configurations

The price is address translation on each memory reference





VM features track historical uses:

- Bare machine, only physical addresses
 - One program owned entire machine
- Batch-style multiprogramming
 - Several programs sharing CPU while waiting for I/O
 - Base & bound: translation and protection between programs (supports swapping entire programs but not demand-paged virtual memory)
 - Problem with external fragmentation (holes in memory), needed occasional memory defragmentation as new jobs arrived

Time sharing

- More interactive programs, waiting for user. Also, more jobs/second.
- Motivated move to fixed-size page translation and protection, no external fragmentation (but now internal fragmentation, wasted bytes in page)
- Motivated adoption of virtual memory to allow more jobs to share limited physical memory resources while holding working set in memory
- Virtual Machine Monitors
 - Run multiple operating systems on one machine
 - Idea from 1970s IBM mainframes, now common on laptops
 - e.g., run Windows on top of Mac OS X
 - Hardware support for two levels of translation/protection
 - Guest OS virtual -> Guest OS physical -> Host machine physical

Virtual Memory Use Today - 1

- Servers/desktops/laptops/smartphones have full demandpaged virtual memory
 - Portability between machines with different memory sizes
 - Protection between multiple users or multiple tasks
 - Share small physical memory among active tasks
 - Simplifies implementation of some OS features
- Vector supercomputers have translation and protection but rarely complete demand-paging
- (Older Crays: base&bound, Japanese & Cray X1/X2: pages)
 - Don't waste expensive CPU time thrashing to disk (make jobs fit in memory)
 - Mostly run in batch mode (run set of jobs that fits in memory)
 - Difficult to implement restartable vector instructions
- Modern GPUs operate similarly to vector supercomputers,
 with translation and protection but not demand paging

Virtual Memory Use Today - 2

- Most embedded processors and DSPs provide physical addressing only
 - Can't afford area/speed/power budget for virtual memory support
 - Often there is no secondary storage to swap to!
 - Programs custom written for particular memory configuration in product
 - Difficult to implement precise or restartable exceptions for exposed architectures

Acknowledgements

- These slides contain material developed and copyright by:
 - Arvind (MIT)
 - Krste Asanovic (MIT/UCB)
 - Joel Emer (Intel/MIT)
 - James Hoe (CMU)
 - John Kubiatowicz (UCB)
 - David Patterson (UCB)
- MIT material derived from course 6.823
- UCB material derived from course CS252