## COMP 3331/9331: Computer Networks and Applications

Week 10
Wireless Links/Networks

Reading Guide: Chapter 7, Sections 7.1 - 7.3

## Wireless Networks

#### **Background:**

- # wireless (mobile) phone subscribers now exceeds # wired phone subscribers (5-to-I)!
- # wireless Internet-connected devices equals # wireline Internet-connected devices
  - laptops, Internet-enabled phones promise anytime untethered Internet access
- two important (but different) challenges
  - wireless: communication over wireless link
  - mobility: handling the mobile user who changes point of attachment to network

We will only focus on wireless challenges

## **Outline**

#### 7.1 Introduction

#### **Wireless**

- 7.2 Wireless links, characteristics
- 7.3 IEEE 802.11 wireless LANs ("Wi-Fi")

## Wireless 101

Frequency/Wave-Length -


C is the speed of light f is frequency  $\lambda$  (lambda) is wavelength


Wavelength


Frequency


$$L = \frac{C}{f}$$


$$f = \frac{C}{\lambda}$$












#### Characteristics of selected wireless links



#### Inside the radio wave spectrum

Almost every wireless technology - from cell phones to garage door openers - uses radio waves to communicate. Some services, such as TV and radio broadcasts, have exclusive use of their frequency within a geographic area. But many devices share frequencies, which can cause interference. Examples of radio waves used by everyday devices reserved

Cell

phones


GHz

areas on this chart for military, federal 2.4 GHz band government and Used by more than 300 industry use consumer devices, including microwave ovens, cordless phones and wireless Wi-Fi Satellite Security networks (Wi-Fi and networks TV alarms

GHz

Highway

toll tags



Auctioned

spectrum

AM radio Remote-Broadcast TV **UHF** channels 535 kHz controlled to 1,700 kHz toys 14-83

GPS (Global positioning systems)

#### SEMT-PERMEABLE ZONE

Weather

radar

Difficult for signals to penetrate dense objects

Infrared light Ultraviolet X-rays

Visible

Satellite

radio

Bluetooth)

GHz

LINE-OF-SIGHT ZONES

Police

radar

GHz

Most of the white

GHz

Signals in this zone can only be

sent short.

unobstructed

distances

Highest

frequencies

Signals in this zone can travel long distances, but could be blocked by trees and other objects

Gamma rays

#### Microwaves Lowest frequencies RADIO WAVE SPECTRUM 3 kHz wavelength

PERMEABLE ZONE Frequencies in this range are considered

more valuable because they can penetrate

dense objects, such as a building made

out of concrete

300 GHz wavelength

#### What is a hertz? One hertz is one cycle per

Higher

frequency

GHz

Cable TV

satellite

transmissions

Radio waves occupy part of the electromagnetic spectrum, a range of electric and magnetic waves of different lengths that travel at the speed of light: other parts of the spectrum include visible light and x-rays; the shortest wavelengths have the highest frequency, measured in hertz

Lower frequency

 $\triangle M$ Wavelength Distance from crest to crest

second. For radio waves, a cycle is the distance from wave crest to crest

1 kilohertz (kHz) = 1,000 hertz

1 megahertz (MHz) = 1 million hertz

1 gigahertz (GHz) = 1 billion hertz

The electromagnetic spectrum


#### Australian radiofrequency spectrum

allocations chart





Australian Communications



## Outline

7.1 Introduction

#### **Wireless**

7.2 Wireless links, characteristics

7.3 IEEE 802.11 wireless LANs ("Wi-Fi")

## Wireless Link Characteristics (I)

important differences from wired link ....

- decreased signal strength: radio signal attenuates as it propagates through matter (path loss)
- interference from other sources: standardized wireless network frequencies (e.g., 2.4 GHz) shared by other devices (e.g., phone); devices (oven) interfere as well
- multipath propagation: radio signal reflects off objects ground, arriving at destination at slightly different times

.... Reliable communication across (even a point to point) wireless link much more "difficult"


## Path Loss/Path Attenuation

- Free Space Path Loss
  - d: distance
  - λ: wavelength
  - f: frequency
  - c: speed of light

$$FSPL = \left(\frac{4\pi d}{\lambda}\right)^{2}$$
$$= \left(\frac{4\pi df}{c}\right)^{2}$$

- Reflection, Diffraction, Absorption
- Terrain contours (urban, rural, vegetation)
- Humidity

## Multipath Effects




- Signals bounce off surface and interfere (constructive or destructive) with one another
- Self-interference

## **Ideal Radios**


(courtesy of Gilman Tolle and Jonathan Hui, ArchRock)

## Real Radios




#### Wireless Link Characteristics (2)

- SNR: signal-to-noise ratio
  - larger SNR easier to extract signal from noise (a "good thing")
- SNR versus BER tradeoffs
  - given physical layer: increase power -> increase SNR->decrease BER
  - given SNR: choose physical layer that meets BER requirement, giving highest thruput
    - SNR may change with mobility: dynamically adapt physical layer (modulation technique, rate)




#### Wireless network characteristics

Multiple wireless senders and receivers create additional problems (beyond multiple access):



#### Hidden terminal problem

- B, A hear each other
- ❖ B, C hear each other
- A, C cannot hear each other means A, C unaware of their interference at B
- Carrier sense will be ineffective




#### Signal attenuation:

- ♣ B,A hear each other
- \* B, C hear each other
- A, C can not hear each other interfering at B

#### Wireless network characteristics

Exposed Terminals



- Node B sends a packet to A; C hears this and decides not to send a packet to D (despite the fact that this will not cause interference) !!
- Carrier sense would prevent a successful transmission

## Outline

7.1 Introduction

#### **Wireless**

7.2 Wireless links, characteristics

7.3 IEEE 802.11 wireless LANs ("Wi-Fi")

## IEEE 802.11 Wireless LAN

#### 802.11b

- 2.4/5 GHz unlicensed spectrum
- up to 11 Mbps

#### 802.11a

5 GHz, up to 54 Mbps

#### 802.11g


2.4/5 GHz, up to 54 Mbps
 802.11n (Wifi 4): multiple
 antennae

2.4/5 GHz, up to 200 Mbps
 802. Hac (Wifi 5): multiple
 antennae

• 5 GHz, > Gbps

all use CSMA/CA for multiple access

## 802.11 LAN architecture



with base stationbase station = access boint

wireless host communicates

- base station = access point (AP)
- Basic Service Set (BSS) (aka "cell") contains:
  - wireless hosts
  - access point (AP): base station


BSS 2

## 802. I I: Channels, association


- 802.11b: 2.4GHz-2.485GHz spectrum divided into 11 channels at different frequencies
  - AP admin chooses frequency for AP
  - interference possible: channel can be same as that chosen by neighboring AP!
- host: must associate with an AP
  - scans channels, listening for beacon frames containing AP's name (SSID) and MAC address
  - selects AP to associate with
  - may perform authentication [Chapter 8]
  - will typically run DHCP to get IP address in AP's subnet


## 802. I Ib channels

#### 802.11b channel assignments (US)



## 802. I I: passive/active scanning





#### passive scanning:


- (1) beacon frames sent from APs
- (2) association Request frame sent: H1 to selected AP
- (3) association Response frame sent from selected AP to H I


#### active scanning:

- (1) Probe Request frame broadcast from H1
- (2) Probe Response frames sent from APs
- (3) Association Request frame sent: H1 to selected AP
- (4) Association Response frame sent from selected AP to H1

## IEEE 802.11: multiple access

- avoid collisions: 2<sup>+</sup> nodes transmitting at same time
- \* 802.11: CSMA sense before transmitting
  - don't collide with ongoing transmission by other node
- \* 802.11: no collision detection!
  - difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
  - can't sense all collisions in any case: hidden terminal, fading
  - goal: avoid collisions: CSMA/C(ollision)A(voidance)





## Multiple access: Key Points

- No concept of a global collision
  - Different receivers hear different signals
  - Different senders reach different receivers
- Collisions are at receiver, not sender
  - Only care if receiver can hear the sender clearly
  - It does not matter if sender can hear someone else
  - As long as that signal does not interfere with receiver
- Goal of protocol
  - Detect if receiver can hear sender
  - Tell senders who might interfere with receiver to shut up

#### IEEE 802.11 MAC Protocol: CSMA/CA

#### <u>Distributed Coordination Function (DCF)</u> 802.11 sender

1 if sense channel idle for **DIFS** then transmit entire frame (no CD)

2 if sense channel busy then

start random backoff time

timer counts down while channel idle

transmit when timer expires


if no ACK, increase random backoff interval, repeat 2

#### 802.11 receiver

- if frame received OK

return ACK after **SIFS** (ACK needed due to hidden terminal problem)

DIFS = DCF Inter Frame space SIFS = Short Inter Frame Space




## Avoiding collisions (more)


- idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames
- sender first transmits small request-to-send (RTS) packets to BS using CSMA
  - RTSs may still collide with each other (but they' re short)
- BS broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes
  - sender transmits data frame
  - other stations defer transmissions

avoid data frame collisions completely using small reservation packets!

#### Collision Avoidance: RTS-CTS exchange



#### Collision Avoidance: RTS-CTS exchange



## Quiz

 The following is the correct sequence of message exchanges as per the reservation process of 802.11 CSMA/CA

- A. RTS->CTS->DATA->CTS
- B. CTS->RTS->DATA->ACK
- c. RTS->CTS->DATA->ACK
- D. RTS->ACK->DATA->CTS

33

## Quiz

Which multiple access technique is used by IEEE 802.11?

- A. CSMA/CD
- B. Slotted ALOHA
- C. CSMA/CA
- D. TDMA
- E. FDMA

## Summary

#### **Wireless**

- wireless links:
  - capacity, distance
  - channel impairments
- IEEE 802.11 ("Wi-Fi")
  - CSMA/CA reflects wireless channel characteristics




# "Having the lecture recordings up – absolute lifesaver when it comes to revision"



Tell us about your experience and shape the future of education at UNSW.



Click the link in Moodle now





## Complete your myExperience and shape the future of education at UNSW.



#### or login to <u>myExperience.unsw.edu.au</u>

(use z I 234567@ad.unsw.edu.au to login)

The survey is confidential, your identity will never be released

Survey results are not released to teaching staff until after your results are published

