

OpenShift Container Platform 3.4 Administrator Solutions

OpenShift Container Platform 3.4 Administrator Solutions Guide

Red Hat OpenShift Documentation Team

Ope	nShift	Container	Platform	3.4 Ad	Iministrator	Solutions
-----	--------	-----------	-----------------	--------	---------------------	-----------

OpenShift Container Platform 3.4 Administrator Solutions Guide

Legal Notice

Copyright © 2017 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution—Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

OpenShift Administrator Solutions topics cover the concepts explored in the Cluster Administration reference documentation, but with a focus on presenting the content in a more accessible step-by-step format, with easy to follow examples and sample configurations.

Table of Contents

CHAPTER 1. OVERVIEW	3
CHAPTER 2. MASTER AND NODE CONFIGURATION	4
2.1. OVERVIEW	4
2.2. PREREQUISITES	4
2.3. CONFIGURING MASTERS AND NODES	4
2.4. CONFIGURATION OPTIONS	7
CHAPTER 3. USER AND ROLE MANAGEMENT	17
3.1. LIMITING AND MONITORING USERS AND PROJECTS	17
3.2. DETERMINING WHICH ROLES USERS GET BY DEFAULT	24
3.3. CONTROLLING USER PERMISSIONS WITH ROLES	28
3.4. SHARING TEMPLATES FOR USE IN PROJECTS ACROSS THE CLUSTER	29
3.5. CREATING A CLUSTER ADMINISTRATOR USER	30
CHAPTER 4. AUTHENTICATION	31
4.1. OVERVIEW	31
4.2. BASIC AUTHENTICATION (REMOTE)	31
4.3. REQUEST HEADER AUTHENTICATION	33
4.4. KEYSTONE AUTHENTICATION	36
4.5. LDAP AUTHENTICATION	38
4.6. GITHUB AUTHENTICATION	42

CHAPTER 1. OVERVIEW

The OpenShift Container Platform Administrator Solutions guide is new as of version 3.3, and the topics cover the most common tasks faced by OpenShift Container Platform administrators, with a focus on use cases and examples that guide the reader through each task.

In this initial version of the guide, you can learn how to:

- Configure masters and nodes using Ansible
- Set limits for users and projects
- Determine which roles users get by default
- Control user permissions with roles
- Share templates across the cluster
- Create a cluster administrator account
- Configure authentication providers

Your feedback on this guide would be greatly appreciated. You can let us know if you find it to be helpful, or if there is a topic you would like us to cover, by contacting openshift-docs@redhat.com.

CHAPTER 2. MASTER AND NODE CONFIGURATION

2.1. OVERVIEW

The master and node configuration files determine the make-up of your OpenShift Container Platform cluster, and define a range of options. These include overriding the default plug-ins, connecting to etcd, automatically creating service accounts, building image names, customizing project requests, configuring volume plug-ins, and much more.

This topic covers the many options available for customizing your OpenShift Container Platform masters and nodes, and shows you how to make changes to the configuration after installation.

The /etc/origin/master/master-config.yaml and /etc/origin/node/node-config.yaml files define a wide range of options that can be configured on the OpenShift master and nodes. These options include overriding the default plug-ins, connecting to etcd, automatically creating service accounts, building image names, customizing project requests, configuring volume plug-ins, and much more.

2.2. PREREQUISITES

For testing environments deployed via the quick install, one master should be sufficient. The quick installation method should not be used for production environments.

Production environments should be installed using the advanced install. In production environments, it is a good idea to use multiple masters for the purposes of high availability (HA). A cluster architecture of three masters is recommended, and HAproxy is the recommended solution for this.

Caution

If etcd is being installed on the *master hosts*, you must configure your cluster to use at least three masters. It cannot use only two masters, because etcd would not be able to decide which one is authoritative. The only way to successfully run only two masters is if you install etcd on hosts other than the masters.

2.3. CONFIGURING MASTERS AND NODES

The method you use to configure your master and node configuration files must match the method that was used to install your OpenShift cluster. If you followed the:

- Advanced installation method using Ansible, then make your configuration changes in the Ansible playbook.
- Quick installation method, then make your changes manually in the configuration files themselves.

2.3.1. Making Configuration Changes Using Ansible

For this section, familiarity with Ansible is assumed.

Only a portion of the available host configuration options are exposed to Ansible. After an OpenShift Container Platform install, Ansible creates an inventory file with some substituted values. Modifying this inventory file and re-running the Ansible installer playbook is how you customize your OpenShift Container Platform cluster.

While OpenShift supports using Ansible as the advanced install method, using an Ansible playbook and inventory file, you can also use other management tools, such as Puppet, Chef, Salt).

Use Case: Configure the cluster to use HTPasswd authentication



Note

This use case assumes you have already set up SSH keys to all the nodes referenced in the playbook.

To modify the Ansible inventory and make configuration changes:

1. Open the ./hosts inventory file:

Example 2.1. Sample inventory file:

```
[OSEv3:children]
masters
nodes
[OSEv3:vars]
ansible_ssh_user=cloud-user
ansible_become=true
deployment_type=openshift-enterprise
[masters]
ec2-52-6-179-239.compute-1.amazonaws.com
openshift_ip=172.17.3.88 openshift_public_ip=52-6-179-239
openshift_hostname=master.example.com
openshift_public_hostname=ose3-master.public.example.com
containerized=True
[nodes]
ec2-52-6-179-239.compute-1.amazonaws.com
openshift_ip=172.17.3.88 openshift_public_ip=52-6-179-239
openshift_hostname=master.example.com
openshift_public_hostname=ose3-master.public.example.com
containerized=True openshift_schedulable=False
ec2-52-95-5-36.compute-1.amazonaws.com
openshift_ip=172.17.3.89 openshift_public_ip=52.3.5.36
openshift_hostname=node.example.com
openshift_public_hostname=ose3-node.public.example.com
containerized=True
```

2. Add the following new variables to the **[0SEv3:vars]** section of the file:

```
# htpasswd auth
openshift_master_identity_providers=[{'name': 'htpasswd_auth',
'login': 'true', 'challenge': 'true', 'kind':
'HTPasswdPasswordIdentityProvider', 'filename':
'/etc/origin/master/htpasswd'}]
# Defining htpasswd users
```

```
openshift_master_htpasswd_users={'jsmith':
   '$apr1$wIwXkFLI$bAygtISk2eKGmPOqaJftB', 'bloblaw':
   '7IRJ$20DmeLoxf4I6sUEKfiA$2aeKnsDJqLJe'
# or
#openshift_master_htpasswd_file=<path/to/local/pregenerated/htpasswdfile>
```

This will change the authentication method from the default **deny all** setting to **htpasswd** and use the specified file to generate user IDs and passwords for **jsmith** and **bloblaw**.

3. Re-run the ansible playbook for these modifications to take effect:

```
$ ansible-playbook -b -i ./hosts ~/src/openshift-
ansible/playbooks/byo/config.yml
```

The playbook updates the configuration, and restarts the OpenShift master service to apply the changes.

You have now modified the master and node configuration files using Ansible, but this is just a simple use case. From here you can see which master and node configuration options are exposed to Ansible and customize your own Ansible inventory.

2.3.2. Making Manual Configuration Changes

After installing OpenShift Container Platform using the quick install, you can make modifications to the master and node configuration files to customize your cluster.

Use Case: Configure the cluster to use HTPasswd authentication

To manually modify a configuration file:

- 1. Open the configuration file you want to modify, which in this case is the <code>/etc/origin/master/master-config.yaml</code> file:
- 2. Add the following new variables to the **identityProviders** stanza of the file:

```
oauthConfig:
...
identityProviders:
- name: my_htpasswd_provider
   challenge: true
   login: true
   mappingMethod: claim
   provider:
       apiVersion: v1
       kind: HTPasswdPasswordIdentityProvider
       file: /path/to/users.htpasswd
```

- 3. Save your changes and close the file.
- 4. Restart the master for the changes to take effect:

```
$ systemctl restart atomic-openshift-master
```

You have now manually modified the master and node configuration files, but this is just a simple use case. From here you can see all the master and node configuration options, and further customize your own cluster by making further modifications.

2.4. CONFIGURATION OPTIONS

2.4.1. Master Configuration File Options

The table below contains the options available for configuring your OpenShift Container Platform *master-config.yaml* file. Use this table as a reference, and then follow the section on making manual configuration changes and substitute in whatever values you want to change.

Table 2.1. Master Configuration File Options

Option	Description	
servingInfo	Describes how to start serving. For example: servingInfo: bindAddress: 0.0.0.0:8443 bindNetwork: tcp4 certFile: master.server.crt clientCA: ca.crt keyFile: master.server.key maxRequestsInFlight: 500 requestTimeoutSeconds: 3600	
corsAllowedO rigins	Specifies the host name to use to access the API server from a web application.	
apiLevels	A list of API levels that should be enabled on startup; for example, v1beta3 and v1 .	
apiServerArg uments	Contains key value pairs that match the API server's command-line arguments and are passed directly to the Kubernetes API server. These are not migrated, but if you reference a value that does not exist, then the server will not start. apiServerArguments: event-ttl: - "15m"	

Option Description assetConfig If present, then the asset server starts based on the defined parameters. For example: assetConfig: logoutURL: "" masterPublicURL: https://master.ose32.example.com:8443 publicURL: https://master.ose32.example.com:8443/console/ servingInfo: bindAddress: 0.0.0.0:8443 bindNetwork: tcp4 certFile: master.server.crt clientCA: "" keyFile: master.server.key maxRequestsInFlight: 0 requestTimeoutSeconds: 0 controllers A list of the controllers that should be started. If set to **none**, then no controllers will start automatically. The default value is * which will start all controllers. When using *, you may exclude controllers by prepending a - in front of the controller name. No other values are recognized at this time. pauseControl When set to **true**, this instructs the master to not automatically start controllers, lers but instead to wait until a notification to the server is received before launching them. Enables controller election, instructing the master to attempt to acquire a lease controllerLe aseTTL before controllers start, and renewing it within a number of seconds defined by this value. Setting this value as a non-negative forces **pauseControllers=true**. The value default is off (0, or omitted) and controller election can be disabled with -1. admissionCon Contains admission control plug-in configuration. OpenShift has a configurable list fig of admission controller plug-ins that are triggered whenever API objects are created or modified. This option allows you to override the default list of plug-ins; for example, disabling some plug-ins, adding others, changing the ordering, and specifying configuration. Both the list of plug-ins and their configuration can be controlled from Ansible.

Option	Description
disabledFeat ures	Lists features that should <i>not</i> be started. This is defined as omitempty because it is unlikely that you would want to manually disable features.
etcdStorageC onfig	Contains information about how API resources are stored in etcd. These values are only relevant when etcd is the backing store for the cluster.
etcdClientIn fo	Contains information about how to connect to etcd. Specifies if etcd is run as embedded or non-embedded, and the hosts. The rest of the configuration is handled by the Ansible inventory. For example:
	<pre>etcdClientInfo: ca: ca.crt certFile: master.etcd-client.crt keyFile: master.etcd-client.key urls: https://m1.aos.example.com:4001</pre>
kubernetesMa sterConfig	Contains information about how to connect to kubelet's KubernetesMasterConfig. If present, then start the kubernetes master in this process.
etcdConfig	If present, then etcd starts based on the defined parameters. For example:
	<pre>etcdConfig: address: master.ose32.example.com:4001 peerAddress: master.ose32.example.com:7001 peerServingInfo: bindAddress: 0.0.0.0:7001 certFile: etcd.server.crt clientCA: ca.crt keyFile: etcd.server.key servingInfo: bindAddress: 0.0.0.0:4001 certFile: etcd.server.crt clientCA: ca.crt keyFile: etcd.server.key storageDirectory: /var/lib/origin/openshift.local.etcd</pre>

Option Description oauthConfig If present, then the /oauth endpoint starts based on the defined parameters. For example: oauthConfig: assetPublicURL: https://master.ose32.example.com:8443/console/ grantConfig: method: auto identityProviders: - challenge: true login: true mappingMethod: claim name: htpasswd_all provider: apiVersion: v1 kind: HTPasswdPasswordIdentityProvider file: /etc/origin/openshift-passwd masterCA: ca.crt masterPublicURL: https://master.ose32.example.com:8443 masterURL: https://master.ose32.example.com:8443 sessionConfig: sessionMaxAgeSeconds: 3600 sessionName: ssn sessionSecretsFile: /etc/origin/master/sessionsecrets.yaml tokenConfig: accessTokenMaxAgeSeconds: 86400 authorizeTokenMaxAgeSeconds: 500 assetConfig If present, then the asset server starts based on the defined parameters. For example: assetConfig: logoutURL: "" masterPublicURL: https://master.ose32.example.com:8443 publicURL: https://master.ose32.example.com:8443/console/ servingInfo: bindAddress: 0.0.0.0:8443 bindNetwork: tcp4 certFile: master.server.crt clientCA: "" keyFile: master.server.key maxRequestsInFlight: 0 requestTimeoutSeconds: 0

Option	Description
dnsConfig	If present, then start the DNS server based on the defined parameters. For example:
	<pre>dnsConfig: bindAddress: 0.0.0.0:8053 bindNetwork: tcp4</pre>
serviceAccou	Holds options related to service accounts:
ntConfig	LimitSecretReferences (boolean): Controls whether or not to allow a service account to reference any secret in a namespace without explicitly referencing them.
	ManagedNames (string): A list of service account names that will be autocreated in every namespace. If no names are specified, then the ServiceAccountsController will not be started.
	MasterCA (string): The certificate authority for verifying the TLS connection back to the master. The service account controller will automatically inject the contents of this file into pods so that they can verify connections to the master.
	PrivateKeyFile (string): Contains a PEM-encoded private RSA key, used to sign service account tokens. If no private key is specified, then the service account TokensController will not be started.
	PublicKeyFiles (string): A list of files, each containing a PEM-encoded public RSA key. If any file contains a private key, then OpenShift uses the public portion of the key. The list of public keys is used to verify service account tokens; each key is tried in order until either the list is exhausted or verification succeeds. If no keys are specified, then service account authentication will not be available.
masterClient s	Holds all the client connection information for controllers and other system components:
	OpenShiftLoopbackKubeConfig (string): the .kubeconfig filename for system components to loopback to this master.
	ExternalKubernetesKubeConfig (string): the .kubeconfig filename for proxying to Kubernetes.
imageConfig	Holds options that describe how to build image names for system components:
	Format (string): Describes how to determine image names for system components
	Latest (boolean): Defines whether to attempt to use the latest system component images or the latest release.

Option Description imagePolicyC Controls limits and behavior for importing images: onfig MaxImagesBulkImportedPerRepository (integer): Controls the number of images that are imported when a user does a bulk import of a Docker repository. This number is set low to prevent users from importing large numbers of images accidentally. This can be set to -1 for no limit. DisableScheduledImport (boolean): Allows scheduled background import of images to be disabled. ScheduledImageImportMinimumIntervalSeconds (integer): The minimum number of seconds that can elapse between when image streams scheduled for background import are checked against the upstream repository. The default value is 900 (15 minutes). MaxScheduledImageImportsPerMinute (integer): The maximum number of image streams that can be imported in the background, per minute. The default value is **60**. This can be set to **-1** for unlimited imports. This can be controlled with the Ansible inventory. policyConfig Holds information about where to locate critical pieces of bootstrapping policy. This is controlled by Ansible, so you may not need to modify this: **BootstrapPolicyFile** (string): Points to a template that contains roles and rolebindings that will be created if no policy object exists in the master namespace. OpenShiftSharedResourcesNamespace (string): The namespace where shared OpenShift resources are located, such as shared templates. OpenShiftInfrastructureNamespace (string): The namespace where OpenShift infrastructure resources are located, such as controller service accounts.

Option Description projectConfi Holds information about project creation and defaults: g DefaultNodeSelector (string): Holds the default project node label selector. ProjectRequestMessage (string): The string presented to a user if they are unable to request a project via the projectrequest API endpoint. ProjectRequestTemplate (string): The template to use for creating projects in response to projectrequest. It is in the format <namespace>/<template>. It is optional, and if it is not specified, a default template is used. SecurityAllocator: Controls the automatic allocation of UIDs and MCS labels to a project. If nil, allocation is disabled: mcsAllocatorRange (string): Defines the range of MCS categories that will be assigned to namespaces. The format is <prefix>/<numberOfLabels>[,<maxCategory>]. The default is **s0/2** and will allocate from $c0 \rightarrow c1023$, which means a total of 535k labels are available. If this value is changed after startup, new projects may receive labels that are already allocated to other projects. The prefix may be any valid SELinux set of terms (including user, role, and type). However, leaving the prefix at its default allows the server to set them automatically. For example, s0:/2 would allocate labels from s0:c0,c0 to s0:c511,c511 whereas **s0:/2,512** would allocate labels from s0:c0,c0,c0 to s0:c511,c511,511. mcsLabelsPerProject (integer): Defines the number of labels to reserve per project. The default is 5 to match the default UID and MCS ranges. uidAllocatorRange (string): Defines the total set of Unix user IDs (UIDs) automatically allocated to projects, and the size of the block each namespace gets. For example, **1000-1999/10** would allocate ten UIDs per namespace, and would be able to allocate up to 100 blocks before running out of space. The default is to allocate from 1 billion to 2 billion in 10k blocks, which is the expected size of ranges for container images when user namespaces are started. routingConfi Holds information about routing and route generation:

q

Subdomain (string): The suffix appended to \$service.\$namespace. to form the default route hostname. Can be controlled via Ansible with openshift_master_default_subdomain. Example:

routingConfig: subdomain:

Option	Description
networkConfi g	To be passed to the compiled-in-network plug-in. Many of the options here can be controlled in the Ansible inventory.
	<pre>» NetworkPluginName (string)</pre>
	<pre>ClusterNetworkCIDR (string)</pre>
	HostSubnetLength (unsigned integer)
	<pre>ServiceNetworkCIDR (string)</pre>
	ExternalIPNetworkCIDRs (string array): Controls which values are acceptable for the service external IP field. If empty, no external IP may be set. It can contain a list of CIDRs which are checked for access. If a CIDR is prefixed with !, then IPs in that CIDR are rejected. Rejections are applied first, then the IP is checked against one of the allowed CIDRs. For security purposes, you should ensure this range does not overlap with your nodes, pods, or service CIDRs.
	For Example:
	<pre>networkConfig: clusterNetworkCIDR: 10.3.0.0/16 hostSubnetLength: 8 networkPluginName: example/openshift-ovs-subnet # serviceNetworkCIDR must match kubernetesMasterConfig.servicesSubnet serviceNetworkCIDR: 179.29.0.0/16</pre>
volumeConfig	Contains options for configuring volume plug-ins in the master node:
	DynamicProvisioningEnabled (boolean): Default value is true, and toggles dynamic provisioning off when false.

2.4.2. Node Configuration File Options

The table below contains the options available for configuring your OpenShift Container Platform *node-config.yaml* file. Use this table as a reference, and then follow the section on making manual configuration changes and substitute in whatever values you want to change.

Table 2.2. Node Configuration File Options

Option	Description
nodeName	The value of the nodeName (string) is used to identify this particular node in the cluster. If possible, this should be your fully qualified hostname. If you are describing a set of static nodes to the master, then this value must match one of the values in the list.

Option	Description
nodeIP	A node may have multiple IPs. This specifies the IP to use for pod traffic routing. If left unspecified, a network look-up is performed on the nodeName, and the first non-loopback address is used.
servingInfo	Describes how to start serving.
masterKubeCo nfig	The filename for the .kubeconfig file that describes how to connect this node to the master.
dnsDomain	Holds the domain suffix.
dnsIP	(string) Contains the IP. Can be controlled with openshift_dns_ip in the Ansible inventory.
networkPlugi nName,omitem pty	Deprecated and maintained for backward compatibility, use NetworkConfig.NetworkPluginName instead.
networkConfi g	Provides network options for the node: NetworkPluginName (string): Specifies the networking plug-in. MTU (unsigned integer): Maximum transmission unit for the network packets.
volumeDirect ory	The directory that volumes will be stored under.
imageConfig	Holds options that describe how to build image names for system components.
allowDisable dDocker	If this is set to true , then the Kubelet will ignore errors from Docker. This means that a node can start on a machine that does not have Docker started.
podManifestC onfig	Holds the configuration for enabling the Kubelet to create pods based from a manifest file or files placed locally on the node.
authConfig	Holds authn/authz configuration options.

Option	Description	
dockerConfig	Holds Docker-related configuration options.	
kubeletArgum ents,omitemp ty	Key-value pairs that are passed directly to the Kubelet that matches the Kubelet's command line arguments. These are not migrated or validated, so if you use them, then they may become invalid. Use caution, because these values override other settings in the node configuration that may cause invalid configurations.	
proxyArgumen ts,omitempty	ProxyArguments are key-value pairs that are passed directly to the Proxy that matches the Proxy's command-line arguments. These are not migrated or validated, so if you use them they may become invalid. Use caution, because these values override other settings in the node configuration that may cause invalid configurations.	
iptablesSync Period	(string) How often iptables rules are refreshed. This can be controlled with openshift_node_iptables_sync_period from the Ansible inventory.	
volumeConfig	Contains options for configuring volumes on the node. It can be used to apply a filesystem quota if the underlying volume directory is on XFS with grpquota enabled.	

CHAPTER 3. USER AND ROLE MANAGEMENT

3.1. LIMITING AND MONITORING USERS AND PROJECTS

3.1.1. Setting Limits for Users and Projects

How can I create limits for users and projects?

You can place limits within your OpenShift cluster using ResourceQuotas and LimitRanges. These quotas and limits allow you to control pod and container limits, object counts, and compute resources. Currently, these limits and quotas only apply to projects and not to users. However, you can make a quota-like limit on how many project requests a user can make.

Creating a quota in a project to limit the number of pods

To create a quota in the "awesomeproject" that limits the number of pods that can be created to a maximum of 10:

1. Create a *resource-quota.yaml* file with the following contents:

```
apiVersion: v1
kind: ResourceQuota
metadata:
   name: compute-resources
spec:
   hard:
    pods: "10"
```

2. Create the quota using the file you just wrote to apply it to the "awesomeproject":

```
$ oc create -f resource-quota.yaml -n awesomeproject
```

After the quota has been in effect for a little while, you can view the usage statistics for the hard limit set on pods.

3. If required, list the quotas defined in the project to see the names of all defined quotas:

```
$ oc get quota -n awesomeproject
NAME AGE
resource-quota 39m
```

4. Describe the resource quota for which you want statistics:

5. Optionally, you can configure the quota synchronization period, which controls how long to wait before restoring quota usage after resources are deleted.

6. If you want to remove an active quota to no longer enforce the limits of a project:

```
$ oc delete quota <quota_name>
```

3.1.1.1. Configuration Options

The procedure above is just a basic example. The following are references to all the available options for limits and quotas:

This *LimitRange* example explains all the container limits and pod limits that you can place within your project:

Example 3.1. Limit Range Object Definition

```
apiVersion: "v1"
kind: "LimitRange"
metadata:
  name: "core-resource-limits" 1
  limits:
    - type: "Pod"
     max:
       cpu: "2" 2
       memory: "1Gi" (3)
     min:
       cpu: "200m" (
       memory: "6Mi" 5
    - type: "Container"
     max:
       cpu: "2" 6
       memory: "1Gi" 7
     min:
       cpu: "100m" 8
       memory: "4Mi" 9
      default:
       cpu: "300m" 6
       memory: "200Mi"
      defaultRequest:
       cpu: "200m" 🖠
       memory: "100Mi"
     maxLimitRequestRatio:
       cpu: "10" 1
```

1

The name of the limit range document.

2	
	The maximum amount of CPU that a pod can request on a node across all containers.
3	The maximum amount of memory that a pod can request on a node across all containers.
4	The minimum amount of CPU that a pod can request on a node across all containers.
5	The minimum amount of memory that a pod can request on a node across all containers.
6	The maximum amount of CPU that a single container in a pod can request.
7	The maximum amount of memory that a single container in a pod can request.
8	The minimum amount of CPU that a single container in a pod can request.
9	The minimum amount of memory that a single container in a pod can request.
10	The default amount of CPU that a container will be limited to use if not specified.
11	The default amount of memory that a container will be limited to use if not specified.
12	The default amount of CPU that a container will request to use if not specified.

13

The default amount of memory that a container will request to use if not specified.

14

The maximum amount of CPU burst that a container can make as a ratio of its limit over request.

Example 3.2. OpenShift Container Platform Limit Range Object Definition

1

The maximum size of an image that can be pushed to an internal registry.

2

The maximum number of unique image tags per image stream's spec.

3

The maximum number of unique image references per image stream's status.

These *ResourceQuota* examples explain all the Object Counts and Compute Resources that you can place within your project:

Example 3.3. object-counts.yaml

apiVersion: v1

```
kind: ResourceQuota
metadata:
  name: core-object-counts
spec:
  hard:
    configmaps: "10" 1
    persistentvolumeclaims: "4" 2
    replicationcontrollers: "20" 3
    secrets: "10" 4
    services: "10" 5
    The total number of ConfigMap objects that can exist in the project.
    The total number of persistent volume claims (PVCs) that can exist in the project.
    The total number of replication controllers that can exist in the project.
```

The total number of secrets that can exist in the project.

5

The total number of services that can exist in the project.

Example 3.4. openshift-object-counts.yaml

1

The total number of image streams that can exist in the project.

Example 3.5. compute-resources.yaml

1

The total number of pods in a non-terminal state that can exist in the project.

2

Across all pods in a non-terminal state, the sum of CPU requests cannot exceed 1 core.

3

Across all pods in a non-terminal state, the sum of memory requests cannot exceed 1Gi.

4

Across all pods in a non-terminal state, the sum of CPU limits cannot exceed 2 cores.

5

Across all pods in a non-terminal state, the sum of memory limits cannot exceed 2Gi.

3.1.2. Limiting the Number of Projects a User Can Have

You can limit the number of projects that a user may request by categorizing users with label selectors with the **oc label** command. A label selector consists of the label name and the label value:

label=value

Once users are labeled, you must modify the default project template in the *master-config.yaml* file using an admission control plug-in. This allows some users to create more projects than others, and you can define different values (or levels) for each label.

Limiting how many projects a user can request by defining three different privilege levels

The label is named **level**, and the possible values are **bronze**, **silver**, **gold**, and **platinum**. Platinum users do not have a maximum number of project requests, gold users can request up to 10 projects, silver users up to 7 projects, bronze users up to 5 projects, and any users without a label are by default only allowed 2 projects.

Each user can only have one value per label. For example, a user cannot be both **gold** and **silver** for the level label. However, when configuring the *master-config.yaml* file, you could select users that have any value for a label with a wildcard; for example, **level=***.

To define privilege levels for project requests:

1. Apply label selectors to users. For example, to apply the **level** label selector with a value of **bronze**:

```
$ oc label user <user_name> level=bronze
```

Repeat this step for all bronze users, and then for the other levels.

2. Optionally, verify the previous step by viewing the list of labeled users for each value:

```
$ oc get users -l level=bronze
$ oc get users -l level=silver
$ oc get users -l level=gold
$ oc get users -l level=platinum
```

If you need to remove a label from a user to make a correction:

```
$ oc label user <user_name> level-
```

 Modify the *master-config.yaml* file to define project limits for this label with the numbers stated in this use case. Find the admissionConfig line and create the configuration below it:

```
admissionConfig:
  pluginConfig:
    ProjectRequestLimit:
      configuration:
      apiVersion: v1
      kind: ProjectRequestLimitConfig
      limits:
      - selector:
            level: platinum
      - selector:
            level: gold
            maxProjects: 10
      - selector:
            level: silver
            maxProjects: 7
```

- selector:

level: bronze
maxProjects: 5
- maxProjects: 2

4. Restart the master host for the changes to take effect.

\$ systemctl restart atomic-openshift-master



Note

If you use a custom project template to limit the number of projects per user, then you must ensure that you keep the modifications by including the following:

ProjectRequester = "openshift.io/requester"

Ownership is established using the **openshift.io/requester** annotation, so your custom project template must have the same annotation.

3.1.3. Controlling and Monitoring Resource Usage

If you configure a project to have ResourceQuota restrictions, then the amount of the defined quota currently being used is stored on the ResourceQuota object itself. In that case, you could check the amount of used resources, such as CPU usage:

\$ oc get quota

However, this would not tell you what is actually being consumed. To determine what is actually being consumed, use the **oc describe** command:

\$ oc describe quota <quota-name>

Alternatively, you can set up cluster metrics for more detailed statistics.

3.2. DETERMINING WHICH ROLES USERS GET BY DEFAULT

When a user first logs in, there is a default set of permissions that is applied to that user. The scope of permissions that a user can have is controlled by the various types of roles within OpenShift:

- ClusterRoles
- ClusterRoleBindings
- Roles (project-scoped)
- RoleBindings (project-scoped)

You may want to modify the default set of permissions. In order to do this, it's important to understand the default groups and roles assigned, and to be aware of the roles and users bound to each project or the entire cluster.

3.2.1. Leveraging Default Groups

There are special groups that are assigned to users. You can target users with these groups, but you cannot modify them. These special groups are as follows:

Group	Description
system:authenticated	This is assigned to all users who are identifiable to the API. Everyone who is not system: anonymous (the user) is in this group.
system:authenticated:oauth	This is assigned to all users who have identified using an oauth token issued by the embedded oauth server. This is not applied to service accounts (they use service account tokens), or certificate users.
system:unauthenticated	This is assigned to users who have not presented credentials. Invalid credentials are rejected with a 401 error, so this is specifically users who did not try to authenticate at all.

You may find it helpful to target users with the special groups listed above. For example, you could share a template with all users by granting **system:authenticated** access to the template.

The "default" permissions of users are defined by which roles are bound to the **system:authenticated** and **sytem:authenticated:oauth** groups. As mentioned above, you are not able to modify membership to these groups, but you can change the roles bound to these groups. For example, to bind a role to the **system:authenticated** group for all projects in the cluster:

 $\$ oadm policy add-cluster-role-to-group <role> system:authenticated

Currently, by default the **system:authenticated** and **sytem:authenticated:oauth** groups receive the following roles:

Role	Description
shared-resource-viewer	For the openshift project. Allows users to see templates and pull images.
basic-user	For the the entire cluster. Allows users to see their own account, check for information about requesting projects, see which projects they can view, and check their own permissions.

Role	Description
self-provisioner	Allows users to request projects.
system:oauth-token-deleter	Allows users to delete any oauth token for which they know the details.
cluster-status	Allows users to see which APIs are enabled, and basic API server information such as versions.
system:webhook	Allows users to hit the webhooks for a build if they have enough additional information.

3.2.2. Viewing Roles and Users for a Project

To view a list of all users that are bound to the project and their roles:

\$ oc get rolebindings NAME **ROLE** USERS **GROUPS** SERVICE ACCOUNTS SUBJECTS system:image-pullers /system:image-puller system:serviceaccounts:asdfasdf4asdf admin /admin jsmith system:deployers /system:deployer deployer system:image-builders /system:image-builder

3.2.3. Viewing Roles and Users for the Cluster

builder

To view a list of users and what they have access to across the entire cluster:

\$ oc get clusterrolebindings ROLE NAME **USERS GROUPS** SERVICE ACCOUNTS SUBJECTS system:job-controller /system:jobcontroller openshift-infra/job-controller system:build-controller /system:buildcontroller openshift-infra/build-controller system:node-admins /system:node-admin system:master system:node-admins registry-registry-role /system:registry

default/registry system:pv-provisioner-controller /system:pvprovisioner-controller openshift-infra/pv-provisioner-controller basic-users /basic-user system:authenticated system:namespace-controller /system:namespacecontroller openshift-infra/namespace-controller system:discovery-binding /system:discovery system:authenticated, system:unauthenticated system:build-strategy-custom-binding /system:buildstrategy-custom system:authenticated cluster-status-binding /cluster-status system:authenticated, system:unauthenticated system:webhooks /system:webhook system:authenticated, system:unauthenticated system:gc-controller /system:gc-controller openshift-infra/gc-controller cluster-readers /cluster-reader system:cluster-readers system:pv-recycler-controller /system:pv-recyclercontroller openshift-infra/pv-recycler-controller system:daemonset-controller /system:daemonsetcontroller openshift-infra/daemonset-controller cluster-admins /cluster-admin system:admin system:cluster-admins system:hpa-controller /system:hpacontroller openshift-infra/hpa-controller system:build-strategy-source-binding /system:buildsystem:authenticated strategy-source system:replication-controller /system:replicationcontroller openshift-infra/replication-controller system:sdn-readers /system:sdn-reader system:nodes system:build-strategy-docker-binding /system:buildstrategy-docker system:authenticated system:routers /system:router system:routers system:oauth-token-deleters /system:oauth-tokensystem:authenticated, deleter system:unauthenticated system:node-proxiers /system:node-proxier system:nodes system:nodes /system:node system:nodes self-provisioners /self-provisioner system:authenticated:oauth system:service-serving-cert-controller /system:serviceserving-cert-controller openshift-infra/service-serving-cert-controller system:registrys /system:registry

```
system:registries
system:pv-binder-controller
                                                 /system:pv-binder-
controller
openshift-infra/pv-binder-controller
system:build-strategy-jenkinspipeline-binding
                                                 /system:build-strategy-
jenkinspipeline
                                     system: authenticated
system:deployment-controller
                                                 /system:deployment-
controller
openshift-infra/deployment-controller
system:masters
                                                 /system:master
system:masters
system:service-load-balancer-controller
                                                 /system:service-load-
balancer-controller
openshift-infra/service-load-balancer-controller
```

These commands can generate huge lists, so you may want to pipe the output into a text file that you can search through more easily.

3.3. CONTROLLING USER PERMISSIONS WITH ROLES

You can define roles (or permissions) for a user before their initial log in so they can start working immediately. You can assign many different types of roles to users such as admin, basic-user, self-provisioner, and cluster-reader.

For a complete list of all available roles:

\$ oadm policy

The following section includes examples of some common operations related to adding (binding) and removing roles from users and groups. For a complete list of available local policy operations, see Managing Role Bindings.

3.3.1. Adding a Role to a User

To bind a role to a user for the current project:

\$ oadm policy add-role-to-user <role> <user_name>

You can specify a project with the -n flag.

3.3.2. Removing a Role from a User

To remove a role from a user for the current project:

\$ oadm policy remove-role-from-user <role> <user_name>

You can specify a project with the -n flag.

3.3.3. Adding a Cluster Role to a User for All Projects

To bind a cluster role to a user for all projects:

\$ oadm policy add-cluster-role-to-user <role> <user_name>

3.3.4. Removing a Cluster Role from a User for All Projects

To remove a cluster role from a user for all projects:

\$ oadm policy remove-cluster-role-from-user <role> <user_name>

3.3.5. Adding a Role to a Group

To bind a role to a specified group in the current project:

\$ oadm policy add-role-to-group <role> <groupname>

You can specify a project with the -n flag.

3.3.6. Removing a Role from a Group

To remove a role from a specified group in the current project:

\$ oadm policy remove-role-from-group <role> <groupname>

You can specify a project with the -n flag.

3.3.7. Adding a Cluster Role to a Group for All Projects

To bind a role to a specified group for all projects in the cluster:

\$ oadm policy add-cluster-role-to-group <role> <groupname>

3.3.8. Removing a Cluster Role from a Group for All Projects

To remove a role from a specified group for all projects in the cluster:

\$ oadm policy remove-cluster-role-from-group <role> <groupname>

3.4. SHARING TEMPLATES FOR USE IN PROJECTS ACROSS THE CLUSTER

Templates are project-scoped resources, so you cannot create them to be readily available at a cluster level. The easiest way to share templates across the entire cluster is with the **openshift** project, which by default is already set up to share templates. The templates can be annotated, and are displayed in the web console where users can access them. Users have **get** access only to the templates and images in this project, via the **shared-resource-viewer** role.

The **shared-resource-viewer** role exists to allow templates to be shared across project boundaries. Users with this role have the ability to see all existing templates and pull images from that project. However, the user still needs to know which project to look in, because they will not be able to view the project in their **oc get projects** list.

By default, this role is granted to the **system:authenticated** group in the **openshift** project. This allows users to process the specified template from the **openshift** project and create the items in the current project:

\$ oc process openshift//<template-name> | oc create -f -

You can also add the registry viewer role to a user, allowing them to view and pull images from a project:

\$ oc policy add-role-to-user registry-viewer <user-name>

3.5. CREATING A CLUSTER ADMINISTRATOR USER

Cluster administrator is a very powerful role, which has ultimate control within the cluster, including the power to destroy that cluster. You can grant this role to other users if they absolutely need to have ultimate control. However, you may first want to examine the other available roles if you do not want to create such a powerful user. For example, **admin** is a constrained role that has the power to do many things inside of their project, but cannot affect (or destroy) the entire cluster.

3.5.1. Creating an Administrator Within a Project

To create a basic administrator role within a project:

\$ oadm policy add-role-to-user admin <user_name> -n project_name>

3.5.2. Creating a Cluster Administrator

To create a cluster administrator with ultimate control over the cluster:

Warning

Be very careful when granting cluster administrator role to a user. Ensure that the user truly needs that level of power within the cluster. When OpenShift is first installed, a certificate based user is created and the credentials are saved in *admin.kubeconfig*. This cluster administrator user can do absolutely anything to any resource on the entire cluster, which can result in destruction if not used carefully.

\$ oadm policy add-cluster-role-to-user cluster-admin <user_name>

CHAPTER 4. AUTHENTICATION

4.1. OVERVIEW

OpenShift Container Platform supports many different authentication methods, as defined in Configuring Authentication:

- Basic Authentication (Remote)
- Request Header
- Keystone
- » LDAP
- GitHub

4.2. BASIC AUTHENTICATION (REMOTE)

Basic Authentication is a generic backend integration mechanism that allows users to log in to OpenShift Container Platform with credentials validated against a remote identity provider.

Caution

Basic Authentication must use an HTTPS connection to the remote server in order to prevent potential snooping of the user ID and password, and to prevent man-in-the-middle attacks.

With **BasicAuthPasswordIdentityProvider** configured, users send their username and password to OpenShift Container Platform, which then validates those credentials against a remote server by making a server-to-server request, passing the credentials as a Basic Auth header. This requires users to send their credentials to OpenShift Container Platform during login.



Note

This only works for username/password login mechanisms, and OpenShift Container Platform must be able to make network requests to the remote authentication server.

4.2.1. Configuring Authentication on the Master

- 1. If you have:
 - Already completed the installation of Openshift, then copy the /etc/origin/master/master-config.yaml file into a new directory; for example:
 - \$ mkdir basicauthconfig; cp master-config.yaml basicauthconfig
 - Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

\$ openshift start master --public-master=<apiserver> --writeconfig=<directory>

For example:

```
$ openshift start master --public-
master=https://myapiserver.com:8443 --write-
config=basicauthconfig
```



Note

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

- 2. Edit the new *master-config.yaml* file's **identityProviders** stanza.
- 3. Copy the example **BasicAuthPasswordIdentityProvider** configuration and paste it to replace the existing stanza.
- 4. Make the following modifications to the **identityProviders** stanza:
 - a. Set the provider **name** to something unique and relevant to your deployment. This name is prefixed to the returned user ID to form an identity name.
 - b. If required, set mappingMethod to control how mappings are established between the provider's identities and user objects.
 - c. Specify the HTTPS **ur1** to use to connect to a server that accepts credentials in Basic authentication headers.
 - d. Optionally, set the ca to the certificate bundle to use in order to validate server certificates for the configured URL, or leave it empty to use the system-trusted roots.
 - e. Optionally, remove or set the **certFile** to the client certificate to present when making requests to the configured URL.
 - f. If **certFile** is specified, then you must set the **keyFile** to the key for the client certificate.
- 5. Save your changes and close the file.
- 6. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=
<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their Basic authentication credentials.

4.2.2. Troubleshooting

TIEIEI IIOUDIOOIIOOIII9

The most common issue relates to network connectivity to the backend server. For simple debugging, run <code>curl</code> commands on the master. To test for a successful login, replace the <code><user></code> and <code><password></code> in the following example command with valid credentials. To test an invalid login, replace them with false credentials.

```
curl --cacert /path/to/ca.crt --cert /path/to/client.crt --key
/path/to/client.key -u <user>:<password> -v
https://www.example.com/remote-idp
```

Successful responses

A 200 status with a sub (subject) key indicates success:

```
{"sub":"userid"}
```

The subject must be unique to the authenticated user, and must not be able to be modified.

A successful response may optionally provide additional data, such as:

A display name using the name key:

```
{"sub":"userid", "name": "User Name", ...}
```

An email address using the **email** key:

```
{"sub":"userid", "email":"user@example.com", ...}
```

A preferred user name using the **preferred_username** key:

```
{"sub":"014fbff9a07c", "preferred_username":"bob", ...}
```

The **preferred_username** key is useful when the unique, unchangeable subject is a database key or UID, and a more human-readable name exists. This is used as a hint when provisioning the OpenShift Container Platform user for the authenticated identity.

Failed responses

- A 401 response indicates failed authentication.
- A non-200 status or the presence of a non-empty "error" key indicates an error: {"error":"Error message"}

```
4.2.3. Verifying Users
```

Once one or more users have logged in, you can run **oc get users** to view a list of users and verify that users were created successfully.

From here, you might want to learn how to control user roles.

4.3. REQUEST HEADER AUTHENTICATION

Configuring Request Header authentication allows users to log in to OpenShift Container Platform using request header values, such as **X-Remote-User**. It is typically used in combination with an

authenticating proxy, which authenticates the user and then provides OpenShift Container Platform with the user's identity via a request header value. This is similar to how the remote user plug-in in OpenShift Enterprise 2 allowed administrators to provide Kerberos, LDAP, and many other forms of enterprise authentication. The benefit of this configuration is that user credentials can be handled by the proxy and never seen by OpenShift.

The proxy must be able to make network requests to the OpenShift Container Platform server. Unauthenticated login attempts are redirected to a configured proxy URL. The proxy can authenticate browser clients regardless of how it is configured, but it must (currently) use either Basic Auth or Kerberos in order to work with the **oc** CLI tooling.

For users to authenticate using this identity provider, they must access https://<master>/oauth/authorize via an authenticating proxy. You can configure the OAuth server to redirect unauthenticated requests to the proxy.

4.3.1. Configuring Authentication on the Master

- 1. If you have:
 - Already completed the installation of Openshift, then copy the /etc/origin/master/master-config.yaml file into a new directory; for example:

```
$ mkdir reqheadauthconfig; cp master-config.yaml
reqheadauthconfig
```

Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-
config=<directory>
```

For example:

```
$ openshift start master --public-
master=https://myapiserver.com:8443 --write-
config=reqheadauthconfig
```



Note

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

- 2. Edit the new *master-config.yaml* file's **identityProviders** stanza.
- 3. View the example **RequestHeaderIdentityProvider** configuration and use it as a guide to replace the existing stanza.
- 4. Modify the **identityProviders** stanza based on which headers you plan to pass in.

- a. Set the provider **name** to something unique and relevant to your deployment. This name is prefixed to the returned user ID to form an identity name.
- b. If required, set mappingMethod to control how mappings are established between the provider's identities and user objects.
- c. Set the **challenge** parameter to **true** to redirect unauthenticated requests from clients expecting **WWW-Authenticate** challenges.
- d. Set the provider.challengeURL parameter to the proxy URL to which to send clients expecting WWW-Authenticate challenges, like the oc CLI client. This parameter can include the \${url} and \${query} tokens in the query portion of the URL.
- e. Set the **login** parameter to **true** to redirect unauthenticated requests from clients expecting login flows.
- f. Set the **provider.loginURL** parameter to the proxy URL to which to send clients expecting login flows, like web browser clients. This parameter can include the **\${ur1}** and **\${query}** tokens in the query portion of the URL.
- g. Set the clientCA parameter to the certificate bundle to use to check incoming requests for a valid client certificate before the request's headers are checked for a user name.

Warning

If you expect unauthenticated requests to reach the OAuth server, a **clientCA** parameter (and optionally, **clientCommonNames**) should be set for this identity provider. Otherwise, any direct request to the OAuth server can impersonate any identity from this provider, merely by setting a request header.

- h. Optionally, set the clientCommonNames parameter to a list of Common Names (cn). If set, a valid client certificate with a Common Name (cn) in the specified list must be presented before the request headers are checked for user names. If empty, then any Common Name is allowed. This must be used in combination with clientCA.
- i. Set the **headers** parameter to the header names to check, in order, for the user identity. The first header containing a value is used as the identity. This parameter is required and is case-insensitive.
- j. Optionally, set the **emailHeaders** parameter to the header names to check, in order, for an email address. The first header containing a value is used as the email address. This parameter is case-insensitive.
- k. Optionally, set the nameHeaders parameter to the header names to check, in order, for a display name. The first header containing a value is used as the display name. This parameter is case-insensitive.
- Optionally, set the preferredUsernameHeaders parameter to the header names to check, in order, for a preferred user name (if different than the immutable identity determined from the headers specified in headers). The first header containing a

value is used as the preferred user name when provisioning. This parameter is case-insensitive.

- 5. Save your changes and close the file.
- 6. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=
<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be redirected to the authenticating proxy, which will authenticate the user.

4.3.2. Creating Users with Request Header Authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as the system that the proxy server is using as an authentication server. That server is the system of record, meaning that users are defined there, and any user with a valid user name for the configured authentication server can log in.

To add a user to OpenShift Container Platform, the user must exist on the system the proxy is using as an authentication server, and if required you must add the users to that system.

4.3.3. Verifying Users

Once one or more users have logged in, you can run **oc get users** to view a list of users and verify that users were created successfully.

From here, you might want to examine advanced LDAP configuration for an example of Request Header authentication in use with Apache. You can also learn how to control user roles.

4.4. KEYSTONE AUTHENTICATION

Keystone is an OpenStack project that provides identity, token, catalog, and policy services. You can integrate your OpenShift Container Platform cluster with Keystone to enable shared authentication with an OpenStack Keystone v3 server configured to store users in an internal database. Once configured, this configuration allows users to log in to OpenShift Container Platform with their Keystone credentials.

4.4.1. Configuring Authentication on the Master

- 1. If you have:
 - Already completed the installation of Openshift, then copy the /etc/origin/master/master-config.yaml file into a new directory; for example:

```
$ cd /etc/origin/master
$ mkdir keystoneconfig; cp master-config.yaml keystoneconfig
```

Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-
config=<directory>
```

For example:

```
$ openshift start master --public-
master=https://myapiserver.com:8443 --write-
config=keystoneconfig
```



Note

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

- 2. Edit the new *keystoneconfig/master-config.yaml* file's **identityProviders** stanza.
- 3. Copy the example **KeystonePasswordIdentityProvider** configuration and paste it to replace the existing stanza.
- 4. Make the following modifications to the **identityProviders** stanza:
 - a. Change the provider **name** ("my_keystone_provider") to match your Keystone server. This name is prefixed to provider user names to form an identity name.
 - b. If required, change mappingMethod to control how mappings are established between the provider's identities and user objects.
 - c. Change the **domainName** to the domain name of your OpenStack Keystone server. In Keystone, usernames are domain-specific. Only a single domain is supported.
 - d. Specify the **url** to use to connect to your OpenStack Keystone server.
 - e. Optionally, change the **ca** to the certificate bundle to use in order to validate server certificates for the configured URL.
 - f. Optionally, change the **certFile** to the client certificate to present when making requests to the configured URL.
 - g. If **certFile** is specified, then you must change the **keyFile** to the key for the client certificate.
- 5. Save your changes and close the file.
- 6. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=
<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their Keystone credentials.

4.4.2. Creating Users with Keystone Authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as, in this case, Keystone. Keystone is the system of record, meaning that users are defined in a Keystone database, and any user with a valid Keystone user name for the configured authentication server can log in.

To add a user to OpenShift Container Platform, the user must exist in the Keystone database, and if required you must create a new Keystone account for the user.

4.4.3. Verifying Users

Once one or more users have logged in, you can run **oc get users** to view a list of users and verify that users were created successfully:

Example 4.1. Output of oc get users command

\$ oc get users

NAME UID FULL NAME

IDENTITIES

bobsmith a0c1d95c-1cb5-11e6-a04a-002186a28631 Bob Smith

keystone:bobsmith 1



Identities in OpenShift Container Platform are comprised of the identity provider name prefixed to the Keystone username.

From here, you might want to learn how to control user roles.

4.5. LDAP AUTHENTICATION

LDAP uses bind operations to authenticate applications, and you can integrate your OpenShift Container Platform cluster to use LDAPv3 authentication. Configuring LDAP authentication allows users to log in to OpenShift Container Platform with their LDAP credentials.

During authentication, the LDAP directory is searched for an entry that matches the provided user name. If a single unique match is found, a simple bind is attempted using the distinguished name (DN) of the entry plus the provided password.

Warning

The basic authentication configuration covered by this topic is not enough to create a secure LDAP authentication solution for OpenShift Container Platform. It has a single point of failure, meaning that if the single LDAP authentication server became unavailable then all OpenShift Container Platform operations requiring authentication would also be unavailable.

Additionally, this basic configuration has no access control of its own; all LDAP users matching the configured filter are able to log into OpenShift Container Platform.

With the SSSD failover setup, FreeIPA and Active Directory can also set rules to specifically restrict which users can and cannot access OpenShift Container Platform.

The following three advanced topics begin where this basic LDAP authentication topic ends, and describe the setup for a fault-tolerant authentication system:

- 1. Setting up SSSD for LDAP Failover
- 2. Configuring Form-Based Authentication
- 3. Configuring Extended LDAP Attributes

4.5.1. Configuring Authentication on the Master

1. If you have:

Already completed the installation of Openshift, then copy the /etc/origin/master/master-config.yaml file into a new directory; for example:

```
$ cd /etc/origin/master
$ mkdir ldapconfig; cp master-config.yaml ldapconfig
```

Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-
config=<directory>
```

For example:

```
$ openshift start master --public-
master=https://myapiserver.com:8443 --write-config=ldapconfig
```



Note

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

- 2. Edit the new *master-config.yaml* file's **identityProviders** stanza.
- 3. Copy the example LDAPPasswordIdentityProvider configuration and paste it to replace the existing stanza.
- 4. Make the following modifications to the **identityProviders** stanza:
 - a. Change the provider **name** ("my_ldap_provider") to something unique and relevant to your deployment. This name is prefixed to the returned user name to form an identity name.
 - b. If required, change mappingMethod to control how mappings are established between the provider's identities and user objects.
 - c. Change id to the attribute to use as the identity, which must be unique and immutable within the identity provider. This option can accept multiple attributes. If more than one is specified, they will be checked in order and the first non-empty attribute will be used. At least one attribute is required. If none of the listed attribute have a value, then authentication fails.
 - d. Change **email** to the attribute to use as the email address. This option can accept multiple attributes. If more than one is specified, they will be checked in order and the first non-empty attribute will be used.
 - e. Change **name** to the attribute to use as the display name. This option can accept multiple attributes. If more than one is specified, they will be checked in order and the first non-empty attribute will be used.
 - f. Optionally, change preferredUsername to the attribute to use as the preferred OpenShift Container Platform username when provisioning a user for this identity. If unspecified, the id attribute is used as the preferred username. This option can accept multiple attributes. If more than one is specified, they will be checked in order and the first non-empty attribute will be used.

The attribute you select as the **preferredUsername** should still be unique, even within the identity provider. The **preferredUsername** attribute is only used when provisioning the user for the initial login. Afterward, the existing OpenShift Container Platform user is looked up by their identity provider ID, in case the **preferredUsername** attribute changes.

Using **preferredUsername** is helpful when the immutable **id** attribute is not a human-recognizable value, and there is another attribute with a value that is more recognizable to the user. For example, if the **id** is something like "e43adf8cc243", you could set **preferredUsername** to **login**, which could have potentially muteable values, such as "bobsmith".

g. Change the **ca** to the certificate bundle to use in order to validate server certificates for the configured URL. If empty, system trusted roots are used. This setting only

applies if **insecure: false**. If the LDAP server requires a different certificate chain, this attribute should contain the filesystem path of that certificate or certificate bundle.

- h. If required, modify the **insecure** parameter. The default is **false**, and this must be **false** when using **ldaps:**// URLs. When **false**, **ldaps:**// URLs connect using TLS, and **ldap:**// URLs are upgraded to TLS. When **true**, no TLS connection is made to the server, however, setting this to **true** creates an invalid configuration for LDAP.
- Define an RFC 2255 URL that specifies the LDAP host and search parameters to use.
- 5. Save your changes and close the file.
- 6. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --master-config=
<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their LDAP credentials.

4.5.2. Creating Users with LDAP Authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as, in this case, LDAP. LDAP is the system of record, meaning that users are defined in LDAP, and any user with a valid LDAP ID for the configured authentication server can log in.

To add a user to OpenShift Container Platform, the user must exist in the LDAP system, and if required you must create a new LDAP account for the user.

4.5.3. Verifying Users

Once one or more users have logged in, you can run **oc get users** to view a list of users and verify that users were created successfully:

Example 4.2. Output of oc get users command

```
$ oc get users

NAME UID FULL NAME

IDENTITIES

bobsmith 166a2367-33fc-11e6-bb22-4ccc6a0ad630 Bob Smith

ldap_provider:uid=bsmith,ou=users,dc=example,dc=com 1
```

1

Identities in OpenShift Container Platform are comprised of the identity provider name prefixed to the LDAP distinguished name (DN).

From here, you might want to learn how to control user roles.

4.6. GITHUB AUTHENTICATION

GitHub uses OAuth, and you can integrate your OpenShift Container Platform cluster to use that OAuth authentication. OAuth basically facilitates a token exchange flow.

Configuring GitHub authentication allows users to log in to OpenShift Container Platform with their GitHub credentials. To prevent anyone with any GitHub user ID from logging in to your OpenShift Container Platform cluster, you can restrict access to only those in specific GitHub organizations.

4.6.1. Registering the Application on GitHub

- 1. On GitHub, click Settings → OAuth applications → Developer applications → Register an application to navigate to the page for a new OAuth application.
- 2. Type an application name. For example: My OpenShift Install
- 3. Type a homepage URL. For example: https://myapiserver.com:8443
- 4. Optionally, type an application description.
- 5. Type the authorization callback URL, where the end of the URL contains the identity provider **name** (defined in the **identityProviders** stanza of the *master configuration file*, which you configure in the next section of this topic):
 - <apiserver>/oauth2callback/<identityProviderName>

For example:

- https://myapiserver.com:8443/oauth2callback/github/
- 6. Click **Register application**. GitHub provides a Client ID and a Client Secret. Keep this window open so you can copy these values and paste them into the master configuration file.

4.6.2. Configuring Authentication on the Master

- 1. If you have:
 - Already completed the installation of Openshift, then copy the /etc/origin/master/master-config.yaml file into a new directory; for example:
 - \$ cd /etc/origin/master
 \$ mkdir githubconfig; cp master-config.yaml githubconfig
 - Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

\$ openshift start master --public-master=<apiserver> --writeconfig=<directory>

For example:

\$ openshift start master --publicmaster=https://myapiserver.com:8443 --writeconfig=githubconfig



Note

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.



Note

Using **openshift start master** on its own would auto-detect host names, but GitHub must be able to redirect to the exact host name that you specified when registering the application. For this reason, you cannot auto-detect the ID because it might redirect to the wrong address. Instead, you must specify the hostname that web browsers use to interact with your OpenShift Container Platform cluster.

- 2. Edit the new *master-config.yaml* file's **identityProviders** stanza.
- 3. Copy the example **GitHubIdentityProvider** configuration and paste it to replace the existing stanza.
- 4. Make the following modifications to the **identityProviders** stanza:
 - a. Change the provider **name** to match the callback URL you configured on GitHub.

For example, if you defined the callback URL as https://myapiserver.com:8443/oauth2callback/github/ then the name must be github.

- b. Change **clientID** to the Client ID from GitHub that you registered previously.
- c. Change **clientSecret** to the Client Secret from GitHub that you registered previously.
- d. Change **organizations** to include a list of one or more GitHub organizations to which a user must have membership in order to authenticate. If specified, only GitHub users that are members of at least one of the listed organizations will be allowed to log in. If this is not specified, then any person with a valid GitHub account can log in.
- 5. Save your changes and close the file.

6. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=
<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their GitHub credentials. On their first login, the user must click **authorize application** to permit GitHub to use their username, password, and organization membership with OpenShift Container Platform. The user is then redirected back to the web console.

4.6.3. Creating Users with GitHub Authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as, in this case, GitHub. GitHub is the system of record, meaning that users are defined by GitHub, and any user belonging to a specified organization can log in.

To add a user to OpenShift Container Platform, you must add that user to an approved organization on GitHub, and if required create a new GitHub account for the user.

4.6.4. Verifying Users

Once one or more users have logged in, you can run **oc get users** to view a list of users and verify that users were created successfully:

Example 4.3. Output of oc get users command

```
$ oc get users

NAME UID FULL NAME

IDENTITIES

bobsmith 433b5641-066f-11e6-a6d8-acfc32c1ca87 Bob Smith

github:873654 1
```



Identities in OpenShift Container Platform are comprised of the identity provider name and GitHub's internal numeric user ID. This way, if a user changes their GitHub username or e-mail they can still log in to OpenShift Container Platform instead of relying on the credentials attached to the GitHub account. This creates a stable login.

From here, you might want to learn how to control user roles.