

# **Supported configurations for Cloud Volumes ONTAP 9.9.1 in Azure**

**Cloud Volumes ONTAP** 

Ben Cammett July 19, 2021

# **Table of Contents**

Suppor	ed configurations for Cloud Volumes ONTAP 9.9.1 in Azure	1
Supp	orted configurations by license	1
Supr	orted disk sizes	3

# **Supported configurations for Cloud Volumes ONTAP 9.9.1 in Azure**

Several Cloud Volumes ONTAP configurations are supported in Azure.

## Supported configurations by license

Cloud Volumes ONTAP is available in Azure as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair is not supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

## Single node systems

You can choose from the following configurations when deploying Cloud Volumes ONTAP as a single-node system in Azure:

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Maximum system capacity (disks + object storage)	500 GB	2 TB <sup>1</sup>	10 TB	368 TB	368 TB per license	2 PB
Supported	• DS3_v2	• DS3_v2	• DS4_v2	• DS5_v2	• DS3_v2	• DS3_v2
virtual machine	• DS4_v2	• E4s_v3	• DS13_v2	• DS14_v2	• DS4_v2	• DS4_v2
types	• DS5_v2		• E8s_v3	• DS15_v2	• DS5_v2	• DS5_v2
	• DS13_v2			• E32s_v3 <sup>2</sup>	• DS13_v2	• DS13_v2
	• DS14_v2			• E48s_v3 <sup>2</sup>	• DS14_v2	• DS14_v2
	• DS15_v2			• E64is_v3 <sup>2</sup>	• DS15_v2	• DS15_v2
	• E4s_v3			• E80ids_v4	• E4s_v3	• E4s_v3
	• E8s_v3			3	• E8s_v3	• E8s_v3
	• E32s_v3 <sup>2</sup>				• E32s_v3 <sup>2</sup>	• E32s_v3 <sup>2</sup>
	• E48s_v3 <sup>2</sup>				• E48s_v3 <sup>2</sup>	• E48s_v3 <sup>2</sup>
	• E64is_v3 <sup>2</sup>				• E64is_v3 <sup>2</sup>	• E64is_v3 <sup>2</sup>
	• E80ids_v4				• E80ids_v4	• E80ids_v4
	• L8s_v2 <sup>4</sup>				• L8s_v2 <sup>4</sup>	• L8s_v2 <sup>4</sup>

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Supported disk types <sup>5</sup>	Standard HDD Disks	Managed Disks	, Standard SSD	Managed Disks	, and Premium	SSD Managed

#### Notes:

- 1. Data tiering to Azure Blob storage isn't supported with PAYGO Explore.
- 2. This VM type uses an Ultra SSD for VNVRAM, which provides better write performance.
- 3. This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
- 4. This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as Flash Cache. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements. Learn more.
- 5. Enhanced write performance is enabled when using SSDs, but not when using the DS3\_v2 virtual machine type.
- 6. For Azure region support, see Cloud Volumes Global Regions.
- 7. Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

### **HA** pairs

You can choose from the following configurations when deploying Cloud Volumes ONTAP as an HA pair in Azure.

	Freemium	PAYGO Standard	PAYGO Premium	Node-based license	Capacity-based license
Maximum system capacity (disks + object storage)	500 GB	10 TB	368 TB	368 TB per license	2 PB
Supported virtual machine types	<ul> <li>DS4_v2</li> <li>DS5_v2¹</li> <li>DS13_v2</li> <li>DS14_v2¹</li> <li>DS15_v2¹</li> <li>E8s_v3</li> <li>E48s_v3¹</li> <li>E80ids_v4²</li> </ul>	• DS4_v2 • DS13_v2	<ul> <li>DS5_v2<sup>1</sup></li> <li>DS14_v2<sup>1</sup></li> <li>DS15_v2<sup>1</sup></li> <li>E8s_v3</li> <li>E48s_v3<sup>1</sup></li> <li>E80ids_v4<sup>2</sup></li> </ul>	<ul> <li>DS4_v2</li> <li>DS5_v2¹</li> <li>DS13_v2</li> <li>DS14_v2¹</li> <li>DS15_v2¹</li> <li>E8s_v3</li> <li>E48s_v3¹</li> <li>E80ids_v4²</li> </ul>	<ul> <li>DS4_v2</li> <li>DS5_v2¹</li> <li>DS13_v2</li> <li>DS14_v2¹</li> <li>DS15_v2¹</li> <li>E8s_v3</li> <li>E48s_v3¹</li> <li>E80ids_v4²</li> </ul>

	Freemium	PAYGO Standard	PAYGO Premium	Node-based license	Capacity-based license
Supported disk types	Premium page blo	obs			

#### Notes:

- Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. High write speed is supported with all instance types when using a single node system. Learn more about choosing a write speed.
- 2. This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
- 3. PAYGO Explore isn't supported with HA pairs in Azure.
- 4. For Azure region support, see Cloud Volumes Global Regions.
- 5. Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

# Supported disk sizes

In Azure, an aggregate can contain up to 12 disks that are all the same type and size.

### Single node systems

Single node systems use Azure Managed Disks. The following disk sizes are supported:

Premium SSD	Standard SSD	Standard HDD
• 500 GB	• 100 GB	• 100 GB
• 1 TB	• 500 GB	• 500 GB
• 2 TB	• 1 TB	• 1 TB
• 4 TB	• 2 TB	• 2 TB
• 8 TB	• 4 TB	• 4 TB
• 16 TB	• 8 TB	• 8 TB
• 32 TB	• 16 TB	• 16 TB
	• 32 TB	• 32 TB

## **HA** pairs

HA pairs use Premium page blobs. The following disk sizes are supported:

- 500 GB
- 1 TB
- 2 TB
- 4 TB

#### **Copyright Information**

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.