# Armors Labs

MFIL Token

**Smart Contract Audit** 

- MFIL Token Audit Summary
- MFIL Token Audit
  - Document information
    - Audit results
    - Audited target file
  - Vulnerability analysis
    - Vulnerability distribution
    - Summary of audit results
    - Contract code
    - Analysis of audit results
      - Re-Entrancy
      - Arithmetic Over/Under Flows
      - Unexpected Blockchain Currency
      - Delegatecall
      - Default Visibilities
      - Entropy Illusion
      - External Contract Referencing
      - Unsolved TODO comments
      - Short Address/Parameter Attack
      - Unchecked CALL Return Values
      - Race Conditions / Front Running
      - Denial Of Service (DOS)
      - Block Timestamp Manipulation
      - Constructors with Care
      - Unintialised Storage Pointers
      - Floating Points and Numerical Precision
      - tx.origin Authentication

# **MFIL Token Audit Summary**

Project name: MFIL Token Contract

Project address: None

Code URL: https://github.com/fido-project/fido-contracts

Commit: 671a306af3cc5d44b33f4647ca8df7a70104ec77

hecoinfo: https://hecoinfo.com/address/0x5CDAFd00AfF95DA3304791A5C9aE00f84506a909#code

Project target: MFIL Token Contract Audit

Blockchain: Huobi ECO Chain (Heco)

Test result: PASSED

Audit Info

Audit NO: 0X202105010008

Audit Team: Armors Labs

Audit Proofreading: https://armors.io/#project-cases

# **MFIL Token Audit**

The FIDO team asked us to review and audit their MFIL Token contract. We looked at the code and now publish our results.

Here is our assessment and recommendations, in order of importance.

# **Document information**

Name	Auditor	Version	Date
MFIL Token Audit	Rock, Sophia, Rushairer, Rico, David, Alice	1.0.1	2021-05-01

# **Audit results**

Note that:

MFIL is a superset of ERC20 tokens. The accuracy of the token is 18 and a total cap of 2,000,000,000. Burnable can be burned, Mintable can be issued, Pausable can be suspended

MFIL token has four colors, which are ordinary user, owner, operator and minter (additional issuer, mining contract)

The owner can modify the address of the operator, the operator can suspend/resume the contract, add/remove minter, and mnter can issue additional tokens.



Note that as of the date of publishing, the above review reflects the current understanding of known security patterns as they relate to the MFIL Token contract. The above should not be construed as investment advice.

Based on the widely recognized security status of the current underlying blockchain and smart contract, this audit report is valid for 3 months from the date of output.

(Statement: Armors Labs reports only on facts that have occurred or existed before this report is issued and assumes corresponding responsibilities. Armors Labs is not able to determine the security of its smart contracts and is not responsible for any subsequent or existing facts after this report is issued. The security audit analysis and other content of this report are only based on the documents and information provided by the information provider to Armors Labs at the time of issuance of this report (" information provided " for short). Armors Labs postulates that the information provided is not missing, tampered, deleted or hidden. If the information provided is missing, tampered, deleted, hidden or reflected in a way that is not consistent with the actual situation, Armors Labs shall not be responsible for the losses and adverse effects caused.)

# Audited target file

file	md5
./ERC20/ERC20Pausable.sol	5ba41b496341f26393f62f30572c037a
./ERC20/ERC20Mintable.sol	eca19f6cccd0fe57e66a29e93f22a728
./ERC20/ERC20Burnable.sol	0dca068ad242853e73f0cf501f9e3cdd
./ERC20/ERC20.sol	ebf1cff6a039a54f1a0568b38bc0e0f9
./Pausable.sol	e70cfad9554608935e5da690a1e8c81a
./libraries/TransferHelper.sol	9bf500f7d995b8348c9b5dcb3aa24312
./libraries/SafeMath.sol	e03e12206057e809eb76c5f681170c32
./Context.sol	2adbd82f6d055a4751566d4671512b03
./Ownable.sol	3c73ff1bfb400374dd48f30345945264
./MFIL.sol	eb7df44eaeecc07d4828f02aa0ce25d4

# **Vulnerability analysis**

# **Vulnerability distribution**

vulnerability level	number
Critical severity	0
High severity	0
Medium severity	0
Low severity	0

# Summary of audit results

Vulnerability	status
Re-Entrancy	safe
Arithmetic Over/Under Flows	safe
Unexpected Blockchain Currency	safe
Delegatecall	safe
Default Visibilities	safe
Entropy Illusion	safe
External Contract Referencing	safe
Short Address/Parameter Attack	safe
Unchecked CALL Return Values	safe
Race Conditions / Front Running	safe
Denial Of Service (DOS)	safe
Block Timestamp Manipulation	safe
Constructors with Care	safe
Unintialised Storage Pointers	safe
Floating Points and Numerical Precision	safe
tx.origin Authentication	safe

# **Contract code**

```
abstract contract Context {
    function _msgSender() internal view virtual returns (address payable) {
        return msg.sender;
    }

    function _msgData() internal view virtual returns (bytes memory) {
        this; // silence state mutability warning without generating bytecode - see https://github.co
        return msg.data;
    }
}
interface IERC20 {
    /**
    * @dev Returns the amount of tokens in existence.
    */
    function totalSupply() external view returns (uint256);
    /**
    * @dev Returns the amount of tokens owned by `account`.
    */
    function balanceOf(address account) external view returns (uint256);
    /**
    * @dev Moves `amount` tokens from the caller's account to `recipient`.
    *
    * Returns a boolean value indicating whether the operation succeeded.
```

```
* Emits a {Transfer} event.
    function transfer(address recipient, uint256 amount) external returns (bool);
     * @dev Returns the remaining number of tokens that `spender` will be
     * allowed to spend on behalf of `owner` through {transferFrom}. This is
     * zero by default.
     * This value changes when {approve} or {transferFrom} are called.
    function allowance(address owner, address spender) external view returns (uint256);
     * \ensuremath{\text{\it Qdev}} Sets 'amount' as the allowance of 'spender' over the caller's tokens.
     * Returns a boolean value indicating whether the operation succeeded.
     * IMPORTANT: Beware that changing an allowance with this method brings the risk
     * that someone may use both the old and the new allowance by unfortunate
     * transaction ordering. One possible solution to mitigate this race
     * condition is to first reduce the spender's allowance to 0 and set the
     * desired value afterwards:
     * https://github.com/ethereum/EIPs/issues/20#issuecomment-263524729
     * Emits an {Approval} event.
    function approve(address spender, uint256 amount) external returns (bool);
     * @dev Moves `amount` tokens from `sender` to `recipient` using the
     * allowance mechanism. `amount` is then deducted from the caller's
     * Returns a boolean value indicating whether the operation succeeded.
     * Emits a {Transfer} event
    function transferFrom(address sender, address recipient, uint256 amount) external returns (bool);
     * @dev Emitted when value tokens are moved from one account (`from`) to
     * another (`to`).
     * Note that `value` may be zero.
    event Transfer(address indexed from, address indexed to, uint256 value);
     * @dev Emitted when the allowance of a `spender` for an `owner` is set by
     * a call to {approve}. `value` is the new allowance.
    event Approval(address indexed owner, address indexed spender, uint256 value);
}
library SafeMath {
     * \ensuremath{\text{\it @dev}} Returns the addition of two unsigned integers, with an overflow flag.
     * Available since v3.4.
    function tryAdd(uint256 a, uint256 b) internal pure returns (bool, uint256) {
        uint256 c = a + b;
        if (c < a) return (false, 0);
        return (true, c);
```

```
}
 * @dev Returns the substraction of two unsigned integers, with an overflow flag.
   _Available since v3.4._
function trySub(uint256 a, uint256 b) internal pure returns (bool, uint256) {
    if (b > a) return (false, 0);
    return (true, a - b);
}
 * @dev Returns the multiplication of two unsigned integers, with an overflow flag.
 * _Available since v3.4._
function tryMul(uint256 a, uint256 b) internal pure returns (bool, uint256) {
   // Gas optimization: this is cheaper than requiring 'a' not being zero, but the
    // benefit is lost if 'b' is also tested.
    // See: https://github.com/OpenZeppelin/openzeppelin-contracts/pull/522
    if (a == 0) return (true, 0);
    uint256 c = a * b;
    if (c / a != b) return (false, 0);
    return (true, c);
}
                                                              division by zero flag.
 * @dev Returns the division of two unsigned integers, with
 * _Available since v3.4._
function tryDiv(uint256 a, uint256 b) internal pure returns (bool, uint256) {
   if (b == 0) return (false, 0);
    return (true, a / b);
}
                                 dividing two unsigned integers, with a division by zero flag.
 * @dev Returns the remainder of
  Available since v3.4.
function tryMod(uint256 a, uint256 b) internal pure returns (bool, uint256) {
    if (b == 0) return (false, 0);
    return (true, a % b);
}
 ^{*} @dev Returns the addition of two unsigned integers, reverting on
 * overflow.
 * Counterpart to Solidity's `+` operator.
 * Requirements:
 * - Addition cannot overflow.
function add(uint256 a, uint256 b) internal pure returns (uint256) {
    uint256 c = a + b;
    require(c >= a, "SafeMath: addition overflow");
    return c;
}
* @dev Returns the subtraction of two unsigned integers, reverting on
 * overflow (when the result is negative).
```

```
* Counterpart to Solidity's `-` operator.
 * Requirements:
 * - Subtraction cannot overflow.
function sub(uint256 a, uint256 b) internal pure returns (uint256) {
    require(b <= a, "SafeMath: subtraction overflow");</pre>
    return a - b;
}
 * @dev Returns the multiplication of two unsigned integers, reverting on
 * Counterpart to Solidity's `*` operator.
 * Requirements:
 * - Multiplication cannot overflow.
function mul(uint256 a, uint256 b) internal pure returns (uint256) {
    if (a == 0) return 0;
    uint256 c = a * b;
    require(c / a == b, "SafeMath: multiplication overflow");
    return c:
}
 * @dev Returns the integer division of two unsigned integers, reverting on
 * division by zero. The result is rounded towards zero.
 * Counterpart to Solidity's `/` operator. Note: this function uses a
 * `revert` opcode (which leaves remaining gas untouched) while Solidity
 * uses an invalid opcode to revert (consuming all remaining gas).
 * Requirements:
 * - The divisor cannot be zero
function div(uint256 a, uint256 b) internal pure returns (uint256) {
    require(b > 0, "SafeMath: division by zero");
    return a / b;
}
 * @dev Returns the remainder of dividing two unsigned integers. (unsigned integer modulo),
 ^{\star} reverting when dividing by zero.
 * Counterpart to Solidity's `%` operator. This function uses a `revert`
 * opcode (which leaves remaining gas untouched) while Solidity uses an
 * invalid opcode to revert (consuming all remaining gas).
 * Requirements:
 * - The divisor cannot be zero.
function mod(uint256 a, uint256 b) internal pure returns (uint256) {
    require(b > 0, "SafeMath: modulo by zero");
    return a % b;
}
* @dev Returns the subtraction of two unsigned integers, reverting with custom message on
 * overflow (when the result is negative).
```

```
* CAUTION: This function is deprecated because it requires allocating memory for the error
     * message unnecessarily. For custom revert reasons use {trySub}.
     * Counterpart to Solidity's `-` operator.
     * Requirements:
     * - Subtraction cannot overflow.
    function sub(uint256 a, uint256 b, string memory errorMessage) internal pure returns (uint256) {
        require(b <= a, errorMessage);</pre>
        return a - b;
    }
     * @dev Returns the integer division of two unsigned integers, reverting with custom message on
     * division by zero. The result is rounded towards zero.
     * CAUTION: This function is deprecated because it requires allocating memory for the error
     * message unnecessarily. For custom revert reasons use {tryDiv}.
     * Counterpart to Solidity's `/` operator. Note: this function uses a
     * `revert` opcode (which leaves remaining gas untouched) while Solidity
     * uses an invalid opcode to revert (consuming all remaining gas).
     * Requirements:
     * - The divisor cannot be zero.
    function div(uint256 a, uint256 b, string memory errorMessage) internal pure returns (uint256) {
        require(b > 0, errorMessage);
        return a / b;
   }
     * @dev Returns the remainder of dividing two unsigned integers. (unsigned integer modulo),
     * reverting with custom message when dividing by zero.
     * CAUTION: This function is deprecated because it requires allocating memory for the error
     * message unnecessarily. For custom revert reasons use {tryMod}.
     * Counterpart to Solidity's `%` operator. This function uses a `revert`
     * opcode (which leaves remaining gas untouched) while Solidity uses an
     * invalid opcode to revert (consuming all remaining gas).
     * Requirements:
     * - The divisor cannot be zero.
    function mod(uint256 a, uint256 b, string memory errorMessage) internal pure returns (uint256) {
        require(b > 0, errorMessage);
        return a % b;
    }
}
contract ERC20 is Context, IERC20 {
   using SafeMath for uint256;
    mapping (address => uint256) private _balances;
    mapping (address => mapping (address => uint256)) private _allowances;
    uint256 private _totalSupply;
    string private _name;
```

```
string private _symbol;
uint8 private _decimals;
 * \ensuremath{\text{\it Qdev}} Sets the values for {name} and {symbol}, initializes {decimals} with
 * a default value of 18.
 * To select a different value for {decimals}, use {_setupDecimals}.
 * All three of these values are immutable: they can only be set once during
 * construction.
constructor (string memory name_, string memory symbol_) {
   _name = name_;
   _symbol = symbol_;
    _{decimals} = 18;
}
/**
 * @dev Returns the name of the token.
function name() public view virtual returns (string memory) {
   return _name;
}
 * @dev Returns the symbol of the token, usually a shorter version of the
 * name.
function symbol() public view virtual returns (string memory) {
   return _symbol;
 * @dev Returns the number of decimals used to get its user representation.
 * For example, if `decimals` equals `2`, a balance of `505` tokens should
 * be displayed to a user as ^{\circ}5,05^{\circ} ( ^{\circ}505 / 10 ** 2^{\circ} ).
 * Tokens usually opt for a value of 18, imitating the relationship between
 * Ether and Wei. This is the value {ERC20} uses, unless {_setupDecimals} is
 * called.
 * NOTE: This information is only used for _display_ purposes: it in
 * no way affects any of the arithmetic of the contract, including
 * {IERC20-balanceOf} and {IERC20-transfer}.
function decimals() public view virtual returns (uint8) {
    return _decimals;
}
/**
 * @dev See {IERC20-totalSupply}.
function totalSupply() public view virtual override returns (uint256) {
   return _totalSupply;
}
 * @dev See {IERC20-balance0f}.
function balanceOf(address account) public view virtual override returns (uint256) {
   return _balances[account];
}
* @dev See {IERC20-transfer}.
```

```
* Requirements:
 * - `recipient` cannot be the zero address.
 * - the caller must have a balance of at least `amount`.
function transfer(address recipient, uint256 amount) public virtual override returns (bool) {
    _transfer(_msgSender(), recipient, amount);
    return true;
}
/**
 * @dev See {IERC20-allowance}.
function allowance(address owner, address spender) public view virtual override returns (uint256)
   return _allowances[owner][spender];
}
 * @dev See {IERC20-approve}.
 * Requirements:
 * - `spender` cannot be the zero address.
function approve(address spender, uint256 amount) public virtual override returns (bool) {
    _approve(_msgSender(), spender, amount);
    return true;
}
 * @dev See {IERC20-transferFrom}.
 * Emits an {Approval} event indicating the updated allowance. This is not
 * required by the EIP. See the note at the beginning of {ERC20}.
 * Requirements:
 * - `sender` and `recipient` cannot be the zero address.
 * - `sender` must have a balance of at least `amount`.
 * - the caller must have allowance for ``sender``'s tokens of at least
 * `amount`.
function transferFrom(address sender, address recipient, uint256 amount) public virtual override
    _transfer(sender, recipient, amount);
    _approve(sender, _msgSender(), _allowances[sender][_msgSender()].sub(amount, "ERC20: transfer
    return true;
}
 * @dev Atomically increases the allowance granted to `spender` by the caller.
 * This is an alternative to {approve} that can be used as a mitigation for
 * problems described in {IERC20-approve}.
 * Emits an {Approval} event indicating the updated allowance.
 * Requirements:
 * - `spender` cannot be the zero address.
function increaseAllowance(address spender, uint256 addedValue) public virtual returns (bool) {
    _approve(_msgSender(), spender, _allowances[_msgSender()][spender].add(addedValue));
    return true;
}
```

```
* @dev Atomically decreases the allowance granted to `spender` by the caller.
 * This is an alternative to {approve} that can be used as a mitigation for
 * problems described in {IERC20-approve}.
 * Emits an {Approval} event indicating the updated allowance.
 * Requirements:
 * - `spender` cannot be the zero address.
 * - `spender` must have allowance for the caller of at least
 * `subtractedValue`.
function decreaseAllowance(address spender, uint256 subtractedValue) public virtual returns (bool
    _approve(_msgSender(), spender, _allowances[_msgSender()][spender].sub(subtractedValue, "ERC2
    return true:
}
 * @dev Moves tokens `amount` from `sender` to `recipient`.
 * This is internal function is equivalent to {transfer}, and can be used to
 * e.g. implement automatic token fees, slashing mechanisms, etc.
 * Emits a {Transfer} event.
 * Requirements:
 * - `sender` cannot be the zero address.
 * - `recipient` cannot be the zero address.
 * - `sender` must have a balance of at least `amount`
 */
function _transfer(address sender, address recipient, uint256 amount) internal virtual {
    require(sender != address(0), "ERC20: transfer from the zero address");
    require(recipient != address(0), "ERC20: transfer to the zero address");
    _beforeTokenTransfer(sender, recipient, amount);
    _balances[sender] = _balances[sender].sub(amount, "ERC20: transfer amount exceeds balance");
    _balances[recipient] = _balances[recipient].add(amount);
emit Transfer(sender, recipient, amount);
}
/** @dev Creates `amount` tokens and assigns them to `account`, increasing
 * the total supply.
 * Emits a {Transfer} event with `from` set to the zero address.
 * Requirements:
 * - `to` cannot be the zero address.
function _mint(address account, uint256 amount) internal virtual {
    require(account != address(0), "ERC20: mint to the zero address");
    _beforeTokenTransfer(address(0), account, amount);
    _totalSupply = _totalSupply.add(amount);
    _balances[account] = _balances[account].add(amount);
    emit Transfer(address(0), account, amount);
}
 * @dev Destroys `amount` tokens from `account`, reducing the
 * total supply.
```

```
* Emits a {Transfer} event with `to` set to the zero address.
     * Requirements:
     * - `account` cannot be the zero address.
     * - `account` must have at least `amount` tokens.
   function _burn(address account, uint256 amount) internal virtual {
       require(account != address(0), "ERC20: burn from the zero address");
       _beforeTokenTransfer(account, address(0), amount);
       _balances[account] = _balances[account].sub(amount, "ERC20: burn amount exceeds balance");
       _totalSupply = _totalSupply.sub(amount);
       emit Transfer(account, address(0), amount);
   }
     * @dev Sets `amount` as the allowance of `spender` over the `owner` s tokens.
     * This internal function is equivalent to `approve`, and can be used to
     * e.g. set automatic allowances for certain subsystems, etc
     * Emits an {Approval} event.
     * Requirements:
     * - `owner` cannot be the zero address.
     * - `spender` cannot be the zero address.
   function _approve(address owner, address spender, uint256 amount) internal virtual {
       require(owner != address(0), "ERC20: approve from the zero address");
       require(spender != address(0), "ERC20: approve to the zero address");
       _allowances[owner][spender] = amount;
       emit Approval(owner, spender, amount);
   }
     * @dev Sets {decimals} to a value other than the default one of 18.
     * WARNING: This function should only be called from the constructor. Most
     * applications that interact with token contracts will not expect
     * {decimals} to ever change, and may work incorrectly if it does.
   function _setupDecimals(uint8 decimals_) internal virtual {
       _decimals = decimals_;
   }
    * @dev Hook that is called before any transfer of tokens. This includes
    * minting and burning.
    * Calling conditions:
     * - when `from` and `to` are both non-zero, `amount` of ``from``'s tokens
     * will be to transferred to `to`.
     * - when `from` is zero, `amount` tokens will be minted for `to`.
     * - when `to` is zero, `amount` of ``from``'s tokens will be burned.
        `from` and `to` are never both zero.
     * To learn more about hooks, head to xref:ROOT:extending-contracts.adoc#using-hooks[Using Hooks]
   function _beforeTokenTransfer(address from, address to, uint256 amount) internal virtual { }
}
```

```
abstract contract Pausable is Context {
    * @dev Emitted when the pause is triggered by `account`.
   event Paused(address account);
    * @dev Emitted when the pause is lifted by `account`.
   event Unpaused(address account);
   bool private _paused;
    * @dev Initializes the contract in unpaused state.
   constructor () {
      _paused = false;
   }
    * @dev Returns true if the contract is paused, and false otherwise.
   function paused() public view virtual returns (bool) {
       return _paused;
   }
     * @dev Modifier to make a function callable only when the contract is not paused.
    * Requirements:
     * - The contract must not be paused.
   modifier whenNotPaused() {
       require(!paused(), "Pausable: paused");
   }
    * Odev Modifier to make a function callable only when the contract is paused.
    * Requirements:
     * - The contract must be paused.
   modifier whenPaused() {
       require(paused(), "Pausable: not paused");
   }
    * @dev Triggers stopped state.
    * Requirements:
     * - The contract must not be paused.
   function _pause() internal virtual whenNotPaused {
       _paused = true;
       emit Paused(_msgSender());
   }
    * @dev Returns to normal state.
```

```
* Requirements:
     * - The contract must be paused.
    function _unpause() internal virtual whenPaused {
        _paused = false;
        emit Unpaused(_msgSender());
   }
}
abstract contract ERC20Pausable is ERC20, Pausable {
    function _beforeTokenTransfer(address from, address to, uint256 amount) internal virtual override
        super._beforeTokenTransfer(from, to, amount);
        require(!paused(), "ERC20Pausable: token transfer while paused");
   }
}
abstract contract ERC20Burnable is Context, ERC20Pausable {
   using SafeMath for uint256;
    * @dev Destroys `amount` tokens from the caller.
     * See {ERC20-_burn}.
    function burn(uint256 amount) public virtual {
        _burn(_msgSender(), amount);
    }
                                                   , deducting from the caller's
     * @dev Destroys `amount` tokens from `account`
     * See {ERC20-_burn} and {ERC20-allowance
     * Requirements:
     * - the caller must have allowance
                                              `accounts``'s tokens of at least
     * `amount`.
    function burnFrom(address account, uint256 amount) public virtual {
        uint256 decreasedAllowance = allowance(account, _msgSender()).sub(amount, "ERC20: burn amount
        _approve(account, _msgSender(), decreasedAllowance);
        _burn(account, amount);
   }
}
abstract contract ERC20Mintable is Context, ERC20Pausable {
   using SafeMath for uint256;
    mapping(address => bool) public isMinter;
    event AddMinter(address indexed minter);
    event RemoveMinter(address indexed minter);
    event Mint(
        address indexed minter,
        address indexed recipient,
        uint256 amount
    );
    modifier onlyMinter() {
        require(isMinter[_msgSender()], "ERC20: sender is not minter");
```

```
}
    function _addMinter(address minter) internal {
        require(!isMinter[minter], "ERC20: already a minter");
        isMinter[minter] = true;
        emit AddMinter(minter);
    }
    function _removeMinter(address minter) internal {
        require(isMinter[minter], "ERC20: not a minter");
        isMinter[minter] = false;
        emit RemoveMinter(minter);
    function mint(address recipient, uint256 amount) external onlyMinter {
        _mint(recipient, amount);
        emit Mint(_msgSender(), recipient, amount);
   }
}
abstract contract Ownable is Context {
    address private _owner;
    event OwnershipTransferred(address indexed previousOwner, address indexed newOwner);
     * @dev Initializes the contract setting the deployer as the initial
   constructor () {
        address msgSender = _msgSender();
        owner = msqSender;
        emit OwnershipTransferred(address(0), msgSender);
   }
    function _initOwner(address owner_) internal {
        require(owner_ != address(0), "Ownable: owner cannot be init to zero address");
        _owner = owner_;
        emit OwnershipTransferred(address(0), _owner);
   }
     * @dev Returns the address of the current owner.
    function owner() public view virtual returns (address) {
        return _owner;
    }
     * @dev Throws if called by any account other than the owner.
    modifier onlyOwner() {
        require(owner() == _msgSender(), "Ownable: caller is not the owner");
   }
     ^{*} @dev Leaves the contract without owner. It will not be possible to call
     * `onlyOwner` functions anymore. Can only be called by the current owner.
     * NOTE: Renouncing ownership will leave the contract without an owner,
     * thereby removing any functionality that is only available to the owner.
    function renounceOwnership() public virtual onlyOwner {
        emit OwnershipTransferred(_owner, address(0));
        _{owner} = address(0);
```

```
* @dev Transfers ownership of the contract to a new account (`newOwner`).
     * Can only be called by the current owner.
    function transferOwnership(address newOwner) public virtual onlyOwner {
        require(newOwner != address(0), "Ownable: new owner is the zero address");
        emit OwnershipTransferred(_owner, newOwner);
        _owner = newOwner;
   }
}
contract MFIL is ERC20Mintable, ERC20Burnable, Ownable {
    using SafeMath for uint256;
    address public operator;
    uint256 private _cap = 20000000000 * 10**18;
    event OperatorshipTransferred(
        address indexed previousOperator,
        address indexed newOperator
    );
    constructor(address _operator)
        ERC20("Mirror FileCoin", "MFIL")
        Pausable()
        Ownable()
    {
        operator = _operator;
        emit OperatorshipTransferred(address(0), operator);
        _setupDecimals(18);
   }
    modifier onlyOperator() {
        require(
            _msgSender() == operator,
            "Operable: caller is not the operator
        );
   }
    function transferOperatorship(address newOperator) external onlyOwner {
        require(
            newOperator != address(0),
            "Operable: new operator is the zero address"
        emit OperatorshipTransferred(operator, newOperator);
        operator = newOperator;
   }
    function pause() external onlyOperator {
        _pause();
    }
    function unPause() external onlyOperator {
        _unpause();
   }
    function addMinter(address minter) external onlyOperator {
        _addMinter(minter);
   }
    function removeMinter(address minter) external onlyOperator {
        _removeMinter(minter);
    }
```

```
* @dev Returns the cap on the token's total supply.
    function cap() public view virtual returns (uint256) {
        return _cap;
     * @dev See {ERC20-_beforeTokenTransfer}.
     * Requirements:
     * - minted tokens must not cause the total supply to go over the cap.
    function _beforeTokenTransfer(
        address from,
        address to,
        uint256 amount
    ) internal virtual override {
        super._beforeTokenTransfer(from, to, amount);
        if (from == address(0)) {
            // When minting tokens
            require(totalSupply().add(amount) <= cap(), "ERC20: cap exceeded");</pre>
    }
}
```

# **Analysis of audit results**

# **Re-Entrancy**

#### • Description:

One of the features of smart contracts is the ability to call and utilise code of other external contracts. Contracts also typically handle Blockchain Currency, and as such often send Blockchain Currency to various external user addresses. The operation of calling external contracts, or sending Blockchain Currency to an address, requires the contract to submit an external call. These external calls can be hijacked by attackers whereby they force the contract to execute further code (i.e. through a fallback function), including calls back into itself. Thus the code execution "re-enters" the contract. Attacks of this kind were used in the infamous DAO hack.

• Detection results:

```
PASSED!
```

· Security suggestion:

no.

# **Arithmetic Over/Under Flows**

#### • Description:

The Virtual Machine (EVM) specifies fixed-size data types for integers. This means that an integer variable, only has a certain range of numbers it can represent. A uint8 for example, can only store numbers in the range [0,255]. Trying to store 256 into a uint8 will result in 0. If care is not taken, variables in Solidity can be exploited if user input is unchecked and calculations are performed which result in numbers that lie outside the range of the data type that stores them.

· Detection results:

PASSED!

· Security suggestion:

no.

# **Unexpected Blockchain Currency**

#### • Description:

Typically when Blockchain Currency is sent to a contract, it must execute either the fallback function, or another function described in the contract. There are two exceptions to this, where Blockchain Currency can exist in a contract without having executed any code. Contracts which rely on code execution for every Blockchain Currency sent to the contract can be vulnerable to attacks where Blockchain Currency is forcibly sent to a contract.

· Detection results:

PASSED!

• Security suggestion: no.

## Delegatecall

# • Description:

The CALL and DELEGATECALL opcodes are useful in allowing developers to modularise their code. Standard external message calls to contracts are handled by the CALL opcode whereby code is run in the context of the external contract/function. The DELEGATECALL opcode is identical to the standard message call, except that the code executed at the targeted address is run in the context of the calling contract along with the fact that msg.sender and msg.value remain unchanged. This feature enables the implementation of libraries whereby developers can create reusable code for future contracts.

• Detection results:

PASSED!

• Security suggestion: no.

#### **Default Visibilities**

#### • Description:

Functions in Solidity have visibility specifiers which dictate how functions are allowed to be called. The visibility determines whBlockchain Currency a function can be called externally by users, by other derived contracts, only internally or only externally. There are four visibility specifiers, which are described in detail in the Solidity Docs. Functions default to public allowing users to call them externally. Incorrect use of visibility specifiers can lead to some devestating vulernabilities in smart contracts as will be discussed in this section.

· Detection results:

PASSED!

· Security suggestion:

no.

# **Entropy Illusion**

#### • Description:

All transactions on the blockchain are deterministic state transition operations. Meaning that every transaction modifies the global state of the ecosystem and it does so in a calculable way with no uncertainty. This ultimately means that inside the blockchain ecosystem there is no source of entropy or randomness. There is no rand() function in Solidity. Achieving decentralised entropy (randomness) is a well established problem and many ideas have been proposed to address this (see for example, RandDAO or using a chain of Hashes as described by Vitalik in this post).

· Detection results:

PASSED!

• Security suggestion:

no.

# **External Contract Referencing**

#### • Description:

One of the benefits of the global computer is the ability to re-use code and interact with contracts already deployed on the network. As a result, a large number of contracts reference external contracts and in general operation use external message calls to interact with these contracts. These external message calls can mask malicious actors intentions in some non-obvious ways, which we will discuss.

· Detection results:

PASSED!

• Security suggestion:

no.

#### **Unsolved TODO comments**

· Description:

Check for Unsolved TODO comments

• Detection results:

PASSED!

· Security suggestion:

nο.

## **Short Address/Parameter Attack**

#### · Description:

This attack is not specifically performed on Solidity contracts themselves but on third party applications that may interact with them. I add this attack for completeness and to be aware of how parameters can be manipulated in contracts.

Detection results:

PASSED!

• Security suggestion:

no.

### **Unchecked CALL Return Values**

#### • Description:

There a number of ways of performing external calls in solidity. Sending Blockchain Currency to external accounts is commonly performed via the transfer() method. However, the send() function can also be used and, for more versatile external calls, the CALL opcode can be directly employed in solidity. The call() and send() functions return a boolean indicating if the call succeeded or failed. Thus these functions have a simple caveat, in that the transaction that executes these functions will not revert if the external call (intialised by call() or send()) fails, rather the call() or send() will simply return false. A common pitfall arises when the return value is not checked, rather the developer expects a revert to occur.

· Detection results:

PASSED!

· Security suggestion:

no.

## Race Conditions / Front Running

#### • Description:

The combination of external calls to other contracts and the multi-user nature of the underlying blockchain gives rise to a variety of potential Solidity pitfalls whereby users race code execution to obtain unexpected states. Re-Entrancy is one example of such a race condition. In this section we will talk more generally about different kinds of race conditions that can occur on the blockchain. There is a variety of good posts on this subject, a few are: Wiki - Safety, DASP - Front-Running and the Consensus - Smart Contract Best Practices.

· Detection results:

PASSED!

· Security suggestion:

no.

# **Denial Of Service (DOS)**

#### • Description:

This category is very broad, but fundamentally consists of attacks where users can leave the contract inoperable for a small period of time, or in some cases, permanently. This can trap Blockchain Currency in these contracts forever, as was the case with the Second Parity MultiSig hack

• Detection results:

PASSED!

• Security suggestion:

no.

### **Block Timestamp Manipulation**

#### • Description:

Block timestamps have historically been used for a variety of applications, such as entropy for random numbers (see the Entropy Illusion section for further details), locking funds for periods of time and various state-changing conditional statements that are time-dependent. Miner's have the ability to adjust timestamps slightly which can prove to be quite dangerous if block timestamps are used incorrectly in smart contracts.

• Detection results:

PASSED!

· Security suggestion:

no.

#### **Constructors with Care**

#### • Description:

Constructors are special functions which often perform critical, privileged tasks when initialising contracts. Before solidity v0.4.22 constructors were defined as functions that had the same name as the contract that contained them. Thus, when a contract name gets changed in development, if the constructor name isn't changed, it becomes a normal, callable function. As you can imagine, this can (and has) lead to some interesting contract hacks.

• Detection results:

PASSED!

· Security suggestion:

no.

## **Unintialised Storage Pointers**

#### • Description:

The EVM stores data either as storage or as memory. Understanding exactly how this is done and the default types for local variables of functions is highly recommended when developing contracts. This is because it is possible to produce vulnerable contracts by inappropriately intialising variables.

· Detection results:

PASSED!

• Security suggestion:

no.

## **Floating Points and Numerical Precision**

#### • Description:

As of this writing (Solidity v0.4.24), fixed point or floating point numbers are not supported. This means that floating point representations must be made with the integer types in Solidity. This can lead to errors/vulnerabilities if not implemented correctly.

• Detection results:

PASSED!

• Security suggestion:

nο

# tx.origin Authentication

## • Description:


Solidity has a global variable, tx.origin which traverses the entire call stack and returns the address of the account that originally sent the call (or transaction). Using this variable for authentication in smart contracts leaves the contract vulnerable to a phishing-like attack.

• Detection results:

PASSED!

• Security suggestion:

no.





contact@armors.io

