

We use optional cookies to improve your experience on our websites, such as through social media connections, and to display personalized advertising based on your online activity. If you reject optional cookies, only cookies necessary to provide you the services will be used. You may change your selection by clicking "Manage Cookies" at the bottom of the page. Privacy Statement Third-Party Cookies

Accept

Reject

Manage cookies

Microsoft Ignite

Nov 19-22, 2024

Register now >



Learn

Discover V Product documentation V Development languages V

Sign in


Feedback

PowerShell

Overview DSC PowerShellGet Utility modules Module Browser API Browser Resources V

Download PowerShell

Version



Remove-PSDrive

Remove-Service

Rename-Computer

Rename-Item

Rename-ItemProperty

Resolve-Path

Restart-Computer

Restart-Service

Resume-Service Set-Clipboard

Set-Content

Set-Item

Set-ItemProperty

Set-Location

Set-Service

Set-TimeZone

Split-Path

Start-Process

Start-Service

Stop-Computer

Stop-Process

Stop-Service

Suspend-Service

Test-Connection

Test-Path

Wait-Process

- > Microsoft.PowerShell.Security
- > Microsoft.PowerShell.Utility
- > Microsoft.WSMan.Management
- > PSDiagnostics
- > PSReadLine
- > ThreadJob

Learn / PowerShell / Microsoft.PowerShell.Management /

Set-Service

Reference

Module: Microsoft.PowerShell.Management

In this article

Syntax

Description

Examples

Parameters

Show 4 more

Starts, stops, and suspends a service, and changes its properties.

Syntax

PowerShell Copy Set-Service [-Name] <String> [-DisplayName <String>] [-Credential <PSCredential>] [-Description <String>] [-StartupType <ServiceStartupType>] [-Status <String>] [-SecurityDescriptorSddl <String>] [-Force] [-PassThru] [-WhatIf] [-Confirm] [<CommonParameters>]

PowerShell Copy Set-Service [-InputObject] <ServiceController> [-DisplayName <String>] [-Credential <PSCredential>] [-Description <String>] [-StartupType <ServiceStartupType>] [-SecurityDescriptorSddl <String>] [-Status <String>] [-Force] [-PassThru] [-WhatIf]

Download PDF

```
[-Confirm]
[<CommonParameters>]
```

Description

This cmdlet is only available on the Windows platform.

The Set-Service cmdlet changes the properties of a service such as the **Status**, **Description**, **DisplayName**, and **StartupType**. Set-Service can start, stop, suspend, or pause a service. To identify a service, enter its service name or submit a service object. Or, send a service name or service object down the pipeline to Set-Service.

Examples

Example 1: Change a display name

In this example, a service's display name is changed. To view the original display name, use Get-Service.

```
PowerShell

Set-Service -Name LanmanWorkstation -DisplayName "LanMan Workstation"
```

Set-Service uses the **Name** parameter to specify the service's name, **LanmanWorkstation**. The **DisplayName** parameter specifies the new display name, **LanMan Workstation**.

Example 2: Change the startup type of services

This example shows how to change a service's startup type.

```
PowerShell

Set-Service -Name BITS -StartupType Automatic
Get-Service BITS | Select-Object -Property Name, StartType, Status

Name StartType Status
----
BITS Automatic Running
```

Set-Service uses the **Name** parameter to specify the service's name, **BITS**. The **StartupType** parameter sets the service to **Automatic**.

Get-Service uses the Name parameter to specify the BITS service and sends the object down the pipeline. Select-Object uses the **Property** parameter to display the **BITS** service's status.

Example 3: Change the description of a service

This example changes the BITS service's description and displays the result.

The Get-CimInstance cmdlet is used because it returns a Win32_Service object that includes the service's Description.

```
PowerShell

Get-CimInstance Win32_Service -Filter 'Name = "BITS"' | Format-List Name, Desc

Name : BITS

Description : Transfers files in the background using idle network bandwidth. If disabled, then any applications that depend on BITS, such as Windo
```

```
Explorer, will be unable to automatically download programs and of Set-Service -Name BITS -Description "Transfers files in the background using idl Get-CimInstance Win32_Service -Filter 'Name = "BITS"' | Format-List Name, Description : BITS

Description : Transfers files in the background using idle network bandwidth.
```

Get-CimInstance sends the object down the pipeline to Format-List and displays the service's name and description. For comparison purposes, the command is run before and after the description is updated.

Set-Service uses the **Name** parameter to specify the **BITS** service. The **Description** parameter specifies the updated text for the services' description.

Example 4: Start a service

In this example, a service is started.

Set-Service uses the **Name** parameter to specify the service, **WinRM**. The **Status** parameter uses the value **Running** to start the service. The **PassThru** parameter outputs a **ServiceController** object that displays the results.

Example 5: Suspend a service

This example uses the pipeline to pause to service.

```
PowerShell

Get-Service -Name Schedule | Set-Service -Status Paused
```

Get-Service uses the **Name** parameter to specify the **Schedule** service, and sends the object down the pipeline. Set-Service uses the **Status** parameter to set the service to **Paused**.

Example 6: Stop a service

This example uses a variable to stop a service.

```
PowerShell

$S = Get-Service -Name Schedule
Set-Service -InputObject $S -Status Stopped
```

Get-Service uses the **Name** parameter to specify the service, **Schedule**. The object is stored in the variable, \$5. Set-Service uses the **InputObject** parameter and specifies the object stored \$5. The **Status** parameter sets the service to **Stopped**.

Example 7: Stop a service on a remote system

This example stops a service on a remote computer. For more information, see Invoke-Command.

```
$Cred = Get-Credential
$S = Get-Service -Name Schedule
Invoke-Command -ComputerName server01.contoso.com -Credential $Cred -ScriptBlock
   Set-Service -InputObject $S -Status Stopped
}
```

Get-Credential prompts for a username and password, and stores the credentials in the \$Cred variable. Get-Service uses the Name parameter to specify the Schedule service. The object is stored in the variable, \$5.

Invoke-Command uses the **ComputerName** parameter to specify a remote computer. The **Credential** parameter uses the \$cred variable to sign on to the computer. The **ScriptBlock** calls Set-Service. The **InputObject** parameter specifies the service object stored \$s. The **Status** parameter sets the service to **Stopped**.

Example 8: Change credential of a service

This example changes the credentials that are used to manage a service.

```
PowerShell

$credential = Get-Credential

Set-Service -Name Schedule -Credential $credential
```

Get-Credential prompts for a username and password, and stores the credentials in the \$credential variable. Set-Service uses the Name parameter to specify the Schedule service. The Credential parameter uses the \$credential variable and updates the Schedule service.

Example 9: Change the SecurityDescriptor of a service

This example changes a service's **SecurityDescriptor**.

```
PowerShell

$SDDL = "D:(A;;CCLCSWRPWPDTLOCRRC;;;SY)(A;;CCDCLCSWRPWPDTLOCRSDRCWDWO;;;BA)(A;;CSet-Service -Name "BITS" -SecurityDescriptorSddl $SDDL
```

The **SecurityDescriptor** is stored in the \$SDDL variable. Set-Service uses the **Name** parameter to specify the **BITS** service. The **SecurityDescriptorSddl** parameter uses \$SDDL to change the **SecurityDescriptor** for the **BITS** service.

Example 10: Set the startup type for multiple services

The Set-Service cmdlet only accepts one service name at a time. However, you can pipe multiple services to Set-Service to change the configuration of multiple services.

Parameters

-Confirm

Prompts you for confirmation before running Set-Service.

Expand table

Туре:	SwitchParameter
Aliases:	cf
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Credential

Specifies the account used by the service as the Service Logon Account.

Type a user name, such as **User01** or **Domain01\User01**, or enter a **PSCredential** object, such as one generated by the <code>Get-Credential</code> cmdlet. If you type a user name, this cmdlet prompts you for a password.

Credentials are stored in a PSCredential object and the password is stored as a SecureString.

① Note

For more information about **SecureString** data protection, see <u>How secure is SecureString?</u>.

This parameter was introduced in PowerShell 6.0.

Expand table

Type:	PSCredential
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Description

Specifies a new description for the service.

The service description appears in **Computer Management, Services**. The **Description** isn't a property of the <code>Get-Service</code> **ServiceController** object. To see the service description, use <code>Get-CimInstance</code> that returns a **Win32_Service** object that represents the service.

Type:	String
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-DisplayName

Specifies a new display name for the service.

① Note

Typically, **Set-Service** only operates on Windows services and not drivers. However, if you specify the name of a driver, **Set-Service** can target the driver.

Expand table

Туре:	String
Aliases:	DN
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Force

Specifies the Stop mode of the service. This parameter only works when -status Stopped is used. If enabled, Set-Service stops the dependent services before the target service is stopped. By default, exceptions are raised when other running services depend on the target service.

Expand table

Туре:	SwitchParameter
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-InputObject

Specifies a **ServiceController** object that represents the service to change. Enter a variable that contains the object, or type a command or expression that gets the object, such as a <code>Get-Service</code> command. You can use the pipeline to send a service object to <code>Set-Service</code>.

Туре:	ServiceController
Position:	0
Default value:	None
Required:	True
Accept pipeline input:	True
Accept wildcard characters:	False

-Name

Specifies the service name of the service to be changed. Wildcard characters aren't permitted. You can use the pipeline to send a service name to Set-Service.

① Note

Typically, Set-Service only operates on Windows services and not drivers. However, if you specify the name of a driver, Set-Service can target the driver.

Expand table

Туре:	String
Aliases:	ServiceName, SN
Position:	0
Default value:	None
Required:	True
Accept pipeline input:	True
Accept wildcard characters:	False

-PassThru

Returns a **ServiceController** object that represents the services that were changed. By default, Set-Service doesn't generate any output.

Expand table

Туре:	SwitchParameter
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-SecurityDescriptorSddl

Specifies the **SecurityDescriptor** for the service in **SddI** format. The account calling **Set-Service** with this parameter must have the WRITE_DAC and WRITE_OWNER permissions. For more information, see **Service** security and access rights.

Expand table

Type:	String
Aliases:	sd
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-StartupType

Specifies the start mode of the service.

The acceptable values for this parameter are as follows:

- Automatic The service is started or was started by the operating system, at system start-up. If an automatically started service depends on a manually started service, the manually started service is also started automatically at system startup.
- AutomaticDelayedStart Starts shortly after the system boots.
- Disabled The service is disabled and cannot be started by a user or application.
- InvalidValue Has no effect. The cmdlet does not return an error but the StartupType of the service is not changed.
- Manual The service is started only manually, by a user, using the Service Control Manager, or by an application.

Expand table

Туре:	ServiceStartupType
Aliases:	StartMode, SM, ST, StartType
Accepted values:	Automatic, AutomaticDelayedStart, Disabled, InvalidValue, Manual
Position:	Named
Default value:	None
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-Status

Specifies the status for the service.

The acceptable values for this parameter are as follows:

- Paused. Suspends the service.
- Running. Starts the service.
- **Stopped**. Stops the service.

Expand table

Туре:	String
Accepted values:	Paused, Running, Stopped
Position:	Named
Default value:	None

Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

-WhatIf

Shows what would happen if Set-Service runs. The cmdlet isn't run.

Expand table

Туре:	SwitchParameter
Aliases:	wi
Position:	Named
Default value:	False
Required:	False
Accept pipeline input:	False
Accept wildcard characters:	False

Inputs

ServiceController

You can pipe a service object to this cmdlet.

String

You can pipe a string that contains a service name to this cmdlet.

Outputs

None

By default, this cmdlet returns no output.

ServiceController

When you use the PassThru parameter, this cmdlet returns a ServiceController object.

Notes

This cmdlet is only available on Windows platforms.

Set-Service requires elevated permissions. Use the Run as administrator option.

Set-Service can only control services when the current user has permissions to manage services. If a command doesn't work correctly, you might not have the required permissions.

To find a service's service name or display name, use <code>Get-Service</code>. The service names are in the **Name** column and the display names are in the **DisplayName** column.

Related Links

- Get-Service
- New-Service

- Restart-Service
- Resume-Service
- Start-Service
- Stop-Service
- Suspend-Service
- Remove-Service

Collaborate with us on **GitHub**

The source for this content can be found on GitHub, where you can also create and review issues and pull requests. For more information, see our contributor guide.



PowerShell feedback

PowerShell is an open source project. Select a link to provide feedback:

🖔 Open a documentation issue

Provide product feedback

Senglish (United States)

✓ ✓ Your Privacy Choices

☆ Theme ∨

Manage cookies **Previous Versions**

Blog ☑

Contribute Privacy ☑ Terms of Use

Trademarks ☑

© Microsoft 2024