EP3120 - Statistical Physics and Applications

froufroujaguar24964

August 26, 2022

Abstract

Instructor: Prabha Mandyam (HSB 309) Teaching Assistant: Sourav Dutta

Lecture Timings: B Slot (Mon – 9am, Tue – 8am, Wed-1pm)

Venue: HSB 210

Course Outline: Some basic concepts in Probability Theory Microstates and macrostates; fundamental postulate of classical statistical mechanics; Thermal equilibrium; Microcanonical ensemble: Boltzmann's formula for Entropy; Laws of thermodynamics; Examples:Two-level systems, Classical ideal gas, Gibbs paradox Closed systems: canonical ensemble; Partition function, free energy; Calculation of thermodynamic quantities. Examples: Equation of state of a classical ideal gas; Energy fluctuations and specific heat. Open systems: grand canonical ensemble; Number fluctuations. Bosons, fermions and the elements of quantum statistics. Ideal fermi gas at absolute zero; application to electrons in metals and semiconductors. Electronic specific heat. Pauli paramagnetism. Blackbody radiation, derivation of Planck's Distribution Law. Radiation pressure. Elements of phase transition phenomena. First order and continuous phase transitions, critical point.

Text books:

M Kardar, Statistical Physics of Particles, Cambridge University Press (2007).

K.Huang, Statistical Mechanics (2nd Edition, Wiley, 1987).

Pre-requisite: PH 1080 - Thermodynamics and Kinetic Theory

Contents

1	Thermodynamics(Review)	2
	1.1 Preliminaries	2
	1.2 Thermodynamic Laws	4
	Statistical mechanics	11
	2.1 Microstates	11
	2.2 Review of probability theory	12

Chapter 1

Thermodynamics(Review)

Lecture 1: First Lecture

1.1 Preliminaries

25 July 2022

Definition 1.1.1. A *Thermodynamic system* is any macroscopic system.

Definition 1.1.2. Thermodynamic Parameters are measurable macroscopic quantities associated with the system, such as the pressure P, the volume V, the temperature T, and the magnetic field H. They are defined experimentally.

Definition 1.1.3. A *Thermodynamic state* is specified by a set of values of all the thermodynamic parameters necessary for the description of the system.

Definition 1.1.4. Thermodynamic equilibrium prevails when the thermodynamic system does not change with time.

Definition 1.1.5. The *equation of state* is a functional relationship among the thermodynamic parameters for a system in equilibrium. If P, V, and T are the thermodynamic parameters of the system, the equation of state takes the form

$$f(P, V, T) = 0$$

which reduces the number of independent variables of the system from three to two. The function f is assumed to be given as part of the specification of the system. It is customary to represent the state of such a system by a point in the three-dimensional P-V-T space. The equation of state then defines a surface in this space, as shown in Fig.1.1. Any point lying on this surface represent a state in equilibrium. In thermodynamics a state is automatically means a state in equilibrium unless otherwise specified.

Definition 1.1.6. A thermodynamic transformation is a change of state. If the initial state is an equilibrium sate, the transformation can be brought about only by changes in the external condition of the system. The transformation is quasi-static if the external condition changes so slowly that at any moment the system is approximately in equilibrium. It is reversible if the transformation retraces its history in time when the external condition retraces its history in time. A reversible transformation is quasi-static, but the converge is not necessarily true. For example, a gas that freely expands into successive infinitesimal volume elements undergoes a quasi-static transformation but not a reversible one.

Definition 1.1.7. The *P-V diagram* of a system is the projection of the surface of the equation of state onto the P-V plane. Every point on the P-V diagram therefore represents an equilibrium state. A reversible transformation is a continuous path on the P-V diagram. Reversible transformations of specific types give rise to paths with specific names, such as *isotherms*, *adiabatics*, etc. A transformation that is not reversible cannot be so represented.

Definition 1.1.8. The concept of *work* is taken over from mechanics. For example, for a system whose parameters are P, V, and T, the work dW done by a system in an infinitesimal transformation in which the volume increases by dV is given by

$$dW = PdV$$

Definition 1.1.9. Heat is what absorbed by a homogeneous system if its temperature increases while no work is done. If ΔQ is a small amount of the heat absorbed, and ΔT is the small change in temperature accompanying the absorption of heat, the heat capacity C is defined by

$$\Delta Q = C\Delta T$$

The heat capacity depends on the detailed nature of the system and is given as a part of the specification of the system. It is an experimental fact that, for the same ΔT , ΔQ is different for different ways of heating up the system. Correspondingly, the heat capacity depends on the manner of heating. Commonly considered heat capacities are C_v and C_p which respectively correspond to heating at constants V and P. Heat capacities per unit mass or per mole of a substance are called specific heats.

Definition 1.1.10. A *heat reservoir*, is a system so large that the gain or loss of any finite amount of heat does not change its temperature.

Definition 1.1.11. A system is thermally isolated if no heat exchange can take place between it and the external world. Thermal isolation may be achieved by surrounding a system with an adiabatic wall. Any transformation the system can undergo in thermal isolation is said to take place adiabatically.

Definition 1.1.12. A thermodynamic quantity is said to be *extensive* if it is proportional to the amount of substance in the system under consideration and is said to be *intensive* if it is independent of the amount of substance in the system under consideration. It is an important empirical fact to a good approximation thermodynamic quantities are either extensive or intensive.

Example. extensive:- volume V, No. of molecules N. intensive:- pressure P, temperature T,specific density $n=\frac{N}{V}$, specific volume $\vartheta=\frac{V}{N}$

Definition 1.1.13. The *ideal gas* is an important idealized thermodynamic system. Experimentally all gases behave in a universal way when they are sufficiently dilute. The ideal gas is an idealization of this limiting behavior. The parameters for an ideal gas are pressure P, volume V, temperature T, and number of molecules N. The equation of state is given by Boyle's law:

$$\frac{PV}{N} = constant$$

(for constant temperature)

The value of this constant depends on the experimental scale of temperature used.

Definition 1.1.14. The equation of state of an ideal gas in fact defines a temperature scale, The ideal-gas temperature T:

$$PV = Nk_bT$$

where

$$k_b = 1.38x10^{-16} \frac{erg}{deg}$$

which is called Boltzmann's constant. Its value is determined by the conventional choice of temperature intervals, namely, the Centigrade degree. This scale has a universal character because the ideal gas has a universal character. The origin T=0 is here arbitrarily chosen. Later we see that it actually has an absolute meaning according to the second law of thermodynamics.

Lecture 2: Second Lecture

1.2 Thermodynamic Laws

26 July 2022

1.2.1 Zeroth Law

Definition 1.2.1. If A is in Thermodynamic equilibrium with B and B is in Thermodynamic equilibrium with C, then C is in thermodynamic equilibrium with A. This law defines the notion of temperature (T).




Figure 1.1: Zeroth Law

1.2.2 First Law

Work Done

Conjugate variables

 $P \rightarrow \Delta V$

 $\mu(\text{Chemical Potential}) \to \Delta N$

 $F \rightarrow \Delta L$

Quasi-static process: PdV = infinitesimal work done.

$$\Delta W = \int_A^B P dV$$

Since, Work done is path dependent it is inexact differential and written as d(bar)W Heat exchange: It is also path dependent so, an inexact differential d(bar)Q = SdT

Definition 1.2.2 (First Law). There exists a quantity called "Internal Energy"

$$\Delta U = \Delta Q - \Delta W$$

$$dU = dQ - dW$$

dU is an exact differential, depends only on initial and final states. It is an extensive quantity.

Ideal gas: State is defined by (P, V, T)

Equation of state is given by $PV = Nk_bT$. This is a constraint so, independent variables reduce to 2.

$$\begin{split} U(P,V) &\Rightarrow dU = \left(\frac{\partial U}{\partial P}\right)_V dP + \left(\frac{\partial U}{\partial V}\right)_P dV \\ U(T,V) &\Rightarrow dU = \left(\frac{\partial U}{\partial T}\right)_V dT + \left(\frac{\partial U}{\partial V}\right)_T dV \\ U(P,T) &\Rightarrow dU = \left(\frac{\partial U}{\partial P}\right)_T dP + \left(\frac{\partial U}{\partial T}\right)_P dT \end{split}$$

Definition 1.2.3 (Specific Heat). $dQ = C_V dT$ or $C_P dT$ response of the system to heat.

Constant Volume Process:

$$dU = dQ - PdV$$

we know for a constant volume process $dQ = C_V dT$,

$$dU = C_V dT - P dV$$

we also know,

$$dU = \left(\frac{\partial U}{\partial T}\right)_V dT + \left(\frac{\partial U}{\partial V}\right)_T dV$$

 \therefore V is constant \Rightarrow dV = 0.

Equating the above 2 equations gives,

$$C_V = \left(\frac{\partial U}{\partial T}\right)_V$$

Constant Pressure process:

we know,

$$dQ = C_P dT$$
$$dU = C_P dT - P dV$$

we also know,

$$dU = \left(\frac{\partial U}{\partial P}\right)_T dP + \left(\frac{\partial U}{\partial T}\right)_P dT$$

dV term is there in the equation. Since, V is a function of P and T we can write,

$$dV = \left(\frac{\partial V}{\partial P}\right)_T dP + \left(\frac{\partial V}{\partial T}\right)_P dT$$

Substituting dV in first equation,

$$dU = C_P dT - P\left(\left(\frac{\partial V}{\partial P}\right)_T dP + \left(\frac{\partial V}{\partial T}\right)_P dT\right)$$

since, constant pressure dP = 0. Therefore,

$$C_P = P\left(\frac{\partial V}{\partial T}\right)_P + \left(\frac{\partial U}{\partial T}\right)_P$$

Definition 1.2.4 (Enthalpy, H). Thermodynamic Potential, Enthalpy H=U+PV

$$dH = dU + PdV$$

$$C_P = \left(\frac{\partial H}{\partial T}\right)_P$$

Heat Engine : Isothermal Process





Figure 1.2: cyclic process

Adiabatic Process : Constant heat Process.

$$dQ = 0$$

$$dU = -dW$$

$$dU = -PdV$$



Example (Ideal Gas Adibatic free expansion).

$$dQ = 0$$
: Adiabatic

$$dW = 0 :: Free Expansion$$

Since, Free expansion.

$$\therefore dU = 0 \to f(P, V) = 0$$

Lecture 3: Third Lecture

$$dU = dQ - dW$$

27 July 2022

Free expansion Irreversible Process

$$\Delta W = 0, \Delta Q = 0 \Rightarrow \Delta U = 0$$

$$U(P, V, T) = U(V, T) (\because PV = Nk_B T)$$

$$\Rightarrow U(V_i, T) = U(V_f, T)$$

Internal energy is purely a function of T.

$$C_V = \left(\frac{\partial U}{\partial T}\right)_V = \frac{dU}{dT}$$

$$H = U + PV = U(T) + Nk_BT$$

$$\Rightarrow H = H(T)$$

$$\therefore C_P = \left(\frac{\partial H}{\partial T}\right)_P$$

$$\Rightarrow C_P = \frac{dU}{dT} + Nk_B$$

$$\Rightarrow C_P = C_V + Nk_B \Rightarrow \gamma = \frac{C_P}{C_V} > 1$$

Adiabatic Process [Ideal Gas]:

$$dQ = 0$$

$$\Rightarrow dU = dW = -PdV$$

$$C_V dT = -PdV$$

$$C_V PdV + C_V VdP + PNk_B dV = 0 \ (\because PdV + VdP = Nk_B dT)$$

$$\Rightarrow C_P PdV + C_V VdP = 0$$

$$\Rightarrow \gamma \frac{dV}{V} + \frac{dP}{P} = 0$$

$$\Rightarrow PV^{\gamma} = Constant.$$

Note. In class a question is raised which is worth discussing.

Exercise. Ideal gas law $\Rightarrow PV = \text{constant}$ for free expansion(Adiabatic Irreversible process.) Adiabatic Process $\Rightarrow PV^{\gamma} = \text{constant}$.

$$P_1V_1 = P_2V_2$$

$$P_1 V_1^{\gamma} = P_2 V_2^{\gamma}$$

dividing both equations gives...

$$V_1^{\gamma - 1} = V_2^{\gamma - 1} \Rightarrow V_1 = V_2$$

But the process is free expansion. Can you explain why?


Answer. We obtained $PV^{\gamma}=$ constant equation by taking dW=-PdV which means the process is reversible.

Where as the free expansion process is Irreversible so, we cannot use $PV^{\gamma}=$ constant for this process.

1.2.3 Second Law

Definition 1.2.5 (Second Law). 1. The sole amount of a cyclic process cannot be the conversion of heat to work.

- 2. (corollary) Efficiency of a carnot engine $\neq 1$.
- 3. It is not possible to have a cyclic process whose sole outcome is transfer of heat form cooler bath to a heater bath.



a to b and c to d are isothermal processes b to c and d to a are adiabatic processes

Figure 1.4: carnot cycle

Efficiency of the carnot engine

$$\eta = \frac{W}{Q_H} = \frac{Q_H - Q_C}{Q_H} = 1 - \frac{Q_C}{Q_H} \tag{1.1}$$

We should do work to dump heat from cooler reservoir to hotter reservoir.

Reverse Carnot cycle \Rightarrow Refrigerator.

Entropy

Proposition 1.2.1 (Claussius Theorem).

$$\oint_{\text{cylclic process}} \frac{dQ}{T} \leq 0 \text{ with equality holding iff the process is reversible.}$$
 (1.2)



Figure 1.5: cyclic process

Definition 1.2.6 (Entropy). Reversible Process



Figure 1.6: reversible process

$$\oint \frac{dQ}{T} = 0$$
(1.3)

$$\oint_{L} \frac{dQ}{T} - \oint_{LL} \frac{dQ}{T} = 0 \tag{1.4}$$

$$\oint \frac{dQ}{T} = 0$$

$$\oint_{I} \frac{dQ}{T} - \oint_{II} \frac{dQ}{T} = 0$$
(1.3)
$$\oint_{I} \frac{dQ}{T} = \oint_{II} \frac{dQ}{T} \Rightarrow S(B) - S(A) \text{ where, S} = \text{entropy.}$$
(1.5)

Absolute notion of entropy

$$\int_{0}^{A} \frac{dQ}{T} = S(A) - S(0) \Rightarrow dQ = TdS(\because S(0) = 0)$$

$$\tag{1.6}$$

Third Law of Thermodynamics 1.2.4


Definition 1.2.7. Impossible to attain 0K. S("Absolute zero") = 0

Chapter 2

Statistical mechanics

2.1 Microstates

In a Macrostate Pressure(P), Volume(V), Temperature(T), Number of particles(N) are thermodynamic variables and Internal energy (U), Enthalpy (H), Entropy (S) are functions of thermodynamic variables. In a Microstate, Number of particles are $O(10^{23})$, Volume $\approx 10^{23}$ molar volume. $\frac{N}{V} = n$, number density in "thermodynamic limit" $N \to \infty, V \to \infty, n = Constant$.



$$H = KE + PE = H(\{p_i, q_i\}_{i=1,2,\dots,3N})$$

Figure 2.1

Hamiltonian, $H \in [E, E + dE]$ is a constraint for Thermal Equilibrium.

Phase space




Figure 2.2: phase space

different $\{q_i, p_i\}$ may give same E each $\{q_i, p_i\}$ is a microstate. Microstate $\equiv (q_1, q_2, \dots, q_N, p_1, p_2, \dots p_N)$ Several microstates, ("Ensemble")("collection") \Rightarrow E(total energy).

What are the Probabilities??

Microcanonical Ensemble: All microstates are equally likely, so long as they give total energy \in

[E, E + dE].

Canonical Ensemble: Probabilities are not equal. Gibbs Canonical Ensemble: Number of particles change.

Lecture 4: Fourth Lecture

Statistical point of view

01 August 2022

Can we derive equilibrium properties of macroscopic systems from the statistical properties of the microscopic parts. Microstate: $(q_1, q_2, \ldots, q_N, p_1, p_2, \ldots p_N)$ N particles. Probabilities of microstates, subject to external constraints (equilibrium condition)

- Eugene wigner; "unreasonable effectiveness of mathematics in the physical sciences."
- Wigner semi-circle distribution. (See tutorial 1 for more information.)

2.2 Review of probability theory

Random Variable: x (discrete, continuos)

Appendix