

# Pacific Campaign and Torpedo Solution Reference (v1.1)

fSocko

July 21, 2016

# Contents

<b>1</b>	<b>Introduction</b>	<b>3</b>
<b>2</b>	<b>Unit Conversion Factors</b>	<b>3</b>
2.1	Speed . . . . .	4
2.2	Nomogram (Metric) . . . . .	4
<b>3</b>	<b>Torpedo Data</b>	<b>5</b>
3.0.1	Mark 10 . . . . .	5
3.0.2	Mark 14 . . . . .	5
3.0.3	Mark 16 . . . . .	5
3.0.4	Mark 18 . . . . .	5
3.0.5	Mark 23 . . . . .	6
3.0.6	Mark 27 "Cutie" . . . . .	6
3.0.7	Torpedo minimum arming distance . . . . .	6
3.0.8	Torpedo max dive angle . . . . .	6
3.0.9	Torpedo maximum turn angle . . . . .	6
3.0.10	Magnetic detonation range . . . . .	6
3.0.11	Circular runner torpedos . . . . .	6
3.0.12	Gyro problems . . . . .	6
3.0.13	Homing torpedos . . . . .	6
<b>4</b>	<b>Trigger Maru Overhaul - Fleet Boat Types</b>	<b>7</b>
<b>5</b>	<b>Calculating AOB Based on Aspect Ratio</b>	<b>11</b>
5.1	Determine an observed <i>aspect ratio</i> . . . . .	11
5.1.1	Determine the Reference Aspect Ratio . . . . .	11
5.2	AOB calculation . . . . .	11
<b>6</b>	<b>Determine the distance to the track of a target</b>	<b>11</b>
<b>7</b>	<b>Determine the lead angle for a perpendicular attack with 0°gyro angle (AKA O'Kane Solution)</b>	<b>11</b>
<b>8</b>	<b>Determine the torpedo gyro angle</b>	<b>12</b>
<b>9</b>	<b>O'Kane Table of Values</b>	<b>12</b>
<b>10</b>	<b>Torpedo spread at range (m) per angle of spread (°)</b>	<b>13</b>
<b>11</b>	<b>Knot to Km Travelled Conversion Chart</b>	<b>13</b>
<b>12</b>	<b>Recognition Manual (Short, Metric)</b>	<b>15</b>

# 1 Introduction


The main purpose of this documentation is to record techniques and methods of early submarine attack techniques in a way which are simple to employ in computer programs (i.e. showing mathematical equations where possible), as well as acting as a reference for Submarine Simulators.

This document is a reference for Torpedo types and common conversion factors, as well as types of US Fleet Boats and Types of US Torpedoes. A brief recognition manual will be provided in an appendix. This document also aims to provide a brief overview of common torpedo solution methods.


## 2 Unit Conversion Factors

Length			Speed		
NM	$\uparrow \times 1852.00$	$\downarrow$	NM/h	$\uparrow \times 1$	$\downarrow$
	m			kt	
	$\uparrow \times 0.00054$	$\downarrow$		$\uparrow \times 1$	$\downarrow$
NM	$\uparrow \times 2025.37$	$\downarrow$	m/s	$\uparrow \times 1.94384$	$\downarrow$
	yd			kt	
	$\uparrow \times 0.00049$	$\downarrow$		$\uparrow \times 0.514444$	$\downarrow$
NM	$\uparrow \times 6076.12$	$\downarrow$	yd/s	$\uparrow \times 1.77745$	$\downarrow$
	ft			kt	
	$\uparrow \times 0.00016$	$\downarrow$		$\uparrow \times 0.562603$	$\downarrow$
Mi	$\uparrow \times 1609.34$	$\downarrow$	ft/s	$\uparrow \times 0.592484$	$\downarrow$
	m			kt	
	$\uparrow \times 0.00062$	$\downarrow$		$\uparrow \times 1.68781$	$\downarrow$
Mi	$\uparrow \times 1760$	$\downarrow$			
	yd				
	$\uparrow \times 0.00057$	$\downarrow$			
m	$\uparrow \times 1.09361$	$\downarrow$			
	yd				
	$\uparrow \times 0.914$	$\downarrow$			
m	$\uparrow \times 3.28084$	$\downarrow$			
	ft				
	$\uparrow \times 0.3048$	$\downarrow$			

## 2.1 Speed



## 2.2 Nomogram (Metric)



### 3 Torpedo Data

The following is torpedo for American torpedo types as used predominantly in the Pacific theatre.

Torpedo data adapted from *SH4 V1.2 Ultimate Torpedo Guide* by Mechan, found at the ubisoft forums (<http://forums.ubi.com/showthread.php/475595-SH4-V1-2-Ultimate-Torpedo-Guide-Forums>). Dated: 06-22-2007, Accessed: 18.08.2015

Slow and Fast speeds and ranges removed as appropriate.

#### 3.0.1 Mark 10

Available from:	Always
Range(m):	3200
Speed(kt):	36
Warhead:	80-160 radius 3-6m
Depth keeping:	70% chance of deviating $\pm 0.8m - \pm 1.2m$
Dud Chance (at AOB):	1% ( $0^\circ$ - $70^\circ$ ) 25% ( $70^\circ$ - $90^\circ$ )
Renown cost:	0

Notes: Default torpedo for the S-Class. Slower and with a shorter range than the Mk. 14, but extremely reliable.

#### 3.0.2 Mark 14

Available from:	Always
Range(Slow)(m):	8200
Range(Fast)(m):	4100
Speed(Slow)(kt):	31
Speed(Fast)(kt):	46
Warhead:	100-170 radius 3-7m
Depth keeping:	70% chance of deviating $\pm 1.5m - \pm 3.3m$
Dud Chance (at AOB):	1% ( $0^\circ$ - $35^\circ$ ); 34% ( $35^\circ$ - $70^\circ$ ); 99% ( $70^\circ$ - $90^\circ$ )
Renown cost:	0

Notes: Default torpedo for all modern fleet boats. Faster and with a longer range than the Mk. 10, it packs a roughly 20% stronger punch but is much less reliable.

#### 3.0.3 Mark 16

Available from:	1945-01-01
Range(m):	12500
Speed(kt):	46
Warhead:	180-250 radius 3.5-8m
Depth keeping:	70% chance of deviating $\pm 1.5m - \pm 3.3m$
Dud Chance (at AOB):	4% ( $0^\circ$ - $35^\circ$ ); 45% ( $35^\circ$ - $70^\circ$ ); 100% ( $70^\circ$ - $90^\circ$ )
Renown cost:	400

Notes: Fast torpedo with an exceptionally long range, but also terribly unreliable.

#### 3.0.4 Mark 18

Available from:	1943-07-12
Range(m):	3650
Speed(kt):	29
Warhead:	120-180 radius 3-7
Depth Keeping:	55% chance of deviating $\pm 1.2m - \pm 2.8m$
Dud Chance (at AOB):	1% ( $0^\circ$ - $35^\circ$ ); 34% ( $35^\circ$ - $70^\circ$ ); 99% ( $70^\circ$ - $90^\circ$ )
Renown cost:	500 (200 from 1944-01-16; 0 from 1944-09-01)

Notes: Slower, 10% more powerful, with a shorter range and much more reliable than the Mk. 14.

### **3.0.5 Mark 23**

Available from:	1943-01-01
Range(m):	4100
Speed(kt):	46
Warhead:	120-180 radius 3-7m
Depth Keeping:	70% chance of deviating $\pm 1.5m - \pm 3.3m$
Dud Chance (at AOB):	1% ( $0^\circ - 35^\circ$ ); 34% ( $35^\circ - 70^\circ$ ); 99% ( $70^\circ - 90^\circ$ )
Renown cost:	100 (0 from 16-01-1944)

Notes: Same range, speed and reliability than the Mk. 14 but roughly 10% more powerful. Definitely replaces the Mk. 10 as the "standard" torpedo from 16-01-1944.

### **3.0.6 Mark 27 "Cutie"**

Available From:	1944-01-01
Range(m):	4570
Speed(kt):	12
Warhead:	50-100 radius 1.5-5
Depth Keeping:	NA
Dud Chance (at AOB):	1% ( $0^\circ - 25^\circ$ )
Renown cost:	500

Notes: Slow acoustic homing torpedo with a small warhead primarily used for defence against destroyers.

### **3.0.7 Torpedo minimum arming distance**

*arming\_distance* is set across all torpedoes to 220m except the Mk. 27, which is 150 meters.

### **3.0.8 Torpedo max dive angle**

*max\_dive\_angle* is set to 20 degrees for all torpedo types.

### **3.0.9 Torpedo maximum turn angle**

*max\_turn\_angle* is  $135^\circ$  for all torpedoes except the Mk. 27, which is  $180^\circ$ .

### **3.0.10 Magnetic detonation range**

*mag\_detonation\_range* is 2m for all torpedoes except for the Mk. 27, which is 1m.

### **3.0.11 Circular runner torpedos**

*circle\_runner\_chance* is 0.5% for all torpedoes except for the Mk. 27, which is 0%.

### **3.0.12 Gyro problems**

The chance of having gyro problems is 0.3% at the introduction time of all torpedoes and drops to 0.2% in later periods for all torpedoes except for the Mk. 16. The *max\_deviation* when having gyro problems is always  $50^\circ$ . This does not apply to the Mk. 27.


### **3.0.13 Homing torpedos**

The Mk. 27 will run straight for 200m before homing.

## 4 Trigger Maru Overhaul - Fleet Boat Types

This section consists of pages 25-28 of the Trigger Maru Overhaul Manual which detail fleet boat types:

### Narwhal class:



(pseudo design added by mod)

Max speed: 17 knots surfaced  
6.5 knots submerge

Test depth: 300 ft

Armament: Four 21" bow torpedo tubes  
Two 21" aft Torpedo Tubes  
Two 6"/53 caliber deck guns  
One 20mm Oerlikon AA gun

Range: 9,000 nm @ 12.75 kts

The *Narwhals* were completed in 1930 and were the culmination of the cruiser sub concept in the [U.S.](#) They were big and roomy, which made them natural candidates for transport missions such as the raid on [Makin](#). However, they could rarely maintain the design speed of 17 knots. Subsequent submarine designs would be considerably smaller than the *Narwhals*.

### Porpoise Class:



Max speed: 17 knots surfaced  
8 knots submerged

Test Depth: 250 feet

Armament: Four 21" bow torpedo tubes  
Two 21" aft torpedo tubes  
One 4"/50 caliber deck gun  
Three 20mm Oerlikon AA guns

Range: 8,700 nm @ 13.5 kts

The *Porpoises* were completed in 1935-1937 and represented a trend away from the cruiser sub concept towards smaller, handier boats. However, they still had slow dive times, though they were capable of diving deep and were quite habitable (for submarines.)

Salmon Class:



Max speed: 21 knots surfaced  
9 knots submerged

Test Depth: 250 feet

Armament: Four 21" bow torpedo tubes  
Four 21" aft Torpedo tubes  
One 4"/50 caliber deck gun  
Three 20mm Oerlikon AA guns

Range: 8,700nm @ 15 kts

The Salmons were completed in 1937-1939 and introduced important innovations. They boasted lightweight high-performance diesel engines designed by private firms, could dive in less than sixty seconds, and used diesel-electric drive, which increased the flexibility of the powerplant. Any combination of engines could be used to either drive the boat or recharge its batteries. They continued the trend towards better habitability, heavier torpedo armament, and improved fire control. The improved batteries allowed a boat to move at two knots submerged for 48 hours. They were still fairly modern boats when war broke out. None were lost in combat.

Sargo Class:



Max speed: 21 knots surfaced  
8.75 knots submerged


Test Depth: 250 feet

Armament: Four 21" bow torpedo tubes  
Four 21" aft Torpedo tubes  
One 4"/50 caliber deck gun  
Three 20mm Oerlikon AA guns

Range: 8,700nm @ 15 kts

The Sargos were completed in 1939 and were quite modern boats for the time. They were essentially slightly modified Salmons. They were required to be able to maintain 17 knots on three of their four diesel engines and to have 25 percent reserve buoyancy. They used a new Navy battery design (Sargo batteries) in place of the commercial batteries previously used. Extra fuel could be carried in some of the ballast tanks at the cost of reducing dive capability. The class introduced the "down express" ballast tank, which was fitted under the forward torpedo room to reduce the dive time; this was flooded at the start of the dive, to pull the ship down, then blown as soon as the ship was underwater.

Tambor and Gar Class:



Max speed: 20.4 knots surfaced  
8.75 knots submerged

Test Depth: 250 feet

Armament: Six 21" bow torpedo tubes  
Four 21" stern torpedo tubes  
One 5"/51 Caliber deck gun  
Two 40mm Bofors cannons  
One 20mm Oerlikon AA gun

Range: 8,700nm @ 15 kts

The Tambor's and Gars were completed in 1940-1941 and were essentially improved Sargs. They established the configuration (six forward torpedo tubes, four rear torpedo tubes, and a total of 24 torpedoes) that characterized all American submarines built during the war, and were designed with gun foundations strong enough to carry a 5" deck gun at Lockwoods insistence. This would later prove to be a boon to the succeeding classes.

No other American submarine class suffered as high losses in proportion to its numbers in the Pacific. Seven of the twelve boats of these types were lost, all but two with all hands.

Gato Class:



Max speed: 21 knots surfaced  
9 knots submerged

Test depth: 300 feet

Armament: Six 21" bow torpedo tubes  
Four 21" stern torpedo tubes  
One 5"/25 caliber deck gun  
Two 40mm Bofors cannons  
One 20mm Oerlikon AA gun

Range: 8,700nm @ 15.18 kts

The *Gato*'s were just beginning to join the fleet at the start of the war. The last peacetime design, they were somewhat larger than their predecessors, improving stability and subdivision and allowing more powerful machinery. Their large engine rooms were subdivided by a pressure-proof bulkhead. They were a good design that was suitable for mass production, and they became the definitive US submarine model of the Pacific War. They set new standards of habitability and endurance, had sophisticated fire control computers (by the standards of the day), and were heavily armed. A couple of these boats continued to serve in the US navy as late as the 1950's and 1960's.

Balao Class:



Max Speed: 20 knots surfaced  
8.75 knots submerged

Test depth: 400 feet

Armament: Six 21" bow torpedo tubes  
Four 21" bow torpedo tubes  
One 5"/25 caliber deck gun  
Two 40mm Bofors cannons  
One 20mm Oerlikon AA gun

Range: 8,700nm @ 15.18 kts

The Balaos were completed in 1943-45 and were essentially Gatos with strengthened hulls. This allowed them to dive deeper, which was tactically important when evading Japanese depth charge attacks. The hull plate was increased in thickness from 0.5625" (14.3mm) to 0.875" (22.2mm) and the plate material was upgraded to high-tensile steel. It was calculated that this would increase the crush depth to 900 feet (270m) but other components, such as propeller shaft glands and the trim pump, could not be redesigned quickly to take the higher pressure and the maximum design operating depth was set to 400 feet (120m). A Gould centrifugal pump was adopted in 1944 that could operate at 600 feet (180m) depth or more, and the refitted Balaos were thereafter able to more fully exploit their thick skins. Many of these boats continued to serve in the US navy as late as the 1960's and 1970's.

Tench Class:



(Tench added by mod)

Max Speed: 20 knots surfaced  
8.75 knots submerged

Test depth: 400 feet

Armament: Six 21" bow torpedo tubes  
Four 21" bow torpedo tubes  
Two 5"/25 caliber deck gun  
Two 40mm Bofors cannons  
One 20mm Oerlikon AA gun

Range: 8,700nm @ 15.18 kts

The design dated to 1943, the *Tenches* were completed in 1945, with just two units ready in time to conduct war patrols. They were evolutionary improvement over the Gato and Balao classes, only about 35 to 40 tons larger, but more strongly built and with a slightly improved internal layout. Many of these boats continued to serve in the US navy as late as the 1960's and 1970's.

## 5 Calculating AOB Based on Aspect Ratio

AOB can be determined given the following data:

- Observed Mast Height
- Observed Ship Length
- Reference Aspect Ratio (i.e.  $\frac{\text{ReferenceLength}}{\text{ReferenceMastHeight}}$ )

### 5.1 Determine an observed *aspect ratio*.

$$AR_{\text{observed}} = \frac{\text{ObservedLength}}{\text{ObservedMastHeight}}$$

As the required figure is a ratio, it does not matter in what units the figures are given. For example, this could be the number of degrees Length and Mast Height subtend, the number of periscope graduations subtended or angular length in metres. It only matters that units for Observed Mast Height and Observed Length are the same.

#### 5.1.1 Determine the Reference Aspect Ratio

Identify the target and find the Length and Mast Height as given in the recognition manual (if possible) or calculate these figures using the SubSkipper ship parser. Proceed as for the observed aspect ratio to get the Reference Aspect Ratio ( $AR_{\text{reference}}$ ).

### 5.2 AOB calculation

$$AOB = \text{arcSin} \frac{AR_{\text{observed}}}{AR_{\text{reference}}}$$

- Note: This method is less accurate as AOB approaches 0. Using this method with a sample size of 16 at various AOBs, the average error was  $9.1^\circ$  and the median error  $6.88^\circ$ . The optimum range for collecting data seems to be around 2000m.
- Note: This method does not compute whether the AOB is on the port or starboard side.
- Note: "The AOB can only go up to 90, and gives no indication of starboard or port side showing. You have to determine that visually.
- AOB (Relative to Target) for each Quadrant:
  - $0^\circ$ -  $90^\circ$ : Use AOB result as is.
  - $90^\circ$ -  $180^\circ$ : Subtract AOB result from 180.
  - $180^\circ$ -  $270^\circ$ : Subtract AOB result from 180.
  - $270^\circ$ -  $360^\circ$ : Subtract AOB result from 360.

## 6 Determine the distance to the track of a target

As you manoeuvre into a firing position, it is useful to know your distance to the track of your target. Knowing the range and AOB of the target:

Track: intersection point between Submarine course and the current target course.

$$\text{Distance to Track} = \text{Range} (\sin(AOB))$$

## 7 Determine the lead angle for a perpendicular attack with $0^\circ$ gyro angle (AKA OKane Solution)

Once you are turned onto a perpendicular intercept course, this method calculates when to fire. The lead angle is simply the target bearing at the moment you fire. The range is irrelevant to the calculation although it is best to plan the attack within 500-1000m.

$$\text{leadangle} = \tan^{-1}([\text{targetspeed}/\text{torpedospeed}])$$

## 8 Determine the torpedo gyro angle

This example will show how to calculate the required gyro angle for a firing solution. This method is somewhat simplified and is best for smaller gyro angles ( $<30^\circ$ ) and shorter ranges ( $<1000$  metres).


$$\sin(\text{leadangle})/\sin(\text{AOB}) = (\text{targetspeed})/(\text{torpedospeed})$$

$$\text{gyroAngle} = \text{targetBearing} - \text{leadAngle}$$

## 9 O'Kane Table of Values


Ship Speed In Knots	Torpedo Speed	
	Slow	Fast
1	$2^\circ$	$1^\circ$
2	$4^\circ$	$2.5^\circ$
3	$5.5^\circ$	$3^\circ$
4	$7^\circ$	$5^\circ$
5	$9^\circ$	$6^\circ$
6	$11^\circ$	$7.5^\circ$
7	$13^\circ$	$8.5^\circ$
8	$14.5^\circ$	$9^\circ$
9	$16^\circ$	$11^\circ$
10	$18^\circ$	$12^\circ$
11	$19.5^\circ$	$13.5^\circ$
12	$21^\circ$	$14.5^\circ$
13	$23^\circ$	$16^\circ$
14	$24^\circ$	$17^\circ$
15	$25^\circ$	$18^\circ$
16	$27^\circ$	$19^\circ$
17	$29^\circ$	$20^\circ$
18	$30^\circ$	$21^\circ$
19	$31.5^\circ$	$22.5^\circ$
20	$33^\circ$	$23.5^\circ$

## 10 Torpedo spread at range (m) per angle of spread (°)



## 11 Knot to Km Travelled Conversion Chart

Kt / Hr	1	2	3	4	5	6	7	8	9	10
1	1.85	3.70	5.56	7.41	9.26	11.11	12.96	14.82	16.67	18.52
2	3.70	7.41	11.11	14.82	18.52	22.22	25.93	29.63	33.34	37.04
3	5.56	11.11	16.67	22.22	27.78	33.34	38.89	44.45	50.00	55.56
4	7.41	14.82	22.22	29.63	37.04	44.45	51.86	59.26	66.67	74.08
5	9.26	18.52	27.78	37.04	46.30	55.56	64.82	74.08	83.34	92.60
6	11.11	22.22	33.34	44.45	55.56	66.67	77.78	88.90	100.01	111.12
7	12.96	25.93	38.89	51.86	64.82	77.78	90.75	103.71	116.68	129.64
8	14.82	29.63	44.45	59.26	74.08	88.90	103.71	118.53	133.34	148.16
9	16.67	33.34	50.00	66.67	83.34	100.01	116.68	133.34	150.01	166.68
10	18.52	37.04	55.56	74.08	92.60	111.12	129.64	148.16	166.68	185.20
11	20.37	40.74	61.12	81.49	101.86	122.23	142.60	162.98	183.35	203.72
12	22.22	44.45	66.67	88.90	111.12	133.34	155.57	177.79	200.02	222.24
13	24.08	48.15	72.23	96.30	120.38	144.46	168.53	192.61	216.68	240.76
14	25.93	51.86	77.78	103.71	129.64	155.57	181.50	207.42	233.35	259.28
15	27.78	55.56	83.34	111.12	138.90	166.68	194.46	222.24	250.02	277.80
16	29.63	59.26	88.90	118.53	148.16	177.79	207.42	237.06	266.69	296.32
17	31.48	62.97	94.45	125.94	157.42	188.90	220.39	251.87	283.36	314.84
18	33.34	66.67	100.01	133.34	166.68	200.02	233.35	266.69	300.02	333.36
19	35.19	70.38	105.56	140.75	175.94	211.13	246.32	281.50	316.69	351.88
20	37.04	74.08	111.12	148.16	185.20	222.24	259.28	296.32	333.36	370.40
21	38.89	77.78	116.68	155.57	194.46	233.35	272.24	311.14	350.03	388.92
22	40.74	81.49	122.23	162.98	203.72	244.46	285.21	325.95	366.70	407.44
23	42.60	85.19	127.79	170.38	212.98	255.58	298.17	340.77	383.36	425.96
24	44.45	88.90	133.34	177.79	222.24	266.69	311.14	355.58	400.03	444.48
25	46.30	92.60	138.90	185.20	231.50	277.80	324.10	370.40	416.70	463.00
26	48.15	96.30	144.46	192.61	240.76	288.91	337.06	385.22	433.37	481.52
27	50.00	100.01	150.01	200.02	250.02	300.02	350.03	400.03	450.04	500.04
28	51.86	103.71	155.57	207.42	259.28	311.14	362.99	414.85	466.70	518.56
29	53.71	107.42	161.12	214.83	268.54	322.25	375.96	429.66	483.37	537.08
30	55.56	111.12	166.68	222.24	277.80	333.36	388.92	444.48	500.04	555.60



## 12 Recognition Manual (Short, Metric)

Name	Speed (kn)	Length (m)	Mast (m)	Draft (m)	Aspect
Auxilary Subchaser	17.00	63.00	11.40	4.20	5.5263
Agano Light Cruiser	35.00	175.00	23.60	5.70	7.4153
Akikaze Destroyer	34.00	102.50	21.80	2.90	4.7018
Akita Maru	13.50	105.00	16.00	7.30	6.5625
Akitsu Escort Carrier	20.00	143.75	35.70	7.84	4.0266
Akizuki Destroyer	33.00	135.00	22.80	3.80	5.9211
Armed Merchant Cruiser	17.50	155.00	26.80	8.70	5.7836
Armed Trawler	12.00	62.00	13.50	4.20	4.5926
Asashio Destroyer	35.00	118.00	27.00	3.40	4.3704
Atami Gunboat	20.00	45.00	7.80	1.10	5.7692
Attacker Escort Carrier	18.00	152.00	33.80	8.20	4.4970
Baltimore Heavy Cruiser	33.00	205.00	30.60	6.50	6.6993
Biyo Maru	12.00	120.00	20.10	7.50	5.9701
Black Swan Sloop	19.50	91.30	27.20	3.50	3.3566
Bogue Escort Carrier	18.00	152.00	11.30	8.20	13.4513
British Medium Old Tanker	10.00	91.50	11.00	4.50	8.3182
Brooklyn Light Cruiser	32.50	185.00	32.30	7.00	5.7276
Buckley Destroyer Escort	24.00	93.20	21.10	3.40	4.4171
Buzyun Maru	11.00	103.00	9.80	6.40	10.5102
Casablanca Escort Carrier	19.00	156.00	13.90	6.30	11.2230
Chitose Seaplane Tender	28.90	192.50	32.60	7.50	5.9049
Clemson Destroyer	35.00	95.00	28.80	3.10	3.2986
Cleveland Light Cruiser	32.50	185.00	36.20	6.60	5.1105
Coastal Composite Freighter	13.00	80.77	17.90	5.48	4.5123
Colorado Battleship	21.00	190.20	43.90	9.10	4.3326
Conte Verde Liner	21.00	173.74	28.60	7.50	6.0748
Dido Light Cruiser	32.00	156.00	36.50	6.30	4.2740
Elco Torpedo Boat	44.00	24.70	5.30	1.20	4.6604
Elite Black Swan Sloop	19.50	91.30	27.20	3.50	3.3566
Etorofu Escort	19.70	66.00	17.90	2.93	3.6872
Evarts Destroyer Escort	19.00	89.50	27.70	3.40	3.2310
Fiji Light Cruiser	32.00	169.00	43.90	5.00	3.8497
Fishing boat	10.00	38.00	18.70	1.80	2.0321
Fishing boat	10.00	38.00	18.70	1.80	2.0321
Fishing Boat	8.00	34.00	7.90	2.40	4.3038
Fishing Trawler	12.00	62.00	13.50	4.20	4.5926
Fleet Carrier	32.50	250.00	54.40	6.80	4.5956
Fletcher Destroyer	35.00	115.00	28.00	4.90	4.1071
Flower Corvette	16.00	60.60	19.70	3.50	3.0761
Fubuki Destroyer	38.00	118.50	22.60	3.50	5.2434
Furutaka Heavy Cruiser	33.00	188.00	25.90	5.20	7.2587
Fuso Battleship	24.70	212.00	48.30	9.50	4.3892
Hakusika Maru	12.00	135.00	20.30	8.70	6.6502
Haruna Maru	11.00	76.00	19.70	4.60	3.8579
Heito Maru	17.00	103.60	16.60	6.50	6.2410
Hira Gunboat	20.00	55.00	10.10	1.10	5.4455
Hiryu Fleet Carrier	34.30	223.30	37.20	7.50	6.0027
Horai Maru	17.00	137.46	25.60	8.53	5.3695
Iowa Battleship	33.00	270.40	44.30	11.00	6.1038
Ise Battleship	25.60	220.00	44.50	9.50	4.9438
Ise Battleship (Late War)	25.60	220.00	49.20	9.50	4.4715
J Class Destroyer	36.00	108.50	28.00	4.60	3.8750
JC Butler Destroyer Escort	24.00	93.30	28.10	2.80	3.3203
Junk	10.00	19.60	17.70	1.20	1.1073
Kasagisan Maru	12.50	86.80	18.10	6.10	4.7956

Name	Speed (kn)	Length (m)	Mast (m)	Draft (m)	Aspect
Kent Heavy Cruiser	31.50	183.00	21.80	5.00	8.3945
King George V Battleship	27.00	244.00	53.90	9.10	4.5269
Kinposan Maru	14.50	108.00	18.50	6.60	5.8378
Kisaragi Destroyer	37.00	102.00	11.20	3.00	9.1071
Kiturin Maru	18.50	130.00	25.70	8.60	5.0584
Kongo Battleship	30.50	220.00	42.50	8.50	5.1765
Kuma Light Cruiser	36.00	163.00	35.60	6.10	4.5787
Landing Ship Tank	10.80	98.70	25.20	3.30	3.9167
Large German Tanker	18.00	190.00	24.20	10.70	7.8512
Large Sampan	10.00	35.00	26.90	2.20	1.3011
Liberty Cargo	13.00	147.00	21.00	5.80	7.0000
Maya Heavy Cruiser	34.00	204.00	33.50	5.90	6.0896
Medium Modern Passenger/Freighter	16.00	105.00	27.40	7.30	3.8321
Minekaze Destroyer	39.00	102.60	21.80	2.90	4.7064
Mogami Heavy Cruiser	35.00	200.00	35.00	6.70	5.7143
Momi Destroyer	18.00	102.60	11.10	2.93	9.2432
Momoyama Maru	11.00	120.00	16.00	4.70	7.5000
Momoyama Maru	11.00	120.00	16.00	4.70	7.5000
Mutsuki Destroyer	37.00	102.00	11.20	3.00	9.1071
Nagara Maru	19.00	137.00	20.50	7.50	6.6829
Naka Light Cruiser	35.25	162.00	31.30	5.10	5.1757
Nevada Battleship	20.50	190.20	43.90	9.10	4.3326
New Mexico Battleship	22.00	190.00	42.00	10.00	4.5238
Nippon Maru	20.00	150.00	16.70	8.60	8.9820
North Carolina Battleship	27.00	220.00	33.40	9.00	6.5868
Northhampton Heavy Cruiser	32.70	183.00	49.00	7.00	3.7347
Okinoshima Minelayer	20.00	123.40	28.50	4.80	4.3298
Old Raked Bow Split Merchant	11.00	120.00	17.30	4.70	6.9364
Omaha Light Cruiser	35.00	168.00	19.50	4.50	8.6154
Patrol Boat 102	35.00	95.00	28.70	3.10	3.3101
Pennsylvania Battleship	21.00	190.20	43.90	9.10	4.3326
Pocket Battleship	28.50	183.00	37.90	7.00	4.8285
River class Frigate	20.00	91.50	25.90	4.00	3.5328
Sampan	10.00	19.50	16.50	1.20	1.1818
Schnellboot	44.00	24.70	5.30	1.20	4.6604
Shimushu Escort	20.00	70.00	24.50	2.93	2.8571
Shiratsuyu Destroyer	34.00	108.00	22.00	3.00	4.9091
Shokaku Fleet Carrier	34.50	250.00	32.40	8.70	7.7160
Small Old Split Freighter	17.00	80.50	17.90	3.70	4.4972
Small Split Freighter	12.50	86.87	18.10	6.10	4.7994
Somers Destroyer	37.00	116.00	31.50	4.20	3.6825
Submarine Tender	18.00	201.00	22.40	9.40	8.9732
T3 Tanker	18.00	190.00	25.50	10.70	7.4510
Taiho Fleet Carrier	33.30	253.70	46.20	9.50	5.4913
Taihosan Maru	13.00	80.50	17.90	3.70	4.4972
Taiyo Escort Carrier	21.00	180.10	15.10	7.50	11.9272
Takao Heavy Cruiser	36.50	204.00	35.30	6.00	5.7790
Tennessee Battleship	20.50	190.00	42.00	10.00	4.5238
Tennessee Battleship	20.50	190.20	43.90	9.10	4.3326
Tribal Destroyer	36.50	115.00	15.40	4.00	7.4675
Troop Transport	16.00	152.00	23.20	8.50	6.5517
Tug Boat	15.00	63.00	11.50	4.20	5.4783
Tyohei Maru	13.00	79.00	14.30	4.60	5.5245
Type C Escort	19.00	89.50	27.70	3.40	3.2310
Type D Escort	19.00	89.50	27.70	3.40	3.2310

Name	Speed (kn)	Length (m)	Mast (m)	Draft (m)	Aspect
V.W Destroyer	34.00	95.00	21.00	3.20	4.5238
Victory Cargo	17.00	139.60	21.80	7.30	6.4037
Wakatake Patrol Boat	18.00	102.60	21.70	2.93	4.7281
West Virginia Battleship	21.00	190.00	42.00	10.00	4.5238
Yamato Battleship	27.40	263.00	39.20	10.80	6.7092
Yugumo Destroyer	35.00	118.00	11.50	3.40	10.2609
Z Class Destroyer	38.00	118.50	22.60	3.50	5.2434
Zinbu Maru	10.00	120.00	18.60	4.70	6.4516