Introduction to High-Performance Computing

Giorgio Amati Alessandro Ceci


Corso di dottorato in Ingegneria Aeronautica e Spaziale 2025 g.amati@cineca.it/g.amaticode@gmail.com alessandro.ceci@uniroma1.it

Agenda

- ✓ HPC: What is it?
- ✓ Hardware: how it works
- ✓ Algorithm vs. Implementation
- ✓ Compiler + Floating point + I/O
- ✓ Parallel Paradigm
- ✓ Conclusions & Comments

HPC: what it is?


✓ These are the main skills for an efficient HPC



Which programming language?

https://en.wikipedia.org/wiki/List of programming languages

- ✓ 690 different programming languages
 - TeX
 - Postscript
 - C--
 - Ballerina
 - Mystic Programming Language (MPL)



Programming Languages

- ✓ A **compiled language** is a programming language whose implementations pass through a compiler. It is a translator that generates machine code from source code
 - e.g. Fortran, C, C++, ...
 - Syntax must be correct before running
 - Can be optimized by the compiler
- ✓ An interpreted language is a programming language that is executed step-by-step, with no pre-runtime translation
 - E.g. Perl, Python, bash,
 - It runs until it finds a syntax error
 - Optimization usually could be very low

Compiler: how it works?

compiler is a computer program that translates computer code written in one programming language (the source language) into another language (the target language). The name "compiler" is primarily used for programs that translate source code from a high-level programming language to a low-level programming language (e.g. assembly language, object code, or machine code) to create an executable program

1. Front-End

- a. Pre-processing
- b. Syntax & Semantic check/analysis

2. Middle-End

a. (general) Optimization

3. Back-End

- a. Machine dependent optimization
- b. Code Generation

Compiler: Optimization level

Have you ever read compiler's manual?

What the different level of optimization means? For nvfortran compiler

- ✓ -O: All -O1 optimizations plus traditional global scalar optimizations performed
- ✓ -O0: Creates a basic block for each statement. No scheduling or global optimizations performed
- O1: Some scheduling and register allocation is enabled. No global optimizations performed
- ✓ -O2: All -O optimizations plus SIMD code generation. Implies -Mvect=simd
- ✓ -O3: All -O2 optimizations plus more aggressive code hoisting and scalar replacement, that may or may not be profitable, Implies -Mvect=simd
- ✓ -O4: All -O3 optimizations plus more aggressive hoisting of guarded expressions performed. Implies -Mvect=simd
- ✓ -fast: Common optimizations; includes -O2 -Munroll=c:1 -Mlre -Mautoinline, Implies
 -Mvect=simd -Mflushz -Mcache_align

Optimization level example: MMM

✓ Different level of optimization for size=1000 matrices (on different machine)

Opzione	IBM xlf (sec.)	HP f77 (sec.)	Portland pgf77 (sec.)
-00	176	185	32.0
-01	(-)	237	30.9
-02	121	115	29.6
-03	122	98.1	7
-04	3.1	98.4	-
-05	3.8	4.9	-

MMM

- ✓ Old example (IBM)
- ✓ Old but "quite" clear
- ✓ Where does this difference in time comes from?

Option	Time (sec.)
-O0	24"
-O2	6.35"
-O3	4.87"
-04	2.14"

Reading the assembler

✓ Old example (IBM)

```
65 | do k = 1, n

66 | do j = 1, n

67 | do i = 1, n

68 | c(i,j) = c(i,j) + a(i,k)*b(k,j)

69 | enddo

70 | enddo

71 | endd0
```

- ✓ Compiler can produce, if you activate the right flags
 - Listing file (for IBM *.lst)
 - Assembler file (for IBM *.s)



reading the assembler: -O0 option

✓ mm.lst

```
68
    0004B4
                                                     gr4=.$STATIC BSS(gr2,0)
               lwz
                          80820008
                                             L4A
                                        1
68
    0004B8
               lwz
                          80640004
                                             L4A
                                                     gr3=j(gr4,4)
                                        2
68
    0004BC
               rlwinm
                          54636824
                                        2
                                             SLL4
                                                     r3=gr3,13
68
    0004C0
               lwz
                          80A40008
                                        1
                                             L4A
                                                     qr5=i(qr4,8)
68
    0004C4
               rlwinm
                          54A51838
                                        2
                                             SLL4
                                                     gr5=gr5,3
68
    0004C8
               add
                          7CC32A14
                                             Α
                                                     gr6=gr3,gr5
68
    0004CC
               addis
                          3CE40100
                                        1
                                             AIU
                                                     gr7=gr4,256
68
    0004D0
               add
                          7CC63A14
                                        1
                                             Α
                                                     gr6=gr6,gr7
    0004D4
               1fd
                                        1
68
                          C826E018
                                             LFL
                                                     fp1=c[](gr6,-8168)
68
    0004D8
               lwz
                          80C40010
                                        1
                                             L4A
                                                     gr6=k(gr4,16)
68
    0004DC
               rlwinm
                          54C76824
                                        2
                                             SLL4
                                                     qr7=qr6,13
68
    0004E0
               add
                          7CE53A14
                                        1
                                             Α
                                                     gr7=gr5,gr7
68
    0004E4
               add
                          7CE43A14
                                        1
                                                     gr7=gr4,gr7
68
    0004E8
               lfd
                          C847E018
                                        1
                                             LFL
                                                     fp2=a[](gr7,-8168)
•••
```

reading the assembler: -O0 option

```
68
    0004EC
               rlwinm
                          54C61838
                                            SLL4
                                                    gr6=gr6,3
68
    0004F0
               add
                          7CE33214
                                            Α
                                                    gr7=gr3,gr6
68
    0004F4
               addis
                          3CC40080
                                            AIU
                                                    gr6=gr4,128
68
    0004F8
               add
                          7CC63A14
                                            Α
                                                    gr6=gr6,gr7
68
    0004FC
               1fd
                          C866E018
                                            LFL.
                                                    fp3=b[](gr6,-8168)
68
    000500
               fmadd
                          FC2208FA
                                            FMA
                                                    fp1=fp1-fp3,fcr
68
    000504
               add
                          7C632A14
                                            Α
                                                    gr3=gr3,gr5
68
    000508
               addis
                          3C840100
                                                    gr4=gr4,256
                                            AIU
68
    00050C
               add
                          7C632214
                                            Α
                                                    gr3=gr3,gr4
68
    000510
               stfd
                          D823E018
                                            STFL
                                                    c[](gr3, -8168) = fp1
```

- mm.lst: 24 instructions but
 - only 1 store
 - only 3 load
 - only 1 fused-multiply and add (i.e. 2 flops)
 - \rightarrow 2/24 peak performance (~8%)

reading the assembler: -O0 option

- mm.lst: 24 instructions but
 - only 1 store
 - only 3 load
 - only 1 fused-multiply and add (i.e. 2 flops)

✓ Other 19 instructions where do they come from?

- ✓ Integer operation to compute address (i.e. element location in memory)
- ✓ 19/24 of total instructions "spent" in understanding where data is!!!
- √ ~80% of total time only to "understand", data fetching could be more expensive (e.g. cache miss)

reading the assembler: -O2 option

✓ mm.lst

68	0003D8	lfd	C8070008	1	LFL	fp0=c(gr7,8)
0	0003DC	mtspr	7F8903A6	1	LCTR	ctr=gr28
0	0003E0	ori	63080000	1	LR	gr8=gr24
0	0003 E4	lfdu	CC662000	1	LFDU	fp3,gr6=b(gr6,8192)
0	0003E8	ori	60 E 90000	1	LR	gr9=gr7
68	0003EC	lfdu	CC280008	1	LFDU	fp1,gr8=a(gr8,8)
68	0003F0	fmadd	FC0100FA	1	FMA	fp0=fp0,fp1,fp3,fcr
0	0003F4	bc	43400018	0	BCF	ctr=CL.111,taken=0%(0,100)
68	0003 F 8	lfd	C8490010	1	LFL	fp2=c(gr9,16)
68	0003FC	lfdu	CC280008	1	LFDU	fp1,gr8=a(gr8,8)
68	000400	stfdu	DC090008	1	STFDU	gr9,c(gr9,8)=fp0
68	000404	fmadd	FC0110FA	1	FMA	fp0=fp2,fp1,fp3,fcr
0	000408	bc	4320FFF0	0	BCT	ctr=CL.29,taken=100%(100,0)
0				CL	.111:	
68	000410	stfdu	DC09000	1	STFDU	gr9,c(gr9,8)=fp0
•••						

reading the assembler: -O2 option

- mm.lst: 15 instructions
 - 2 store
 - 5 load
 - 2 fused-multiply and add
 - \rightarrow 4/15 peak performance (~26%)

√ mm.s

```
_L3d8:
                                         # 0x000003d8 (H.10.NO_SYMBOL+0x3d8)
                fp0,8(r7)
        lfd
                CTR, r28
        mtspr
                r8,r24,0x0000
        oril
                fp3,8192(r6)
        lfdu
        oril
                r9,r7,0x0000
        lfdu
                fp1,8(r8)
                fp0,fp1,fp3,fp0
                        "any"
        .machine
                BO_dCTR_ZERO_8,CRO_LT,__L40c
        bc
__L3f8:
                                         # 0x000003f8 (H.10.NO_SYMBOL+0x3f8)
        lfd
                fp2,16(r9)
                fp1,8(r8)
        lfdu
                fp0,8(r9)
        stfdu
       fma
                fp0,fp1,fp3,fp2
                BO_dCTR_NZERO_9,CRO_LT,__L3f8
```

reading the assembler: -O3 option

✓ mm.lst

```
68
       000478
                  lfd
                          C8910008
                                        1
                                             LFL
                                                     fp4=a(gr17,8)
 0
       00047C
                  mtspr
                          7D0903A6
                                             LCTR
                                                     ctr=qr8
 0
       000480
                  ori
                          62260000
                                             LR
                                                     gr6=gr17
 0
       000484
                  1fdu
                          CC042000
                                                     fp0, gr4=b(gr4, 8192)
                                             LFDU
       000488
                                        1
 0
                  ori
                          60A70000
                                             LR
                                                     gr7=gr5
68
       00048C
                  lfd
                          C8650008
                                             LFL
                                                     fp3=c(qr5,8)
68
       000490
                  1fd
                          C8D10010
                                             LFL
                                                     fp6=a(gr17,16)
68
       000494
                  1fd
                          C8E50010
                                             LFL
                                                     fp7=c(gr5,16)
68
       000498
                  1fd
                          C8310018
                                             LFL
                                                     fp1=a(gr17,24)
68
       00049C
                  1fdu
                          CCA60020
                                        1
                                             LFDU
                                                     fp5,gr6=a(gr6,32)
68
       0004A0
                  1fd
                          C8450018
                                             LFL
                                                     fp2=c(qr5,24)
                                        1
68
       0004A4
                   fmadd
                          FC64183A
                                             FMA
                                                     fp3=fp3,fp4,fp0,fcr
68
       0004A8
                  1fd
                          C8850020
                                        1
                                             LFL
                                                     fp4=c(qr5,32)
68
                          FCC6383A
       0004AC
                   fmadd
                                             FMA
                                                     fp6=fp7,fp6,fp0,fcr
68
       0004B0
                  bc
                          43400048
                                        0
                                             BCF
                                                     ctr=CL.126, taken=0%(0,100)
68
                        CL.127:
68
       0004B4
                   fmadd
                          FC21103A
                                        1
                                             FMA
                                                     fp1=fp2,fp1,fp0,fcr
```

reading the assembler: -O3 option

✓ mm.lst

```
68
       0004B8
                   stfd
                          D8670008
                                                     c(qr7,8) = fp3
                                             STFL
68
                  1fd
       0004BC
                          C8470028
                                             LFL
                                                     fp2=c(gr7,40)
68
       0004C0
                   stfd
                          D8C70010
                                                     c(gr7,16) = fp6
                                             STFL
68
       0004C4
                  1fd
                          C8660008
                                                     fp3=a(gr6,8)
                                             LFL
68
                   fmadd
                          FC85203A
                                        1
       0004C8
                                             FMA
                                                     fp4=fp4,fp5,fp0,fcr
68
       0004CC
                  1fd
                          C8A70030
                                             LFL
                                                     fp5=c(gr7,48)
68
                   1fd
                          C8C60010
       0004D0
                                             LFL
                                                     fp6=a(gr6,16)
                                        1
68
       0004D4
                   stfd
                          D8270018
                                             STFL
                                                     c(gr7, 24) = fp1
68
       0004D8
                   fmadd
                          FC63103A
                                                     fp3=fp2,fp3,fp0,fcr
                                             FMA
68
                                        1
       0004DC
                  lfd
                          C8470038
                                             LFL
                                                     fp2=c(gr7,56)
68
       0004E0
                   lfd
                          C8260018
                                             LFL
                                                     fp1=a(gr6,24)
68
       0004E4
                   fmadd
                          FCC6283A
                                        1
                                             FMA
                                                     fp6=fp5,fp6,fp0,fcr
68
       0004E8
                   stfdu
                          DC870020
                                        1
                                             STFDU
                                                     qr7, c(qr7, 32) = fp4
68
                  1fd
                          C8870020
                                        1
       0004EC
                                             LFL
                                                     fp4=c(gr7,32)
68
       0004F0
                  1fdu
                          CCA60020
                                             LFDU
                                                     fp5,gr6=a(gr6,32)
                  bc
                          4320FFC0
                                        0
                                                     ctr=CL.127, taken=100%(100,0)
       0004F4
                                             BCT
68
                         CL.126:
```

reading the assembler: -O3 option

- ✓ mm.lst: 34 instructions
 - 4 store
 - 16 load
 - 6 fused-multiply and add
 - \rightarrow 12/34 peak performance (~35%)

✓ mm.s

lfd	fp4,8(r17)
mtspr	CTR, r8
oril	r6,r17,0x0000
lfdu	fp0,8192(r4)
oril	r7,r5,0x0000
lfd	fp3,8(r5)
lfd	fp6,16(r17)
lfd	fp7,16(r5)
lfd	fp1,24(r17)
lfdu	fp5,32(r6)
lfd	fp2,24(r5)
fma	fp3,fp4,fp0,fp3
lfd	fp4,32(r5)
fma	fp6,fp6,fp0,fp7

reading the assembler: -O5 option

- mm.lst: 344 instructions
 - 64 store
 - 128 load
 - 100 fused-multiply and add
 - \rightarrow 200/344 peak performance (~58%)
 - → unrolling outer loop
 - → blocking

MMM

- ✓ Old example (IBM pwr)
- ✓ Old but quite clear
- ✓ Now we know where these figures comes from

Option	Time (sec.)	%flops instructions
-00	24"	8%
-O2	6.35"	26%
-O3	4.87"	37%
-04	2.14"	58%

Compiler: what it can do?


Many optimization:

- ✓ Dead and redundant code removal
- Copy propagation
- ✓ Code motion
- ✓ Strength reduction
- ✓ Common subexpression elimination
- ✓ Register allocation
- ✓ Loop pipelining/unrolling
- Cache blocking
- ✓ Loop interchange/reordering
- ✓ Function inlining
- **√** ...

Code Motion

✓ A compiler can move instructions (e.g. outside of a loop) only if it realizes that the result is not affected by this transformation

```
do i = 1, n
   somma = somma + a(i)*b(j)*c(k)
enddo
```





```
temp = b(j)*c(k)
do i = 1, n
    somma = somma + a(i)*temp
enddo
```

Common Subexpression Elimination

✓ A compiler can group operations to reduce total number of instructions

```
x = c*sin(a)*cos(b)
y = c*sin(a)*sin(b)
x = c*cos(a)
    temp = c*sin(a)
   x = temp*cos(b)
y = temp*sin(b)
z = c*cos(a)
```

Strength Reduction

- ✓ Math Functions can be very expensive
- ✓ the compiler can change one operation with another equivalent one but less expensive
 - \blacksquare a**2 \rightarrow a*a
- ✓ but only at high level of optimization
- ✓ or use fast math libraries
 - but result can be different → Finite precision

Function	Cycles
sin(x)	230
exp(x)	535
log(x)	423
acos(x)	635
x**1.5	945
x**2	27
sqrt(x)	54
x**2.0	674
1/x	50

inlining


inline expansion, or inlining, is a manual or compiler optimization that replaces a function call site with the body of the called function. Inline expansion is similar to macro expansion, but occurs during compilation, without changing the source code (the text), while macro expansion occurs prior to compilation, and results in different text that is then processed by the compiler.

- ✓ The code is less compact and more verbose
- ✓ All overhead of function is removed, allowing further optimization
- ✓ profiling can help to spot fast functions
 - \blacksquare \rightarrow gprof

inlining: example

- ✓ The code is less compact and more verbose
- ✓ Overheads of function are removed, allowing further optimization (e.g. unrolling)

```
do i = 1, n
   call somma(a,b,c)
enddo
subroutine somma
real a,b,c
c = c + a*b
return
```



Loop reordering

- ✓ Using high optimization levels, the compiler "can" reorder loops to make it more efficient (i.e. cache efficient)
- ✓ But it can be confused by
 - Coding style
 - pointers
 - functions inside the loop
 - too much nested loops
 - I/O statements

```
72 do i = 1, n
73 do k = 1, n
74 do j = 1, n
75 c(i,j) = c(i,j) + a(i,k)*b(k,j)
76 enddo
77 enddo
78 enddo
```

Loop reordering: example

✓ 2048 Matrix size: 114" (-O0) vs. 3.3" (-O3)

mm. F90:

```
mm:
    75, FMA (fused multiply-add) instruction(s) generated
qamati01@dqx03:/$ nvfortran -O3 -Minfo mm.F90 mod tools.F90 -o mm.fast
mm. F90:
mm:
    64, Memory zero idiom, array assignment replaced by call to pgf90 mzero8
    72, Loop interchange produces reordered loop nest: 74,73,72
        Generated vector simd code for the loop
    73, Zero trip check eliminated
    74, Zero trip check eliminated
        Loop not fused: function call before adjacent loop
    75, FMA (fused multiply-add) instruction(s) generated
```

qamati01@dqx03:/\$ nvfortran -00 -Minfo mm.F90 mod tools.F90 -o mm.slow

Loop reordering

- ✓ Too much loops can confuse the compiler
- ✓ Remember: compilers are "conservative". They do not perform optimization unless they are sure of having no side effects!

```
81 do ii = 1, n, step
82
     do kk = 1, n, step
83
         do jj = 1, n, step
84
            do j = jj, jj+step-1
85
               do k = kk, kk+step-1
86
                   do i = ii, ii+step-1
87
                      c(i,j) = c(i,j) + a(i,k)*b(k,j)
88
                   enddo
89
               enddo
90
            enddo
91
         enddo
92
      enddo
93
  enddo
```

Loop reordering: example

√ 4096 Matrix size: 384" (-O0) vs. 19.1" (-O3) vs 11.1" (-O3, correct loop ordering)

qamati01@dqx03:/\$ nvfortran -00 -Minfo mm.F90 mod tools.F90 -o mm.slow

```
mm:
    75, FMA (fused multiply-add) instruction(s) generated
gamati01@dgx03:$ nvfortran -03 -Minfo mm.F90 mod tools.F90 -o mm.fast
mm:
    73, Memory zero idiom, array assignment replaced by call to pgf90 mzero8
    81, Loop not fused: function call before adjacent loop
        Loop not vectorized/parallelized: too deeply nested
    82, Loop not vectorized/parallelized: too deeply nested
    83, Loop not vectorized/parallelized: too deeply nested
    85, Zero trip check eliminated
    86, Zero trip check eliminated
        Generated vector simd code for the loop
    87, FMA (fused multiply-add) instruction(s) generated
```

pointers: an example

Kinetic code

✓ Using pointer to "swap" arrays: current → old

```
real(mystorage), dimension(:,:,:), pointer :: a01,a02,a03,a04,a05
real(mystorage), dimension(:,:,:), pointer :: a06,a07,a08,a09,a10
real(mystorage), dimension(:,:,:), pointer :: a11,a12,a13,a14,a15
real(mystorage), dimension(:,:,:), pointer :: a16,a17,a18,a19
!
real(mystorage), dimension(:,:,:), pointer :: b01,b02,b03,b04,b05
real(mystorage), dimension(:,:,:), pointer :: b06,b07,b08,b09,b10
real(mystorage), dimension(:,:,:), pointer :: b11,b12,b13,b14,b15
real(mystorage), dimension(:,:,:), pointer :: b16,b17,b18,b19
```

pointers: an example

```
nvfortran -DPGI
                -O2 -Mnodepchk -DFUSED
                                        -c col MC.F90
                                    20000
       time
             0.800468E-01
                             100/
Mean
       time
             0.811069E-01
                             200/
                                    20000
Mean
       time
             0.819973E-01
                             300/
                                    20000
Mean
       time
             0.813246E-01
                             400/
                                    20000
Mean
       time
             0.807486E-01
                             500/
                                    20000
Mean
```

```
nvfortran -DPGI
                 -O2 -Mnodepchk -Mcontiguous -DFUSED -c col MC.F90
Mean
        time
              0.426128E-01
                              100/
                                     20000
        time
              0.425005E-01
                                      20000
Mean
                              200/
                              300/
Mean
        time
              0.423607E-01
                                     20000
        time
              0.424811E-01
                              400/
                                     20000
Mean
        time
              0.421280E-01
Mean
                              500/
                                      20000
•••
```

pointers: language can help!

✓ Fortran2008 has an attribute for contiguous pointers to leverage compiler's efforts.

```
real(mystorage), dimension(:,:,:), contiguous, pointer :: a01,a02,a03,a04,a05
real(mystorage), dimension(:,:,:), contiguous, pointer :: a06,a07,a08,a09,a10
real(mystorage), dimension(:,:,:), contiguous, pointer :: a11,a12,a13,a14,a15
real(mystorage), dimension(:,:,:), contiguous, pointer :: a16,a17,a18,a19
```

```
nvfortran -DPGI -O2 -Mnodepchk -DFUSED -c col MC.F90
                             100/
Mean
       time 0.430257E-01
                                    20000
Mean
       time 0.431001E-01
                             200/
                                    20000
       time 0.431249E-01
                             300/
Mean
                                    20000
Mean
       time 0.431014E-01
                             400/
                                    20000
Mean
       time 0.433579E-01
                             500/
                                    20000
```

Another example.....

Implementing Turbulence model (Smagorinsky Model) in a 3D Lattice Boltzmann model

$$u_{total} =
u_0 + \underbrace{(C_S \Delta)^2 |S|}_{
u_t}$$

$$S_{ij} = -rac{3\omega_s}{2
ho_{(0)}}\Pi_{ij}^{(neq)}$$


$$\Pi_{ij}^{(neq)} = \sum_q c_{qi} c_{qj} \; f_q^{(neq)}$$

An example.....

$$\Pi_{ij}^{(neq)} = \sum_q c_{qi} c_{qj} \ f_q^{(neq)}$$

- √ 19*6*2 multiplications
- √ 19*6 sums
- ✓ 19*6*3 loads

What can a compiler do?



first "optimization"

$$\Pi_{ij}^{(neq)} = \sum_q c_{qi} c_{qj} \ f_q^{(neq)}$$

- √ 19*6*2 multiplications
- √ 19*6 sums
- ✓ 19*6*2 loads

What can a compiler do? Maybe this.....

```
Pxx = cx(01)*cx(01)*n01 + cx(02)*cx(02)*n02 + & cx(03)*cx(03)*n03 + cx(04)*cx(04)*n04 + & cx(05)*cx(05)*n05 + cx(06)*cx(06)*n06 + & cx(07)*cx(07)*n07 + cx(08)*cx(08)*n08 + & cx(09)*cx(09)*n09 + cx(10)*cx(10)*n10 + & cx(11)*cx(11)*n11 + cx(12)*cx(12)*n12 + & cx(13)*cx(13)*n13 + cx(14)*cx(14)*n14 + & cx(15)*cx(15)*n15 + cx(16)*cx(16)*n16 + & cx(17)*cx(17)*n17 + cx(18)*cx(18)*n18 + & cx(19)*cx(19)*n19

Pyy = cy(01)*cy(01)*n01 + cy(02)*cy(02)*n02 + &
```

Some performance figures

- ✓ Left: time for 256³ simulation without Smagorinsky Model
- ✓ Right: time for 256³ simulation with Smagorinsky Model

```
# Time for section
                                 # Time for section
# init
              0.115159E+01
                                 # init
                                               0.111767E+01
        time
                                         time
 loop time
              0.716699E+02
                                  loop time
                                               0.866046E+02
# coll time
              0.641728E+02
                                 # coll
                                         time
                                               0.791241E+02
 bc
        time 0.645609E+01
                                 # bc
                                         time 0.645086E+01
 diagno time
              0.102584E+01
                                 # diagno time
                                               0.101066E+01
```

- ✓ the Smagorinsky model introduce a 1.23x slowdown!
- ✓ Can it be reduced?

Looking at operation

- ✓ For each Tensor element Pij we perform
 - 19*3 load operation
 - 19 sums
 - 19*2 products

```
Pxy = cx(01)*cy(01)*n01 + cx(02)*cy(02)*n02 + & cx(03)*cy(03)*n03 + cx(04)*cy(04)*n04 + & cx(05)*cy(05)*n05 + cx(06)*cy(06)*n06 + & cx(07)*cy(07)*n07 + cx(08)*cy(08)*n08 + & cx(09)*cy(09)*n09 + cx(10)*cy(10)*n10 + & cx(11)*cy(11)*n11 + cx(12)*cy(12)*n12 + & cx(13)*cy(13)*n13 + cx(14)*cy(14)*n14 + & cx(15)*cy(15)*n15 + cx(16)*cy(16)*n16 + & cx(17)*cy(17)*n17 + cx(18)*cy(18)*n18 + & cx(19)*cy(19)*n19
```

- ✓ But cx(j),cy(j),cz(j) can assume only values among -1,0,+1
 - only 10 non zero values for cx(j),cy(j),cz(j)

Second optimization:

$$\Pi_{ij}^{(neq)} = \sum_q c_{qi} c_{qj} \ f_q^{(neq)}$$

```
A compiler can't do that!
```

```
Pxx = n01 +n02 +n03 +n04 +n05 +n10 +n11 +n12 +n13 +n14
Pyy = n01 +n03 +n07 +n08 +n09 +n10 +n12 +n16 +n17 +n18
Pzz = n02 +n04 +n06 +n07 +n09 +n11 +n13 +n15 +n16 +n18
!
Pxz = -n02 +n04 +n11 -n13
Pxy = -n01 +n03 +n10 -n12
Pyz = +n07 -n09 +n16 -n18
```

Drastic operation reduction!

- ✓ Only 36 sums
- ✓ No multiplication at all
- ✓ no load of cx (pop), cy (pop), cz (pop) vectors

other performance figures

- ✓ Left: time for 256³ simulation with Smagorinsky Model (no optimized)
- ✓ Right: time for 256³ simulation with Smagorinsky Model (optimized)

```
# Time for section
                                 # Time for section
 init
              0.111767E+01
                                 # init
        time
                                          time
                                                0.112207E+01
 loop time
              0.866046E+02
                                   loop
                                                0.730055E+02
                                         time
 coll time
              0.791241E+02
                                 # coll
                                         time
                                                0.655008E+02
 bc
        time
              0.645086E+01
                                 # bc
                                           time
                                                 0.646228E+01
 diagno time
              0.101066E+01
                                 # diagno time
                                                0.102758E+01
```

✓ Now the Smagorinsky impact is negligible...

Comment (personal)

- ✓ Compilers can help you, but you must be aware of what they can or cannot do
- ✓ Coding style can help/confuse compilers
- ✓ Optimization capability of today compilers is decreasing
 - more optimization work is demanded to developers
- ✓ Play with different compilers (if possible)
- ✓ Play with different optimization level/flag
- ✓ Use flags to understand what's going on under the hood
 - e.g. -Minfo for nvidia compilers

Finite precision

A computer uses finite precision. This means that some rules are different respect infinite precision (standard algebra)

✓ Sum is no more additive. You can choose three number a,b,c so that

$$(a+b)+c \neq a+(b+c)$$

✓ in finite precision we an "infinite numbers" that behaves like a zero

$$(a+c) = a \to c \equiv 0$$

Cancellation issue

- ✓ Cancellation happens we we have big and little number to add/subtract
- ✓ Programmer has to take care (with parentheses) of the right order
- ✓ Compiler can alter the order and produce wrong results
- \checkmark for a = 0.333333 we perform different operation with different values of b

	b = 1.60	b = 6553.6	b = 3355443	b = 1.3421773E+07
b - b + a	0.3333333	0.3333333	0.3333333	0.3333333
b + a - b	0.3333334	0.3334961	0.2500000	0.0000000E+00
a + b - b	0.3333334	0.3334961	0.2500000	0.0000000E+00
a - b + b	0.3333334	0.3334961	0.2500000	0.0000000E+00

"Group" quantities with the same range

Floating point: IEEE p754


The **IEEE Standard for Floating-Point Arithmetic** (**IEEE 754**) is a technical standard for floating-point arithmetic established in 1985 by the Institute of Electrical and Electronics Engineers (IEEE). The standard addressed many problems found in the diverse floating-point implementations that made them difficult to use reliably and portably. Many hardware floating-point units use the IEEE 754 standard.

- ✓ arithmetic formats: sets of binary and decimal floating-point data, which consist of finite numbers (including signed zeros and subnormal numbers), infinities, and special "not a number" values (NaNs)
- ✓ interchange formats: encodings (bit strings) that may be used to exchange floating-point data in an efficient and compact form
- ✓ rounding rules: properties to be satisfied when rounding numbers during arithmetic and conversions
- ✓ operations: arithmetic and other operations (such as trigonometric functions) on arithmetic formats
- ✓ exception handling: indications of exceptional conditions (such as division by zero, overflow, etc.)

Floating point: binary representation

- ✓ Machine Epsilon: minimum non zero value with respect to 1.0
- ✓ Range: max/min values that can be represented

Precisione	Precisione p	Machine epsilon	Range
Singola	24	$2^{-23} \simeq 1.2 \times 10^{-7}$	$10^{-38} < x < 10^{38}$
Doppia	53	$2^{-52} \simeq 1.2 \times 10^{-16}$	$10^{-308} < x < 10^{308}$



Single vs. Double precision


- ✓ Double precision has a wider range respect single precision and is less subject to cancellation issues
- ✓ But today HW is two times faster for single precision computation respect double one (do you remember vectorization?)
 - Both CPU and GPU
- ✓ Half precision is 4 times faster respect double precision.
 - GPU and next generation CPU (it is used for ML)

Hint:

- ✓ Check if single precision is fine for you
- ✓ Use mixed precision: i.e., single precision for stored data, double for all computation
- ✓ Use compiler flags to check if you code is IEEE compliant

TG-Vortex:example

- ✓ Taylor-Green Vortices are a 2D flow configuration where energy decay has an analytical exponential law.
- ✓ Performance (right) in MLUPs, higher is better (GPU)



Precision	MLUPs
Half/Single-	11844
Single	7296
Single/Double	7314
Double/Double	4369

HW trends

- ✓ GPU are today the building block of HPC cluster
- ✓ HW is developed not according to HPC needs
- ✓ "mala tempora currunt"
- ✓ NVIDIA GPUs evolution

Figure of Merit	Volta 2017 (V100)	Ampere 2020 (A100)	Hopper 2022 (H200)	Blackwell 2024 (B200)
FP64 FMA (TFLOP/s)	7.8	9.75	33.5	40
FP64 Tensor (TFLOP/s)	N/A	19.5	67	40
FP32 FMA (TFLOP/s)	15.7	19.5	67	80
FP16 Tensor (TFLOP/s)	125	312	989	2250
BF16 Tensor (TFLOP/s)	125	312	989	2250
INT8 Tensor (TOP/s)	N/A	624	1979	4500
Memory BW (TB/s)	0.9	2.0	4.8	8.0

Finite precision issues: computing Pl

✓ Simple way to compute Pi

$$\frac{\pi^2}{6} = \sum_{n=1}^{\infty} \frac{1}{n^2}$$

```
! forward sum...
    do i=1,elements
       sum1=sum1+(1.0/(float(i)*float(i)))
    end do
 backward sum
    do i=elements, 1, -1
       sum2=sum2+(1.0/(float(i)*float(i)))
    end do
   write(6,*) 'forward =', sqrt(6.0*sum1)
    write(6,*) 'backward=', sqrt(6.0*sum2)
```

Finite precision issues: computing PI

- ✓ Backward is more precise with respect to forward....
- ✓ Why?

Elements	Backword	Forward
100	0.9969709148	0.9969709907
1'000	0.9996961603	0.9996962361
10'000	0.9999695955	0.9999365829
100'000	0.9999969162	0.9999365829
1'000'000	0.9999997242	0.9999365829
10'000'000	0.9999999519	0.9999365829

I/O issues

- √ I/O operations are really expensive.
 - Cycles are order of nanoseconds
 - Memory access are order of 100 or 1000 cycles
 - I/O access can be order of 100000 cycles (milliseconds)
- ✓ Writing on rotating disks implies great latencies

Golden rules

#1: write/read on the disk only if it is mandatory

#2: write/read only what is really important

#3: always use binary and never formatted data (e.g. ASCII) for "huge" dump

I/O Example

√ I/O operations are really expensive

```
! formatted
do k=1,nd
    do j=1,nd
        do i=1,nd
            write(69,*) a(i,j,k)
        enddo
    enddo
enddo
```

```
! unformatted (1)
do k=1,nd
     do j=1,nd
         do i=1,nd
              write(79) a(i,j,k)
         enddo
    enddo
enddo
```

```
! unformatted (2)
write(82)
(((a(i,j,k),i=1,nd),j=1,nd),k=1,nd)
```

```
! unformatted (3) write(83) a
```

I/O Example

- √ I/O operations are really expensive.
- ✓ time writing on /scratch
- ✓ Time presented here only as relative reference
 - It heavily depends from the filesystem configuration

	time (sec.)
Formatted	6.88
unformatted-1	1.41
unformatted-2	0.34
unformatted-3	0.10

I/O Some strategies

- ✓ I/O is the bottleneck: avoid it when possible
- ✓ I/O subsystem work with locks: simplify application
- ✓ I/O has its own parallelism: use MPI-I/O or other libraries
- ✓ I/O is slow: compress (to reduce) output data
- ✓ Raw data could be not portable: use library
- ✓ I/O C/Fortran APIs are synchronous: use dedicated I/O tasks
- ✓ Application DATA are too large: analyze it "on the fly", (e.g. re-compute vs. write)

Carefully plan your data production/workflow BEFORE the simulation

Moving Data

Bits per Second Requirements						
10PB	25,020.0 Gbps	3,127.5 Gbps	1,042.5 Gbps	148.9 Gbps	34.7 Gbps	
1PB	2,502.0 Gbps	312.7 Gbps	104.2 Gbps	14.9 Gbps	3.5 Gbps	
100TB	244.3 Gbps	30.5 Gbps	10.2 Gbps	1.5 Gbps	339.4 Mbps	
10TB	24.4 Gbps	3.1 Gbps	1.0 Gbps	145.4 Mbps	33.9 Mbps	
1TB	2.4 Gbps	305.4 Mbps	101.8 Mbps	14.5 Mbps	3.4 Mbps	
100GB	238.6 Mbps	29.8 Mbps	9.9 Mbps	1.4 Mbps	331.4 Kbps	
10GB	23.9 Mbps	3.0 Mbps	994.2 Kbps	142.0 Kbps	33.1 Kbps	
1GB	2.4 Mbps	298.3 Kbps	99.4 Kbps	14.2 Kbps	3.3 Kbps	
100MB	233.0 Kbps	29.1 Kbps	9.7 Kbps	1.4 Kbps	0.3 Kbps	
	1H	8H	24H	7Days	30Days	

Recap

- √ i/O is very slow
- ✓ I/O is very very slow
- √ I/O is very very very slow
- ✓ Have I pointed out that I/O is slow already?
- ✓ the compiler is your best friend, but sometimes your worst enemy
- ✓ take care of floating point operation
- ✓ Code refactoring is crucial: a "clean" code is important, but could be inefficient

References

- ✓ <u>D. Goldberg. 'What every computer scientist should know about floating-point arithmetic'. Computing Survey of ACM, March 1991.</u>
- M. L Overton. 'Numerical computations with IEEE Floating Point Arithmetic'. SIAM, 2001.
- M. Abramowitz and I. Stegun. 'Handbook of Mathematical Functions' 1974
- ✓ J.H. Wilkinson. 'Rounding errors in algebraic processes'. Dover.
- ✓ Dongarra et al. 'Investigating half precision arithmetic to accelerate dense linear system solvers'