Reverse Engineering

4. Disassembling and Obfuscation

Ing. Tomáš Zahradnický, EUR ING, Ph.D.
Ing. Martin Jirkal
Ing. Josef Kokeš



Czech Technical University in Prague Faculty of Information Technology Department of Computer Systems

Version 2019-09-28

Table of Contents I

- Disassembling
 - Linear Sweep
 - Recursive Traversal
 - Extended Linear Sweep
 - Hybrid Approach
- Obfuscation Techniques
 - Motivation
 - Metrics
- 3 Layout Obfuscations
- 4 Control Flow Transformations
 - Opaque Predicates and Variables
- 5 Computation Transformations
 - Insertion of Dead or Irrelevant Code
 - Extension of Loop Conditions
 - Conversion of a Reducible CFG to Non-Reducible

Table of Contents II

- Removal of Library Calls and Programming Idioms
- Table Interpretation
- Addition of Redundant Operands
- Code Parallelization

- 6 Aggregation Transformations
 - Inlining
 - Outlining
 - Interleaving
 - Cloning
 - Loop Transformations

Disassembling

Disassembling

Disassembling is a process of translation of binary code into a code in a human-readable assembly language of the target CPU.

- An application performing the disassembling is called a disassembler.
- Disassembly (a product of a disassembled executable) is used to perform static code analysis, or for the dynamic (live) code analysis within a debugger.
- Disassembly:
 - contains a huge number of lines of code;
 - lacks a lot of information present at compile time (variable names, debugging information, label names) due to stripping and optimization;
 - mixes code and data how to distinguish between them?
- There are two approaches to disassembling a linear sweep and a recursive traversal [4]. Each of them has its own pros and cons.

Linear Sweep

Linear Sweep

Linear sweep performs disassembly in a linear fashion, byte by byte, from the start of the .text section toward its end.

- Fast and simple.
- PowerPC uses fixed length instruction encoding. Each instr. 4 B.
- x86 uses variable length instruction encoding. Its instructions can have 1–15 bytes. Infinitely long instructions can theoretically be created with redundant prefixes, but anything longer than 15 bytes generates an exception.
 - cc int3.
 - cd 03 int 3.
 - f0 65 81 84 d8 78 56 34 12 ef cd ab 90 lock add dword ptr gs:[eax+ebx*8+12345678h], 90abcdefh.
- Once an instruction is disassembled, processing of another starts, and so on. This process is repeated for the entire .text section.

Ambiguous Control Flow

WinDbg 6.12.0002.633

Original code

```
xor eax, eax

----- jz good // Always jump

_emit 0xf0

_emit 0x3e

_emit 0x81

_emit 0x84

v _emit 0x98

good: mov eax, ebx

mov eax, ebx

mov eax, ebx

mov eax, ebx

mov eax, ebx
```

IDA Pro 6.7

```
00402cd8 xor eax, eax
00402cda jz short near ptr loc_402CDC+5
00402cdc db 3Eh
00402cdc lock add dword ptr [eax+ebx*4-3C743C75h], 0C38BC38Bh
```

OllyDbg 2.01

```
00402cd8 33c0
              xor eax, eax
00402cda 7405
              je short 00402ce1
00402cdc f0
              db f0
                         // Correct!
00402cdd 3e db 3e // Correct!
00402cde 81 db 81
                       // Correct!
00402cdf 84 db 84
                        // Correct!
00402ce0 98 cwde
                         // Bogus!
00402ce1 8bc3 mov eax,ebx // Correct!
00402ce3 8bc3 mov eax.ebx // Correct!
              mov eax.ebx // Correct!
00402ce5 8bc3
00402ce7 8bc3
              mov eax,ebx // Correct!
```

Mixed Code & Data

```
0.000> 11 011d4780 I.200
 011d4780 55
                            push ebp
 011d4838 83bdd0feffff03
                            cmp dword ptr [ebp-130h],3
 011d483f 7727
                            ia
                                 011d4868
 011d4841 8b8dd0feffff
                            mov ecx, dword ptr [ebp-130h]
                                dword ptr ds: [011d490c+ecx*4]
 011d4847 ff248d0c491d01
 011d484e e85bc9ffff
                            call func0 (011d11ae)
 011d4853 eb13
                            jmp 011d4868
 011d4855 e82cc9ffff
                            call func1 (011d1186)
                            imp 011d4868
 011d485a eb0c
 011d485c e820c9ffff
                            call func2 (011d1181)
                            jmp 011d4868
 011d4861 eb05
 011d4863 e8fbc8ffff
                            call func3 (011d1163)
 011d4868 33c0
                            xor
                                eax,eax
 011d4897 5d
                            pop
                                ebp
 011d4898 c21000
                            ret
                                 10h
 011d489b 90
                            nop
 011d489c 05000000a4
                            add eax.0A4000000h
 011d48a1 48
                            dec
                                 eax
 011d48a2 1d01f4ffff
                            sbb
                                eax, OFFFFF401h
 011d490c 4e
                                                                 // Data in the .text section!
                            dec
                                 esi
 011d490d 48
                                                                 // Data in the .text section!
                            dec
                                 eax
 011d490e 1d0155481d
                            sbb eax, 1D485501h
                                                                 // Data in the .text section!
 011d4913 015c481d
                            add
                                 dword ptr [eax+ecx*2+1Dh],ebx
                                                                // Data in the .text section!
                                 dword ptr [ebx+48h].esp
 01144917 016348
                            add
                                                                 // Data in the .text section!
 011d491a 1d01ccccc
                            sbb eax,0CCCCCC01h
                                                                 // Data in the .text section!
```

Linear Sweep Continued

- As we have observed, linear sweep blindly disassembled one instruction after another. This was working fine when we started disassembly at a function's start (push ebp at 011d4780). Initially it was going OK, later the disassembler got confused by the following constructs:
 - ambiguous control flow;
 - 2 data in code.
- Both resulted in a meaningless disassembly!
 - → Any disassembler using only linear sweep (WinDbg, gdb, objdump [3]) cannot distinguish code from data.
- ightarrow Linear sweep is by itself insufficient ightarrow we need a more robust method.

Recursive Traversal I

Recursive traversal, in contrast to the linear sweep, disassembles code by watching its flow rather than linearly parsing all contents of the .text section. The traversal starts typically at the executable's entry point and disassembles the first instruction there. The code section with that instruction is marked as visited. If the instruction was a branch instruction, the return address (if any) is remembered and the analysis recursively starts at the branch target location. Once all analyses of the branch target are performed, the analysis resumes after the call/conditional jump instruction if necessary.

This approach:

- is slower;
- distinguishes code from data:
 - all locations not visited are considered to be data



Recursive Traversal II

Recursive traversal, in contrast to the linear sweep, disassembles code by watching its flow rather than linearly parsing all contents of the .text section. The traversal starts typically at the executable's entry point and disassembles the first instruction there. The code section with that instruction is marked as visited. If the instruction was a branch instruction, the return address (if any) is remembered and the analysis recursively starts at the branch target location. Once all analyses of the branch target are performed, the analysis resumes after the call/conditional jump instruction if necessary.

This approach:

- is slower;
- partially distinguishes code from data:
 - all locations not visited are considered to be data
 - but there are jump tables, indirectly called functions, etc.



Recursive Traversal III

Recursive Traversal [4]

```
procedure Disassemble( addr, instrList ) {
  if( addr.visited )
    return;
  do {
    instr = DecodeInstr( addr );
    addr.visited = true:
    add instr to instrList:
    if ( instr is a branch or function call ) {
      T = set of possible control flow successors of instr;
      for each target in T do {
        Disassemble( target, instrList);
    else
      addr += instr.length; /* addr of next instruction */
  } while addr is a valid instruction address;
```

Recursive Traversal Summary

- Recursive traversal is based on the assumption that we can identify all possible control flow successors of each control flow instruction.
- Control flow is watched and every address recursive traversal visits is marked as code.
- What will be the possible control flow when we encounter an indirect jump (jump to a jump table item, a computed goto, or a call through a VMT)? Easy to tell with a CFG, but we don't have one!
- What to do with the rest of the code segment that was not visited?
 - recursive traversal won't even try to disassemble that part and can't tell anything about it without further analyses.
 - **linear sweep** would disassemble it; some portions would disassemble well, others not since they are data.
- Recursive traversal has complementary strengths and weaknesses with linear sweep. Which one should we use? Let's try to improve both algorithms.

Extended Linear Sweep

Linear sweep could not deal with data embedded in the .text section such as jump tables and/or string constants. Such data caused disassembly errors by being improperly identified as instructions. **Linear sweep** can, however, be improved:

The Idea [4]

If we have relocation information available, jump tables in the .text section must have their entries in the relocation table. Based on the entries in the relocation table, we can identify possible jump tables within the .text section and mark them as data.

Each entry a_i in a jump table must satisfy [4]:

- \bullet the memory locations containing a_i are marked relocatable; and
- ② the address a_i itself must be within the .text section.



A Jump Table in the Program I

Let us verify the idea with the following program:

A sample jump table

```
switch (uintval) {
  case 0:
    func0():
    break;
  case 1:
    func1():
    break:
  case 2:
    func2():
    break:
  case 3:
    func3():
    break;
```

A sample a jump table (assembler)

```
text:00414838
                               [ebp+uintval], 3
                               short loc_414868
.text:0041483F
                               ecx. [ebp+uintval]
text:00414841
                          mov
                               ds:off 41490C[ecx*4]
text:00414847
                          qmi
.text:0041484E loc_41484E:
.text:0041484E
                          call func0
.text:00414853
                          jmp short loc_414868
.text:00414855 loc_414855:
                          call func1
text:00414855
                          imp short loc 414868
text:00414854
----- BEGIN of data in the .text section ------
.text:0041490C off 40C5E0 dd offset loc 41484E // case 0
.text:00414910
                         dd offset loc_414855 // case 1
.text:00414914
                         dd offset loc_41485C // case 2
.text:00414918
                          dd offset loc 414863 // case 3
----- END of data in the .text section ------
```

A Jump Table in the Program II

If we dump the .reloc section with dumpbin, we get this output:

```
C:\...\> dumpbin /RELOCATIONS jumptable.exe
                 8C SizeOfBlock
  14000 RVA,
                                          ----- REGIN of data in the text section -----
    90C HIGHLOW
                          0041484E
                                          .text:0041490C off_40C5E0 dd offset loc_41484E // case 0
       HTGHI.OW
                          00414855
                                          .text:00414910
                                                           dd offset loc_414855 // case 1
    910
    914
        HTGHI.OW
                          0041485C
                                           .text:00414914
                                                             dd offset loc 41485C // case 2
    918 HIGHLOW
                          00414863
                                           .text:00414918
                                                                  dd offset loc 414863 // case 3
                                          ----- END of data in the .text section ------
```

There are 4 consecutive items in the relocation table relocating 4 consecutive pointers in the .text segment. Since no more than 2 of them can form a part of an x86 instruction, the remaining 2 (loc. 00414914 and 00414918) must be data. The first 2 items could possibly be code.

Note: EXE file images not using ASLR normally do not have the .reloc section, unlike DLLs. When ASLR is enabled for an image, it must always be relocatable and thus have the .reloc section, as in the example above.

Extended Linear Sweep Continued

We have identified only 2 out of 4 items as data. We can partition the .text section into segments delimited by jump tables and then disassemble all code in between the segments, checking whether each disassembled instruction in front of the jump table was successfully disassembled and whether it overflowed into the data in between the segments. In case of an overflow, the instruction isn't instruction but data!

Extended Linear Sweep [4]

- Mark all jump table items as data, except for the first 2 in each table (on x86, these can form a part of an instruction).
- ② For each sequence of unmarked addresses in the .text segment:
 - a) Use **linear sweep**, stop when a marked location is reached.
 - b) If the last instruction overlaps into a marked location, mark it as data.
 - Examine the last correctly disassembled instruction, mark as data if necessary.

Hybrid Approach

Recursive traversal has complementary strengths and weaknesses with **linear sweep**. Let's combine the best of both approaches [4] and:

- Use extended linear sweep for the initial disassembly;
- Use **recursive traversal** to verify the disassembly of each function in the executable.

The verification is performed as follows:

- Recursive traversal is used for each instruction in each function;
- Each instruction I obtained at address a_I is checked. If it was not obtained also by the linear sweep, an error is raised.
- 3 If no error is produced for the function, report success.

Obfuscation — Motivation

The motivation for using obfuscation techniques is to keep your code secret and to make its comprehension difficult. Regular software uses these techniques to prevent people from reverse engineering serial number schemes, defeating copy protections, disabling hardware dongles, DRMs, etc. Malware uses these techniques frequently to resist analysis.

The purpose of these techniques is to:

- Occupant to the disassembler (the static analysis);
- confuse the debugger (the dynamic analysis);
- 3 confuse the decompiler;
- confuse the human reading the disassembly in either tool.

These techniques include code obfuscation, control flow transformations, encryption, checksumming, debugger detection and anti-debugger code, etc. The longer the analysis takes, the fewer people keep doing it:-).

Protection Taxonomy [1]

Intellectual protection can be classified as:

- legal protection
- technical protection
 - obfuscation
 - encryption
 - (partial) server-side execution
 - trusted native code

A transformation target can be modified using:

- layout obfuscation
- control obfuscation
- data obfuscation
- preventive transformation



Obfuscation Metrics I

Obfuscation

Obfuscation makes something obscure. Obfuscation in computer software is a process of changing the transformation target into an obfuscated target in a way which is difficult to comprehend while preserving the functionality of the target.

Transformation Target

Transformation target is an object to be obfuscated. The target can be a program's source code as well as its executable in a binary form.

Sample transformation targets:

- javascript code in your HTML pages;
- java classes and archives, .NET source files and executable code;
- PHP source code, C/C++ source code, ...;
- executables.



Obfuscation Metrics II

Obfuscated product is the transformation target after the application of a set of obfuscating transformations. Any of these transformations, besides not changing the original program's behavior, should be **potent**, **resilient**, and their **cost** should be minimal.

Potency [1]

The potency $\mathcal{T}_{pot}(P)$ of a transformed program P' measures how much the transformation of a program P confuses a human reader.

$$\mathcal{T}_{pot}(P) = E(P')/E(P) - 1,$$

where E(P) is the complexity of P calculated by **some** metric.

Metrics such as **program length**, **cyclomatic complexity**, **nesting complexity**, **data flow complexity**, . . . can be used; obfuscations increase the complexity of whatever a particular metric measures.



Obfuscation Metrics III

Resilience [1]

Resilience measures how difficult it is for an automatic deobfuscator to undo the transformation.

$$\mathcal{T}_{res} = \mathsf{Resilience}(\mathcal{T}_{deobfuscator \ effort}, \ \mathcal{T}_{programmer \ effort}),$$

where $\mathcal{T}_{programmer\ effort}$ is the amount of time required to create an auto-deobfuscator reducing \mathcal{T}_{pot} , while $\mathcal{T}_{deobfuscator\ effort}$ is the execution time and space required by the auto-deobfuscator to reduce \mathcal{T}_{pot} .

Resilience \mathcal{T}_{res} can be: **trivial**, weak, strong, full, or one-way.

$\mathcal{T}_{deob.eff.} \setminus \mathcal{T}_{prog.eff.}$	Local	Global	Inter-procedural	Inter-process
Polynomial	trivial	weak	strong	full
Exponential	weak	strong	full	full

Table: Resilience($\mathcal{T}_{deobfuscator\ effort}$, $\mathcal{T}_{programmer\ effort}$) [1].



Layout Obfuscations I

Layout obfuscations [1] target the lexical structure of the application. This includes the source code formatting, comments, variable and function names, layouts of classes and data structures, etc.

Before obfuscation:

```
static public float AverageStudentGrade(Student student) {
  float grade = 0.0f; float credits = 0.0f;
  /* Grade calculated as a weighted average g=sum(grade_i*credits_i)/sum(credits_i) */
  if( student.Courses().Empty() ) return 0.0f;
  for_each(course in student.Courses()) {
    grade += course.Credits() * course.Grade();
    credits += course.Credits();
  }
  return grade/credits;
}
```

After (comments removed, data types, methods, and classes renamed):

```
static public float a(a b) {
  float c = 0.0f; float d = 0.0f;
  if( b.a().a() ) return 0.0f;
  for_each(e in b.a()) {
    c += e.a() * e.b();
    d += e.a();
  }
  return c/d;
```

Layout Obfuscations II

Transformation	Potency	Resilience	Cost
Scramble identifiers	medium	one-way	free
Change formatting	low	one-way	free
Remove comments	high	one-way	free
Remove debug info	high	one-way	free

Table: Quality of Layout Obfuscations [1].

Control Flow Transformations

Control flow transformations obfuscate the control flow. They can be divided into **aggregation**, **ordering**, and **computation** transformations [1].

- Aggregation transformations break apart computations belonging together and merge computation that do not.
- Ordering transformations randomize the order of computations.
- Computation transformations add redundant and/or dead code or make algorithmic changes.

Many control flow obfuscations depend on the use of **opaque variables** and **opaque predicates**.

Opaque Predicates and Variables I

A variable or predicate is opaque if its value or property is known to the obfuscator at the obfuscation time but is difficult for the deobfuscator to deduce [1].

An opaque construct consists of an **if** statement testing the value of an opaque predicate or variable ovar for a specific value VAL which was known at the obfuscation time:

Our primary purpose is to confuse both the disassembler and any human being studying our code. Let's look at the disassemblers first.

Opaque Predicates and Variables II

Linear sweep is poor at distinguishing code from data and thus vulnerable to data (junk, jump tables, ...) inside (or in between) functions. We will use this fact to combine the never-to-be executed branch of an opaque predicate with junk data. We can produce such data within the _asm block with the _emit keyword:

The _emit keyword is used to insert an opcode of a jmp instruction into the binary. **Linear sweep** disassemblers will typically understand the imul instruction as a part of the emitted jmp instruction's address.

Opaque Predicates and Variables III

```
216 00f0482f 33c0 xor eax.eax
217 00f04831 83f801 cmp eax.]
218 00f04834 7501 jne HelloWorld|wWinMain+0xb7 (00f04837)

HelloWorld|wWinMain+0xb6 [c:\users\tomas zahradnicky\documents\visual stud
219 00f04836 e9f7ea8b45 jmp 67c3332

HelloWorld|wWinMain+0xb7 [c:\users\tomas zahradnicky\documents\visual stud
220 00f04837 f7ea imul edx
```

Figure: WinDbg 6.12.0002.633

Figure: OllyDbg 1.10

Figure: OllyDbg 2.01

The fact that the code beyond the never_execute label is never executed is easily detected with **recursive traversal**.

Opaque Predicates and Variables IV

```
Figure: IDA Pro 6.7 initial.
```

.text:0041482F	XO		, eax
.text:00414831	cm	p eax	, 1
.text:00414834	jn	z shoi	rt loc 414837
.text:00414834	:		
.text:00414836	db	0E9h	
.text:00414837	:		
.text:00414837			
.text:00414837	loc 414837:		
.text:00414837	- im	ul edx	

Figure: IDA Pro 6.7 corrected.

Note: Although the transformation could fool a disassembler, it is trivially correctable by a human. We find the potency **low**. This construct could be handled by an automatic deobfuscator in a polynomial time within the local procedure scope. For these reasons the resilience is **trivial**. The cost is, however, **cheap** and that's why it is so popular.

Let's use an **opaque predicate** to fool both recursive and linear disassemblers. The code below loads security cookie from the stack 1 and exclusively ors it with the ebp value 2. The same code is used at the end of any function using canaries. Our code uses it as an opaque value.

The xor'd value in eax at 2 might theoretically be zero, but it is very unlikely $(1:2^{32})$. When nonzero 3, continue to 7. This is the normal control flow. The disassembler is unable to tell whether the condition is always true or not since it is calculated at runtime. The <code>_emit</code> at line 4 creates a random <code>jxx</code> instruction jumping 0x00 bytes behind it 5, that is at the another <code>_emit</code> at line 6. This <code>_emit</code> generates the first byte of a random <code>jmp</code> or call instruction. The remaining bytes are taken from instructions following the macro.

The OBFUSCATE macro takes a _random value as an argument in order to generate slightly different assembly each time it is used. There are 64 possible combinations it can generate.

```
OBFUSCATE(238);
cbSelf.QuadPart = 0;
OBFUSCATE(372);
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
OBFUSCATE(118);
CreateConsole();
OBFUSCATE(235);
```

```
OBFUSCATE(238):
cbSelf.QuadPart = 0;
OBFUSCATE(372);
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
                              8B45 FC
OBFUSCATE(118):
                              75 03
                                                             HelloWor,010DCC7E
CreateConsole();
                              ZE
EA
                                 ØF57CØ66 ØF13
                                                      FAR 130F:66C0570F
OBFUSCATE(235);
                              ΕĊ
                              8B45 FC
                                                       EAX.DWORD PTR SS:[EBP-4]
                              75 03
                                                       SHORT HelloWor.010DCC90
                              74 00
                                                            HelloWor.010DCC8F
                                                   DB
                              EΒ
                              8D45 EC
                                                   EA EAX.DWORD PTR SS:[EBP-14]
                              8D45 10
                                                       EAX.DWORD PTR SS:[EBP+10]
                              8055 FC
                                                       EDX.DWORD PTR
                                                       ECX.DWORD PTR SS:[EBF
                                 10010000
                                                          lloWor.010DCDC0
                                                      ESP,8
EAX.DWORD PTR SS:[EBP-4]
                              8845 FC
                                                          ŔT HelloWor.010DCCB0
                              75 03
                              76 00
                                                             HelloWor.010DCCAF
                              ĒΒ
                                                   DB EB
                                                        HelloWor.010DCEA0
```

```
OBFUSCATE(238);
cbSelf.QuadPart = 0;
OBFUSCATE(372);
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
                                8B45 FC
                                              MOV EAX.DWORD PTR SS:[EBP-4]
OBFUSCATE(118): 00C1CC77
                                33C5
75 03
7E 00
EA 8D4
                                              XOR EAX.EBP
CreateConsole();00C1CC79
                                              JNE SHORT 00C1CC7E
                                              JLE SHORT 0001007D
                                   8D45EC0F
                                              JMP FAR C057:0FEC458D
OBFUSCATE(235);
                   00C1CC84
                                              DB 50
                                8Ď
                                              DB 8D
                                              DB
                                                 45
                                              DB
                                                 66
                                              DB
                                                 ØF
                                                 13
                   00C1CC8A
                                              DB
                   00C1CC8B
                                45
                                              DB 45
                                ÉČ
                                              DB ÉC
                   00C1CC8C
                   AAC1CC8D
                                508D55FC
                                              DD FC558D50
                                8D
                                              DB 8D
                   00C1CC92
                                4Đ
                                              DB 4D
                   ØØC1CC93
                                              DB F8
                   00C1CC94
                                              DB E8
                   00C1CC95
                                              DB F7
```

```
OBFUSCATE(238):
cbSelf.QuadPart = 0;
OBFUSCATE(372):
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
                      .text:0040CC74
                                                    mov
                                                           eax. [ebp-41
OBFUSCATE(118): .text:0040CC77
                                                    xor
                                                           eax, ebp
                                                           short near ptr loc_40CC7D+1
                                                    inz
CreateConsole():
                                                    ile
                                                           short $+2
                      .text:0040CC7D
OBFUSCATE(235);
                                                                           : CODE XREF: .text:0040CC7Bfi
                      .text:0040CC7D loc 40CC7D:
                      .text:0040CC7D
                                                                           ; .text:0040CC791j
                      .text:0040CC7D
                                                    imp
                      .text:0040CC7D
                      .text:0040CC84
                                                    dd 10458D50h, 45130F66h, 558D50ECh, 0F84D8DFCh, 0F7E8h
                      .text:0040CC84
                                                    dd 1D2E800h. 0A6A0000h. 50F4458Dh. 5045E856h. 758BFFFFh
                                                    dd 14C48310h, 5589CE8Bh, 0E8F88BE8h, 224h, 774F685h
                      .text:0040CC84
                                                    db 56h, 0FFh, 15h
                      .text:0040CCC0
                      .text:0040CCC3
                                                    dd offset UnmapViewOfFile
                      .text:0040CCC7
                                                    dh 8Bh
                      .text:0040CCC8
                                                    dd 358BEC45h
                      .text:0040CCCC
                                                    dd offset CloseHandle
                      .text:0040CCD0
                                                    dd 74FFF883h, 0D6FF5003h, 83F8458Bh, 374FFF8h, 0EBD6FF50h
                      .text:0040CCD0
                                                    dd 0F8C1E901h. 83C03302h. 17501F8h. 83EAF7E9h. 2E7703FFh
                      .text:0040CCF8
```

Let's see how it works on this C code:

```
OBFUSCATE(238);
cbSelf.QuadPart = 0;
OBFUSCATE(372);
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
OBFUSCATE(118);
CreateConsole();
OBFUSCATE(235);
```

Though our efforts confused both **linear sweep** and **recursive traversal** disassemblers and perhaps some human being too, our construct is only slightly more **potent** than the previous one. Regarding its **resilience**, it is also slightly better. The opaque value we use is the stack canary. We could use the return address as well. Static analyses should not be able to predict, unless they discover what is really tested, the value of the variable. Anyway the **resilience** is **weak**. How could we improve this?

Computation Transformations

Computation transformations are control flow transformations that **hide the real control-flow** behind **irrelevant statements**, add code for which there are no high level language constructs, **insert dead code**, or remove real control-flow abstractions or introduce spurious ones [1]. This includes:

- Insertion of dead or irrelevant code
- Extension of loop conditions
- Conversion of a reducible flow graph to non-reducible
- Removal of library calls and programming idioms
- Table interpretation
- Addition of redundant operands
- Code parallelization

Insertion of Dead or Irrelevant Code I

These transformations insert code which is not relevant to the original code in order to confuse the reader. This can be achieved by insertion of a never-execute branch behind an opaque predicate, or by adding code that is completely irrelevant to the original functionality.

Opaque predicates can be inserted somewhere into a code block. We can go further and place a portion of the original code in the true branch of the predicate and the same thing in the false branch, but with different obfuscation transformations. The result will be the same. Another possibility is to slightly change the false branch to evaluate to something (slightly) different.

Irrelevant code might e.g. perform similar computation but store its result in a different location.

Insertion of Dead or Irrelevant Code II

We have already seen an example of doing this:

```
OBFUSCATE(238);
cbSelf.QuadPart = 0;
OBFUSCATE(372);
MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
OBFUSCATE(118);
CreateConsole();
```

The code inserted by the OBFUSCATE macro used an opaque variable, the stack canary, to create a dead branch that never executed.

Another example:

Extension of Loop Conditions

Extending loop conditions makes loop termination more complex by using an opaque predicate or variable in the bounds checking condition:

text:0040CDA5

.text:0040CDA6

.text:0040CDA0 sub 40CDA0

.text:0040CDA2 loc_40CDA2:

```
char array[10];
unsigned int i;
for( i=0; i<10; ++i )
{
    array[i] = i;
}</pre>
```


May become:

```
.text:0040CD70 sub 40CD70
                              push esi
.text:0040CD71
                                   esi, ecx
                                                  // i
.text:0040CD73
                                   edx, edx
                              xor
                                   ecx, 1
.text:0040CD75
                                   eax, eax
.text:0040CD7A
                              xor
.text:0040CD7C
                                   esp, [esp+0]
                                                 // align no-op
                              test cl. 1
.text:0040CD80 loc 40CD80:
.text:0040CD83
                                   short loc 40CD98
                                   eax, OAAh
.text:0040CD85
.text:0040CD9A
                                   short loc_40CD98
                                   ecx, eax
.text:0040CD8C
.text:0040CD8F
                                   [edx+esi], dl
.text:0040CD92
                              add
                                   eax, 11h
.text:0040CD95
                              inc
                                   edv
.text:0040CD96
                                   short loc 40CD80
.text:0040CD98 loc_40CD95:
                              qoq
                                   esi
                            □retri □ > 4 ≥ > 4 ≥ >
text:0040CD99
```

mov

inc ear

cmp

eax, eax

eax, OAh

[eax+ecx], al

short loc_40CDA2

Conversion of a Reducible CFG to Non-Reducible I

The purpose of this obfuscation is to make the flow graph of a function complex and prevent its decompilation.

- The flow graph of a function is reducible if it only uses structured statements, e.g. for-loops, do-while-loops, while-loops, if-then(-else), break, and continue.
- Once you start using goto easy in C/C++, impossible in Java (but possible in Java bytecode (!)) the flow graph becomes ireducible.
- Ireducible flow graphs make for a nasty high level code. This is especially evident in Java where goto is not available.
- The use of constructs that are not available in the high level language also falls into this category.

Conversion of a Reducible CFG to Non-Reducible II

Let's start with a simple Java program and explore its bytecode [5]:

```
public class a
                                           .method public static main([Liava/lang/String:)V
                                           .limit stack 3
 static public void main(String[] args)
                                           limit locals 2
                                             iconst 0
                                             istore_1; met002_slot001
   int i;
   for(i=0: i<10: ++i)
                                           met002 2:
                                             iload_1; met002_slot001
      System.console().writer().
                                             bipush 10
       println("Step: " + i):
                                             if icmpge met002 42
                                             invokestatic java/lang/System.console()Ljava/io/Console;
                                             invokevirtual java/io/Console.writer()Ljava/io/PrintWriter:
                                             new java/lang/StringBuilder
                                             dup
                                             invokespecial java/lang/StringBuilder.<init>()V
                                             ldc "Step:
                                             invokevirtual java/lang/StringBuilder.append(Ljava/lang/Str
                                               ing;)Ljava/lang/StringBuilder;
                                             iload_1; met002_slot001
                                             invokevirtual java/lang/StringBuilder.append(I)Ljava/lang/StringBui
                                             invokevirtual java/lang/StringBuilder.toString()Ljava/lang/String;
                                             invokevirtual java/io/PrintWriter.println(Ljava/lang/String;)V
                                             iinc 1 1
                                             goto met002 2
                                           met002_42:
                                             return
```

.end method

Conversion of a Reducible CFG to Non-Reducible III

```
.method public static main([Ljava...
.limit stack 3
limit locals 2
  iconst 0
  istore_1; met002_slot001
met002 2:
  iload_1; met002_slot001
  bipush 10
  if icmpge met002 42
  invokestatic java/lang/System.con...
  invokevirtual java/io/Console.wri...
  new java/lang/StringBuilder
  dup
  invokespecial java/lang/StringBui...
  ldc "Step:
  invokevirtual java/lang/StringBui...
  iload 1 : met002 slot001
  invokevirtual java/lang/StringBui...
  invokevirtual java/lang/StringBui...
  invokevirtual java/jo/PrintWriter...
  iinc 1 1
  goto met002_2
met002 42:
  return
.end method
```

```
// Decompiled by Jad v1.5.8e. Copyright 2001 Pavel Kouznetsov.
// Jad home page: http://www.geocities.com/kpdus/jad.html
import java.jo.Console:
import java.io.PrintWriter;
public class a
 public a() { }
 public static void main(String args∏)
    for(int i = 0; i < 10; i++)
     System.console().writer().println((new StringBuilder()).
       append("Step: ").append(i).toString());
    }
}
// Decompiled by JD-GUI 1.0.0, JD-Core 0.7.1
// JD home page: http://id.benow.ca/
import java.jo.Console:
import java.io.PrintWriter;
public class a
 public static void main(String[] paramArrayOfString)
    for (int i = 0; i < 10; i++) {
     System.console().writer().println("Step: " + i);
   }
 }
                         4 D F 4 D F 4 D F 4 D F
```

Conversion of a Reducible CFG to Non-Reducible IV

As you have seen, the decompiler was very accurate. Now, let's try to insert an opaque predicate with a goto statement. The predicate will call the java.util.Random.nextInt() method to get a random number. The result will always be in the interval [0, 9].

```
new java/util/Random ; Create a new instance of the class
dup ; Duplicate the stack top
invokespecial java/util/Random.<init>()V ; Call the ctor, result is void
bipush 10 ; Push byte as int
invokevirtual java/util/Random.nextInt(I)I ; Call nextInt(10), result is int
```

Now the stack top contains a random number, let's compare it with 10.

```
bipush 10 ; Push byte as int if_icmpge never ; If random >= 10 GOTO never
```

Let's test for a different high bound in the first iteration:

```
iload_1
bipush 12
goto test_bounds
```

Conversion of a Reducible CFG to Non-Reducible V

```
.method public static main([Ljava/lang/String;)V
.limit stack 4
limit locals 2
  iconst 0
  istore_1; met002_slot001
 new java/util/Random
  dup
  invokespecial java/util/Random.<init>()V
 bipush 10
  invokevirtual java/util/Random.nextInt(I)I
  bipush 10
  if_icmpge never
 iload 1
 bipush 12
  goto test bound
loop_start:
  iload_1
  bipush 10
test bound:
  if_icmpge met002_42
  invokestatic java/lang/System.console()Ljava/io/Console;
  invokevirtual java/io/Console.writer()Ljava/io/PrintWriter;
 new java/lang/StringBuilder
 dup
  invokespecial java/lang/StringBuilder.<init>()V
  ldc "Step:
  invokevirtual java/lang/StringBuilder.append(Ljava/lang/String;)Ljava/lang/StringBuilder;
```

Conversion of a Reducible CFG to Non-Reducible VI

```
iload_1
   invokevirtual java/lang/StringBuilder.append(I)Ljava/lang/StringBuilder;
    invokevirtual java/lang/StringBuilder.toString()Ljava/lang/String;
    invokevirtual java/io/PrintWriter.println(Ljava/lang/String;)V
  never:
    iinc 1 1
   goto loop_start
 met002 42:
    return
  end method
// Decompiled by JD-GUI 1.0.0, JD-Core 0.7.1
// JD home page: http://jd.benow.ca/
import java.io.Console;
import java.io.PrintWriter;
import java.util.Random;
public class b
 public static void main(String[] paramArrayOfString)
    int i = 0:
    if (new Random().nextInt(10) < 10)
      tmpTernaryOp = 12;
      System.console().writer().println("Step: " + i);
   i++:
```

Conversion of a Reducible CFG to Non-Reducible VII

```
// Decompiled by Jad v1.5.8e. Copyright 2001 Pavel Kouznetsov.
// Jad home page: http://www.geocities.com/kpdus/jad.html
import java.io.Console;
import java.io.PrintWriter;
import java.util.Random;
public class b
 public b() { }
 public static void main(String args[])
   int i = 0:
    if((new Random()).nextInt(10) >= 10) goto _L2; else goto _L1
 _L1:
   i: 12: goto L3
 _L7:
   i; 10;
  L3:
    JVM INSTR icmpge 65; goto _L4 _L5
 _L4:
   break MISSING_BLOCK_LABEL_31;
 L5:
   break; /* Loop/switch isn't completed */
   System.console().writer().println((new StringBuilder()).append("Step: ").append(i).toString());
  L2:
   i++; if(true) goto _L7; else goto _L6
  _L6:
```

Conversion of a Reducible CFG to Non-Reducible VIII

Decompilers got confused by using the goto statement. If we do the same thing in C, we find that this method is not very efficient here:

```
__declspec(noinline)
                                                              sub esp. 8
                                               .text:0040CDC0
void LoopsIred1(volatile char* array) {
                                               .text:0040CDC3
                                                              push esi
  int i:
                                               .text:0040CDC4
                                                              push edi
                                               .text:0040CDC5 mov [esp+10h+var 8], ecx
  asm{
                                               .text:0040CDC9 mov esi, [esp+10h+var_8]
   mov esi, array
                                               .text:0040CDCD
                                                              mov edi, esi
   mov edi. esi
                                               .text:0040CDCF
                                                              mov eax, ___security_cookie_complement
                                               .text:0040CDD4
                                                              xor eax, ___security_cookie
                                               .text:0040CDDA
                                                              jnz short never_taken
  // Opaque predicate, always false
                                               .text:0040CDDC
                                                              xor edx. edx
  if ((__security_cookie
                                               .text:0040CDDE
                                                              jmp short loc_40CDE9
        __security_cookie_complement) != 0)
                                               .text:0040CDE0
                                                              mov edx, [esp+10h+var_4]
   goto insideloop:
                                               text:0040CDE4
                                                              lodsh
                                                              ror al. 1
  for (i = 0; i < 10; ++i) {
                                               text:0040CDE5
                                               .text:0040CDE7
                                                               stosb
   arrav[i] = i:
                                               .text:0040CDE8
                                                              inc edx
   insideloop:
                                               .text:0040CDE9
                                                              cmp edx. OAh
    _asm {
                                               .text:0040CDEC
                                                               ige short loc_40CDF3
      lodsh
                                               .text:0040CDEE
                                                              mov [edx+ecx], dl
     ror al,1
                                               .text:0040CDF1
                                                               jmp
                                                                   short loc 40CDE4
      stosb
                                               .text:0040CDF3
                                                               pop
                                                                   edi
                                               .text:0040CDF4
                                                                   esi
                                                               qoq
                                               .text:0040CDF5
                                                                   esp. 8
                                                               add
                                               text:0040CDF8 retn
```

Conversion of a Reducible CFG to Non-Reducible IX

```
char usercall sub 40CDC0@<al>(char *pArray@<ecx>) {
  char *v1;
            // esi@1
  char *v2;  // edi@1
  char result; // al@1
  signed int i: // edx@2
 char v5; // al@4
  signed int v6: // [sp+Ch] [bp-4h]@0
 v1 = pArray;
 v2 = pArray;
  result = __security_cookie ^__security_cookie_complement;
 if ( __security_cookie != __security_cookie_complement ) {
   i = v6:
   goto LABEL 4:
  }
 for ( i = 0: i < 10: ++i ) {
   pArray[i] = i;
   LABEL_4:
   v5 = *v1++:
   result = __ROR1__(v5, 1);
   *v2++ = result;
 return result;
```

As you can see, our obfuscation is not effective against C/C++. IDA was able to decompile it almost perfectly, including the ror instruction. If we were in Java, the situation would be very different because there wouldn't be a goto to use!

Conversion of a Reducible CFG to Non-Reducible X

Apparently potency depends on the language being obfuscated and the quality of the opaque predicate. If we are obfuscating Java, the potency is **medium** to **high**, as we are using bytecode instructions that have no corresponding high-level counterparts. In C, the potency is **low** to **medium**.

Resilience strongly depends on the deobfuscator.

The cost of this obfuscation is **low**.

Removal of Library Calls and Programming Idioms

Calls to library functions can tell reverse engineers a lot about our program. These calls cannot be renamed by the obfuscator. The way to obfuscate them is to provide an obfuscator-developed alternatives and use these alternatives instead of the original APIs. Such APIs include string manipulation functions, memory allocation, STL classes, etc. All of these can be replaced by alternative implementations which can be renamed and obfuscated. This increases program size and is quite potent (medium) and provides a strong resilience. The cost depends on what we want to replace.

Changing commonly used programming idioms such as traversing a linked list, arrays, etc., also falls under this category. Can we replace a linked list with something else?

Table Interpretation I

This obfuscation has a **strong** resilience, but it is also **costly**. Its simplest form requires splitting a portion of a program's code into several (or many) chunks and using a loop to iterate through many iterations, each of them running only one of the chunks. A **switch** statement, computed **gotos** or jump tables can be used. If we want to add extra resilience, the table might even have 2 or more levels!

This table approach can be interpreted as running the chunked program under a mini virtual machine. Each chunk has its number and represents an opcode of a "VM-instruction". A list of chunk numbers is then the VM's program! If we want to go even further, each of these instructions could have its own operands, there can be registers, variables, etc.

Table Interpretation II

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
                                                               LPTSTR lpCmdLine.
 int nCmdShow
                                                               int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*1*/ cbSelf.QuadPart = 0;
 /*2*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*3*/ CreateConsole();
 /*4*/ ExamineRelocations( pSelf, cbSelf );
 /*5*/ UnmapSelfFromMemorv(hFile, hMapping, pSelf):
  /*6*/ return 0;
```

```
int WINAPI _tWinMainAsTable(
   HINSTANCE hInstance,
   HINSTANCE hPrevInstance,
   LPTSTR lpCmdLine,
   int nCmdShow
)
{
   HANDLE hFile = INVALID_HANDLE_VALUE;
   HANDLE hMapping = INVALID_HANDLE_VALUE;
   LPVOID pSelf = NULL;
   LARGE_INTEGER cbSelf;

// The program is the same up to this point!

// Now, let us define instructions of our VM.
// That is, one instruction for each line
// on the left marked with an a /*#*/.
// We will add a no-op instruction too!
```

Table Interpretation III

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*5*/ cbSelf.QuadPart = 0;
 /*1*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*4*/ CreateConsole();
 /*0*/ ExamineRelocations( pSelf, cbSelf );
 /*3*/ UnmapSelfFromMemory(hFile, hMapping, pSelf);
 /*6*/ {}
 /*2*/ return 0;
```

```
int WINAPI tWinMainAsTable(
 HINSTANCE hInstance,
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 typedef enum instr {
    instr init size = 5, instr map file = 1,
    instr_create_console = 4, instr_return = 2
    instr_examine_relocations = 0, instr_nop = 6
   instr_unmap_file = 3
 l instr:
 // Instructions were numbered randomly.
 // Space conserved, they are not in order.
 // This has no impact on the program.
```

// Now let's create a program for our VM.
// --- a sequence of the above instructions.

Table Interpretation IV

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*5*/ cbSelf.QuadPart = 0;
 /*1*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*4*/ CreateConsole();
 /*0*/ ExamineRelocations( pSelf, cbSelf );
 /*3*/ UnmapSelfFromMemory(hFile, hMapping, pSelf);
 /*6*/ {}
 /*2*/ return 0;
```

```
int WINAPI tWinMainAsTable(
 HINSTANCE hInstance,
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 typedef enum instr {
    instr init size = 5, instr map file = 1,
    instr_create_console = 4, instr_return = 2
    instr_examine_relocations = 0, instr_nop = 6
   instr_unmap_file = 3
 l instr:
 static instr g_Instructions[] = {
    instr_nop, instr_init_size, instr_map_file,
   instr_nop, instr_create_console, instr_nop,
   instr_examine_relocations, instr_nop,
   instr_unmap_file, instr_nop, instr_return
 1:
 // Now add the VM as a switch statement.
```

Table Interpretation V

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*5*/ cbSelf.QuadPart = 0;
 /*1*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*4*/ CreateConsole();
 /*0*/ ExamineRelocations( pSelf, cbSelf );
 /*3*/ UnmapSelfFromMemory(hFile, hMapping, pSelf);
 /*6*/ {}
 /*2*/ return 0:
```

```
typedef enum instr {
  instr_init_size = 5, instr_map_file = 1,
  instr create console = 4, instr return = 2
  instr examine relocations = 0, instr nop = 6
  instr_unmap_file = 3
} instr;
static instr g Instructions [] = {
  instr_nop, instr_init_size, instr_map_file,
  instr_nop, instr_create_console, instr_nop,
  instr examine relocations, instr nop,
  instr_unmap_file, instr_nop, instr_return
};
for (
  unsigned int i = 0:
  i < sizeof(g_Instructions) / sizeof(instr);</pre>
  switch (g_Instructions[i])
    // Case branches not shuffled for clarity
    case instr_init_size:
      cbSelf.QuadPart = 0:
      break:
    case instr_map_file:
      MapSelfIntoMemory(hFile, hMapping,
        pSelf, cbSelf);
      break:
    case instr_create_console:
      CreateConsole();
      break:
```

4 D > 4 A > 4 B > 4 B >

Table Interpretation VI

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*5*/ cbSelf.QuadPart = 0;
 /*1*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*4*/ CreateConsole();
 /*0*/ ExamineRelocations( pSelf, cbSelf );
 /*3*/ UnmapSelfFromMemory(hFile, hMapping, pSelf);
 /*6*/ {}
 /*2*/ return 0:
```

```
static instr g_Instructions[] = {
  instr_nop, instr_init_size, instr_map_file,
  instr nop, instr create console, instr nop,
  instr_examine_relocations, instr_nop,
  instr_unmap_file, instr_nop, instr_return
};
for (
  unsigned int i = 0;
  i < sizeof(g_Instructions) / sizeof(instr);</pre>
  ++i
  switch (g Instructions[i])
    // Case branches not shuffled for clarity
    case instr_init_size:
      cbSelf.QuadPart = 0;
      break;
    case instr map file:
      MapSelfIntoMemory(hFile, hMapping,
        pSelf, cbSelf);
      break:
    case instr_create_console:
      CreateConsole():
      break:
    case instr_examine_relocations:
      ExamineRelocations(pSelf, cbSelf):
      break;
    case instr unmap file:
      UnmapSelfFromMemory(hFile, hMapping, pSelf);
      break:
            4 D > 4 A > 4 B > 4 B >
```

Table Interpretation VII

```
int WINAPI tWinMain(
 HINSTANCE hInstance.
 HINSTANCE hPrevInstance,
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID HANDLE VALUE:
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL;
 LARGE INTEGER cbSelf:
 /*5*/ cbSelf.QuadPart = 0;
 /*1*/ MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 /*4*/ CreateConsole():
 /*0*/ ExamineRelocations( pSelf, cbSelf );
 /*3*/ UnmapSelfFromMemory(hFile, hMapping, pSelf);
 /*6*/ {}
 /*2*/ return 0:
static instr g Instructions [] = {
 instr_nop, instr_init_size, instr_map_file,
 instr_nop, instr_create_console, instr_nop,
 instr examine relocations, instr nop.
 instr_unmap_file, instr_nop, instr_return
};
```

```
for (
  unsigned int i = 0;
  i < sizeof(g Instructions) / sizeof(instr);</pre>
  ++i
  switch (g_Instructions[i])
    // Case branches not shuffled for clarity
    case instr init size:
      cbSelf.QuadPart = 0:
      break:
    case instr_map_file:
      MapSelfIntoMemory(hFile, hMapping,
        pSelf, cbSelf):
      break:
    case instr_create_console:
      CreateConsole():
      break;
    case instr examine relocations:
      ExamineRelocations(pSelf, cbSelf):
      break;
    case instr_unmap_file:
      UnmapSelfFromMemory(hFile, hMapping, pSelf);
      break;
    case instr_nop: break;
    case instr return: return 0:
 }
```

Table Interpretation VIII




Figure: wWinMain as table interpretation.

Table Interpretation IX

As we have seen, our simple program got completely changed by the obfuscation. The heart of the function now lies in the

```
jmp dword ptr ds:[0040c804+4*eax]
```

instruction. The jump table is a global variable, as is the VM-program at 00410e10.

```
.rdata:00410E10 dword_410E10 dd 6, 5, 1, 6
.rdata:00410E20 dd 4, 6, 6, 0
.rdata:00410E30 dd 6, 3, 6, 2
```

The amount of code has grown significantly so this transformation's potency is **high** with respect to the code size metric. The transformation has a **strong** resilience. Transforming a program into the table form is, unfortunately, **costly**.

Addition of Redundant Operands I

Redundant operands increase the program's length and complexity. Not only can we add redundant operands to function/method calls, but we can also extend arithmetic expressions by using opaque variables.

Note: We have to be careful as performing redundant operations on floating point numbers will result in additional rounding and will have an impact on the accuracy of the computed variable.

We might have already noticed the use of this method in the example for extending loop conditions. The second loop iterator j was redundant, as were all the calculations with it.

Addition of Redundant Operands II

```
int RedundantOps( int iRedundantBound ) {
                                                   .text:000AC780
                                                                   xor
                                                                         ecx. ecx
    int i;
                                                   .text:000AC782
                                                                   push
                                                                         ebx
    static unsigned char array[256];
                                                   .text:000AC783
                                                                         edx. [ecx-1]
                                                                   lea
    static unsigned char oarrav[256]:
                                                                         al, dl
                                                   .text:000AC786
                                                                   mov
                                                   .text:000AC788
                                                                   lea
                                                                         ebx, [ecx+1]
    for( i=0; i<iRedundantBound; ++i ) {</pre>
                                                   .text:000AC78B
                                                                   imul
                                                                         d1
      oarrav[i] = (i + 1)*(i + 1):
                                                   .text:000AC78D
                                                                   mov
                                                                         dl. al
      oarray[i]-= (i - 1)*(i - 1);
                                                   .text:000AC78F
                                                                         al. bl
                                                                   mov
      array[i]=oarray[i]-3*i;
                                                   .text:000AC791
                                                                   imul
                                                                         b1
                                                   text:000AC793
                                                                   sub
                                                                         al, dl
                                                                         dl. cl
    return 0:
                                                   text:000AC795
                                                                   mov
                                                   .text:000AC797
                                                                         d1. d1
                                                                   add
                                                   text:000AC799
                                                                         byte B3F60[ecx], al
                                                                   mov
                                                                         ebx. [edx+ecx]
                                                   .text:000AC79F
                                                                   lea
Here we have added a redundant
                                                   .text:000AC7A2
                                                                         al, bl
                                                                   sub
                                                                         byte_B4060[ecx], al
                                                   .text:000AC7A4
                                                                   mov
argument int iRedundantBound to
                                                   text:000AC7AA
                                                                   inc
                                                                         ecx
the function and also a redundant opaque
                                                                         ecx, 100h
                                                   .text:000AC7AB
                                                                   cmp
                                                                         short loc_AC783
array static unsigned char oarray.
                                                   .text:000AC7B1
                                                   .text:000AC7B3
                                                                         eax, eax
                                                                   xor
The iRedundantBound argument contains
                                                   .text:000AC7B5
                                                                   gog
                                                                         ebx
```

array is used only as a scratch space to calculate $(i+1)^2 - (i-1)^2 - 3i = i$. The result then initializes array [i]=i. The amount of code has grown so the potency of this transformation is medium to high, but the resilience of the transformation is weak. The transformation is cheap.

.text:000AC7B6

retn

MIE-REV, 2019, Lecture 4

the upper array bound and will always be

set to 256 by the obfuscator. The opaque

Code Parallelization I

Threads are used to make multiple operations run in parallel by partitioning a problem into smaller chunks, solving them in parallel and the assembling the computed result together. This principle can also be used to obfuscate code:

- If the blocks are data-independent: let each thread evaluate one block from the sequence.
- If the blocks are data-dependent: make a sequence of code blocks and let the first thread execute the first block, then unblock the second thread to execute the second code block, etc.
- Create one or more threads doing nothing useful (updating opaque predicates, throwing exceptions, ...).

Code Parallelization II

Code parallelization's potency is **high** because parallel programs are difficult to understand. The resilience is **strong** because any automatic deobfuscator must consider all threads and their possible interactions within the program. This can lead to up to O(n!) complexity! The transformation of a program into parallel is **costly**.

Parallelization is usually done by means of threads. For extra resilience (full) we can move portions of the code into one or more separate processes and use some form of interprocess communication mechanisms (shared memory, named and anonymous pipes, shared files, local and remote network sockets, RPC endpoints, ...) to run target's code in parallel.

Code Parallelization III

```
int WINAPI _tWinMain(
 HINSTANCE hInstance,
 HINSTANCE hPrevInstance.
 LPTSTR lpCmdLine,
 int nCmdShow
 HANDLE hFile = INVALID_HANDLE_VALUE;
 HANDLE hMapping = INVALID_HANDLE_VALUE;
 LPVOID pSelf = NULL:
 LARGE_INTEGER cbSelf;
 cbSelf.QuadPart = 0:
 MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
 CreateConsole():
 ExamineRelocations( pSelf, cbSelf );
 UnmapSelfFromMemorv(hFile, hMapping, pSelf):
 return 0:
```

Here each line of the program is transformed into a separate thread. Thread1 and Thread2 can run in parallel. Thread3 must wait until both finish their work. Thread4 must wait for Thread3 and uses Windows events to do that. Thread5 must again wait for Thread4.

```
volatile LONG __declspec(align(8))
  g_ThreadOneTwoDone = 0;
LPVOID WINAPI Thread1(LPVOID pUserData) {
  LARGE_INTEGER* pcbSelf = (LARGE_INTEGER*)pUserData;
  pcbSelf->QuadPart = 0:
  InterlockedIncrement( &g_ThreadOneTwoDone );
  return 0;
LPVOID WINAPI Thread2(LPVOID pUserData) {
  CreateConsole();
  InterlockedIncrement( &g ThreadOneTwoDone ):
  return 0;
LPVOID WINAPI Thread3(LPVOID pUserData) {
  while( g_ThreadOneTwoDone != 2 )
  MapSelfIntoMemory(hFile, hMapping, pSelf, cbSelf);
  SetEvent(...): /* unblock thread 4 */
  return 0:
LPVOID WINAPI Thread4(LPVOID pUserData) {
  WaitForSingleObject(...); /* wait for thread 3 */
  ExamineRelocations( pSelf, cbSelf );
  SetEvent(...); /* unblock thread 5 */
  return 0:
               4 D > 4 A > 4 B > 4 B >
```

Inlining I

Inlining is a process of copying a function's body to all locations the function is called from.

Compilers use inlining during the optimization phase for short functions, constructors, etc., to save on the prologue and epilogue code, passing arguments and issuing a call instruction.

```
int F1()
                                                                            int main()
int main()
                            f1;
                                                                               m1;
  m1:
                            f2;
                                                                               f1;
                                             \rightarrow inlining \rightarrow
  F1();
                                                                               f2:
  m2:
                                                                               m2;
                         int G1()
  G1():
                                                                               g1;
  m3;
                                                                               m3:
                            g1;
```

Functions F1 and G1 no longer exist in the inlined product, this information is irreversibly lost and that is why inlining is a **one-way** transformation.

Inlining II

Obfuscators use inlining to make functions more complex. The more local variables and the more lines of code a function has, the more difficult it is to analyze since it removes abstractions the programmer used. The reverse engineer will have no idea which function was inlined and where, especially if all copies of the function got inlined and the original function is no longer present in a non-inlined form in the program.

Inlining is a cheap transformation with medium potency and one-way resilience, particularly when combined with the next technique — outlining.

Outlining

Outlining is a process inverse to inlining. A portion of a function code is removed from the body, put aside, converted into a standalone (outlined) function, and replaced by a call instruction. Obfuscators use outlining, particularly in conjunction with inlining, to create potent and resilient transformations:

```
m1:
                                                                                    f1:
int main()
                                                         int main()
  m1;
                                                                                  int G1()
  f1;
                      \rightarrow outlining \rightarrow
                                                           F1();
  f2;
                                                                                    f2:
                                                           G1();
  m2;
                                                                                    m2;
                                                           H1():
  g1;
                                                                                    g1;
  m3;
                                                                                  int H1()
```

int F1()

Interleaving I

Interleaving is an optimization technique exploiting the physical properties of the given media to increase the access or transfer speeds. In obfuscation, interleaving refers to the practice of combining the code and arguments of two or more functions into a single function, along with a new argument (or a global variable) which allows the caller to select one of the individual branches.

```
int F1() {
   f1;
   f2;
} \rightarrow interleaving \rightarrow int G1() {
   g1;
}
```

```
int H1(int which)
{
    switch (which) {
        case 1:
            f1;
            f2;
            break;
        case 2:
            g1;
            break;
    };
}
```

Interleaving II

Interleaving can also be used to hide variables and make it difficult to understand their purpose by combining them with other variables, as well as opaque predicates, into a single blob. Getters and setters can then be used to access the component parts of the blob, incidentally increasing code size and complexity.

Note that this technique is extremely **costly**. Its potency is heavily dependent on the actual interleaving mechanism and resilience tends to be rather **weak** as the removing code needs to be already present in the program.

Cloning

The Method Cloning obfuscation in somewhat similar to opaque predicates in that it inserts unnecessary branching for the reverse engineer to analyze. However, instead of using opaque predicates, we use the method dispatch mechanism of the programming language. This is achieved by transforming a single parent class C with a virtual method into a hierarchy (or set) of classes C1, C2, etc., each created using a different obfuscation transformation. Depending on the actual class instance created, it will appear to the reverse engineer that different methods are being called, while in fact all of them perform exactly the same function.

Loop Transformations

Various loop transformations can be used for the purpose of obfuscation:

- Loop Blocking is used in optimization to split the body of a loop into sections which will fit into a cache, improving the cache behavior of the target architecture.
- Loop Unrolling replicates the body of the loop multiple times, saving
 on the code needed for jumps to the next iteration and allowing for
 better optimization of the use of registers. It is particularly effective
 in cases where the number of iterations is known in advance.
- Loop Fission splits the loop into several loops with the same iteration mechanism, but different bodies. These loops can then e.g. run in parallel.

All of these techniques increase code metrics such as code size or the cyclomatic complexity, which provides their potency. Their resilience is quite weak if used on their own, but increases significantly when combined with other obfuscation techniques. The price is cheap and sometimes free.

Bibliography I

- Collberg C., Thomborson C., Low, D.: A Taxonomy of Obfuscating Transformations, Technical Report #148, University of Auckland, Auckland, New Zealand, 1997/2009. Available online at https://researchspace.auckland.ac.nz/bitstream/handle/2292/3491/TR148.pdf.
- Eilam, E.: Reversing Secrets of Reverse Engineering, Wiley Publishing, Inc., 2005.
- Eagle, C.: The IDA Pro Book The unofficial guide to the world's mode popular disassembler, 2nd ed., No Starch Press, 2011.
- Schwarz, B., Debray, S., Andrews, G.: Disassembly of Executable Code Revisited, Proceedings of the IEEE Working Conference on Reverse Engineering, Oct. 2002, pp. 45-54. Available online at http://ftp.cs.arizona.edu/~debray/Publications/disasm.pdf.

Bibliography II



Wikipedia Foundation, Inc.: Java bytecode instruction listings, Available online at https://en.wikipedia.org/wiki/Java_bytecode_instruction_listings, 2015.