Reverse Engineering

3. Analysis of C++ Classes

Ing. Tomáš Zahradnický, EUR ING, Ph.D. Ing. Josef Kokeš



Czech Technical University in Prague Faculty of Information Technology Department of Information Security

Version 2022-09-09

Table of Contents

- Classes and Structures
 - A Class vs a Structure
 - Structure Layout and Size Determination
 - Inheritance
 - Polymorphism

- Run Time Type Information
 - Motivation
 - The typeid operator
 - The dynamic_cast operator

Classes and Structures

The class and struct keywords mean the same thing, the only difference is in their default protection. While class has its content private by default, struct has it public. Thus we can write equivalently:

```
class C {
  public:
    int m_Field;
};
```

```
class C {
  int m_Field;
};
```

```
struct C {
  int m_Field;
};
```

```
struct C {
  private:
    int m_Field;
};
```

Structures

Let's start with a sample struct and observe its memory layout:

A Sample Struct

char f Char:

struct SampleStruct {

```
short f_Short;
int f_Int;
SampleStruct()
   : f_Char(0x11),
     f_Short(0x55AA),
     f_Int(0x12345678)
   {
   }
};
SampleStruct g_Struct[4];
```

The Sample Struct's Memory Layout

As you can see, all fields in the structure are aligned according to the ABI alignment rules. This is why the f_{Short} field is aligned to a 2-byte boundary. Why is padding 0x00, then 0x31, 0xF3, and 0x9A?

Structure size determination

The structure can be allocated either on the stack or on the heap. Stack-allocated structures are allocated with the sub esp, __LOCAL_SIZE instruction and their size is a __LOCAL_SIZE component. If a structure is allocated at runtime on the heap, it is allocated with new keyword or a memory allocation function such as malloc, HeapAlloc, or LocalAlloc. These functions take structure size as their argument.

```
Allocating a structure with malloc
```

```
0x80483c2
           <main+18>:
                       sub
                             $0xc, %esp
0x80483c5
           <main+21>:
                      push
                             $0x8
                                                     // Structure size
0x80483c7
           <main+23>:
                       call
                             0x8048370 <malloc@plt> // EAX := ptr to the struct
0x80483cc
           <main+28>:
                      movb
                             $0x11,(%eax)
                                                     // ptr->f_Char=0x11
0x80483cf
          <main+31>: movw
                             $0x55AA.0x2(%eax)
                                                     // ptr->f_Short=0x55AA
                                                     // ptr->f_Int=0x12345678
0x80483d5
           <main+37>:
                      movl
                             $0x12345678,0x4(%eax)
0x80483dc
           <main+44>:
                             $0x10, %esp
                       add
```

Structure size determination II

Allocation with the new operator

Allocation with the <u>new</u> operator is similar to the previous case, except that a constructor is called for the structure, if one exists. This case is shown below:

Allocating a structure with the **new** operator

```
0x4006d1
           <main(int, const char**)+75>:
                                                     $0x8,%edi
                                                                          // Structure size
0x4006d6
           <main(int, const char**)+80>:
                                               callq 0x400580 <_Znwm@plt>// Call new here
0x4006db
           <main(int, const char**)+85>:
                                               mov
                                                     %rax,%rbx
                                                                          // Store this pointer into RBX
0x4006de
           <main(int, const char**)+88>:
                                               mov
                                                     %rbx.%rdi
                                                                          // Copy this ptr into RDI
                                               callg 0x400752 <SampleStruct::SampleStruct()>
0x4006e1
           <main(int, const char**)+91>:
0x400752
           <SampleStruct::SampleStruct()>:
                                               push
                                                     %rbp
           <SampleStruct::SampleStruct()+1>:
0x400753
                                               mov
                                                     %rsp,%rbp
0x400756
           <SampleStruct::SampleStruct()+4>:
                                                     %rdi,-0x8(%rbp)
                                               mov
0x40075a
           <SampleStruct::SampleStruct()+8>:
                                                     -0x8(%rbp),%rax
                                               mov
0x40075e
           <SampleStruct::SampleStruct()+12>: movb
                                                     $0x11.(%rax)
                                                                          // ptr->f Char=0x11
0x400761
           <SampleStruct::SampleStruct()+15>: mov
                                                     -0x8(%rbp),%rax
0x400765
           <SampleStruct::SampleStruct()+19>: movw
                                                     $0x55aa,0x2(%rax)
                                                                          // ptr->f_Short=0x55AA
           <SampleStruct::SampleStruct()+25>: mov
0x40076b
                                                     -0x8(%rbp),%rax
           <SampleStruct::SampleStruct()+29>: movl
0x40076f
                                                     $0x12345678,0x4(\( \text{rax} \) ptr->f Int=0x12345678
0x400776
           <SampleStruct::SampleStruct()+36>: pop
                                                     %rbp
0x400777
           <SampleStruct::SampleStruct()+37>: retq
```

Structure size determination III

Other methods

Structure size can also be determined from the instructions manipulating with the structure. If the structure is copied or an array of structures of the same type is used, instructions such as mul often contain the size of our structure. E.g.:

```
for( i=0; i<N; ++i )
  pStructureArray[i].f_Field=0xff;</pre>
```

Suboptimal with mul

Better with add

```
mov $0x600ec8,%rax // Array base
loop:
movb $0xff,(%rax)
add $0xc,%rax // Move to the next item
cmp $0x603da8,%rax // Array end
jne loop
```

Inheritance I

A structured data type can contain another structured data type as its member. There is nothing special about this. Structured data types can inherit from other structured data types. Let's see what happens when a multiple inheritance is used. Suppose we have a class inheriting from CUnknown (see the Polymorphism section) and from another class Rect. The base class CUnknown implements reference counting, while Rect contains 4 ints. Together they form the CRef countedRect class.

```
typedef struct Rect {
  int f_X, f_Y, f_Width, f_Height;
} Rect, *RectPtr, **RectHandle;
class CRefcountedRect : public CUnknown, public Rect {
 public:
    virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPV0ID* ppv0bject ):
                                      CRefcountedRect(int x, int v, int w, int h)
                                       : m_Area(w*h) {
                                          f X = x: f Y = v: f Width = w: f Height = h:
                                      }:
                                      ~CRefcountedRect();
    virtual
                                      get_Area() const { return m_Area; }
    virtual int
                                      get Rect() const { return static cast<const Rect*>(this): }
    const Rect*
 protected:
    int m Area:
}:
                                                                       4 D > 4 A > 4 B > 4 B >
```

Inheritance II

Memory layout of the CRefcountedRect			
	CRefcountedRect*-	pVMT (see	later)
7fffffffe0c0:	CUnknown*	d0 0c 40	00 00 00 00 00
	m_RefCount		
7fffffffe0c8:		01 00 00	00 00 00 00 00
		f_X	f_Y
7fffffffe0d0:	Rect*	> 10 00 00	00 20 00 00 00
		f_Width	f_Height
7fffffffe0d8:		40 00 00	00 80 00 00 00
		m_Area	
7fffffffe0e0:		00 20 00	00

Polymorphism I

Once a structured data type contains virtual methods, it must contain a virtual method table (VMT). If the object inherits from multiple objects with virtual methods, it inherits two or more VMTs. Each VMT is a table of function pointers to virtual methods; all virtual methods are called via this table. VMT is stored as the first item in the class, followed by first base class data. Then the second VMT follows, second data, etc.

```
#include <Unknum.h>
class CUnknown : public IUnknown {
  public:
    virtual HRESULT STDMETHODCALLTYPE QuervInterface( REFIID riid, LPV0ID* ppv0bject );
    virtual III.ONG
                  STDMETHODCALLTYPE AddRef(void):
    virtual ULONG STDMETHODCALLTYPE Release(void):
    CUnknown(): m RefCount(1) {}
    virtual ~CUnknown() { m_RefCount = -1; }
  protected:
    volatile ULONG __declspec(align(8)) m_RefCount;
};
ULONG STDMETHODCALLTYPE CUnknown::AddRef(void) {
  return InterlockedIncrement(&m_RefCount);
}
ULONG STDMETHODCALLTYPE CUnknown::Release(void) {
  ULONG ulNewValue = InterlockedDecrement(&m RefCount):
  if (ulNewValue == 0)
    delete this;
  return ulNewValue:
```

Polymorphism II

return ulNewValue;

Once a structured data type contains virtual methods, it must contain a virtual method table (VMT). If the object inherits from multiple objects with virtual methods, it inherits two or more VMTs. Each VMT is a table of function pointers to virtual methods; all virtual methods are called via this table. VMT is stored as the first item in the class, followed by first base class data. Then the second VMT follows, second data, etc.

```
#include <Unknum.h>
class CUnknown : public IUnknown {
 public:
   virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPV0ID* ppv0bject );
   virtual ULONG
                 STDMETHODCALLTYPE AddRef(void):
                  STDMETHODCALLTYPE Release(void):
   virtual ULONG
                                                    VMT
   CUnknown(): m RefCount(1) {}
   virtual ~CUnknown() { m_RefCount = -1; }
                                                    &CUnknown::QueryInterface
 protected:
                                                    &CUnknown::AddRef
   volatile ULONG __declspec(align(8)) m_RefCount;
};
                                                    &CUnknown::Release
ULONG STDMETHODCALLTYPE CUnknown::AddRef(void) {
                                                    &CUnknown::~CUnknown
 return InterlockedIncrement(&m_RefCount);
}
ULONG STDMETHODCALLTYPE CUnknown::Release(void) {
 ULONG ulNewValue = InterlockedDecrement(&m RefCount):
 if (ulNewValue == 0)
   delete this;
```

4 D F 4 D F 4 D F 4 D F

Polymorphism III

The layout of the CUnknown class would then be:

Object layout

```
this --> +0 pVMT -----> +0 &CUnknown::QueryInterface
+4 padding +4 &CUnknown::AddRef
+8 m_RefCount +8 &CUnknown::Release
+c &CUnknown::~CUnknown
```

Calling a method through a VMT

```
40245C mov eax,dword ptr [ebp+8]// Load this into EAX
40245F mov ecx,dword ptr [eax] // Load this->pVMT into ECX
402461 mov edx,dword ptr [ebp+8]// Load this into EDX
402464 push edx // Push this as the first arg.
402465 mov eax,dword ptr [ecx+4]// Retrieve the method from VMT [AddRef]
402468 call eax // Call AddRef
```

Note 1: You might have noticed that the AddRef method does not receive its argument in ECX, contrary to what we might have expected. This is because the STDMETHODCALLTYPE changes the calling convention to __stdcall and this means all parameters are pushed onto the stack. Even for methods!

Note 2: The class contains a padding in front of the m_RefCount field because of the __declspec(align(8)). This is required because the InterlockedXXX functions require aligned data.

Setting object's VMT (Windows)

```
CUnknown::CUnknown():
  00401110 push ebp
 00401111 mov ebp,esp
                             CUnknown's VMT
  00401113 sub esp,44h
                              004293BC 80 22 40 00 c0 14 40 00 ."Q.A.Q.
  00401116 push ebx
                              004293C4 20 23 40 00 10 14 40 00
                                                                 #0...0.
  00401117 push esi
  00401118 push edi
  00401119 mov dword ptr [ebp-4],ecx
                                                // this was passed in ECX
  0040111C mov ecx, dword ptr [ebp-4]
  0040111F call IUnknown::IUnknown (4011D0h)
                                                // An implicit constructor
  00401124 mov eax, dword ptr [ebp-4]
  // Assign the VMT pointer to this->pVMT offset
  00401127 mov
               dword ptr [eax],offset CUnknown::'vftable' (4293BCh)
  0040112D mov eax, dword ptr [ebp-4]
               dword ptr [eax+8],1
                                                // Set m RefCount=1
  00401130 mov
  00401137 mov
               eax, dword ptr [ebp-4]
  0040113A pop
               edi
  0040113B pop
               esi
  0040113C pop ebx
 0040113D mov
               esp,ebp
  0040113F pop
               ebp
  00401140 ret
```

Polymorphism IV

If a class is abstract and has some methods declared, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
#include <Unknwn.h>
class CUnknown : public IUnknown {
  public:
    virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPVOID* ppvObject );
    virtual ULONG STDMETHODCALLTYPE AddRef(void);
    virtual ULONG STDMETHODCALLTYPE Release(void);

    CUnknown() { m_RefCount = 1; }
    virtual -CUnknown() { m_RefCount = -1; }
    protected:
        volatile ULONG __declspec(align(8)) m_RefCount;
};

// Implementations of AddRef and Release remain the same
```

13/30

Polymorphism V

If a class is abstract and has some methods declared, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
#include <Unknum.h>
class CUnknown : public IUnknown {
 public:
   virtual HRESULT STDMETHODCALLTYPE QuervInterface(
                  STDMETHODCALLTYPE AddRef(void):
    virtual ULONG
   virtual ULONG
                   STDMETHODCALLTYPE Release(void):
   CUnknown() { m_RefCount = 1; }
   virtual ~CUnknown() { m RefCount = -1; }
   protected:
     volatile ULONG __declspec(align(8)) m_RefCount;
}:
// Implementations of AddRef and Release remain the same
```

Original VMT

&CUnknown::QueryInterface

&CUnknown::AddRef &CUnknown::Release

&CUnknown::~CUnknown

Polymorphism VI

If a class is abstract and has some methods declared, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
VMT with pure methods
#include <Unknum.h>
class CUnknown : public IUnknown {
 public:
                                                & purecall
   // QuervInterface is left undefined
                                                &CUnknown::AddRef
   virtual ULONG STDMETHODCALLTYPE AddRef(void);
   virtual ULONG
                 STDMETHODCALLTYPE Release(void):
                                                &CUnknown::Release
   // Constructor is left undefined
   virtual ~CUnknown() { m RefCount = -1; }
                                                &CUnknown::~CUnknown
   protected:
     volatile ULONG __declspec(align(8)) m_RefCount;
}:
// Implementations of AddRef and Release remain the same
```

Setting object's VMT (Linux 64-bit)

```
// An implicit constructor
 00400fd0 push
                  %rbp
 00400fd1 mov
                  %rsp,%rbp
  00400fd4 mov
                  %rdi,-0x8(%rbp)
                                                    // this pointer stored in a local var
  00400fd8 mov
                  -0x8(%rbp),%rax
                                                    // this pointer to RAX
                  $0x4014d0.(%rax)
                                                    // VMT assigned to this->pVMT
  00400fdc mova
 00400fe3 pop
                  %rbp
 00400fe4 retq
CUnknown::CUnknown():
                                                    // An implicit constructor
 00400ff0 push
                  %rbp
  00400ff1 mov
                  %rsp,%rbp
  00400ff4 sub
                  $0x10, %rsp
                  %rdi,-0x8(%rbp)
  00400ff8 mov
  00400ffc mov
                  -0x8(%rbp),%rax
                  %rax,%rdi
 00401000 mov
                                                    // this passed in RDI
 00401003 callq
                  0x400fd0 <IUnknown::IUnknown()>
                                                    // Implicit constructor called here
 00401008 mov
                  -0x8(%rbp),%rax
 0040100c movq
                  $0x401490,(%rax)
                                                    // VMT assigned to this->pVMT
 00401013 leaveg
 00401014 reta
```

IUnknown's VMT

+18

TUnknown::TUnknown():

```
00000000004014d0 < ZTV8IUnknown+16>:
     0000000000400840 <__cxa_pure_virtual@plt>
+0
     0000000000400840 < cxa pure virtual@plt>
+8
+10 0000000000400840 < cxa pure virtual@plt>
```

```
CUnknown's VMT
```

```
0000000000401490 < ZTV8CUnknown+16>:
      0000000000400840 < cxa pure virtual@plt>
      00000000000400976 <CUnknown::AddRef()>
 +8
+10 0000000000400994 <CUnknown::Release()>
 +18 00000000004009AC <CUnknown::~CUnknown()>
```

0000000000000000 empty

Polymorphism VII

Pure virtual methods' addresses in the VMT are replaced by the address of the purecall function. This function calls a purecall handler if one's present and then aborts the program if not already aborted by the handler.

Source code of the _purecall function from purevirt.c

```
void __cdecl _purecall( void ) {
 _purecall_handler purecall = (_purecall_handler) DecodePointer(__pPurecall);
 if( purecall != NULL )
   purecall():
   /* shouldn't return, but if it does, we drop back to default behaviour */
 #if defined ( DEBUG)
    _NMSG_WRITE(_RT_PUREVIRT);
 #endif /* defined ( DEBUG) */
  /* do not write the abort message */
  _set_abort_behavior(0, _WRITE_ABORT_MSG);
  abort():
```

Virtual Method Tables in Reverse Engineering

As you have noticed, constructors set the object's VMT if one's present. This happens even if there's no constructor. In that case an implicit constructor is used (e.g. see the IUnknown ctor). Since each VMT is a global table shared by all instances of the same object, we can:

- use a VMT pointer to tell whether an unknown object is of a certain type by comparing its VMT pointer to a list of VMT pointers;
- examine pointers in the object's memory; if they point to a VMT, we've discovered multiple inheritance or composition;
- examine pointers in each VMT and identify code belonging to the object.

The above information can be further extended by studying the object's type information, which is used in RTTI.

Motivation I

Slide no. 9 uses static_cast<const Rect*>(this) to cast the this pointer into a pointer to a Rect. The Rect* pointer is also a "this" pointer of a derived class and is different from the CRefcountedRect* this pointer. What code was behind the static_cast?

```
CRefcountedRect::get_Rect() const:
 004027C0
            push
                  ebp
  004027C1
            mov
                  ebp.esp
  004027C3
                  esp.48h
            sub
  004027C6
            push
                  ebx
 004027C7
            push
                  esi
 004027C8
            push
                  edi
  00402709
                  dword ptr [ebp-4].ecx
                                                          // Store this into ebp-4
            mov
 004027CC
                  dword ptr [ebp-4],0
                                                          // Static_cast does nothing for a NULL pointer
            cmp
 004027D0
                  CRefcountedRect::get_Rect+1Dh (4027DDh)
                  eax, dword ptr [ebp-4]
 004027D2
                                                          // Load this into EAX
            mov
 004027D5
            add
                  eax, 10h
                                                          // Move the this pointer by 16 bytes
 004027D8
                  dword ptr [ebp-48h],eax
                                                          // Store the casted result
            mov
 004027DB
            qmp
                  CRefcountedRect::get_Rect+24h (4027E4h)
                  dword ptr [ebp-48h],0
 004027DD
            mov
                                                          // Static_cast failed, store NULL as the result
                  eax, dword ptr [ebp-48h]
 004027E4
            mov
 004027E7
                  edi
            pop
 004027E8
                  esi
            pop
 004027E9
                  ebx
            pop
 004027EA
            mov
                  esp,ebp
  004027EC
            pop
                  ebp
  004027ED ret
```

Motivation II

How do we go back from Rect* to CRefcountedRect*? When we want to upcast an object pointer, we can try dynamic_cast:

```
const Rect* pRect = pRefcountedRect->get_Rect();
const CRefcountedRect* pRefCountedRect2 = dynamic_cast<const CRefcountedRect*>(pRect);
printf("pRefcountedRect=%p\npRect=%p\npRefcountedRect2=%p\n", pRefcountedRect, pRect, pRefCountedRect2);
1>c:\users\...\tokens.cpp(892): error C2683: 'dynamic_cast' : 'Rect' is not a polymorphic type
```

Upcasting was not possible, since Rect was not polymorphic, i.e. did not have a VMT. We can add one by adding a virtual destructor:

```
typedef struct Rect {
  int f_X, f_Y, f_Width, f_Height;
  virtual ~Rect();
} Rect, *RectPtr, **RectHandle;
```

The result

```
pRefcountedRect = 0012FE98
pRect = 0012FEA8
pRefCountedRect2 = 0012FE98
```

How did dynamic_cast know that it was possible to cast this pointer to a Rect into a pointer to CRefcountedRect?

18/30

The typeid operator I

Run Time Type Information (RTTI) is used when typeid or dynamic_cast operators are used. Let's see what typeid provides to us:

The type_info class is defined in typeinfo.h as follows:

There's a class name, a valuable piece of information!

The typeid operator II

When we look at assembly code of our code on the last slide, there's a type mismatch. While the result is a type_info reference, the value assigned into rtiCRefcountedRect is a _RTTITypeDescriptor pointer. The internals of this structure are hidden in a private rtti.h file. A similar structure, TypeDescriptor, with the same layout, is found in ehdata.h and describes the first field in the structure to be a VMT pointer:

Note: Normally, when using the typeid operator, the compiler changes it into a mov instruction assigning the _RTTITypeDescriptor* into the result (wherever possible), or calls the __RTtypeid function which returns an RTTITypeDescriptor*.

The typeid operator III

```
extern "C" PVOID __CLRCALL_OR_CDECL __RTtypeid (
 PVOID inptr // Pointer to polymorphic object
) throw(...)
 if (!inptr) {
   throw bad_typeid ("Attempted a typeid of NULL pointer!");
   return NULL;
  __try {
   // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *) ((*((void***)inptr))[-1]);
   if (((const void *)pCompleteLocator->pTypeDescriptor) != NULL) {
     return (PVOID) COL PTD(*pCompleteLocator);
    }
   else
     throw __non_rtti_object("Bad read pointer - no RTTI data!");
     return NULL;
    }
  except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                                  ? EXCEPTION_EXECUTE_HANDLER : EXCEPTION_CONTINUE_SEARCH)
    throw __non_rtti_object ("Access violation - no RTTI data!");
   return NULL;
}
```

Dynamic_cast to a void* |

void* pv = dynamic_cast<void*>(pRect);

The dynamic_cast operator is typically used for upcasting (from a base class in direction from the base class to derived classes). When casting to a void* the __RTCastToVoid function from rtti.cpp is called:

```
eax, dword ptr [pRect]
 0040264B mov
 0040264E push eax
 0040264F call RTCastToVoid (4032C8h)
 00402654 add esp,4
 00402657 mov
                 dword ptr [pv],eax
extern "C" PVOID _ CLRCALL OR CDECL _ RTCastToVoid (
  PVOID inptr // Pointer to polymorphic object
) throw(...)
 if (inptr == NULL)
   return NULL:
  trv {
   return FindCompleteObject((PVOID *)inptr);
  }
  except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                              ? EXCEPTION EXECUTE HANDLER : EXCEPTION CONTINUE SEARCH)
   throw __non_rtti_object ("Access violation - no RTTI data!");
   return NULL:
7
```

Dynamic_cast to a void* |

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
   // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
   _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
   char *pCompleteObject = (char *)inptr - COL_OFFSET(*pCompleteLocator);

   // Adjust by construction displacement, if any
   if (COL_CDOFFSET(*pCompleteLocator))
    pCompleteObject -= *(int *)((char *)inptr - COL_CDOFFSET(*pCompleteLocator));
   return (PVOID) pCompleteObject;
}
```

As you can see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is private and undocumented.

Dynamic_cast to a void* |||

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
    // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
    char *pCompleteObject = (char *)inptr - COL_OFFSET(*pCompleteLocator);

    // Adjust by construction displacement, if any
    if (COL_CDOFFSET(*pCompleteLocator))
    pCompleteObject -= *(int *)((char *)inptr - COL_CDOFFSET(*pCompleteLocator));
    return (PVOID) pCompleteObject;
}
```

As you can see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is private and undocumented.

WHO CARES?

Dynamic_cast to a void* IV

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
    // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
    char *pCompleteObject = (char *)inptr - pCompleteLocator->offset;

    // Adjust by construction displacement, if any
    if (pCompleteLocator->cdOffset)
        pCompleteObject -= *(int *)((char *)inptr - pCompleteLocator->cdOffset);
    return (PVOID) pCompleteObject;
}
```

As you can see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is:

```
typedef struct _RTTITypeDescriptor {
 void* __vftbl; // VMT pointer
                 // ??
 void* data:
 char d name[1]: // Mangled data type name
} RTTITypeDescriptor, TypeDescriptor;
typedef struct _RTTICompleteObjectLocator {
 DWORD
                                 signature;
                                                             // version of the structure, COL_SIG_REVO==0
                                                             // offset of this VMT in the complete class
 LONG.
                                offset;
 LONG.
                                cdOffset:
                                                             // construction displacement offset
 TypeDescriptor*
                                pTvpeDescriptor:
  _RTTIClassHierarchyDescriptor* pClassHierarchyDescriptor;
RTTICompleteObjectLocator:
```

Dynamic_cast to a non-void* |

When we use the dynamic_cast operator with a non-void* data type, MSVC calls the __RTDynamicCast internal function instead.

```
const CRefcountedRect* pRefCountedRect2 = dynamic_cast<const CRefcountedRect*>(pRect);
 00402C58
           push
                                                                       // 0 for pointers, 1 for refs
 00402C5A push offset CRefcountedRect `RTTI Type Descriptor' (432110h) // To coerce to
                offset Rect 'RTTI Type Descriptor' (4320FCh)
 00402C5F
                                                                       // Coerce from
 00402C64 push 0
                                                                       // A VMT offset in the object
                 eax.dword ptr [ebp-0A8h]
                                                                        // An object to coerce
  00402C66 mov
 00402C6C push eax
 00402C6D call _RTDynamicCast (40331Eh)
 00402C72 add esp,14h
 00402C75 mov
                 dword ptr [ebp-OACh],eax
                                                                       // Store the coerced result
```

As we can see, passing an _RTTITypeDescriptor* is enough to verify whether CRefcountedRect derives from Rect. How is this information verified?

24 / 30

Dynamic_cast to a non-void* |

```
extern "C" PVOID _CLRCALL_OR_CDECL _RTDynamicCast (
 PVOID inptr, // Pointer to polymorphic object
 LONG VfDelta, // Offset of vfptr in object
 PVOID SrcType, // Static type of object pointed to by inptr
 PVOID TargetType, // Desired result of cast
  BOOL isReference) // TRUE if input is reference, FALSE if input is ptr
 throw(...)
    PVOID pResult=NULL:
    _RTTIBaseClassDescriptor *pBaseClass;
    // dynamic_cast returns nothing for a NULL ptr
    if (inptr == NULL)
     return NULL;
    __try {
     PVOID pCompleteObject = FindCompleteObject((PVOID *)inptr);
      _RTTICompleteObjectLocator *pCompleteLocator=(_RTTICompleteObjectLocator*) ((*((yoid***)inptr))[-1]);
      // Adjust by vfptr displacement, if any
      inptr = (PVOID *) ((char *)inptr - VfDelta);
      // Calculate offset of source object in complete object
      ptrdiff_t inptr_delta = (char *)inptr - (char *)pCompleteObject;
      if (!(CHD_ATTRIBUTES(*COL_PCHD(*pCompleteLocator)) & CHD_MULTINH)) {// if not multiple inheritance
        pBaseClass = FindSITargetTypeInstance( pCompleteLocator, ( RTTITypeDescriptor *) SrcType,
                                               ( RTTITypeDescriptor *) TargetType );
      } else if ...
      // Branches for multiple non-virtual and virtual inheritance.
```

Dynamic_cast to a non-void* |||

```
if (pBaseClass != NULL)
    // Calculate ptr to result base class from pBaseClass->where
    pResult = ((char *) pCompleteObject) + PMDtoOffset(pCompleteObject, BCD WHERE(*pBaseClass));
  else
    pResult = NULL;
    if (isReference)
      throw bad cast("Bad dynamic cast!"):
  }
}
__except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                                ? EXCEPTION EXECUTE HANDLER : EXCEPTION CONTINUE SEARCH) {
  pResult = NULL;
  throw __non_rtti_object("Access violation - no RTTI data!");
return pResult;
```

Dynamic_cast to a non-void* IV

Each VMT[-1] contains the _RTTICompleteObjectLocator* pLoc pointer and the pLoc->pTypeDescriptor->d_name field tells us the type name! Having the name is the first step. We can go examine the structures below [2, 3] and discover the entire hierarchy!

```
typedef struct PMD {
 ptrdiff_t mdisp; //vftable offset
 ptrdiff t pdisp: //vftable offset
 ptrdiff t vdisp: //vftable offset (for virtual base class)
};
typedef const struct s RTTIBaseClassDescriptor {
 TypeDescriptor
                               *pTypeDescriptor;
                               numContainedBases;
 DWORD
  PMD
                                where:
                               attributes:
 DWORD
  _RTTIClassHierarchyDescriptor *pClassHierarchyDescriptor;
RTTIBaseClassDescriptor:
typedef const struct s_RTTIBaseClassArray {
  RTTIBaseClassDescriptor *pArrayOfBaseClassDescriptors[1]; // A variable sized array
RTTIBaseClassArray:
typedef const struct s RTTIClassHierarchyDescriptor {
  DWORD
                      signature:
 DWORD
                      attributes:
 DWORD
                     numBaseClasses;
 RTTIBaseClassArray *pBaseClassArray:
RTTIClassHierarchyDescriptor:
```

Dynamic_cast in g++

A brief glance

Let's check where the VMT and object metadata is stored in g++. The following code comes from libstdc++, namely gcc-4.9-4.9.2/gcc-4.9.2/libstdc++-v3/libsupc++/dyncast.cc:

We can see that the pointer to the VMT is also the first member of the structured type, and the metadata also precedes the VMT. There's a difference between MSVC and g++ — if a NULL pointer is passed to dynamic_cast in MSVC a NULL is returned, while g++ crashes dereferencing a NULL reference.

Type Information in Reverse Engineering

Type information presents another useful source of information about the reverse engineered target. We can extract the following:

- class name;
- class hierarchy.

There are IDA Pro scripts that do this work for us [1] and dump the hierarchy.

If we wanted to find this information ourselves, we would have to parse the code section and look for a typical constructor code — assigning the VMT to the first data member of the object. From the VMT[-1] pointer we could get to the type information and extract it.

Bibliography

- lgorsk: Reversing Microsoft Visual C++ Part II: Classes, Methods and RTTI. Available online at http://www.openrce.org/articles/full_view/23, 2006.
 - Microsoft Corp.: rttidata.h: Available online at http: //read.pudn.com/downloads10/sourcecode/os/41823/WINCEOS/ COREOS/CORE/CORELIBC/CRTW32/RTTI/rttidata.h__.htm.
- Passion_wu128: rtti.h: Available online at http://m.blog.csdn.net/blog/passion_wu128/38511957, 2014.