Reverse Engineering

3. Introduction into Reverse Engineering III.

Ing. Tomáš Zahradnický, EUR ING, Ph.D.



Czech Technical University in Prague Faculty of Information Technology Department of Computer Systems

Development of these materials was supported by the development project Update and development of security courses and Shelltest no. 18104/105/1051504H000.

Version 2017-11-18

Table of Contents

- Classes and Structures
 - A Class vs a Structure
 - Structure Layout and Size Determination
 - Inheritance
 - Polymorphism
- Run Time Type Identification
 - Motivation
 - The typeid operator
 - The dynamic_cast operator

Classes and Structures

The class and struct keyword means the same thing, the only difference is in its default protection. While class has its content private by default, struct has it public. Thus these two notations are equivalent:

```
class C {
  public:
    int m_Field;
};
```

```
class C {
  int m_Field;
};
```

```
struct C {
  int m_Field;
};
```

```
struct C {
  private:
    int m_Field;
};
```

Structures

Let's start with a sample struct and observe its memory layout:

A Sample Struct

```
struct SampleStruct {
  char f_Char;
  short f_Short;
  int f_Int;
  SampleStruct()
    : f_Char(0x11),
      f_Short(0x55AA),
      f_Int(0x12345678)
  {
    }
};
SampleStruct g_Struct[4];
```

The Sample Struct's Memory Layout

As you can see, all fields in the structure are aligned according to the ABI alignment rules. This is why the f_Short field is aligned to a 2-byte boundary. Why is padding 0x00, then 0x31, 0xF3, and 0x9A?

Structure size determination

The structure can be allocated either on the stack or on the heap. Stack-allocated structures are allocated with the sub esp, __LOCAL_SIZE instruction and their size is a __LOCAL_SIZE component. If a structure is allocated at runtime on the heap, it is allocated with new keyword or a memory allocation function such as malloc, HeapAlloc, or LocalAlloc. These functions take structure size as their argument.

```
Allocating a structure with malloc
```

```
$0xc, %esp
0x80483c2
           <main+18>:
                       sub
0x80483c5
           <main+21>:
                       push
                             $0x8
                                                     // Structure size
0x80483c7
           <main+23>:
                       call
                             0x8048370 <malloc@plt>
                                                     // EAX := ptr to the struct
0x80483cc
           <main+28>:
                       movb
                             $0x11.(%eax)
                                                     // ptr->f_Char=0x11
                                                     // ptr->f_Short=0x55AA
0x80483cf
          <main+31>: movw
                             $0x55AA,0x2(\%eax)
0x80483d5
           <main+37>:
                       Tvom
                             $0x12345678,0x4(%eax)
                                                     // ptr->f_Int=0x12345678
0x80483dc
           <main+44>:
                       add
                             $0x10, %esp
```

Structure size determination II

Allocation with the new operator

Allocation with the <u>new</u> operator is similar to the previous case, except that a constructor is called for the structure, if one exists. This case is shown below:

Allocating a structure with the **new** operator

```
0x4006d1
                                                                         // Structure size
           <main(int, const char**)+75>:
                                                     $0x8, %edi
0x4006d6
           <main(int, const char**)+80>:
                                               callg 0x400580 < Znwm@plt>// Call new here
0x4006db
           <main(int, const char**)+85>:
                                               mov
                                                     %rax,%rbx
                                                                         // Store this pointer into RBX
0x4006de
           <main(int, const char**)+88>:
                                                     %rbx,%rdi
                                                                         // Copy this ptr into RDI
                                               mov
                                               callg 0x400752 <SampleStruct::SampleStruct()>
0x4006e1
           <main(int, const char**)+91>:
0x400752
           <SampleStruct::SampleStruct()>:
                                               push
                                                     %rbp
0x400753
           <SampleStruct::SampleStruct()+1>:
                                                     %rsp,%rbp
                                               mov
           <SampleStruct::SampleStruct()+4>:
0x400756
                                                     %rdi,-0x8(%rbp)
                                               mov
0x40075a
           <SampleStruct::SampleStruct()+8>:
                                                     -0x8(%rbp),%rax
                                               mov
0x40075e
           <SampleStruct::SampleStruct()+12>: movb
                                                     $0x11,(%rax)
                                                                         // ptr->f_Char=0x11
0x400761
           <SampleStruct::SampleStruct()+15>: mov
                                                     -0x8(%rbp),%rax
0x400765
           <SampleStruct::SampleStruct()+19>: movw
                                                     $0x55aa.0x2(%rax)
                                                                         // ptr->f_Short=0x55AA
0x40076b
           <SampleStruct::SampleStruct()+25>: mov
                                                     -0x8(%rbp),%rax
           <SampleStruct::SampleStruct()+29>: movl
                                                     $0x12345678,0x4(%rax)/ ptr->f_Int=0x12345678
0x40076f
           <SampleStruct::SampleStruct()+36>: pop
0x400776
                                                     %rbp
0x400777
           <SampleStruct::SampleStruct()+37>: retq
```

Structure size determination III

Other methods

Structure size can also be determined from the instructions manipulating with the structure. If the structure is copied or an array of structures of the same type is used, instructions such as mul often contain the size of our structure. E.g.:

```
for( i=0; i<N; ++i )
  pStructureArray[i].f_Field=0;</pre>
```

Suboptimal with mul

Better with add

```
mov $0x600ec8,%rax // Array base
loop:
movb $0x11,(%rax)
add $0xc,%rax // Move to the next item
cmp $0x603da8,%rax // Array end
jne loop
```

Inheritance I

A structured data type can contain another structured data type as its member. There is nothing special about this. Structured data types can inherit from other structured data types. Let's see what happens when a multiple inheritance is used. Suppose we have a class inheriting from CUnknown (see the Polymorphism section) and from another class Rect. The base class CUnknown implements reference counting, while Rect contains 4 ints. Together they form the CRef countedRect class.

```
typedef struct Rect {
 int f X, f Y, f Width, f Height:
} Rect, *RectPtr, **RectHandle;
class CRefcountedRect : public CUnknown, public Rect {
 public:
   virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPV0ID* ppv0bject );
                                      CRefcountedRect(int x, int y, int w, int h)
                                       : m Area(w*h) {
                                          f X = x: f Y = v: f Width = w: f Height = h:
    virtual
                                      ~CRefcountedRect():
                                      get Area() const { return m Area; }
    virtual int
    const Rect*
                                      get_Rect() const { return static_cast<const Rect*>(this); }
 protected:
   int m_Area;
};
                                                                       4 D > 4 D > 4 D > 4 D > -
```

Inheritance II

```
Memory layout of the CRefcountedRect
           CRefcountedRect*-| pVMT (see later)
m_RefCount
                             01 00 00 00 00 00 00 00
7fffffffe0c8:
                            f_X
                                      f_Y
                       ----> 10 00 00 00 20 00 00 00
7fffffffe0d0: Rect*----
                             f_Width
                                      f_Height
                             40 00 00 00 80 00 00 00
7fffffffe0d8:
                             f_Area
                             00 20 00 00
7fffffffe0e0:
```

Polymorphism I

#include <Unknum.h>

Once a structured data type contains virtual methods, it must contain a virtual method table (VMT). If the object inherits from multiple objects with virtual methods, it inherits two or more VMTs. Each VMT is a table of function pointers to virtual methods; all virtual methods are called via this table. VMT is stored as the first item in the class, followed by first base class data. Then the second VMT follows, second data, etc.

```
class CUnknown : public IUnknown {
 public:
   virtual HRESULT STDMETHODCALLTYPE QuervInterface( REFIID riid, LPV0ID* ppv0bject );
   virtual ULONG STDMETHODCALLTYPE AddRef(void):
   virtual ULONG
                    STDMETHODCALLTYPE Release(void):
   CUnknown(): m RefCount(1) {}
   virtual ~CUnknown() { m_RefCount = -1; }
 protected:
   volatile ULONG __declspec(align(8)) m_RefCount;
};
ULONG STDMETHODCALLTYPE CUnknown::AddRef(void) {
 return InterlockedIncrement(&m_RefCount);
}
ULONG STDMETHODCALLTYPE CUnknown::Release(void) {
 ULONG ulNewValue = InterlockedDecrement(&m RefCount):
 if (ulNewValue == 0)
   delete this:
 return ulNewValue;
                                                                       4 D > 4 D > 4 D > 4 D >
```

Polymorphism II

#include <Unknum.h>

Once a structured data type contains virtual methods, it must contain a virtual method table (VMT). If the object inherits from multiple objects with virtual methods, it inherits two or more VMTs. Each VMT is a table of function pointers to virtual methods; all virtual methods are called via this table. VMT is stored as the first item in the class, followed by first base class data. Then the second VMT follows, second data, etc.

```
class CUnknown : public IUnknown {
 public:
   virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPV0ID* ppv0bject );
   virtual ULONG STDMETHODCALLTYPE AddRef(void):
   virtual ULONG
                  STDMETHODCALLTYPE Release(void);
   CUnknown(): m RefCount(1) {}
                                                    VMT
   virtual ~CUnknown() { m_RefCount = -1; }
                                                    &CUnknown::QueryInterface
 protected:
   volatile ULONG __declspec(align(8)) m_RefCount;
                                                    &CUnknown::AddRef
};
                                                    &CUnknown::Release
ULONG STDMETHODCALLTYPE CUnknown::AddRef(void) {
                                                    &CUnknown::~CUnknown
 return InterlockedIncrement(&m_RefCount);
}
ULONG STDMETHODCALLTYPE CUnknown::Release(void) {
 ULONG ulNewValue = InterlockedDecrement(&m RefCount):
 if (ulNewValue == 0)
   delete this:
```

return ulNewValue;

4 日 5 4 周 5 4 3 5 4 3 5

Polymorphism III

The layout of the CUnknown class would then be:

Object layout

```
this --> +0 pVMT -----> +0 &CUnknown::QueryInterface
+4 padding +4 &CUnknown::AddRef
+8 m_RefCount +8 &CUnknown::Release
+c &CUnknown::~CUnknown
```

Calling a method through a VMT

```
40245C mov eax,dword ptr [ebp+8]// Load this into EAX
40245F mov ecx,dword ptr [eax] // Load this->pVMT into ECX
402461 mov edx,dword ptr [ebp+8]// Load this into EDX
402464 push edx // Push this as the first arg.
402465 mov eax,dword ptr [ecx+4]// Retrieve the method from VMT [AddRef]
402468 call eax // Call AddRef
```

Note 1: You might have noticed that the AddRef method does not receive its argument in ECX in contrast to what we might have expected. This is because the STDMETHODCALLTYPE changes the calling convention to __stdcall and this means all parameters are pushed onto the stack. Even for methods!

Note 2: The class contains a padding in front of the m_RefCount field because of the __declspec(align(8)). This is required because the InterlockedXXX functions require aligned data.

Setting object's VMT (Windows)

```
CUnknown::CUnknown():
  00401110 push ebp
 00401111 mov ebp,esp
                             CUnknown's VMT
  00401113 sub esp,44h
                              004293BC
                                       80 22 40 00 c0 14 40 00 ."@.A.@.
  00401116 push ebx
                              004293C4 20 23 40 00 10 14 40 00
                                                                 #0...0.
  00401117 push esi
  00401118 push edi
  00401119 mov dword ptr [ebp-4],ecx
                                                // this passed in ECX
  0040111C mov ecx, dword ptr [ebp-4]
  0040111F call IUnknown::IUnknown (4011D0h)
                                                // An implicit ctor
  00401124 mov eax, dword ptr [ebp-4]
  // Assign the VMT pointer to this->pVMT offset
  00401127 mov dword ptr [eax], offset CUnknown::'vftable' (4293BCh)
  0040112D mov eax, dword ptr [ebp-4]
               dword ptr [eax+8],1
                                                // Set m RefCount=1
  00401130 mov
  00401137 mov
               eax, dword ptr [ebp-4]
  0040113A pop
               edi
  0040113B pop
               esi
  0040113C pop ebx
 0040113D mov
               esp,ebp
  0040113F pop
               ebp
  00401140 ret
```

Polymorphism IV

If a class is abstract and has some methods defined, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
#include <Unknwn.h>
class CUnknown : public IUnknown {
  public:
    virtual HRESULT STDMETHODCALLTYPE QueryInterface( REFIID riid, LPVOID* ppvObject );
    virtual ULONG STDMETHODCALLTYPE AddRef(void);
    virtual ULONG STDMETHODCALLTYPE Release(void);

    CUnknown() { m_RefCount = 1; }
    virtual ~CUnknown() { m_RefCount = -1; }
    protected:
        volatile ULONG __declspec(align(8)) m_RefCount;
};

// Implementations of AddRef and Release remain the same
```

Polymorphism V

#include <Unknum.h>

If a class is abstract and has some methods defined, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
class CUnknown : public IUnknown {
  public:
    virtual HRESULT STDMETHODCALLTYPE QueryInterface(
    virtual ULONG STDMETHODCALLTYPE AddRef(void);
    virtual ULONG STDMETHODCALLTYPE Release(void);
    CUnknown() { m_RefCount = 1; }
    virtual 'CUnknown() { m_RefCount = -1; }
    protected:
    volatile ULONG __declspec(align(8)) m_RefCount;
};

// Implementations of AddRef and Release remain the same
```

Original VMT

```
&CUnknown::QueryInterface
&CUnknown::AddRef
&CUnknown::Release
&CUnknown::~CUnknown
```

Polymorphism VI

#include <Unknum.h>

If a class is abstract and has some methods defined, it still has a VMT. Its constructor (even an implicit one) assigns it to the this->pVMT field. If some of the virtual methods are not implemented, what should their slot in the VMT contain?

```
class CUnknown : public IUnknown {
  public:
    // QueryInterface is left undefined
    virtual ULONG STDMETHODCALLTYPE AddRef(void);
    virtual ULONG STDMETHODCALLTYPE Release(void);
    // Constructor is left undefined
    virtual "CUnknown() { m_RefCount = -1; }
    protected:
    volatile ULONG __declspec(align(8)) m_RefCount;
};

// Implementations of AddRef and Release remain the same
```

VMT with pure methods

```
&_purecall
&CUnknown::AddRef
&CUnknown::Release
&CUnknown::~CUnknown
```

Setting object's VMT (Linux 64-bit)

```
TUnknown::TUnknown():
                                                    // An implicit constructor
 00400fdc push
                  %rbp
 00400fdd mov
                  %rsp,%rbp
  00400fe0 mov
                  %rdi,-0x8(%rbp)
                                                    // this pointer stored in a local var
  00400fe4 mov
                  -0x8(%rbp),%rax
                                                    // this pointer to RAX
 00400fe8 mova
                  $0x4014d0.(%rax)
                                                    // VMT assigned to this->pVMT
 00400fef pop
                  %rbp
 00400ff0 retq
CUnknown::CUnknown():
                                                    // An implicit constructor
 00400fee push
                  %rbp
  00400fef mov
                  %rsp,%rbp
 00400ff2 sub
                  $0x10,%rsp
                  %rdi,-0x8(%rbp)
  00400ff6 mov
  00400ffa mov
                  -0x8(%rbp),%rax
 00400ffe mov
                  %rax,%rdi
                                                    // this passed in RDI
 00401001 callq
                  0x400fd8 <IUnknown::IUnknown()>
                                                    // Implicit constructor called here
 00401006 mov
                  -0x8(%rbp),%rax
 0040100a movq
                  $0x401490,(%rax)
                                                    // VMT assigned to this->pVMT
 00401011 leaveg
 00401012 reta
```

IUnknown's VMT

```
00000000004014d0 <_ZTV8IUnknown+16>:
+0 000000000400840 <__cxa_pure_virtual@plt>
+8 0000000000400840 < _cxa_pure_virtual@plt>
```

```
+8 0000000000400840 <__cxa_pure_virtual@plt>
+10 0000000000400840 <__cxa_pure_virtual@plt>
```

CUnknown's VMT

```
0000000000401490 <_ZTV8CUnknown+16>:
+0 000000000400840 <__cxa_pure_virtual@plt>
+8 000000000400976 <CUnknown::AddRef()>
```

+10 000000000400994 <CUnknown::Release()>

+18 000000000000000 empty

Polymorphism VII

Pure virtual methods' addresses in the VMT are replaced by the address of the _purecall function. This function calls a purecall handler if one's present and then aborts the program if not already aborted by the handler.

Source code of the _purecall function from purevirt.c

```
void __cdecl _purecall( void ) {
 _purecall_handler purecall = (_purecall_handler) DecodePointer(__pPurecall);
  if( purecall != NULL )
   purecall();
    /* shouldn't return, but if it does, we drop back to default behaviour */
  #if defined ( DEBUG)
    _NMSG_WRITE(_RT_PUREVIRT);
  #endif /* defined ( DEBUG) */
  /* do not write the abort message */
  _set_abort_behavior(0, _WRITE_ABORT_MSG);
  abort();
```

Virtual Method Tables in Reverse Engineering

As you have noticed, constructors set the object's VMT if one's present. This happens even if there's no constructor. In that case an implicit constructor is used (e.g. see the IUnknown ctor). Since each VMT is a global table shared by all instances of the same object, we can:

- use a VMT pointer to tell whether an unknown object is of a certain type by comparing its VMT pointer to a list of VMT pointers;
- examine pointers in the object's memory; if they point to a VMT, we've discovered multiple inheritance;
- examine pointers in each VMT and identify code belonging to the object.

The above information can be further extended by studying the object's type information, which is used in RTTI.

Motivation I

Slide no. 9 uses static_cast<const Rect*>(this) to cast the this pointer into a pointer to a Rect. The Rect* pointer is also a "this" pointer of a derived class and is different from the CRefcountedRect* this pointer. What code was behind the static_cast?

```
CRefcountedRect::get_Rect() const:
  004027C0
            push
                  ebp
  004027C1
            mov
                  ebp, esp
 004027C3
                  esp.48h
            sub
 004027C6
                  ebx
            push
            push
                  esi
  004027C7
 004027C8
            push
                  edi
  00402709
                  dword ptr [ebp-4].ecx
                                                           // Store this into ebp-4
            mov
 004027CC
            cmp
                  dword ptr [ebp-4],0
                                                           // Static_cast does nothing for a NULL pointer
                  CRefcountedRect::get_Rect+1Dh (4027DDh)
 004027D0
                  eax, dword ptr [ebp-4]
 004027D2
                                                           // Load this into EAX
            mov
 004027D5
                  eax.10h
            add
                                                           // Move the this pointer by 16 bytes
                  dword ptr [ebp-48h],eax
                                                           // Store the casted result
 004027D8
            mov
 004027DB
            qmp
                  CRefcountedRect::get_Rect+24h (4027E4h)
                  dword ptr [ebp-48h],0
                                                           // Static cast failed, store NULL as the result
 004027DD
            mov
 004027E4
                  eax, dword ptr [ebp-48h]
            mov
 004027E7
            pop
                  edi
 004027E8
                  esi
            pop
 004027E9
                  ebx
            pop
 004027EA
                  esp,ebp
            mov
  004027EC
                  ebp
            pop
  004027ED
           ret.
```

Motivation II

How do we go back from Rect* to CRefcountedRect*? When we want to upcast an object pointer, we can try dynamic_cast:

```
const Rect* pRect = pRefcountedRect->get Rect():
const CRefcountedRect* pRefCountedRect2 = dynamic_cast<const CRefcountedRect*>(pRect);
printf("pRefcountedRect=%p\npRefcountedRect2=%p\n", pRefcountedRect, pRefcountedRect, pRefCountedRect2);
1>c:\users\...\tokens.cpp(892): error C2683: 'dynamic_cast': 'Rect' is not a polymorphic type
```

Upcasting was not possible, since Rect was not polymorphic, i.e. did not have a VMT. We can add one by adding a virtual destructor:

```
typedef struct Rect [
  int f_X, f_Y, f_Width, f_Height;
 virtual "Rect():
} Rect, *RectPtr, **RectHandle;
```

The result

```
pRefcountedRect = 0012FE98
pRect
                 = 0012FEA8
pRefCountedRect2 = 0012FE98
```

How did dynamic_cast know that it was possible to cast this pointer to a Rect into a pointer to CRefcountedRect?

The typeid operator I

Run Time Type Identification (RTTI) is used when typeid or dynamic_cast operators are used. Let's see what typeid provides to us:

The type_info class is defined in typeinfo.h as follows:

There's a class name, a valuable piece of information!



The typeid operator II

When we look at assembly code of our code on the last slide, there's a type mismatch. While the result is a type_info reference, the value assigned into rtiCRefcountedRect is a _RTTITypeDescriptor pointer. The internals of this structure are hidden in a private rtti.h file. A similar structure, TypeDescriptor, with the same layout, is found in ehdata.h and describes the first field in the structure to be a VMT pointer:

```
typedef struct TypeDescriptor {
  #if defined(_WIN64) || defined(_RTTI) /*IFSTRIP=IGN*/
    const void * _EH_PTR64 pVFTable; // Field overloaded by RTTI
  #else
    DWORD hash; // Hash value computed from type's decorated name
  #endif
 void * _EH_PTR64 spare; // reserved, possible for RTTI
  char name[]; // The decorated name of the type; 0 terminated.
} TypeDescriptor:
```

Note: Normally, when using the typeid operator, the compiler changes it into a mov instruction assigning the _RTTITypeDescriptor* into the result (wherever possible), or calls the __RTtypeid function which returns an _RTTITypeDescriptor*.

The typeid operator III

```
extern "C" PVOID __CLRCALL_OR_CDECL __RTtypeid (
 PVOID inptr // Pointer to polymorphic object
) throw(...)
 if (!inptr) {
   throw bad_typeid ("Attempted a typeid of NULL pointer!");
   return NULL:
  __try {
   // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    RTTICompleteObjectLocator *pCompleteLocator = ( RTTICompleteObjectLocator *) ((*((void***)inptr))[-1]):
   if (((const void *)pCompleteLocator->pTvpeDescriptor) != NULL) {
     return (PVOID) COL_PTD(*pCompleteLocator);
    }
    else
    ſ
     throw __non_rtti_object("Bad read pointer - no RTTI data!");
     return NULL:
  __except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                                     EXCEPTION EXECUTE HANDLER: EXCEPTION CONTINUE SEARCH)
    throw __non_rtti_object ("Access violation - no RTTI data!");
   return NULL:
```

Dynamic_cast to a void* |

The dynamic_cast operator is typically used for upcasting (from a base class in direction from the base class to derived classes). When casting to a void* the __RTCastToVoid function from rtti.cpp is called:

```
void* pv = dynamic_cast<void*>(pRect);
 0040264B mov
                 eax, dword ptr [pRect]
 0040264E push eax
 0040264F call RTCastToVoid (4032C8h)
 00402654 add esp,4
 00402657 mov
                 dword ptr [pv],eax
extern "C" PVOID __CLRCALL_OR_CDECL __RTCastToVoid (
  PVOID inptr // Pointer to polymorphic object
) throw(...)
  if (inptr == NULL)
   return NULL;
 __try {
   return FindCompleteObject((PVOID *)inptr);
  __except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                                 EXCEPTION_EXECUTE_HANDLER : EXCEPTION_CONTINUE_SEARCH)
  ł
   throw non rtti object ("Access violation - no RTTI data!"):
   return NULL;
```

Dynamic_cast to a void* |

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
    // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
    char *pCompleteObject = (char *)inptr - COL_OFFSET(*pCompleteLocator);

    // Adjust by construction displacement, if any
    if (COL_CDOFFSET(*pCompleteLocator))
    pCompleteObject -= *(int *)((char *)inptr - COL_CDOFFSET(*pCompleteLocator));
    return (PVOID) pCompleteObject;
}
```

As you see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is private and undocumented.

Dynamic_cast to a void* |||

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
    // Ptr to CompleteObjectLocator should be stored at vfptr[-i]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
    char *pCompleteObject = (char *)inptr - COL_OFFSET(*pCompleteLocator);

    // Adjust by construction displacement, if any
    if (COL_CDOFFSET(*pCompleteLocator))
    pCompleteObject -= *(int *)((char *)inptr - COL_CDOFFSET(*pCompleteLocator));
    return (PVOID) pCompleteObject;
}
```

As you see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is private and undocumented.

WHO CARES?

Dynamic_cast to a void* IV

```
static PVOID __CLRCALL_OR_CDECL FindCompleteObject (PVOID *inptr) // Pointer to polymorphic object
{
    // Ptr to CompleteObjectLocator should be stored at vfptr[-1]
    _RTTICompleteObjectLocator *pCompleteLocator = (_RTTICompleteObjectLocator *)
    char *pCompleteObject = (char *)inptr - pCompleteLocator->offset;

    // Adjust by construction displacement, if any
    if (pCompleteLocator->cdOffset)
    pCompleteObject -= *(int *)((char *)inptr - pCompleteLocator->cdOffset);
    return (PVOID) pCompleteObject;
}
```

As you see, the function extracts an _RTTICompleteObjectLocator pointer from within a field in front of the VMT. The structure is:

```
typedef struct RTTITypeDescriptor {
 void* vftbl: // VMT pointer
 void* data:
                // ??
 char d_name[1]; // Mangled data type name
RTTITypeDescriptor. TypeDescriptor:
typedef struct _RTTICompleteObjectLocator {
  DWORD
                                 signature:
                                                             // version of the structure, COL SIG REVO==0
 LONG.
                                 offset:
                                                             // offset of this VMT in the complete class
                                                             // construction displacement offset
 LONG.
                                 cdOffset:
 TypeDescriptor*
                                pTvpeDescriptor:
  RTTIClassHierarchyDescriptor* pClassHierarchyDescriptor:
} _RTTICompleteObjectLocator;
```

Dynamic_cast to a non-void* |

When we use the dynamic_cast operator with a non-void* data type, MSVC calls the __RTDynamicCast internal function instead.

```
const CRefcountedRect* pRefCountedRect2 = dynamic_cast<const CRefcountedRect*>(pRect);
 00402C58
           push
                                                                         // 0 for pointers, 1 for refs
           push offset CRefcountedRect 'RTTI Type Descriptor' (432110h) // To coerce to
 00402C5A
                 offset Rect 'RTTI Type Descriptor' (4320FCh)
                                                                        // Coerce from
 00402C5F
 00402C64 push 0
                                                                         // A VMT offset in the object
 00402C66 mov
                 eax.dword ptr [ebp-0A8h]
                                                                         // An object to coerce
 00402C6C push eax
 00402C6D call __RTDynamicCast (40331Eh)
 00402C72 add
                 esp.14h
                 dword ptr [ebp-OACh].eax
  00402075
                                                                         // Store the coerced result
           mov
```

As we can see, passing an _RTTITypeDescriptor* is enough to verify whether CRefcountedRect derives from Rect. How is this information verified?

Dynamic_cast to a non-void* |

```
extern "C" PVOID __CLRCALL_OR_CDECL __RTDynamicCast (
  PVOID inptr, // Pointer to polymorphic object
 LONG VfDelta, // Offset of vfptr in object
 PVOID SrcType. // Static type of object pointed to by inptr
 PVOID TargetType, // Desired result of cast
 BOOL isReference) // TRUE if input is reference, FALSE if input is ptr
  throw(...)
    PVOID pResult=NULL;
    _RTTIBaseClassDescriptor *pBaseClass;
    // dynamic_cast returns nothing for a NULL ptr
    if (inptr == NULL)
     return NULL:
    __try {
     PVOID pCompleteObject = FindCompleteObject((PVOID *)inptr);
      _RTTICompleteObjectLocator *pCompleteLocator=(_RTTICompleteObjectLocator*) ((*((yoid***)inptr))[-1]);
      // Adjust by vfptr displacement, if any
      inptr = (PVOID *) ((char *)inptr - VfDelta);
      // Calculate offset of source object in complete object
      ptrdiff_t inptr_delta = (char *)inptr - (char *)pCompleteObject;
      if (!(CHD_ATTRIBUTES(*COL_PCHD(*pCompleteLocator)) & CHD_MULTINH)) {// if not multiple inheritance
        pBaseClass = FindSITargetTypeInstance( pCompleteLocator, (_RTTITypeDescriptor *) SrcType,
                                               ( RTTITypeDescriptor *) TargetType );
      } else if ...
      // Branches for multiple non-virtual and virtual inheritance.
```

Dynamic_cast to a non-void* |||

```
if (pBaseClass != NULL)
    // Calculate ptr to result base class from pBaseClass->where
    pResult = ((char *) pCompleteObject) + PMDtoOffset(pCompleteObject, BCD_WHERE(*pBaseClass));
  else
    pResult = NULL:
    if (isReference)
      throw bad cast("Bad dynamic cast!"):
7
__except (GetExceptionCode() == EXCEPTION_ACCESS_VIOLATION
                                ? EXCEPTION EXECUTE HANDLER : EXCEPTION CONTINUE SEARCH) {
 pResult = NULL;
  throw __non_rtti_object("Access violation - no RTTI data!");
return pResult;
```

Dynamic_cast to a non-void* IV

Each VMT[-1] contains the _RTTICompleteObjectLocator* pLoc pointer and the pLoc->pTypeDescriptor->d_name field tells us the type name! Having the name is the first step. We can go further by examining the below structures [2, 3] and discover the entire hierarchy!

```
typedef struct PMD {
 ptrdiff_t mdisp; //vftable offset
 ptrdiff t pdisp: //vftable offset
 ptrdiff t vdisp: //vftable offset (for virtual base class)
};
typedef const struct s RTTIBaseClassDescriptor {
 TypeDescriptor *pTypeDescriptor;
                numContainedBases;
 DWORD
                 where:
  DWORD
                 attributes;
} _RTTIBaseClassDescriptor;
typedef const struct _s_RTTIBaseClassArray {
  _RTTIBaseClassDescriptor *pArrayOfBaseClassDescriptors[1]; // A variable sized array
RTTIBaseClassArray:
typedef const struct _s_RTTIClassHierarchyDescriptor {
  DWORD
                      signature;
 DWORD
                      attributes:
                      numBaseClasses;
 DWORD
 _RTTIBaseClassArray *pBaseClassArray;
RTTIClassHierarchvDescriptor:
```

Dynamic_cast in g++

A brief glance

Let's check where the VMT and object metadata is stored in g++. The following code comes from libstdc++, namely gcc-4.9-4.9.2/gcc-4.9.2/libstdc++-v3/libsupc++/dyncast.cc:

We can see that the pointer to the VMT is also the first member of the structured type, and the metadata also precedes the VMT. There's a difference between MSVC and g++ — if a NULL pointer is passed to dynamic_cast in MSVC a NULL is returned, while g++ crashes dereferencing a NULL reference.

Type Information in Reverse Engineering

Type information presents another useful source of information about the reverse engineered target. We can extract the following:

- class name;
- class hierarchy.

There are IDA Pro scripts that do this work for us [1] and dump the hierarchy.

If we wanted to find this information ourselves, we would have to parse the code section and look for a typical constructor code — assigning the VMT to the first data member of the object. From the VMT[-1] pointer we could get to the type information and extract it.

Bibliography

- Igorsk: Reversing Microsoft Visual C++ Part II: Classes, Methods and RTTI. Available online at http://www.openrce.org/articles/full_view/23, 2006.
- Microsoft Corp.: rttidata.h: Available online at http: //read.pudn.com/downloads10/sourcecode/os/41823/WINCEOS/ COREOS/CORE/CORELIBC/CRTW32/RTTI/rttidata.h__.htm.
- Passion_wu128: rtti.h: Available online at http://m.blog.csdn.net/blog/passion_wu128/38511957, 2014.