

Assembly Language: Function Calls

Goals of this Lecture



Help you learn:

- Function call problems
- IA-32 solutions
 - Pertinent instructions and conventions

Function Call Problems



Calling and returning

- How does caller function jump to callee function?
- How does callee function jump back to the right place in caller function?

Passing arguments

How does caller function pass arguments to callee function?

Storing local variables

Where does callee function store its local variables?

Returning a value

How does callee function send return value back to caller function?

Handling registers

 How do caller and callee functions use same registers without interference?

Running Example



Caller

```
void f(void)
{     ...
     n = add3(3, 4, 5);
     ...
}
```

Callee

```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example

Problem 1: Calling and Returning



How does caller *jump* to callee?

I.e., Jump to the address of the callee's first instruction

How does the callee *jump back* to the right place in caller?

 I.e., Jump to the instruction immediately following the most-recently-executed call instruction

Attempted Solution: jmp Instruction



Attempted solution: caller and callee use jmp instruction

```
f:
    ...
    jmp g  # Call g

fReturnPoint:
    ...
```

```
g:
...
jmp fReturnPoint # Return
```

Attempted Solution: jmp Instruction



Problem: callee may be called by multiple callers

```
f1:

...

jmp g # Call g

f1ReturnPoint:

...
```

```
g:
...
jmp ??? # Return
```

```
f2:

...

jmp g # Call g

f2ReturnPoint:

...
```

Attempted Solution: Use Register



Attempted solution: Store return address in register

```
f1:
   movl $f1ReturnPoint, %eax
   jmp g # Call g
f1ReturnPoint:
   ...
```

```
f2:
    movl $f2ReturnPoint, %eax
    jmp g # Call g
f2ReturnPoint:
    ...
```

```
g:

jmp *%eax # Return

Special form of
```

jmp instruction

Attempted Solution: Use Register



Problem: Cannot handle nested function calls

```
f:
   movl $fReturnPoint, %eax
   jmp g  # Call g
fReturnPoint:
   ...
```

Problem if f() calls g(), and g() calls h()

Return address g() -> f() is lost

```
g:
  movl $gReturnPoint, %eax
  jmp h  # Call h

gReturnPoint:
  ...
  jmp *%eax # Return
```

```
h:
...
jmp *%eax # Return
```

IA-32 Solution: Use the Stack




Observations:

- May need to store many return addresses
 - The number of nested function calls is not known in advance
 - A return address must be saved for as long as the invocation of this function is live, and discarded thereafter
- Stored return addresses are destroyed in reverse order of creation
 - f() calls g() => return addr for g is stored
 - g() calls h() => return addr for h is stored
 - h() returns to g() => return addr for h is destroyed
 - g() returns to f() => return addr for g is destroyed
- LIFO data structure (stack) is appropriate

IA-32 solution:


- Use the STACK section of memory
- Via call and ret instructions



call and ret Instructions



ret instruction "knows" the return address




Implementation of call



ESP (stack pointer) register points to top of stack

Instruction	Effective Operations
pushl src	subl \$4, %esp
	movl src, (%esp)
popl dest	movl (%esp), dest
	addl \$4, %esp



Implementation of call



EIP (instruction pointer) register points to next instruction to be executed

Instruction	Effective Operations
pushl src	subl \$4, %esp
	movl src, (%esp)
popl dest	movl (%esp), dest
	addl \$4, %esp
call addr	pushl %eip jmp addr

Note: Can't really access EIP directly, but this is implicitly what call is doing

ESP ____ before call


call instruction pushes return addr (old EIP) onto stack, then jumps

12

Implementation of call



Instruction	Effective Operations
pushl src	subl \$4, %esp
	movl src, (%esp)
popl dest	movl (%esp), dest
	addl \$4, %esp
call addr	<pre>pushl %eip jmp addr</pre>



Implementation of ret



Instruction	Effective Operations
pushl src	subl \$4, %esp
	movl src, (%esp)
popl dest	movl (%esp), dest
	addl \$4, %esp
call addr	<pre>pushl %eip jmp addr</pre>
ret	popl %eip

Note: can't really access
EIP directly, but this is
implicitly what ret is
doing

ESP — before ret

Old EIP


ret instruction pops stack, thus placing return addr (old EIP) into EIP

16

Implementation of ret



Instruction	Effective Operations
pushl src	subl \$4, %esp
	movl src, (%esp)
popl dest	movl (%esp), dest
	addl \$4, %esp
call addr	<pre>pushl %eip jmp addr</pre>
ret	popl %eip



Running Example



Caller

```
f:
...
# Call the function
call add3
...
```

Callee

add3: ... ret

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example

Problem 2: Passing Arguments



Problem: How does caller pass arguments to callee?

```
void f(void)
{     ...
     n = add3(3, 4, 5);
     ...
}
```

```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

IA-32 Solution: Use the Stack




Observations (déjà vu):

- May need to store many arg sets
 - The number of arg sets is not known in advance
 - Arg set must be saved for as long as the invocation of this function is live, and discarded thereafter
- Stored arg sets are destroyed in reverse order of creation
 - f() calls g() => arg set for g is created
 - g() calls h() => arg set for h is created
 - h() returns to g() => arg set for h is destroyed
 - g() returns to f() => arg set for g is destroyed
- LIFO data structure (stack) is appropriate

IA 32 solution:

Use the STACK section of memory






Before executing call instruction... ESP




Caller pushes args in reverse order

- Push Nth arg first
- Push 1st arg last
- So 1st arg is at top of the stack at the time of the call





Caller executes call instruction






```
Callee accesses args relative to ESP
   Arg1 as 4 (%esp)
   Arg2 as 8 (%esp)
                                    ESP
                                                Old EIP
                                                  Arg1
                                                  Arg...
                                                  ArgN
```




Callee executes ret instruction





Caller pops args from the stack



Running Example



```
f:

# Push arguments
push1 $5
push1 $4
push1 $3

# Call the function
call add3

# Pop arguments
add1 $12, %esp
...
```

```
add3:

# Use arguments

movl 4(%esp), %eax

addl 8(%esp), %eax

addl 12(%esp), %eax

...

ret
```

Base Pointer Register: EBP




Problem:

- As callee executes, ESP may change
 - E.g., preparing to call another function
- Error-prone for callee to reference args as offsets relative to ESP

Solution:

- Use EBP (base pointer) register
 - EBP doesn't change during callee's execution
- Use EBP as fixed reference point to access args






Before executing call instruction... ESP **EBP**




Caller pushes args in reverse order

- Push Nth arg first
- Push 1st arg last
- So 1st arg is at top of the stack at the time of the call





Caller executes call instruction






Need to save old value of EBP

Before overwriting EBP register

Callee executes "prolog"

```
pushl %ebp
movl %esp, %ebp
```






Callee executes "prolog"

```
pushl %ebp

movl %esp, %ebp
```

Regardless of ESP, callee can reference Arg1 as 8 (%ebp), Arg2 as 12 (%ebp), etc.






Before returning, callee must restore ESP and EBP to their old values

Callee executes "epilog"

mov1 %ebp, %esp


popl %ebp





Callee executes "epilog"

```
movl %ebp, %esp
popl %ebp
```




Passing Args on the Stack (v2)



```
Callee executes "epilog"
```


```
movl %ebp, %esp
popl %ebp
```



Passing Args on the Stack (v2)




Callee executes ret instruction



Passing Args on the Stack (v2)



Caller pops args from the stack



Running Example



```
f:

# Push arguments
pushl $5
pushl $4
pushl $3

# Call the function
call add3

# Pop arguments
addl $12, %esp
...
```

```
add3:
   pushl %ebp
   movl %esp, %ebp
...
# Use arguments
   movl 8(%ebp), %eax
   addl 12(%ebp), %eax
   addl 16(%ebp), %eax
...
   movl %ebp, %esp
   popl %ebp
   ret
```

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example

Problem 3: Storing Local Variables



Where does callee function store its *local variables?*

```
void f(void)
{     ...
     n = add3(3, 4, 5);
     ...
}
```

```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

IA-32 Solution: Use the Stack



Var set for h

Var set for q

Var set for f

Observations (déjà vu again!):

- May need to store many local var sets
 - The number of local var sets is not known in advance
 - Local var set must be saved for as long as the invocation of this function is live, and discarded thereafter
- Stored local var sets are destroyed in reverse order of creation
 - f() calls g() => local vars set for g is created
 - g() calls h() => local vars set for h is created
 - h() returns to g() => local vars set for h is destroyed
 - g() returns to f() => local vars set for g is destroyed
- LIFO data structure (stack) is appropriate

IA 32 solution:

Use the STACK section of memory

Storing Variables on the Stack



Callee allocates space for its local variables on the stack


- Via push1 instructions
- Via sub1 \$4, %esp instructions

Example: allocate memory for two integers

- subl \$4,%esp # int i;
- push1 \$5 # int j = 5;

Callee references local variables as negative offsets relative to EBP

- -4(%ebp) # Access i
- -8 (%ebp) # Access j



ESP

EBP

Running Example



```
f:

# Push arguments
pushl $5
pushl $4
pushl $3

# Call the function
call add3

# Pop arguments
addl $12, %esp
...
```

```
add3:
  pushl %ebp
   movl %esp, %ebp
   # Allocate mem for local var
   subl $4, %esp
   # Use arguments
   mov1 8(%ebp), %eax
   addl 12(%ebp), %eax
   addl 16(%ebp), %eax
   # Use local variable
   movl %eax, -4(%ebp)
   movl %ebp, %esp
   popl %ebp
   ret
```

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example

Problem 4: Return Values



Problem: How does callee function send return value back to caller function?

```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

IA-32 Solution: Use EAX



In principle

Store return value in stack frame of caller

Or, for efficiency

- Known small size => store return value in register
- Other => store return value in stack

IA-32 convention

- Integer or pointer:
 - Store return value in EAX
- Floating-point number:
 - Store return value in floating-point register
 - (Beyond scope of COS 217)
- Structure:
 - Store return value on stack
 - (Beyond scope of COS 217)

Running Example



```
f:
   # Push arguments
  pushl $5
  pushl $4
  pushl $3
   # Call the function
   call add3
   # Pop arguments
   addl $12, %esp
   # Use return value
  movl %eax, n
```

```
add3:
  pushl %ebp
  movl %esp, %ebp
   # Allocate mem for local var
   subl $4, %esp
   # Use arguments
  mov1 8(%ebp), %eax
   addl 12(%ebp), %eax
   addl 16(%ebp), %eax
   # Use local variable
  movl %eax, -4(%ebp)
   # Indicate return value
  movl -4(%ebp), %eax
  movl %ebp, %esp
  popl %ebp
   ret
```

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example

Problem 5: Handling Registers



Observation: Registers are a finite resource

- In principle: Each function should have its own registers
- In reality: All functions share same small set of registers

Problem: How do caller and callee use same set of registers without interference?

- Callee may use register that the caller also is using
- When callee returns control to caller, old register contents may have been lost
- Caller function cannot continue where it left off

IA-32 Solution: Register Conventions

ESP



Callee-save registers: EBX, ESI, EDI

- If necessary...
 - Callee saves to stack after prolog
 - Callee restores from stack before epilog
- Caller can assume that values in EBX, ESI, EDI will not be changed by callee

Caller-save registers: EAX, ECX, EDX

- If necessary...
 - Caller saves to stack before call
 - Caller restores from stack after call

Var2 Var1 Saved EBX, ESI, EDI Old EBP Old EIP Arg1 Arg... ArgN Saved EAX, ECX, EDX 52

Running Example



```
f:

# Save EAX, ECX, EDX
pushl %eax
pushl %ecx
pushl %edx

# Push arguments
pushl $5
pushl $4
pushl $3

# Call the function
call add3
```

```
# Pop arguments
addl $12, %esp

# Use return value
movl %eax, n

# Restore EAX, ECX, EDX
popl %edx
popl %ecx
popl %eax
...
```

Running Example



```
add3:
  pushl %ebp
  movl %esp, %ebp
  # Save EBX, ESI, EDI
  pushl %ebx
  pushl %esi
  pushl %edi
  # Allocate mem for local var
   subl $4, %esp
  # Use arguments
  movl 8(%ebp), %eax
  addl 12 (%ebp), %eax
  addl 16(%ebp), %eax
  # Use local variable
  movl %eax, -16(%ebp)
```

Not necessary to save callee-save registers in this particular function

```
# Indicate return value
movl -4(%ebp), %eax

# Restore EBX, ESI, EDI
movl -12(%ebp), %edi
movl -8(%ebp), %esi
movl -4(%ebp), %ebx

movl %ebp, %esp
popl %ebp
ret
```

Stack Frames



Summary of IA-32 function handling:

Stack has one **stack frame** per active function invocation

ESP points to top (low memory) of current stack frame

EBP points to bottom (high memory) of current stack frame

Stack frame contains:

- Values of caller-save registers
- Arguments to be passed to callee function
- Return address (old EIP)
- Old EBP
- Values of callee-save registers
- Local variables

Agenda



Calling and returning

Passing arguments

Storing local variables

Returning a value

Handling registers

An example




```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

```
void f(void)
{     ...
     n = add3(3, 4, 5);
     ...
}
```



n = add3(3, 4, 5);






```
n = add3(3, 4, 5);
```

Low memory


Save caller-save registers if necessary
push! %eax
push! %ecx
push! %edx





```
n = add3(3, 4, 5);
```


```
# Save caller-save registers if necessary
push! %eax
push! %ecx
push! %edx
# Push arguments
push! $5
push! $4
push! $3
```





```
n = add3(3, 4, 5);
```

```
# Save caller-save registers if necessary
push! %eax
push! %eax
push! %edx
# Push arguments
push! $5
push! $4
push! $3
# Call add3
call add3
```






```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

```
# Save old EBP push! %ebp
```


Prolog





```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

```
# Save old EBP
pushl %ebp
# Change EBP
movl %esp, %ebp
```






```
Low memory
int add3(int a, int b, int c)
{ int d;
                                                ESP '
                                                         Old EDI
   d = a + b + c;
   return d;
                                                         Old ESI
                                                         Old EBX
                                                EBP:
                                                         Old EBP
# Save old EBP
                                                         Old EIP
pushl %ebp
# Change EBP
movl %esp, %ebp
# Save callee-save registers if necessary
pushl %ebx
               Unnecessary here; add3 will not
                                                         Old EDX
pushl %esi
                change the values in these registers
pushl %edi
                                                         Old ECX
                                                         Old EAX
                                                                    64
                                          High memory
```



```
int add3(int a, int b, int c)
{   int d;
   d = a + b + c;
   return d;
}
```

```
# Save old EBP
push! %ebp
# Change EBP
mov! %esp, %ebp
# Save caller-save registers if necessary
push! %ebx
push! %esi
push! %edi
# Allocate space for local variable
sub! $4, %esp
```






```
Low memory
int add3(int a, int b, int c)
                                                  ESP
{ int d;
                                                           Old EDI
   d = a + b + c;
   return d;
                                                           Old ESI
                                                           Old EBX
                                                  EBP -
                                                           Old EBP
# Save old EBP
                                                           Old EIP
pushl %ebp
# Change EBP
movl %esp, %ebp
# Save caller-save registers if necessary
pushl %ebx
                                                           Old EDX
pushl %esi
pushl %edi
                                                           Old ECX
# Allocate space for local variable
                                                           Old EAX
subl $4, %esp
                            Access args as positive
# Perform the addition
                            offsets relative to EBP
movl 8(%ebp), %eax
addl 12(%ebp), %eax
                            Access local vars as neg
addl 16(%ebp), %eax
                            offsets relative to FBP
movl %eax, -16(%ebp)
                                                                      66
                                           High memory
```



```
int add3(int a, int b, int c)
{    int d;
    d = a + b + c;
    return d;
}
```

```
# Copy the return value to EAX
movl -16(%ebp), %eax
# Restore callee-save registers if necessary
movl -12(%ebp), %edi
movl -8(%ebp), %esi
movl -4(%ebp), %ebx
```





```
int add3(int a, int b, int c)
{   int d;
   d = a + b + c;
   return d;
}
```

```
# Copy the return value to EAX
movl -16(%ebp), %eax
# Restore callee-save registers if necessary
movl -12(%ebp), %edi
movl -8(%ebp), %esi
movl -4(%ebp), %ebx
# Restore ESP
movl %ebp, %esp

Epilog
```


Low memory ESP ' Old EBP **EBP** Old EIP Old EDX Old ECX Old EAX High memory



```
int add3(int a, int b, int c)
{   int d;
   d = a + b + c;
   return d;
}
```

```
# Copy the return value to EAX
movl -16(%ebp), %eax
# Restore callee-save registers if necessary
movl -12(%ebp), %edi
movl -8(%ebp), %esi
movl -4(%ebp), %ebx
# Restore ESP
movl %ebp, %esp
# Restore EBP
popl %ebp

Epilog
```






```
int add3(int a, int b, int c)
{   int d;
   d = a + b + c;
   return d;
}
```


```
# Copy the return value to EAX
movl -16(%ebp), %eax
# Restore callee-save registers if necessary
movl -12(%ebp), %edi
movl -8(%ebp), %esi
movl -4(%ebp), %ebx
# Restore ESP
movl %ebp, %esp
# Restore EBP
popl %ebp
# Return to calling function
```

ret






```
# Save caller-save registers if necessary
push! %eax
push! %ecx
push! %edx
# Push arguments
push! $5
push! $4
push! $3
# Call add3
call add3
# Pop arguments
add! $12, %esp
```





```
# Save caller-save registers if necessary
push! %eax
push! %ecx
push! %edx
# Push arguments
push! $5
push! $4
push! $3
# Call add3
call add3
# Pop arguments
add! %12, %esp
# Use return value
mov! %eax, n
```






```
Low memory
n = add3(3, 4, 5);
# Save caller-save registers if necessary
pushl %eax
pushl %ecx
pushl %edx
# Push arguments
pushl $5
pushl $4
pushl $3
# Call add3
call add3
# Pop arguments
addl %12, %esp
# Use return value
movl %eax, n
                                                    ESP -
# Restore caller-save registers if necessary
popl %edx
popl %ecx
popl %eax
                                                    EBP —
                                                                          73
                                             High memory
```



```
n = add3(3, 4, 5);
```

```
# Save caller-save registers if necessary
pushl %eax
pushl %ecx
pushl %edx
# Push arguments
pushl $5
pushl $4
pushl $3
# Call add3
call add3
# Pop arguments
addl %12, %esp
# Use return value
movl %eax, n
# Restore caller-save registers if necessary
popl %edx
popl %ecx
popl %eax
# Proceed!
```



Summary



Function calls in IA-32 assembly language

Calling and returning

- call instruction: push EIP onto stack and jump
- ret instruction: pop from stack to EIP

Passing arguments

- Caller pushes onto stack
- Callee accesses as positive offsets from EBP
- Caller pops from stack

Summary (cont.)



Storing local variables

- Callee pushes onto stack
- Callee accesses as negative offsets from EBP
- Callee pops from stack

Handling registers

- Caller saves and restores EAX, ECX, EDX if necessary
- Callee saves and restores EBX, ESI, EDI if necessary

Returning values

Callee places data of integer types and addresses in EAX