Turbolence and Mixing course by Professor Jaan Kalda, TalTech lecture notes by

student Enrico Di Lavore

26 November 2021

1 Lect.1: Intro on main concepts and classification of turbolence

1.1 Trajectories:

Also called Pathlines, are typically a lagrangian idea. Are the trajectories of the individual fluid particles. Those can be computed integrating the equation

$$d\mathbf{x} = \mathbf{v}(\mathbf{x}, t)dt$$

given the initial positions. The direction of the trajectory is locally determined by the streamlines of the fluid at each moment in time.

1.2 Streamlines:

Are the family of curves that are instantaneously tangent to V vector field. These show the direction in which a massless (without inertia) fluid element would travel at any point in time. Streamlines are defined by:

$$\frac{\mathrm{d}\mathbf{x_s}}{\mathrm{d}s} \times \mathbf{v}(\mathbf{x_s}) = 0 \Rightarrow \frac{\mathrm{d}\mathbf{x_s}}{\mathrm{d}s} \parallel \mathbf{v}(\mathbf{x_s})$$

where s indicate the particular streamline (curvilinear abscissa). Intuitively, the cross product equal to zero impose the two vectors to be **parallel**. From here the tangential direction.

(The reader is suggested to check also Streamtube; Streamlines and timelines which provide a snapshot of some flowfield characteristics, whereas streaklines and pathlines depend on the full time-history of the flow) Note that if the flow is **stationary** then all those lines coincide.

1.3 Turbolence:

In fluid dynamics, turbolence or turbulent flow is fluid motion characterized by **chaotic changes** in pressure and flow velocity. It cause mixing.

The onset of turbulence can be predicted by the dimensionless **Reynolds number** Re, the ratio of kinetic energy to viscous damping in a fluid flow. $Re = \frac{v \cdot L}{\nu}$

1.4 Laminar flow:

It occurs when a fluid flows in parallel layers, with no disruption between those layers. The shear forces between stream lines cause a typical speed function. It is characterised by small values of Re number.

Can be seen in the picture that the speed is constant everywhere and decreasing with a certain function close to the plumb surface.

This is known as boundary layer.

1.5 Mixing:

It is a **random transport** of *something* (passive or active, scalar or vector field) Vectorial field case **diffusion equation**:

$$\frac{\mathrm{d}\mathbf{n}}{\mathrm{d}t} = \frac{\partial\mathbf{n}}{\partial t} + (\mathbf{v}\nabla)\mathbf{n} = D \cdot \Delta\mathbf{n}$$

-The first term $\frac{\mathrm{d}n}{\mathrm{d}t}$ is the Lagrangian (material) derivative

-In the second term $\frac{\partial n}{\partial t}$ is the Eulerian derivative

1.5.1 Why should diffusion be considered as a random transport?

Insert: heat stochastic theory, proabilistic approach on evaporation, photo electric effect...

1.6 Advection:

The advection term is often used as synonim for convection. More technically, convection applies to the movement of a fluid (often due to density gradients created by thermal gradients), whereas advection is the movement of some material by the velocity of the fluid. We consider here advection of a scalar quantity ψ in ndimensions:

$$\frac{\partial \psi}{\partial t} + \nabla \cdot (\psi \mathbf{v}) = 0$$

What this equation means? We analyse the 1 dimensional case: The flux density Φ of the quantity ψ is $\Phi = c\psi$ where c is the drift speed of a substance e.g. in a tube with flowing liquid. ψ represent the concentration of the substance. Substituting this equation into local conservation law, we get the **transport equation** for the concentration ψ : $\frac{\partial \psi}{\partial t} + c\psi_x = 0$ From the differential analysis you know that $\psi(x,t) = F(x-ct)$, that is a travelling wave. You can see that the profile of function $\psi(x)$ is rigidly shifting.

1.7 Transport & diffusion equation in n-dim:

The reader can have fun (if haven't had in the past) to obtain the transport and diffusion equation in the n- dimensional case: considering the quantity ψ it is

$$\frac{\partial \psi(\mathbf{x}, t)}{\partial t} = \mathbf{c} \nabla \psi(\mathbf{x}, t) - k \Delta \psi(\mathbf{x}, t)$$

1.8 Passive: vector field or scalar

A vector field **A** (or a scalar A) is said to be passive if the velocity field does **not depend** on **A** (or A) mixing state evolution. $\mathbf{v} \neq f(\mathbf{A}(\mathbf{X},t))$ (or $\mathbf{v} \neq f(A(\mathbf{X},t))$)

1.8.1 e.g. Passive scalar:

If we consider heat diffusion in a mixing process, in Hp. of *incompressible* fluid we can write that $\rho(T) = const.$

In this case T° is an attribute of the *fluid particle* that does not influence the motion of the fluid itself.

Other examples of scalars that are good to be modeled as passive:

- · Dye concentration \mathbf{n} in a fluid (which values as ρ, ν ... must be similar enough to the fluid ones in order to not influence the time evolution) is considered passive if its concentration is low enough.
- · Others?

1.8.2 e.g. Passive vector field:

If we consider electro-magnetic field in a medium (as water) while studing ships propellers phenomena as cavitation or flutter, then is a good Hp. to consider E-M field as a **passive vector field**. Indeed it is not influencing noticeably the solution $\mathbf{v}(\mathbf{X},t)$ of this particular problem.

1.9 Active: vector field or scalar

A vector field **A** or scalar A is said to be active if the velocity field does **depend** on A mixing state evolution. $\mathbf{v} = f(\mathbf{A}(\mathbf{X}, t) \ (\text{ or } \mathbf{v} = f(A(\mathbf{X}, t)))$

1.9.1 e.g. Active scalar:

We consider again T in a fluid. This time the latest is said *compressible* if $\rho(T) \neq const$. As in convection phenomena, $\nabla \rho$ generates buoyancy forces among the fluid particles. In this case, T is influencing the motion through density.

1.9.2 e.g. Active vector field:

· If we are considering a star, here we must consider the E.M. field propagating through the plasma as an active vector field: indeed it generates reciprocal forces between two infinitesimal volumes of plasma dV_1 and dV_2 .

This forces generate accelerations which, integrated over time, influence \mathbf{v} field. This will be seen in a later chapter regarding Magneto-Hydro-Dynamics (MHD). By the way, if the field is small in the (so called) kinematic magnetic dynamo, then it can be considered passive. Magnetic dynamo equation:

$$\left[\frac{\partial}{\partial t} + (\mathbf{v}\nabla)\right]\mathbf{B} = D\Delta\mathbf{B}$$

·The angular speed ω is active vector field by definition: indeed

$$\omega = \nabla \times \mathbf{v}$$

Turbolence, as the mixing problem of an active field, is the last unsolved problem of classical physics: the vorticity.

1.10 Mixing of passive scalars:

$$\frac{\partial n}{\partial t} + (\mathbf{v}\nabla)n = D \cdot \Delta n$$

We can define compressibility P as $P = \frac{< v_{pot}^2>}{< v_{pot}^2> + < v_{sol}^2>}$

where pot stands for **potential component** and sol for **solenoidal component**. We see that $P \in [0; 1]$, (0 means incompressible).

1.10.1 Helmoltz decomposition analogy:

What we have just seen comes from the decomposition of the velocity vector field into its solenoidal component (vector potential) \mathbf{A} and potential component ϕ

$$\mathbf{v} = \nabla \times \mathbf{A} - \nabla \phi$$

This is analogue to see first and second Maxwell equations in the solenoidal-potential framework:

$$div(\mathbf{B}) = \nabla \cdot \mathbf{B} = 0 \Rightarrow \mathbf{B} = \nabla \times \mathbf{A}$$

$$\nabla \times \mathbf{E} = 0 \Rightarrow \mathbf{E} = -\nabla \phi$$

1.11 Sound propagation

The set of equations involved into the sound propagation is composed by:

1.11.1 Continuity equation:

$$(\frac{\partial}{\partial t} + \nabla \cdot \mathbf{v})\rho = 0 \Rightarrow \frac{\partial \rho}{\partial t} = -\rho(\nabla \cdot \mathbf{v})$$

where $|v| \ll C_s(soundspeed)$

Its meaning is related with Divergence theorem: we can see that the time derivative of the density is equal in modulus to the velocity vector field divergence times the density. If we see the intuitive meaning of the divergence of the velocity vector field (i.e. how much a point behave as a source or sink), by multiplying by the density, we get how much the point behaves as "mass source " (or sink). That is the time derivative of the local density.

1.11.2 Newton 2^{nd} law (Linear momentum balance law):

$$\left(\frac{\partial}{\partial t} + \mathbf{v}\nabla\right)\mathbf{v} = -\frac{\nabla p}{\rho}$$

Basically it is $a = \frac{F}{m} = \frac{F}{\rho \cdot V}$ with volume V \rightarrow 0; with the acceleration explicited in Eulerian form on the left-hand side

1.11.3 Adiabatic law: $p\rho^{-\gamma} = const.$

Hp. the air parcel, subjected to repeated compression-decompression cycles, does not exchange heat with its neighbour parcels; although in reality heat is actually flowing from the high pressure zones (that have just increased their temperature adiabatically starting from common average temperature) to the low pressure zones (with lower temperature for the same reason).

1.12 Lengmuir waves in 2D:

Let G_e^- be a set of electrons laying on a rigid square grid (frame) of $n \times m$ elements $(n, m) \in \mathbb{N}$. Similarly, let G_p^+ be a set of protons laying on another square grid of $n \times m$ elements.

We overlap those two grids, but with certain phase-shifts along two axis: λ_x and λ_y .

(See picture). We can intuitively see that the minimum of the electro-static potential happens when the phase-shifts $\lambda_x = \lambda_y = 0$. This is the global minimum. (The proof is left to the reader).

Also, the electrostatic potential will increase while getting away from the main overlapping mode (when $\lambda_x = \lambda_y = 0$ and boundaries of the grid also coincide). The reader can prove that there will be also others equilibria, corresponding to a shift equal to the grid spacing. The latest are local minima.

This system, if left with initial conditions $\lambda_x \neq 0$ or $\lambda_y \neq 0$ will oscillate "as a pendulum" around the minimum. Beware to the fact that this is not exactly an harmonic oscillator, since the electrostatic force $f_{q_1q_2} \propto r_{1,2}^{-2}$, instead the spring force is linear. The same idea can be applied to not-squared grids (e.g. exagonal grid) and in more than 2 dimensions.

1.12.1 $n, m \to \infty$ case

We can also intuitively see that with $n, m \to \infty$, the function electric potential $U = U(\lambda_x, \lambda_y)$ tend to be a periodic function, and every of the ∞^2 minima will be at the same potential U.

1.12.2 Modulation instability: not complete

Stable is sol of non-linear Shroedinger equation. See graph. Important for optical cable communication: solitons=very short pulse

1.13 Overdamped motion of brownian particle in energy landscape: not complete

We consider an electron in an electric field. It holds that:

 ${f F}=-e
abla\phi$ and ${f v}=-be
abla\phi$ We need a parametric evaluation about when a fluid is compressible or not.

The parameter that we are looking for is Mach number Ma.

2 Lect.2: Advection and diffusion with stationary flow field

2.1 Double way to represent advection and diffusion

Those two ways are equivalent, the convenience depends on the situation. The first is a non-linear ODE, the latter is a linear PDE.

2.1.1 as a set of brownian particles

$$\dot{r} = \dot{f}(t) + \mathbf{v}(r)$$

2.1.2 as the concentration of a tracer

$$\frac{\partial n}{\partial t} + (\mathbf{v}\nabla)n = D\Delta n$$

2.2 Analysis as in high school:

Starting with just a diffusion along x, the simplest random walk is with random unit steps done in unit time. $\dot{r} = f(t)$.

By time-discretization we get: $r_{t+1} - r_t = s_t = \pm 1$ (random)

The current coordinate r is given by: $r(t) = \sum_{i=1}^{t} s_i$

We can compute the average of the random walk in a time interval:

$$< r^{2}(t) > = < \sum_{i=1}^{t} s_{i} \sum_{j=1}^{t} s_{j} > = < \sum_{i,j=1}^{t} s_{i}s_{j} > = \sum_{i,j=1}^{t} < s_{i}s_{j} > = \sum_{i,j=1}^{t} \delta_{ij} = t$$

where δ_{ij} is Kroneker delta.

If we declare a length step λ and a time step τ , this can be rewritten as: $\langle r_t^2 \rangle = \frac{\lambda^2 t}{\tau}$ Then the diffusivity D is defined as $D = \frac{\lambda^2}{2\tau}$, so that $\langle r_t^2 \rangle = 2Dt$

2.3 Description by mean of random white-noise forcing

We consider the auto-correlation function: still with $\dot{r} = f(t)$, we compute:

$$r = \int_0^t f(t') dt' \Rightarrow r^2 = \int_0^t \int_0^t f(t') f(t'') dt' dt'' \Rightarrow$$
$$\Rightarrow \langle r^2 \rangle = \int_0^t \int_0^t \langle f(t') f(t'') \rangle$$

But we know that $\langle f(t)f(t') \rangle = 2D\delta(t-t')$, then we substitute and get:

$$< r^2 > = \int_0^t \int_0^t 2 D \, \delta(t' - t'') \, dt' \, dt'' = \int_0^t 2 D \, dt' = 2 D \, t$$

3 Appendix:convenctions, symbols and letters

If it is not differently specified, then:

- -bold letters refers to vectors, otherwise are scalars
- -Hp. \leftrightarrow Hypothesis

3.1 Greek and standard alphabet:

 \times vectorial (cross) product T temperature [K] ρ density $[kg \cdot m^{-3}]$

 ν kinematic viscosity $[m^2 \cdot s^{-1}]$ n concentration $[m^{-3}]$ **B** magnetic field $[T = kg \cdot s^{-2} \cdot A^{-1}]$ **v** velocity $[m \cdot s^{-1}]$

acceleration: in n-dim

$$\mathbf{a} = \frac{\mathrm{d}\mathbf{v}}{\mathrm{d}t} = (a_j) = (\frac{\partial v_j}{\partial t} + \sum_{i=1}^n v_i \frac{\partial v_j}{\partial x_i})$$

3.2 Math symbols:

Laplacian: sum of the 2^{nd} order partial derivatives

$$\Delta = \sum_{i=1}^{n} \frac{\partial}{\partial x_i^2}$$

gradient: vector of the 1^{st} order partial derivatives

$$\nabla = (\frac{\partial}{\partial x_i})$$