parameter. The term *parameter* has two different meanings—it can refer either to a TeX parameter or to a macro parameter.

A TEX parameter is a control sequence that names a value. The value of a parameter can be a number, a dimension, an amount of glue or muglue, or a token list. For example, the \parindent parameter specifies the distance that TEX skips at the start of an indented paragraph.

You can use the control sequence for a parameter either to retrieve the value of the parameter or to set that value. TeX interprets the control sequence as a request for a value if it appears in a context where a value is expected, and as an assignment otherwise. For example:

\hskip\parindent

produces horizontal glue whose natural size is given by \parindent, while:

\parindent = 2pc % (or \parindent 2pc)

sets \parindent to a length of two picas. The assignment:

\parindent = 1.5\parindent

uses \parindent in both ways. Its effect is to multiply the value of \parindent by 1.5.

You can think of a parameter as a built-in register. You'll find a complete list of the T_EX parameters on pages 272–275 of The T_EXbook.

A macro parameter is a placeholder for text that is to be plugged into the definition of a macro. See "macro" (p. 'macro') for more information about this kind of parameter.