Spin state s is a unit vector in \mathbb{C}^2 .

$$|s\rangle = \begin{pmatrix} c_1 \\ c_2 \end{pmatrix}, \quad c_1^*c_1 + c_2^*c_2 = 1$$

Here is $|s\rangle$ as a linear combination of basis states "up" and "down."

$$|s\rangle = c_1|u\rangle + c_2|d\rangle, \quad |u\rangle = \begin{pmatrix} 1\\0 \end{pmatrix}, \quad |d\rangle = \begin{pmatrix} 0\\1 \end{pmatrix}$$

These are the spin operators.

$$\sigma_x = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}, \quad \sigma_y = \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix}, \quad \sigma_z = \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}$$

Expectation of spin operators is a projection of s onto Euclidean space.

$$\langle x \rangle = \langle s | \sigma_x | s \rangle, \quad \langle y \rangle = \langle s | \sigma_y | s \rangle, \quad \langle z \rangle = \langle s | \sigma_z | s \rangle$$

Spin polarization vector \mathbf{P} is

$$\mathbf{P} = \begin{pmatrix} \langle x \rangle \\ \langle y \rangle \\ \langle z \rangle \end{pmatrix} = \langle s | \sigma | s \rangle$$

where

$$\sigma = \begin{pmatrix} \sigma_x \\ \sigma_y \\ \sigma_z \end{pmatrix}$$

Let θ and ϕ be polar and azimuth angles such that

$$\mathbf{P} = \begin{pmatrix} \sin \theta \cos \phi \\ \sin \theta \sin \phi \\ \cos \theta \end{pmatrix}$$

Then

$$|s\rangle = \begin{pmatrix} \cos(\theta/2) \\ \sin(\theta/2) \exp(i\phi) \end{pmatrix}$$

In component notation $\sigma = \sigma^{\alpha\beta}{}_{\gamma}$ hence

$$P^{\alpha} = s_{\beta}^* \sigma^{\alpha\beta}{}_{\gamma} s^{\gamma}$$

In Eigenmath a transpose is needed to swap α and β so that summed-over indices are adjacent.

$$P^{\alpha} = s_{\beta}^* \sigma^{\beta \alpha}{}_{\gamma} s^{\gamma}$$

Hence the Eigenmath code is P = dot(conj(s), transpose(sigma),s)