Locust Forecast Web App User Guide

Version 1.0, May 18, 2020

Based on HYSPLIT Locust Forecast

Version 0.1.6




Table of Contents

1.	Introduction	4
2.	Single Swarm Run Specification Page	5
	Swarm name	5
	Start date and direction	5
	Start Location	6
	Locust Flight Time	7
	Plot Options	7
	Advanced	8
	Start a new batch run	8
	Restore Default values	8
	Start Simulation	8
3.	Screen Outputs During Single-Swarm Run	9
	JOB NUMBER	9
	MODEL STATUS	9
	MODEL DETAILS	10
	RESULTS	10
	LINKS	11
4.	Outputs from Single-Swarm Run	12
	run-name_progress.txt	12
	run-name_ run_setup_summary.txt	12
	run-name_trajplot.ps	12
	run-name_trajplot.pdf	12
	run-name_trj_001.png	12
	run-name_MAPTEXT.txt	12
	run-name_CONTROL.1.txt, run-name_CONTROL.2.txt,	12
	run-name_SETUP.1.txt, run-name_SETUP.2.txt,	12
	run-name_MESSAGE.1.txt, run-name_MESSAGE.2.txt,	13
	run-name_tdump.1, run-name_tdump.2,	13
	run-name_tdump.1.full, run-name_tdump.2.full,	13
	GIS Shapefile Outputs	13

5	. Multiple-Swarm (Batch-mode) Simulation	. 14
	Batch-run Input Page	. 14
	Carry out a batch-run simulation	. 14
	Screen outputs during batch-run simulations	. 18
	Output Files from Batch-Run Simulations	. 19

1.Introduction


Countries in Eastern Africa and the Middle East are affected by outbreaks of desert locust swarms, creating significant threats to food security in these regions. Advance knowledge of where a given swarm might go, and/or where it might have come from, can aid efforts to mitigate the devastating impacts caused by these voracious pests. Locusts are believed to be relatively passive fliers, with movements primarily influenced by the wind. They also fly together in a swarm, making them ideal candidates for simulation using HYSPLIT's air *trajectory* modeling capabilities (as opposed to HYSPLIT's air *dispersion* functionality). This web app allows users to specify takeoff and landing times (e.g., relative to sunset and sunrise) and flying height(s) to create forward or backward flight-path simulations from identified swarm locations. Crucial information output from the simulations are estimates of where a given swarm may land in the coming days.

This web app was <u>developed</u> based on a request from Keith Cressman, the senior locust forecasting officer at the United Nations Food and Agriculture Organization (FAO). The FAO <u>coordinates desert locust response and mitigation</u> efforts globally. FAO's Cressman had been using HYSPLIT for locust forecasting and asked how locust behavior (e.g., taking off and landing each day) could be efficiently <u>accounted for in simulations</u>, and he has been consulted throughout the process in efforts to make the app as useful as possible to locust forecasters. His expertise regarding locust forecasting has played a fundamental role in the development of this tool.

There are two different ways to use this web application:

- **Single Swarm:** The user specifies parameters for the simulation of a single swarm, including swarm name, starting date and location, meteorological data to use, direction (forward or backward), take-off and landing times, flying height(s), and graphical output options. Once inputs are set, the user "Starts Simulation", and a complete set of output data files and graphics are produced that can be downloaded.
- Multiple Swarms (batch mode): The user creates a CSV file based on a provided template, with one row for each swarm to be simulated, and columns that provide all of the inputs necessary for simulating that particular swarm. The user uploads the CSV file by "dropping" it onto the batch-run input page. If all inputs are acceptable, the batch run can be started, and a full set of output files and graphics are generated for each swarm in the batch.

2. Single Swarm Run Specification Page



Swarm name

Enter the user-defined swarm name in this box. All output files from this simulation will have that swarm name associated with them. The name must consist only of alphanumeric characters (not exceeding 20 characters), and there can be no spaces or any special characters other than underscore (). Example: *Kenya_A_05_14_2020*

Start date and direction

Meteorological data: The user can select either the default GFS Model 0.25° (Global) dataset or the GFS Model 1.0° degree (Global) dataset. The 0.25° dataset has a horizontal resolution of ~25 km, and supports forecasts up to 3 days into the future. The 1.0° dataset has a horizontal resolution of ~100 km and supports forecasts up to 7 days in the future. Additional information on these forecast data sets is <u>available</u>. For simulations (or parts of simulations) that occur in the past, a quasi-analysis version of the GFS Model output is used. In this quasi-analysis version, initial-time-step results are saved from each forecast, and these short-term, more highly accurate results are

patched together to make a continuous dataset. Information about the 1.0° quasianalysis dataset is available <u>here</u>, and information about the 0.25° quasi-analysis dataset is available <u>here</u>.

Start date (UTC): Selectable in a drop-down calendar, the day you would like the simulation to start, in Universal Time Coordinates (UTC). The default start date is the current date.

Direction: Select Forward (default) or Backward.

Duration: The number of days you would like the simulation to be for. The user can select 1,2,3,5, or 7 days from the drop-down menu. As noted above, if 0.25° GFS data are used, a maximum of 3 days in the future can be simulated. If 1.0° GFS data are used, the simulation can be carried out for up to 7 days into the future. The default duration is 3 days.

First-day start time (UTC): (optional) The user can enter the UTC hour and minute of the locust take-off time, and this will <u>over-ride</u> any sunrise-offset take-off time set below *for the first day of the simulation*. For subsequent days of the simulation, the sunrise-offset set below is used. This can be used, for example, in the special case where local knowledge of the actual swarm take-off time exists. The default is for this not to be specified.

First-day ending time (UTC): (optional) The user can enter the UTC hour and minute of the locust landing time, and this will <u>over-ride</u> any sunset-offset landing time set below *for the first day of the simulation*. For subsequent days of the simulation, the sunset-offset set below is used. This can be used, for example, in the special case where local knowledge of the actual swarm landing time exists, and this setting might be particularly useful for backward simulations from that particular landing time. The default is for this not to be specified.

Start Location

Latitude: Latitude of the starting location for the first day of the simulation (decimal degrees). North latitudes are positive (e.g., 3.5) and South latitudes are negative (e.g., - 3.5), and thus, the value must be between -90 to 90 degrees.

Longitude: Longitude of the starting location for the first day of the simulation (decimal degrees). East longitudes are positive (e.g., 3.5) and West longitudes are negative (e.g., -3.5), and thus, the value must be between -180 and 180 degrees.

Height: Starting height, in meters above ground level, for each day of the simulation. The default vertical motion is to fly at a constant height above ground level (see Vertical Motion Option below), and if this default setting is used, the swarm is assumed to fly at this initial height for its entire flight. The user can optionally set a 2nd and even a 3rd height here as well, and simulations will be done for each starting height. Since wind speed and direction can vary with height, the choice of starting height will generally

make a difference in the forecast swarm paths. The default setting is for one starting height of 500 m above ground level to be specified.

Locust Flight Time


Fly without overnight stops: If this box is checked, the swarm is assumed to fly continuously without stopping, once it has taken off, for the duration of the simulation. This may be useful in situations where the swarm is crossing a large body of water and the user knows they will not choose to land in the water. The default is for this box *not* to be checked.


Time to take off after sunrise: The user enters the time (in hours) that the swarm is estimated to take off, after the local sunrise time. The default is 2 hours.

Time to land before sunset: The user enters the time (in hours) that the swarm is estimated to land, before the local sunset time. The default is 1 hour.

Plot Options

Map background: There are three choices here, and the default is the "STAMEN Terrain" background. Examples of the three types of map backgrounds are shown below. The STAMEN backgrounds are from http://maps.stamen.com/, while the ARL Map background uses the basic HYSPLIT map background graphics.





STAMEN Terrain

STAMEN Toner

ARL Map

Plot radius: The map output is centered on the start location and extends out this distance in each cardinal direction (North, South, East, and West). The default is 1000 km. For longer-duration simulations (or if there are faster wind-speeds), this may need to be increased to show the entire flight path on the map. For shorter-duration simulations (or if there are slower wind-speeds), the user may wish to reduce this radius to create a more zoomed-in view of the flight path. In the above examples, a 1000-km plot radius was used for a 3-day simulation.

Advanced

Vertical motion option: There are five options that can be chosen. The default is option #4 which specifies that the locusts are assumed to stay at the same height above the ground during their entire flight, until landing. With this option, the starting height set above -- in meters above the ground -- is the flying height throughout the simulation.

Here are all of the options:

- 0: Uses vertical velocities estimated from the meteorological data set. This setting is often used In air-pollution simulations with HYSPLIT, but is not considered the default for the flight of locusts.
- 1: Isobaric -- vertical height during flight is adjusted so that the locusts encounter the same pressure throughout the flight as when they started.
- 2: Isentropic -- vertical height during flight is adjusted so that the locusts encounter the same entropy throughout the flight as when they started.
- 3: Constant Density -- vertical height during flight is adjusted so that the locusts encounter the same air density throughout the flight as when they started.
- 4: Constant Height above the ground -- vertical height during flight is kept the same as the starting height, in meters above ground level. This is the same as the "constant-sigma" option in HYSPLIT.

Start a new batch run

Pressing this button will take you to the multiple-swarm (batch-mode) run specification page. This functionality is described below.

Restore Default values

Pressing this button will restore all inputs to their default values on the single-swarm run specification page.

Start Simulation

Pressing this button will start the simulation based on the current inputs specified. If there are errors in any of the inputs, or if any required fields are not set, an error message will be displayed. If the inputs are acceptable, and the run is proceeding as expected, one will soon begin to see the "run-time screen outputs" described in the next section.

3. Screen Outputs During Single-Swarm Run

The following elements are displayed on the screen during a successful single-swarm simulation. Not all elements occur immediately, and some are updated throughout the run. The run has finished successfully when the link to a "Zipped file of all graphics and diagnostics (for redistribution)" is displayed at the bottom of the output, in the Links section, as described below.

Zipped file of all graphics and diagnostics (for redistribution)

JOB NUMBER

The first item that appears is a title screen that shows the "Job Number" for this particular simulation. This job number is set by the system, but is associated with all of the output files for the simulation. In the examples below, the swarm name chosen was <code>ARL_Map_Background</code> and the <code>run-name</code> is constructed by appending the Job Number (in this example: <code>51</code>) to this swarm name, i.e., in this case, <code>ARL_Map_Background_51</code>. All output files have this run-name associated with them. For example, the png map output has the file name <code>ARL_Map_Background_51.png</code>



MODEL STATUS

The second item that appears is the Model Status box that scrolls through various intermediate screen outputs as the simulation proceeds. The full contents of this "Model Status" box is included in the run outputs as *run-name_progress.txt*. In the example shown here, the file name in the outputs would be called

ARL_Map_background_51_progress.txt

```
Model Status

11:16:34.961 INFO - Please wait for further information....
11:16:34.961 INFO - Model submitted on 2020-05-16 11:16:34.961486
11:16:34.992 INFO - utc offset 2.45 at lat 3.5, lon 37.0
11:16:34.992 INFO - sunrise 5:46, sunset 18:03 at lat 3.5, lon 37.0
11:16:34.992 INFO - sunrise 3:19, sunset 15:36 UTC
11:16:34.992 INFO - takeoff time 2020-05-16 05:19:00+00:00
```

```
Model Status

11:16:46.287 INFO - adding ARL_Map_background_51_GIS_traj03.txt

11:16:46.287 INFO - Creating file ARL_Map_background_51.zip for redistribution.

11:16:46.354 INFO - Finished generating graphics for job 51

11:16:46.354 INFO - The model and graphics are now complete.

11:16:46.355 INFO - 2020-05-16 11:16:46.355020

11:16:46.399 INFO - Posted status COMPLETED for job 51
```

MODEL DETAILS

The third item that appears is the Model Details box. This is simply a concise summary of the key swarm specifications set by the user for this simulation. The full contents of this "Model Status" box is included in the run outputs as

run_name_run_setup_summary.txt. In the example shown here, the file name in the
outputs would be called ARL_Map_background_51_run_setup_summary.txt

```
Model Details

Run name: ARL_Map_background_51
Meteorological data: GFS0p25
Start location: lat. 3.5000 deg, lon. 37.0000 deg, height(s) 500.0 m
Start date: 2020-05-16
Simulation duration: 3.0 day(s)
Simulation direction: FORWARD
Locust flight time: takeoff after sunrise 2.0 hr(s), land before sunset 1.0 hr(s)
Vertical motion: 4
```

RESULTS

The fourth item that appears is the Results box. When the run finishes successfully, this box should be fully populated with links as shown in the example below. One can click on the "PNG" link to quickly see the map output from the simulation. In this section of the

screen output, one can also Start a new single swarm run or, if desired, Start a new batch run.

Note: if it is desired to save all of the output files associated with this run, it is recommended that the user click on the link in the section below to download the **Zipped** file of all graphics and diagnostics (for redistribution)


Simulation results are available on the system for a short time. If one has forgotten to download the outputs and would like to go "back" and see the results, and if the simulation has not yet been deleted from the system, one can use the Job Number to create a URL with the following pattern (in the example below, the Job Number is "51", as it has been throughout this example).

https://locusts.arl.noaa.gov/display?id=51

Results	Click on text link or dropdown menu to view images.					
	Name	PNG Plots	PostScript Plots	PDF Plots	Zipped GIS Shapefiles	
	Trajectory plots	PNG	PS	PDF	ZIP	
	Start a new batch run		Start a new single swarm run			

LINKS

The item that appears at the bottom is the Links box. When the run finishes successfully, this box should be fully populated with links to HYSPLIT input and output files for each day of the simulation (Trajectory, SETUP, CONTROL, and MESSAGE), as well as a link to download all of these files, plus all of the graphics and other files associated with the run in a zip file.



4. Outputs from Single-Swarm Run

When the zipped file of all graphics and diagnostics (for redistribution) is downloaded, it contains the following files. As noted above, all files associated with the swarm simulation include the run-name (the swarm-name + the Job Number). In the list of files below, this will be simply expressed as "run-name".

run-name_progress.txt

The full contents of the Model Status box outputs that scroll during the simulation. These are primarily diagnostic outputs that may be useful in troubleshooting if unexpected results are obtained.

run-name run setup summary.txt

A concise summary of the key swarm specifications set by the user for this simulation, including: run-name, meteorological data used, start location, start date, duration simulation, direction, locust flight time parameters, and vertical motion option used.

run-name_trajplot.ps

The output map for the simulation, in postscript format.

run-name_trajplot.pdf

The output map for the simulation, in pdf format.

run-name_trj_001.png

The output map for the simulation, in png format.

run-name_MAPTEXT.txt

The text that appears at the bottom of the output maps.

run-name_CONTROL.1.txt, run-name_CONTROL.2.txt, ...

The HYSPLIT CONTROL file for each day's trajectory simulation. The CONTROL file is described in the HYSPLIT documentation here.

run-name_SETUP.1.txt, run-name_SETUP.2.txt, ...

The HYSPLIT SETUP.CFG file for each day's trajectory simulation. The SETUP.CFG file is described in the HYSPLIT documentation here.

run-name_MESSAGE.1.txt, run-name_MESSAGE.2.txt, ...

The HYSPLIT MESSAGE file for each day's trajectory simulation. The MESSAGE file is described in the HYSPLIT documentation here.

run-name_tdump.1, run-name_tdump.2, ...

The HYSPLIT tdump (trajectory data dump) file for each day's trajectory simulation. The tdump files are described in the HYSPLIT documentation here. Note that these tdump files are the results after the web-app has removed the entries after the landing time. These tdump files are the ones used in making the graphical outputs. For a forward run, the last line in the tdump file will show the latitude and longitude of the estimated landing site for that day, for the given simulation. Here is the last line from tdump.1 for the example being discussed here. The latitude and longitude are shown in red font, and the meaning of each of the columns are shown below the line. If more than one starting height was chosen, there will be one trajectory line for each trajectory for each output time step. The tdump file contains position data at 5-minute intervals, and all times reported are UTC (e.g., see: Universal/https://www.heresult.com/universal/https:

run-name_tdump.1.full, run-name_tdump.2.full, ...

The full HYSPLIT tdump (trajectory data dump) file for each day's trajectory simulation *before* the web-app removes the lines after the landing time. The tdump files are described in the HYSPLIT documentation <u>here</u>. These are intermediate files and are only included for diagnostic purposes.

GIS Shapefile Outputs

Shapefile (run-name_**GIS_traj01.shp**) and associated files that can be imported into a GIS application for the first day's simulation.

run-name_GIS_traj01.att, run-name_GIS_traj01.dbf, run-name_GIS_traj01.prj, run-name_GIS_traj01.shp, run-name_GIS_traj01.shx, run-name_GIS_traj01.txt

Comparable files are present for each day of the simulation (02, 03, ...).

5. Multiple-Swarm (Batch-mode) Simulation

A batch-run functionality is available, in which many swarms can be run at the same time.

Batch-run Input Page

The batch-run input page can be reached from the single-swarm input page or the single-swarm output page, by pressing the button:

Start a new batch run

This takes you to the batch-run input page:




Carry out a batch-run simulation

To carry out a batch-run simulation the user drags and drops a specially formatted CSV file into the "Batch file drop zone".

A sample file is available for download from the "Download a sample CSV file" link. The CSV file can be edited in a spreadsheet like Excel, <u>but must be saved as a CSV file</u>. A CSV file is a plain-text "Comma Separated Values" file, where each column of data is separated by a comma.

The example screenshot below shows how the CSV looks if it is edited in Excel (or a comparable spreadsheet app). Some formatting has been applied (colored fonts, word-wrapping, etc.) to make the content more readable. Formatting can be done in the spreadsheet file, but a version of the file must be saved as a CSV file for use with the locust batch-processing functionality. When you save the file as a CSV file, any special formatting is lost, as the file is only plain-text. The user may want to save the file as both a CSV file and a spreadsheet file (with formatting) for ease in further work with the template.

The first three lines of the CSV file -- in red text in the screenshot below -- should not be edited, and must be present. User-entered data for each swarm to be simulated begins on the 4th line, and each swarm to be simulated is entered on a different line (2 different swarms are shown in blue text in the screenshot below, on lines 4 and 5). A maximum of 20 swarms can be simulated with the current system.



Here is what the CSV-saved version of the above "spreadsheet view" actually looks like in a plain-text editor. This is an example of the actual format of any file that is "dropped" into the batch-file drop zone in the web-app.

Only certain date formats are currently accepted by the app, and the user may have to adjust the formatting of dates in the spreadsheet app being used, or these can be adjusted by editing the CSV file in a text editor. The three acceptable date formats for the UTC Start Date (column 3) are:


YYYY-M-D - e.g., 2020-05-17

M/D/YYYY - e.g., 5/17/2020


D.M.YYYY - e.g., 17.5.2020

The CSV file is prepared by the user, with one line for each swarm to be simulated. At the current time, there is a maximum of 20 swarms that can be run at the same time.


Once the CSV file is "dropped" into the app, a table is displayed showing the inputs specified in the CSV file for each swarm. In the example below, we have purposely introduced an error in the latitude for the 2nd swarm: the latitude is set to -94 degrees, a value outside of the acceptable range. The purpose of this intentional error is to show what happens when one tries to run the batch when there is one or more errors.



Then, the "START batch simulation" button can be pushed. If there is an error in one or more of the inputs, this will be indicated. In this initial example, the latitude for the 2nd swarm was -94, which is an invalid input (the latitude must be between -90 and 90). If this occurs, the user must edit the CSV file to fix the error, and then re-drop it in the batch-file drop zone. If there are no errors found by the app, the batch-run simulation will commence.



Here is the screenshot of the table displayed after the CSV file was edited to change the offending latitude to a valid number (in this case, changed from -94 to 4, for the 2nd swarm).




As noted above, if there are no errors found by the app, the batch-run simulation will commence.


Screen outputs during batch-run simulations

During execution of the batch run, the user will see the status of each swarm as being either RUNNING, QUEUED, or COMPLETED.

In the first screenshot, below, the first swarm is being run, and the 2nd swarm is queued (i.e., waiting to run).



In the next screenshot, below, both swarms are now completed. The user can look at the runtime output display for a given swarm, the PNG map of a given swarm, or download the full set of output files for a given swarm. The user can also download a full set of output files for all of the swarms in a single zip file.



Output Files from Batch-Run Simulations

The same files as described above for the single-swarm runs are provided for each swarm run in batch mode. When a single zip file is downloaded with the results, all of the output files are included in a single folder. This was done so that the user can easily see all of the graphics file (e.g., all of the png output maps) without having to move from one folder to another. Also, if the shapefiles are imported into a GIS system, they can be imported easily without having to switch among folders for each individual swarm.