



Contents

1.	Contents	2
	Change history	
	Overview	
	Introduction	
	Getting started	
	Basic text file structure	
6.		
6.5	·	
	Uploading to Clickatell FTP site	
8.	Log file format and reports	
	Message parameters	
9.		
9.	·	
10.	Batch messaging	
11	8-BIT messaging	
12.	Message examples	
12.	•	
	2.3 8-bit SMS examples	
13.	Appendix A: Error codes	
14.	Appendix B: Message statuses	
15.	Terminology	
16.	Contact details	31



Change history

Approximately six (6) months of changes are reflected.

Visit http://www.clickatell.com/downloads/ftp/Clickatell FTP.pdf to check for updates to this document.

Version	Date	Section	Changes to Documentation
2.4.8	12 December 2012	5	Updated the link to the API guide
2.4.7	13 June 2012	9	Added the text parameter to message parameter details

Overview

This technical document is intended for developers who wish to use the Clickatell FTP API for sending messages and describes the various programming methods and commands used by developers when using this API.

The FTP API allows you to send SMS messages using an FTP client. You create a file containing the list of recipients and their phone numbers and submit it to our FTP server. From then, our server takes care of the delivery. The server is checked regularly to ensure delivery of messages. The FTP API is best suited for bulk SMS sending.

To use this API, you need to register at (http://www.clickatell.com/register/?product=1). When you sign up for an FTP account you will be given a username, password and api_id: keep these at hand. Once you have registered and been activated you will receive 10 free credits with which to test our service. Messages sent with these credits contain a canned (pre-populated) message. You can test the API using these credits, and purchase credits to start sending your own, customised messages

It is recommended that you have an understanding of profiles before reading this document. Information is available at http://www.clickatell.com/help-support/developer-apis/routing-profile-guide. Please note that we request delivery acknowledgement for **every** message we send, although delivery acknowledgement status will only be delivered to you if requested.

There are a number of different ways of gaining access to the gateway:

- SMTP enabling a server or client generated email to be delivered as an SMS.
- HTTP / HTTPS submitting either a POST or GET to the API server.
- FTP uploading a text file to our FTP Server.
- XML posting to our gateway using XML over HTTP/S.
- COM Object for Windows based development.
- SOAP submit SOAP packets over HTTP/S.
- SMPP customers requiring a high throughput binary socket connection.



In order to reduce testing costs, Clickatell offers a test number range. Messages sent to any number on this prefix will only be charged 1/3 of a credit. Use the number 279991xxxxx (for South Africa) or 1999xxxxxxx (for the U.S.) where "xxxxx" represents any numeric string. Message statuses will be returned.

We will cover the FTP method in this document. Additional documentation is available for the other methods.

Introduction

The product is intended for clients who can build up a text file, based on an existing database of recipients. A text file will be uploaded to Clickatell's FTP site. This method is suitable for a once-off high volume message dispatch. It can either be a single message to all recipients or multiple personalised messages to each recipient. The recommended batch size is 10 000 messages, with a maximum of 50 000 messages per file.

It requires the use of two passwords. A product specific password is used to log on to the FTP server (obtained within online account), and your account password which is used within the text file. Both FTP and FTP over SSL is supported.

The maximum size of your FTP folder on ftpupload.clickatell.com is 5MB which includes log files. Once this capacity limit is reached, you will need to delete files before new files may be added. Files are automatically deleted 48 hours after last modification. Each line in the text file may be a maximum of 8192 bytes

Important: FTP files are processed immediately. Only once our system begins sending the SMS messages will our system generate a log file. Should you need to cancel a FTP send please phone our 24/7 support centre: +27 21 910 7700

Getting started

In order to use the Clickatell gateway you need a Clickatell account and at least one registered connection (API sub-product instance) between your application and our gateway. Each connection method is known as a sub-product (of our API product). You can follow these steps to get started:

Step 1 - register for a Clickatell account

If you do not already have a Clickatell Central account, you need to register for one. If you already have a Clickatell Central account, proceed to Step 2 for instructions on how to edit an API connection on your account.

- Go to http://www.clickatell.com/products/sms_gateway.php, and choose the appropriate API sub-product (connection method) you wish to use.
- Click on the registration hyperlink.
- Select the Account type you would like to use (Local or International)
- Enter your personal information to complete the registration form
- Accept Terms & Conditions
- Click Continue an email containing your login details will be sent to the email address you have provided



Step 2 - Login to your account

When you have logged in you will be on the Clickatell Central landing page. You will receive 10 free credits which you can use to test the Clickatell Gateway. Please note that for security reasons these 10 credits contain pre-set Clickatell content.

A HTTP API will be added to your account for you. This will allow you to start testing the Clickatell Gateway immediately. You can purchase credits when you are ready to start sending personalised messages.

Step 3 - Adding an FTP API to your account

To add a FTP API to your account select **APIs** from the main menu and then select **Setup a new API** from the submenu. Click the Add FTP API button on the Setup API page that opens. You can then complete all the required details to configure your API.

After successfully adding a connection, a confirmation message will be displayed with a unique API ID and information on how to get started.

The getting started section displays the API connection parameters and authentication details. These details are required when connecting to the Clickatell gateway to send a message.

Note: For more information on managing your API connections within your Clickatell account see our API guide at http://www.clickatell.com/help-support/developer-apis/clickatell-api/



Basic text file structure

To send an SMS message using the Clickatell FTP upload facility, the system interprets variables that you pass through in the uploaded text file. Each line in the text file may be a maximum of 8192 bytes and represents a variable in the form of:

variablename:value variablename:value variablename:value

We endeavour to strip any superfluous white space that may occur either side of the colon, however to avoid any erroneous characters appearing from the text file, we suggest that you keep to the format shown above.

Note: We accept plain-text files with DOS, MAC or UNIX line breaks.

Authentication within the text file to be uploaded

In order to deliver a message, the system needs to authenticate the request as coming from a valid source. Account details are therefore included when creating your text file to upload into your FTP folder. These account details are:

user: Your main Clickatell account username.

api id: This is the numeric code referred to as 'FTP Login' on the control window.

password: Your main Clickatell account password.

You can upload multiple files on the same FTP account details simultaneously.

A log file will be created once the uploaded file has been parsed and validated. This will be available in your FTP directory. It will be the same name as your uploaded file, with the added extension ".log". See the section entitled LOG FILE FORMAT AND REPORTS for the format.

Example:

api_id:1234 user:xxxxxxxx password:xxxxxxxxxxx



Send a message

Once you have set up the three authentication variables listed above, there are only a further two parameters that are required before you can send an SMS via FTP.

to:xxxxxxxxxxxxxxx

This parameter sets the destination address. You may send the same SMS to one or more recipients in a single text file. There are two ways to achieve this: either using comma-delimited destination addresses (ensure that there are no spaces before or after the comma).

Example:

All on one line (up to a maximum of 8192 bytes)

or multiple lines (the preferred method)

The last variable is the text parameter. The text parameter can run over multiple lines. This enables you to insert new lines in your SMS

Example:

Text File:	Resultant SMS:
text:Line 1	Line 1
text:Line 2	Line 2
text:Line 3	Line 3

We are now ready to send an SMS.

Example:

api_id:1234 user:xxxxxxxxx password:xxxxxxxxxx to:1234567890,1234567890 text:This is my first test SMS

All parameters that can be used in the text file are discussed in detail under the section entitled "Parameters in Detail".



Uploading to Clickatell FTP site

The files themselves should be uploaded to our FTP site: ftpupload.clickatell.com.

This can be accessed through a web browser that supports FTP, by typing in the following URL:

ftp://ftpupload.clickatell.com

The FTP login (API ID) and product specific password are used to log into your FTP folder on ftpupload.clickatell.com. This information can be obtained/set-up by logging into your online account and going to Product Control-->FTP.

login/username (api_id): This is the numeric code referred to as 'FTP Login' on the control window. password: This is the password you set-up for the product, under the products preferences.

The maximum size of your FTP folder on ftpupload.clickatell.com is 5MB. Once this capacity limit is reached, you will need to delete files before new files may be added.

Log file format and reports

The log file consists of a single line for every mobile number that you have sent to, via your uploaded file. On each line there will be the destination address and either a unique message ID, or a validation error code. The complete list of errors can be found in appendix A. Please note that a message ID (apiMsgld) only indicates that the system is able to process the message and is not an indication of successful delivery.

Example:

ID: b2ffff503d348a0af5335e72dc3f21b8 To:1234567890

ID: 5621234b34400b9974d80260211f2ee To:2345678901

ID: 799e4150adfcd8f02c512afc69f28bf1 To:3456789012

ID: 8e652dcd3e0ac225966a34312e01bc58 To:4567890123

Detailed reporting of sent messages can also be viewed and exported from within your online account.



Message parameters

Table of parameters

There are a variety of messaging and SMS features supported by the gateway, which can be activated by including a number of additional parameters. These parameters include those in the table below. Parameters are case-sensitive.

Name	Parameter name	Short description	Default value	Restricted values
API product ID	api_id	The value for this mandatory parameter can be found logging in online and going to APIs → Manage APIs		
Username	user	The username you specified.		
Password	password	Your account password.		
Session ID	session_id	The session ID from the <i>auth</i> command. Not applicable to the FTP, SMPP or SMTP APIs.		
Destination address	to	The number of the handset to which the message must be delivered. The number should be in international number format.		No '00' prefix or leading "+" symbol should be used.
Text	text	The text content of the message. Note that some characters take up two characters because of GSM encoding standards		http://support.clic katell.com/faq.ph p?mode=view_e ntry&kbid=121&k bcat=26
Source address	from	The source/sender address that the message will appear to come from also known as "Sender ID". These must be registered within your online account and approved by us before they may be used. MO numbers rented from us do not require approval.	gateway assigned number	A valid international format number between 1 and 16 characters long, or an 11 character alphanumeric string.
Enable callback	callback	Enables you to receive message delivery statuses via an HTTP, SOAP or XML callback which is posted to a URL of yours using the GET or POST method. This is done every time a message status is updated.	0	0,1,2,3,4,5,6,7 Read detailed description of parameter.
Delivery time	deliv_time	Delays delivery of SMS to mobile device in minutes relative to the time at which the SMS was received by our gateway. This should be greater than 10 minutes for best effect. Smaller time frames may be delivered too soon.		The upper limit is 7 days, or 10080 minutes.



Name	Parameter name	Short description	Default value	Restricted values
Concatenation	concat	Enables you to send messages longer than a standard message.	1	1,2,3
Maximum credits	max_credits	Overrides the maximum charge specified online in "profiles". It works within the bounds of the profiles. In other words a profile must exist for the maximum credit that you set.	As per profiles	0.8,1,1.5,2,2.5,3
Required features	req_feat	Some parameters and features are not set as "required" by default, and may be dropped if the least-cost route does not support them. This parameter allows you to ensure that the features set when an SMS is sent are supported by the gateway used. This could increase the cost per message if a more expensive gateway is used.		Read detailed description of parameter.
Delivery queue	queue	Delivers the message through one of three queues assigned to each client account. Messages in the highest priority queue will be delivered first.	3	1, 2,3 1 is highest priority.
Gateway escalation	escalate	Prompts an escalation to an alternative route, if messages are queued on the least-cost route.	0	0 - off 1 - Escalate immediately to an alternative route if messages are queued on the least-cost route.
Mobile originated	mo	We route via a pre-defined carrier to enable the ability for a reply to be received back. This is only applicable to clients that have subscribed to a two-way messaging service.	0	0 – Off. We use our normal routing rules. 1 – Enable Reply.
Client message ID	cliMsgld	Client message ID defined by user for message tracking.		Up to 32 alphanumeric characters. No spaces.
Unicode message	unicode	Two digit language code. Convert your text to Unicode [UCS-2 encoding]. See http://www.Unicode.org/.	0	0 – No Unicode 1 – Send as Unicode.
Message type	msg_type	Optional parameter which must be set to send specially formatted messages; e.g. logos and ringtones.	SMS_TE XT	
User data header	udh	Allows you to set your own		Set UDH data



Name	Parameter name	Short description	Default value	Restricted values
		message types. Do not use if you set the message type parameter. When set, Clickatell assumes the data is 8 bit. See 8 bit messaging for more information.		manually.
Data	data	The data content of a message, if the UDH component is set manually.		
Validity period	See detailed information on message parameter	The validity period in minutes relative to the time at which the SMS was received by our gateway. The message will not be delivered if it is still queued on our gateway after this time period.	1440 minutes (24 hours)	Set value in X minutes from 1 – 1440 minutes.

Additional parameters are also available to the FTP API:

Name	Parameter name	Short description	Default value	Restricted values
CSV Line	CSV	Used in conjunction with text parameter to handle personalised batch messaging.		The mobile number must be the first value in the CSV field.
Delimiter	delimiter	Specify a specific character to be used to delimit values in the CSV field. Useful if certain values contain a comma. If not set, defaults to a comma.	,	
CSV Template	csvtemplate	Used in conjunction with text parameter to handle personalised batch messaging where additional message parameters need to be set on a message by message basis		
URL encoded text	urltext	Useful for special Greek characters, etc.		
Scheduled Time	scheduled_time	Specify when a message gets delivered.		



Message parameters in detail

Destination address (to)

SMS messages need to be sent in the standard international format, with country code followed by number. No leading zero to the number and no special characters such as "+" or spaces must be used. For example, a number in the UK being 07901231234 should be changed to 447901231234.

If have you set the preferred dial prefix preference within your client account after logging in on-line, any mobile numbers starting with zero will have the zero stripped and replaced with your default prefix. If the mobile number does not have a zero, the default prefix will not be changed.

Parameter:

to:xxxxxxxxxx

Text

This is the default parameter that is used to add message content. A single text message can contain up to 160 characters or 140 bytes.

Note: If you are adding special characters to a message it can be confusing to the recipient, use the urltext parameter instead to translate all "special" characters to their corresponding hexadecimal codes.

Source address (from)

The source address (**from**), also known as the sender ID, can be either a valid international format number between 1 and 16 characters long, or an 11 character alphanumeric string. These must be registered within your online account and approved by us before they may be used. MO numbers rented from us do not require approval

Note that characters such as spaces, punctuation, Unicode and other special characters may not always be supported to all destinations and could interfere with your delivery. We suggest that you refrain from using such characters on the source address. If this is set, then delivery acknowledgements may be unavailable. The use of an alphanumeric source address with 8-bit messaging may cause message failure. This service is not guaranteed across all mobile networks and may interfere with delivery to certain handsets.

Note: To ensure that this feature is supported when delivering your message, the required features (**reg feat**) parameter for this feature must be set.

Parameter:

from:xxxxxxxxxx

Delivery acknowledgement (deliv_ack)

In order to determine whether an SMS has been received by a handset or not, we request delivery acknowledgement for every message we send. The ability to receive reliable delivery acknowledgements varies between mobile networks. Please test to a specific mobile network first, before assuming that you will receive handset acknowledgments for messages that are delivered.

If a GSM handset is 'absent', e.g. switched off or out of coverage, the SMS will be delivered according to a retry cycle once the handset is back in coverage. A delivery receipt will only be returned if and when the retry is delivered. If the validity period or retry cycle (typically 24 hours) is exceeded, the SMS will fail and show 'Error Delivering Message' or status 8.

A delivery acknowledgment can be monitored via the callback URL or online reports.



Callback URL (callback)

Final or intermediary statuses are passed back by the API depending on the **callback** value set in the original post. This is done by means of:

- HTTP GET
- HTTP POST
- XML GET
- XML POST
- SOAP GET
- SOAP POST

Validation of Callback URL

The URL entered in your Clickatell central account to receive 'SMS Status notifications' is validated to check if a callback can be completed. If the callback URL is invalid, a message is displayed indicating an Invalid URL.

Call Retry

A retry mechanism allowing eight retries is activated if a status update is not delivered.

For Example:

- 1. 2 minutes after the original attempt
- 2. 4 minutes after last retry
- 3. 8 minutes after last retry
- 4. 16 minutes after last retry
- 5. 32 minutes after last retry
- 6. 64 minutes after last retry
- 7. 128 minutes after last retry
- 3 days after last retry (max retries reached)

The callback URL and optional "username" and "password" authentication parameters can be set in the preferences section of the particular API product within your client account, after logging in online. The URL must begin with either http:// (non-encrypted) or https:// (encrypted). These are NOT your Clickatell username and password but are a username and password of your choice to add additional security.

The variables returned are apiMsgld, cliMsgld, to, timestamp, from, status and charge.

Callback value	Message status types returned	Message status code returned
0	No message status returned.	
1	Returns only intermediate statuses.	003
2	Returns only final statuses of a message.	004, 005, 007, 009, 010, 012
3	Returns both intermediate and final statuses of a message.	003, 004, 005, 007, 009, 010, 012
4	Returns only error statuses of a message.	005, 007, 009, 010, and 012
5	Returns both intermediate and error statuses of a message.	003, 005, 007, 009, 010, 012
6	Returns both final and error statuses of a message.	004, 005, 007, 009, 010, 012



7	Returns both intermediate,	final and e	rror 003, 004, 005, 007, 009, 010,	012
	statuses of a message.			

Examples

- HTTP

Sample callback to your callback URL using an HTTP get:

https://www.yoururl.com/script.asp?api_id=12345&apiMsgld=996f364775e24b8432f45d77da8eca47&cliMsgld=abc123×tamp=1218007814&to=279995631564&from=27833001171&status=003&charge=0.300000

- XML

The following data is sent in XML MT callbacks in a parameter called 'data':

Sample callback to your callback URL using an XML GET:

https://www.yoururl.com/script.php?data=<?xml

version="1.0"?>< callback>< apiMsgId>996411ad91fa211e7d17bc873aa4a41d</apiMsgId></cli>
<math display="block">MsgId>< timestamp>1218008129</timestamp>< to>279995631564</to><from>27833001171</from>< charge>0.300000</charge>< status>004</status></callback>

- SOAP

With the SOAP callback method, a SOAP packet will be sent with a parameter called 'data'. Below is an example packet that will be sent to you via GET or POST.

Example of a SOAP packet that will be sent to you via **GET** or **POST**:



```
<timestamp xsi:type="xsd:int">1213690834</timestamp>
    <status xsi:type="xsd:int">003</status>
        <charge xsi:type="xsd:float">0.300000</charge>
        </tns:mt_callback>
        </SOAP-ENV:Body>
        </SOAP-ENV:Envelope>
```

This is an example callback URL that will be sent to your application:

http://www.yoursite.com/your_url.php?data="<?xml version="1.0" encoding="ISO-8859-1"?><SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/" xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/" xmlns:xsd="http://www.w3.org/2001/XMLSchema" xmlns:xsi="http://www.w3.org/2001/XMLSchema" xmlns:xsi="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="mt_callback"><SOAP-ENV:Body><tns:mt_callback xmlns:tns="mt_callback"><SOAP-ENV:Body><tns:mt_callback xmlns:tns="mt_callback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lback"><20lb

Delivery time (deliv_time)

The delivery of an SMS message may be delayed by setting an amount of time in **minutes** relative to the time at which it was received by our gateway. We will store the message until the required time frame has elapsed. The maximum delay time is 10080 minutes or 7 days.

Parameter:

deliv time:120



Concatenation (concat)

If this value is set to 1, 2 or 3 the message will span across 1, 2 or 3 SMS messages where applicable. One text SMS will be sent for every 160 characters or 140 bytes. If a message is concatenated, it reduces the number of characters contained in each message by 7. With 8-bit concatenated messages, each SMS can support up to 140 bytes including the UDH headers.

For more information on characters that require two character places please visit: http://www.clickatell.com/help-support/frequently-asked-questions/ and search for 'Why do some characters take two spaces?'

Please be aware that a single Unicode SMS can only contain a maximum of 70 characters. If a Unicode message is concatenated, it reduces the number of characters contained in each message part by 7.

Values set are:

Value	Status
1	Default - No concatenation: only 1 message.
2	Concatenate a maximum of 2 messages.
3	Concatenate a maximum of 3 messages.
N	Concatenate a maximum of N messages. (Delivery is dependent on mobile and gateway. A maximum of 3 is recommended. The maximum amount of messages that can be concatenated is 35).

Parameter:

concat:2

Maximum credits (max_credits)

This parameter overrides the maximum charge associated with message delivery, as set by the profiles selected within your client account after logging in online. This parameter can be used to limit the cost of a message to a particular value and is bound by the maximum credit value specified in your profiles.

A valid API message ID can still be returned for messages that are not delivered as a result of the maximum credits value set. These messages will have a status of routing error (009).

The credit value in this parameter can be set to any amount of credits. To set your delivery profile, go to Manage account → Account overview and click the link Control the routing of messages located in the section titled Account Type.

Parameter:

max_credits:4



Required features (req feat)

This parameter specifies the features that must be present in order for message delivery to occur. If all features are not present, the message will not be delivered. This prevents SMS messages arriving at a destination via the least-cost gateway, without certain features. This would, for instance, prevent the dropping of a sender ID.

This means that we will not route messages through a gateway that cannot support the required features you have set. For certain message types, we always set the required feature bitmask where relevant. These are FEAT_8BIT, FEAT_UDH, FEAT_UCS2 and FEAT_CONCAT.

This parameter is set using a combined decimal number to refer to the additional required features.

E.g.: 32 + 512 = 544 - Numeric sender ID and Flash SMS both required.

The value you would set to ensure that Flash and numeric sender ID are both supported, would therefore be **544.**

To ensure that delivery acknowledgment and alphanumeric IDs are supported you would use the value **8240** (16 + 32 + 8192).

Hex value	Decimal	Feature	Description
0x0001	1	FEAT_TEXT	Text – set by default.
0x0002	2	FEAT_8BIT	8-bit messaging – set by default.
0x0004	4	FEAT_UDH	UDH (Binary) - set by default.
0x0008	8	FEAT_UCS2	UCS2 / Unicode – set by default.
0x0010	16	FEAT_ALPHA	Alpha source address (from parameter).
0x0020	32	FEAT_NUMER	Numeric source address (from parameter).
0x0200	512	FEAT_FLASH	Flash messaging.
0x2000	8192	FEAT_DELIVACK	Delivery acknowledgments.
0x4000	16384	FEAT_CONCAT	Concatenation – set by default.

Parameter:

req_feat:###

Delivery queue

Setting this parameter will assign the message to one of three queues assigned to each user account. This sets the priority of a message sent to us, relative to other messages sent from the same user account. Messages in queue number 1, will always be delivered before messages in queue number 2 and 3, while messages in the 3rd queue, will have the lowest priority (relative to queues 1 and 2).

This is useful when delivering, for example, a single high priority message while you have a large batch going through that same account. The large batch will be queued through queue number 3 (default), and urgent alerts (sent through queue 1), will be delivered ahead of those messages in the batch (queue 3), regardless of when they are actually sent to us.

Values set are:

Value	Status
1	Use first / primary user queue (highest priority).



2	Use second user queue.
3	Use third user queue (lowest priority) - Default status.

Parameter:

queue:1

Gateway escalation (escalate)

By default, the message router will select the lowest cost route (matching features and reliability) that is available for a given destination.

This parameter ensures that, should a message be delayed due to gateway congestion or some other reason on the initial gateway selected by our router, then alternative routes that match the required features will be sought. This is done by moving through the available gateways in order of increasing cost, up to the maximum charge set by the user either using the parameter that defines the maximum credits or based on the profiles selected.

When urgent and high priority messages are sent, they should be posted with escalate set to 1 (on), combined with a high maximum credit value to ensure that the greatest number of gateways are available.

Values set are:

Value	Status
0	Off – Default value.
1	On - Escalate immediately to an alternative route if the messages are queued on the least-cost route.

Parameter:

escalate:1

Mobile originated (mo)

This parameter is only used when a message is sent to a handset and a reply is expected.

PLEASE NOTE: This parameter is only valid for clients that have signed up and paid for our twoway messaging service. An alternative to our least-cost gateway may be used, which could result in a higher cost per message. Please email Clickatell support for pricing or view online.

When sending a normal MT message to a handset and you expect a reply to your registered MO number, please set the **mo** parameter to "1".

Values to set are:

Value	Status
0	Off - Default status. We use the normal routing feature.
1	Enables reply ability. We route via a pre-defined carrier to enable the ability to reply.

It is important that the user specifies the correct **from** parameter together with this parameter. If no **from** parameter is specified, we will use a default originator number as set by Clickatell. You will NOT receive these replies.

If you specify the originator (the purchased MO number), then we will route the message such that it can be replied to by the recipient. This reply will be sent to you.



Parameter:

mo:1

Client message ID (climsgid)

This parameter is set by the user to enable internal message tracking. It allows the user to set their own tracking ID for each message. Once set for a given message, this may be used in place of the Clickatell issued API message ID (apimsgid) for querying message.

A client message ID (**climsgid**) may be any combination of alphanumeric characters excluding spaces. A maximum of 32 characters may be used.

Parameter:

climsgid:xxxx

Unicode (unicode)

If this value is set to 1, the text field must contain two-byte Unicode. Each SMS can handle a maximum of 70 characters. Each Unicode character must be hex-encoded. More information is available at http://www.Unicode.org/.

Note: When using the batch send facility for delivering Unicode messages, it is not possible to substitute variables into the message content. This is only possible with Germanic characters.

Values set are:

Value	Status
0	Off - default status.
1	On - delivers the text as two-byte Unicode.

We provide a converter to convert text to Unicode within your client account online. Go to "Converters" from within your account online.

Parameter:

unicode:1

E.g. $\Omega\Psi\Theta$

becomes: text:03A903A80398



Message type (msg_type)

A wide variety of messages can be sent through our gateway. We have pre-defined a number of SMS message-types in the API, so that you do not have to set the UDH (user data header) manually. You may optionally set the UDH rather than using one of the message types set below. Message types are case sensitive.

For non-Nokia message types (EMS, etc.), please generate your own UDH and data according to the manufacturers specifications of the message type you wish to send.

This parameter need not be included if the SMS is a standard text message.

Values set are:

Value	Description
SMS_TEXT	This is the default message type. It is optional to specify this parameter.
SMS_FLASH	To send an SMS that displays immediately upon arrival at the phone.
SMS_NOKIA_OLOGO	Send an operator logo to a Nokia handset.
SMS_NOKIA_GLOGO	Send a group logo to a Nokia handset.
SMS_NOKIA_PICTURE	Send a picture message to certain Nokia handsets.
SMS_NOKIA_RINGTONE	Send a ringtone to a Nokia handset.
SMS_NOKIA_RTTL	Send an RTTTL format ringtone to Nokia handsets.
SMS_NOKIA_CLEAN	Remove operator logo from a Nokia handset.
SMS_NOKIA_VCARD	Send a business card to a Nokia handset.
SMS_NOKIA_VCAL	Send an event calendar to a Nokia handset.

Command:

Please see the messaging examples at the end of this document.

Validity period (val_period)

A message may be given a time frame for which it is valid. After this period the message will expire. This parameter takes an amount of time in **minutes** relative to the time at which the message was received by our gateway. If the message is queued on our gateway for a period exceeding the validity period set then a routing error of 115 will be returned. The default validity period is 1440 minutes (24 hours).

Note: The validity period is not passed on to the upstream gateway.

Parameter:

val_period:120

URL encoded text

Used instead of the **data** or **text** parameter, the **uritext** parameter can be used to send URL encoded text, which will be decoded back to normal text before the message is delivered to the phone.

It is possible that text could consist of characters that will confuse email-clients. To prevent possible errors, the URL encoding scheme translates all "special" characters to their corresponding hexadecimal



codes. These special characters include control characters (carriage returns, line feeds, etc.), certain alphanumeric symbols (%, ', ", #, &, ?, =, /, :), and other characters (Greek Bulgarian and Cyrilic characters, etc).

For example, the string "Your URL encoded text!" could be sent as below.

Parameter:

urltext:Your%20URL%20encoded%20text%21

Scheduled Time

The purpose of this parameter is to allow you to specify when you want a message to be delivered. This parameter is different to the existing deliv_time parameter as it does not specify a delay time, but a delivery time.

The new parameter will accept a delivery time in one of the following formats:

- 1. Unix timestamp
- 2. Date in time in UTC format (YYYY-MM-DDTHH:mm:ssZ)

Examples:

1) Unix timestamp:

scheduled_time:1233133393

2) UTC date format:

scheduled_time:2009-01-30T14:00:00Z

The same limitations of the deliv time parameter apply here:

- 1. The maximum scheduled time range is 7 days
- 2. Actual delivery time of scheduled messages can always be handled up to 5 minutes too early.

Batch messaging

This facility enables one to do high volume delivery and server-side message merging. It offers the enduser the ability to define all elements common to a batch, and then send only the parameters that change on a message by message basis. The following parameters are used for batch messaging.

Name	Parameter name	Short description	Default value	Restricted values
CSV Line	CSV	Each csv line has a mobile number followed by a list of field values that are used to customise a text message. The text parameter value acts as a template with placeholders inserted into the text which are replaced by these field values when the message is sent.		The mobile number must be the first value in the CSV field.
CSV template	csvtemplate	Used in conjunction with the text and csv parameters to handle personalised batch messaging where additional message parameters (such as delivery time) need to be		



		set on a message by message basis. These parameter values are added		
		after the mobile number in the CSV Line.		
Delimiter	delimiter	Specifies a specific character to be used to delimit values in the CSV parameter field values. Useful if certain values contain a comma.	, (comma)	If you use the default delimiter you will not be able to use a comma in your field values. If you are using a TAB character, there must be no white space either before or after the TAB.

CSV line parameter (csv)

csv:mobile_number[delimiter]field-value[delimiter]field-value[delimiter]field-value etc.

Where field-value is the data to be inserted into the template, and [delimiter] is the value as determined by the delimiter parameter.

Placeholders may be inserted within the message body itself. These will take the form of #field1# through to #fieldn#. See example below. If you wish to customise the whole message on each csv line, you would then use:

text:#field1#

Example:

api id:1234

user:xxxxxxxxx

password:xxxxxxxxxxxx

text:Hi #field1#, your balance is #field2#, please come to the office on #field3#

delimiter:

csv:1234567890|Fred|€15.50|Mondays,Wednesdays,Fridays

csv:1234567890|Jane|€299.45|Tuesdays,Thursdays,Saturdays

Note: If a ',' (comma) was used as the default delimiter, then it would only have passed through 'Mondays' as the value of field3 for Fred and 'Tuesdays' for Jane.

CSV template parameter (csvtemplate)

csvtemplate:[parameter-1],[parameter-2],[parameter-n]

Example:

csvtemplate:deliv_time,cliMsgld,val_period_etc.

These values would then appear on the **csv** line immediately after the mobile number. The field-values for each of the placeholders that you have inserted in your text (text parameter) are then appended to the csv line.

Format: csv:mobile_number [optional csvtemplate parameters] template_placeholder_parameters

Example:

api_id:1234 user:xxxxxxxxx password:xxxxxxxxxxx



text:Hi #field1#, your balance is #field2#, please come to the office on #field3# delimiter:|

csvtemplate:deliv_time|cliMsgld|val_period

csv:1234567890|10|id_1|60|Fred|€15.50|Mondays,Wednesdays,Fridays csv:1234567890|40|id_2|60|Jane|€299.45|Tuesdays,Thursdays,Saturdays

A maximum of 50 000 csv lines can be uploaded at one time as long as the file size remains under the folder size limit. If larger volumes of messages must be sent then the file should be split and uploaded one file at a time. The files in the ftp folder should be deleted before the next file is uploaded.



8-BIT messaging

Through the FTP interface, one is also able to send 8-bit messages. These are most often used for ringtones and logos, but one can also send vCards, vCalendar appointments and EMS messages. When sending 8-bit messages, you need to set the user data header (UDH) of the SMS as well as sending the data. If you are comfortable with the creation of your own UDH, we also enable you to set it directly using the **udh** parameter. To simplify the process, we have provided a number of pre-defined message types (see the **msg_type** parameter).

With the standard *text* parameter, line breaks are automatically inserted. The parameter **data**, is thus used for 8-bit messaging.

Example:

msg_type:SMS_NOKIA_RINGTONE

data:024A3A5585E195B198040042D9049741A69761781B6176156174288B525D85E0A26C24C49A617 628930BB125E055856049865885D200



Message examples

Here are some examples that demonstrate how to use the API. All values in these examples should be replaced by your own values.

Simple examples

Standard text file

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890

text:This is my first ftp to SMS message

Flash SMS with sender ID

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 text:Sending a flash message with sender id. msg_type:SMS_FLASH from:ME

Example with HTTP delivery back and callback request set

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 text:Sending a message requesting a delivery acknowledgment. deliv_ack:1 callback:3

Batch message examples

Sending the same message to multiple recipients

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890,9397433991,4387347839 text:This is my first email to SMS message



Sending a personalised message to multiple recipients

api_id:xxxxx user:xxxxx password:xxxxx text:Hi #field1#, your voucher number is #field2#. Delimiter:| csv:447901234567|John|agh1234te csv:447902345678|John|hfe8423ss csv:447904567890|John|njg6983ju csv:447903456789|John|cds2267wq

or

text:#field1#
Delimiter:,
csy:447901234567 Mary - your appe

csv:447901234567,Mary - your appointment is at 9:15 on Saturday 14th May csv:447902345678,Craig - your appointment is at 14:30 on Wednesday 18th May

Configuring individual messages in a batch

api_id:1234
user:xxxxxxxx
password:xxxxxxxxx
text:Hi #field1#, your balance is #field2#, please come to the office on #field3#
delimiter:|
csvtemplate:deliv_time|cliMsgld|val_period
csv:1234567890|10|id_1|60|Fred|€15.50|Mondays,Wednesdays,Fridays
csv:1234567890|40|id_2|60|Jane|€299.45|Tuesdays,Thursdays,Saturdays

8-bit SMS examples

Note: Setting an alphanumeric Sender ID (from parameter) when sending 8-bit messages may result in message failure.

Sending a ringtone

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 msg_type:SMS_NOKIA_RINGTONE data:024A3A5585E195B198040042D9049741A69761781B61761561728 data:8B525D85E0A26C24C49A617628930BB125E055856049865885D200

Sending an operator logo

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 msg_type:SMS_NOKIA_OLOGO



Removing an operator logo

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 msg_type:SMS_NOKIA_CLEAN data:00

Sending a VCARD

api_id:xxxxx user:xxxxx password:xxxxx to:1234567890 msg_type:SMS_NOKIA_VCARD data:BEGIN%3AVCARD%0D%0AVERSION%3A2.1%0D%0AN%3ABloggs%3BJoe%0D%0ATEL%3BPR EF%3A%2B1234567890%0D%0AEND%3AVCARD%0D%0A



Appendix A: Error codes

The following list of error messages are generated by the Clickatell gateway during a validation phase before we accept the message. These error messages are sent back to your application. There will be no message charge if these errors are generated when sending a message. Data regarding messages that do not pass initial validation will not be included in your Clickatell Central reports.

Number	Description	Detail	
001	Authentication failed	Authentication details are incorrect.	
002	Unknown username or password	Authorization error, unknown user name or incorrect password.	
003	Session ID expired	The session ID has expired after a pre-set time of inactivity.	
004	Account frozen		
005	Missing session ID	Missing session ID attribute in request.	
007	IP Lockdown violation	You have locked down the API instance to a specific IP address and then sent from an IP address different to the one you set.	
101	Invalid or missing parameters	One or more required parameters are missing or invalid	
102	Invalid user data header	The format of the user data header is incorrect.	
103	Unknown API message ID	The API message ID is unknown. Log in to your API account to check the ID or create a new one.	
104	Unknown client message ID	The client ID message that you are querying does not exist.	
105	Invalid destination address	The destination address you are attempting to send to is invalid.	
106	Invalid source address	The sender address that is specified is incorrect.	
107	Empty message	The message has no content	
108	Invalid or missing API ID	The API message ID is either incorrect or has not been included in the API call.	
109	Missing message ID	This can be either a client message ID or API message ID. For example when using the stop message command.	
110	Error with email message		
111	Invalid protocol		
112	Invalid message type		
113	Maximum message parts exceeded	The text message component of the message is greater than the permitted 160 characters (70 Unicode characters). Select concat equal to 1,2,3-N to overcome this by splitting the message across multiple messages.	
114	Cannot route message	This implies that the gateway is not currently routing messages to this network prefix. Please email support@clickatell.com with the mobile number in question.	



115	Message expired	Message has expired before we were able to deliver it to the upstream gateway. No charge applies
116	Invalid Unicode data	The format of the unicode data entered is incorrect.
120	Invalid delivery time	The format of the delivery time entered is incorrect.
121	Destination mobile number blocked	This number is not allowed to receive messages from us and has been put on our block list.
122	Destination mobile opted out	The user has opted out and is no longer subscribed to your service.
123	Invalid Sender ID	A sender ID needs to be registered and approved before it can be successfully used in message sending.
128	Number delisted	This error may be returned when a number has been delisted.
130	Maximum MT limit exceeded until <unix TIME STAMP></unix 	This error is returned when an account has exceeded the maximum number of MT messages which can be sent daily or monthly. You can send messages again on the date indicated by the UNIX TIMESTAMP.
201	Invalid batch ID	The batch ID which you have entered for batch messaging is not valid.
202	No batch template	The batch template has not been defined for the batch command.
301	No credit left	Insufficient credits
302	Max allowed credit	
901	Internal error	Please retry



Appendix B: Message statuses

These are message statuses that are generated after the Clickatell gateway has accepted the message for delivery. Data regarding messages passing initial validation and accepted for delivery will be included in your Clickatell Central reports.

Number	Hex	Description	Detail
001	0x001	Message unknown	The message ID is incorrect or reporting is delayed.
002	0x002	Message queued	The message could not be delivered and has been queued for attempted redelivery.
003	0x003	Delivered to gateway	Delivered to the upstream gateway or network (delivered to the recipient).
004	0x004	Received by recipient	Confirmation of receipt on the handset of the recipient.
005	0x005	Error with message	There was an error with the message, probably caused by the content of the message itself.
006	0x006	User cancelled message delivery	The message was terminated by a user (stop message command) or by our staff.
007	0x007	Error delivering message	An error occurred delivering the message to the handset.
800	0x008	OK	Message received by gateway.
009	0x009	Routing error	An error occurred while attempting to route the message.
010	0x00A	Message expired	Message has expired before we were able to deliver it to the upstream gateway. No charge applies.
011	0x00B	Message queued for later delivery	Message has been queued at the gateway for delivery at a later time (delayed delivery).
012	0x00C	Out of credit	The message cannot be delivered due to a lack of funds in your account. Please re-purchase credits.
014	0x00E	Maximum MT limit exceeded	The allowable amount for MT messaging has been exceeded.



Terminology

- Receive Messages: A message sent (originating) from a mobile handset to an application via Clickatell.
- Sending Messages: A message sent from an application to (terminating on) a mobile handset via Clickatell.
- Premium rated message: A mobile user is charged a premium for the message that they send to a particular short or long code. This service is not available in all regions; please contact an Account Manager for more information.
- Revenue share: This refers to the portion of the premium charge associated with a premium rated message, which is passed on to the content provider.
- Content provider: This is the Clickatell customer who is offering one or more services that are usually premium rated SMS system.
- Customer: A registered Clickatell customer utilising the Clickatell API for message delivery and receipt.
- Sender ID: The "from" address that appears on the user's handset. This is also known as the message originator or source address. A Sender ID must be registered within your account and approved by us before it may be used.
- **Destination address**: The mobile number/MSISDN of the handset to which the message must be delivered. The number should be in international number format, e.g. country code + local mobile number, excluding the leading zero (0).
- Source address: See 'Sender ID' above.
- Short code: A short number which is common across all the operators for a specific region.
- Subscriber: The mobile network subscriber who owns the mobile number (MSISDN) which will send or receive SMSs, or be billed for premium rated services.
- **Upstream gateway:** A network operator, third party or our own short message service centre (SMSC).

Contact details

Phone: +27 21 910 7700 Fax: +27 21 910 7701 Website: www.clickatell.com

Help URL: http://support.clickatell.com/index.php

Support: support@clickatell.com
Info: info@clickatell.com
Sales: sales@clickatell.com