# User Guide for circuitmacro.sty

# Luca Giaccone

# August 8, 2025

# Contents

1	Intr	oduction
<b>2</b>	Con	nmands Overview and Examples
	2.1	Resistor: \R
	2.2	Inductor: \L
	2.3	Capacitor: \C
	2.4	Generic bipole (e.g. impedance): \B
	2.5	Switch open: \SwOpen
	2.6	Switch closed: \SwClosed
	2.7	Short circuit (e.g. connection): \Short
	2.8	Open circuit: \Open
	2.9	Independent voltage source: \Vs
	2.10	Independent current source: \Is
	2.11	Controlled voltage source: \cVs
		Controlled current source: \cls
		Voltage: \V
		Current: \I
		Nodes: \Nodes
		Terminal: \Terminal
		Label: \Label
		Power load (single phase or three phase): \PLoad
		Star connected load: \YLoad
		Triangle connected load: \DLoad
		Three phase line: \triLine
		Three phase connection: \triShort
		Three phase generator: \triGen
3	Exa	mple Circuits
	3.1	Example 1: first order circuit
	3.2	Example 2: AC Circuit
	3.3	Example 3: Three-Phase Circuit

### 1 Introduction

This document provides a complete user guide for the circuitmacro.sty package, authored by Luca Giaccone. The package extends circuitikz by introducing macros that simplify the drawing of common DC, AC, and three-phase circuit components. The only external dependencies are:

- circuitikz
- xstring

Put the file either in project directory or in the TEXHOME tree. These are the corret path for different operating systems:

macOS: /Users/<username>/Library/texmf/tex/latex/circuitmacro/
Linux: /home/<username>/texmf/tex/latex/circuitmacro/

# 2 Commands Overview and Examples


### 2.1 Resistor: $\R$

#### Signature:

\R[<circuitikz options>]{<start>}{<end>}{<label>}

#### Example:

```
\begin{circuitikz}
\R{0,0}{0,3}{R_1}
\R*{3,0}{3,3}{R_2}
\R[i=$I_3$]{4,0}{7,3}{R_3}
\R[v=$V_4$, i^<=$I_4$, *-*]{7,0}{10,3}{R_4}
\end{circuitikz}
```




# 2.2 Inductor: $\L$

#### Signature:

\L[<circuitikz options>]{<start>}{<end>}{<label>}

```
\begin{circuitikz}
\L{0,0}{0,3}{L_1}
\L*{3,0}{3,3}{L_2}
\L[i=$I_3$]{4,0}{7,3}{L_3}
\L[v=$V_4$, i^<=$I_4$, *-*]{7,0}{10,3}{L_4}
\end{circuitikz}
```




# 2.3 Capacitor: \C

#### Signature:

\C[<circuitikz options>]{<start>}{<end>}{<label>}

#### Example:

```
\begin{circuitikz}
\C{0,0}{0,3}{C_1}
\C*{3,0}{3,3}{C_2}
\C[i=$I_3$]{4,0}{7,3}{C_3}
\C[v=$V_4$, i^<=$I_4$, *-*]{7,0}{10,3}{C_4}
\end{circuitikz}
```




# 2.4 Generic bipole (e.g. impedance): \B

#### Signature:

\B[<circuitikz options>]{<start>}{<end>}{<label>}

```
\begin{circuitikz}
\B{0,0}{0,3}{\bar{Z}_1}
\B*{3,0}{3,3}{\bar{Z}_2}
\B[i=$I_3$]{4,0}{7,3}{\bar{Z}_3}
\B[v=$V_4$, i^<=$I_4$, *-*]{7,0}{10,3}{\bar{Z}_4}
\end{circuitikz}
```




### 2.5 Switch open: \SwOpen

#### Signature:

\SwOpen[<circuitikz options>]{<start>}{<end>}{<label>}

#### Example:

```
\begin{circuitikz}
\SwOpen{0,0}{0,3}{t=0}
\SwOpen*{3,0}{3,3}{t=0}
\SwOpen{4,0}{7,3}{t=0}
\SwOpen[v=$v_s(t)$, *-*]{7,0}{10,3}{t=0}
\end{circuitikz}
```




## 2.6 Switch closed: \SwClosed

#### Signature:

\SwClosed[<circuitikz options>]{<start>}{<end>}{<label>}

```
\begin{circuitikz}
  \SwClosed{0,0}{0,3}{t=0}
  \SwClosed*{3,0}{3,3}{t=0}
  \SwClosed{4,0}{7,3}{t=0}
  \SwClosed[v=$v_s(t)$, *-*]{7,0}{10,3}{t=0}
  \end{circuitikz}
```




# 2.7 Short circuit (e.g. connection): \Short

#### Signature:

\Short[<circuitikz options>]{<start>}{<end>}

#### Example:

```
\begin{circuitikz}[scale=1]
  \Short{0,0}{0,3}
  \Short[i<=$I_{cc2}$,*-*]{2.5,0}{2.5,3}
  \Short[i_=$I_{cc3}$, o-o]{4,0}{7,3}
  \Short[i_<=$I_{cc4}$]{7,0}{10,3}
\end{circuitikz}
```




### 2.8 Open circuit: \Open

### Signature:

\Open[<circuitikz options>]{<start>}{<end>}

#### Example:

```
\begin{circuitikz}[scale=1]
  \Open[v=$V_{oc1}$, *-*]{0,0}{0,3}
  \Open[v_=$V_{oc2}$, o-o]{2.5,0}{2.5,3}
  \Open[v<=$V_{oc3}$, *-*]{4,0}{7,3}
  \Open[v_<=$V_{oc4}$, o-o]{7,0}{10,3}
\end{circuitikz}
```




# 2.9 Independent voltage source: \Vs

#### Signature:

\Vs[<circuitikz options>]{<start>}{<end>}{<label>}

```
\begin{circuitikz}
 \Vs[i=$I_1$]{0,3}{0,0}{E_1}
 \Vs*{3,3}{3,0}{E_2}
 \Vs{4,0}{7,3}{}
 \Vs*[i=$I_4$, *-*]{7,0}{10,3}{E_4}
 \end{circuitikz}
```




### 2.10 Independent current source: \Is

#### Signature:

\Is[<circuitikz options>]{<start>}{<end>}{<label>}

#### Example:

```
\begin{circuitikz}
\Is[v>=$V_1$]{0,0}{0,3}{A_1}
\Is*{3,0}{3,3}{A_2}
\Is{7,3}{4,0}{A_3}
\Is*[v^>=$V_4$, *-*]{10,3}{7,0}{A_4}
\end{circuitikz}
```




# 2.11 Controlled voltage source: \cvs

#### Signature:

\cVs[<circuitikz options>]{<start>}{<end>}{<label>}

```
\begin{circuitikz}
  \cVs[i=$I_1$]{0,3}{0,0}{E_1}
  \cVs*{3,3}{3,0}{E_2}
  \cVs{4,0}{7,3}{}
  \cVs*[i=$I_4$, *-*]{7,0}{10,3}{E_4}
  \end{circuitikz}
```




## 2.12 Controlled current source: \cIs

#### Signature:

\cIs[<circuitikz options>]{<start>}{<end>}{<label>}

#### Example:

```
\begin{circuitikz}
\cIs[v>=$V_1$]{0,0}{0,3}{A_1}
\cIs*{3,0}{3,3}{A_2}
\cIs{7,3}{4,0}{A_3}
\cIs*[v^>=$V_4$, *-*]{10,3}{7,0}{A_4}
\end{circuitikz}
```




# 2.13 Voltage: $\V$

#### Signature:

\V{<start>}{<end>}{<label>}

```
\begin{circuitikz}[scale=1]
\V{0,0}{0,3}{V_1}
\V*{3,0}{3,3}{V_2}
\V{4,0}{7,3}{V_3}
\V{10,3}{7,0}{V_4}
\end{circuitikz}
```




# 2.14 Current: $\I$

#### Signature:

 $\I{<start>}{<end>}{<label>}$ 

#### Example:

```
\begin{circuitikz}
\I{0,0}{0,1}{I_1}
\I*{2,0}{2,1}{I_2}
\I{4,0}{5,1}{I_3}
\I{8,1}{7,0}{I_4}
\end{circuitikz}
```



# 2.15 Nodes: \Nodes

#### Signature:

\Nodes{coordinates1}{coordinates1} ... {coordinatesn}

#### Example:

```
\begin{circuitikz}
\Nodes{0,0}{1,1}
\Nodes*{4,0}{5,0}{5,1}{4,1}
\end{circuitikz}
```

• 0


### 2.16 Terminal: \Terminal

\Terminal{from}{to}{label}

#### Example:

```
\begin{circuitikz}
    % some resistors
    \R[*-*]{1,1}{1,3}{R_1}
    \R{1,3}{3,3}{R_2}
    \R[*-*]{3,3}{3,1}{R_3}
    \R[1,1]{3,1}{R_4}

    % terminals
    \Terminal{0,0}{1,1}{A}
    \Terminal{0,4}{1,3}{B}
    \Terminal{4,4}{3,3}{C}
    \Terminal{4,0}{3,1}{D}
\end{circuitikz}
```




### 2.17 Label: \Label

# 2.18 Power load (single phase or three phase): \PLoad

\PLoad[labe1][label2]{dx}{dy}{origin}

```
\begin{circuitikz}
  \PLoad[P][Q]{2}{4}{0,0}
  \PLoad[Q_c]{3}{1}{7,0}
  \end{circuitikz}
```




### 2.19 Star connected load: \YLoad

#### Signature:

 $\label{label2} $$ \Upsilon(B|R|L|C) {scale} {start} {end} {gap} {label1} {label2} {label3} $$$ 

#### Example:

```
\begin{circuitikz}
 \YLoad{1}{0,0}{3,0}{2}{\bar{Z}}{}{}
 \YLoad[R]{0.8}{7,-1}{8.5,1}{1.5}{R_1}{R_2}{R_3}
 \YLoad*[C]{0.5}{13,0}{11,0}{1}{C}{}}
\end{circuitikz}
```




### 2.20 Triangle connected load: \DLoad

#### Signature:

 $\label{label2} $$\DLoad[B|R|L|C]{scale}{start}{end}{gap}{label1}{label2}{label3}$$ 

```
\begin{circuitikz}
\DLoad{1}{0,0}{3,0}{2}{\bar{Z}_1}{\bar{Z}_2}{\bar{Z}_3}
\DLoad{0.5}{7,0}{10,0}{2}{\bar{Z}_1}{\bar{Z}_2}{\bar{Z}_3}
\DLoad[R]{0.5}{4,-5}{6,-3}{2}{R}{}}
\end{circuitikz}
```




# 2.21 Three phase line: $\triLine$

#### Signature:

 $\label{label2} $$ \tilde{B}_L^C_{scale}{\frac{gap}{label1}{label2}{label3}} $$ $$ \tilde{B}_L^C_{scale}{\frac{gap}{label1}{label2}{label3}} $$$ 

#### Example:

```
\begin{circuitikz}
 \triLine{1}{0,0}{3,0}{2}{\bar{Z}}{}}
 \triLine[R]{0.8}{7,-1}{8.5,1}{1.5}{R_1}{R_2}{R_3}
 \triLine*[C]{0.5}{13,0}{11,0}{1}{C}{}}
\end{circuitikz}
```




# 2.22 Three phase connection: \triShort

#### Signature:

\triShort[<circuitikz options>][<cut>]{start}{end}{gap}

```
\begin{circuitikz}
 \triShort{0,0}{3,0}{2}
 \triShort[*-][1]{7,2}{7,-3}{1}
 \triShort*[*-][1]{12,2}{12,-2}{1}
 \end{circuitikz}
```




## 2.23 Three phase generator: \triGen

#### Signature:

 $\triGen[V|I][scale]{start}{end}{gap}{label1}{label2}{label3}$ 

(N.B. scale does not work perfectly here. It is included for future development and it is suggested to leave it to the default value (i.e. 1). In this version labels, plus sign for voltage generators and arrows for current generators do not scale according to scale parameters.)


```
\begin{circuitikz}
\triGen{0,0}{3,0}{2}{\bar{E}_1}{\bar{E}_2}{\bar{E}_3}
\triGen*{8,-2}{11,1}{2}{\bar{E}_1}{\bar{E}_2}{\bar{E}_3}
\triGen[I]{5,-3}{5,-6}{2}{\bar{A}_1}{\bar{A}_2}{\bar{A}_3}
\end{circuitikz}
```



# 3 Example Circuits


# 3.1 Example 1: first order circuit

```
\begin{circuitikz}
\Vs{0,3}{0,0}{E_1}
\R{0,3}{3,3}{R_1}
\R{0,0}{3,0}{R_2}
\Is[*-*]{3,0}{3,3}{A_1}
\R[-*]{3,3}{6,0}{R_3}
\R[-*]{3,3}{6,3}{R_4}
\SwOpen{6,3}{9,3}{t=0}
\C[v<=$v(t)$]{9,3}{9,0}{C_1}
\Short{6,0}{6,3}
\end{circuitikz}
```



# 3.2 Example 2: AC Circuit

```
\begin{circuitikz}
\Vs{0,6}{0,0}{\bar{E}_1}
\Is[*-*]{3,3}{6,3}{\bar{A}_1}
\B[*-, v<=$\bar{V}_1$]{3,6}{3,3}{\bar{Z}_1}
\B[-*, i=$\bar{I}_2$]{3,3}{3,0}{\bar{Z}_2}
\B[i^<=$\bar{I}_3$]{6,6}{6,3}{\bar{Z}_3}
\B[v<=$\bar{V}_4$]{6,3}{6,0}{\bar{Z}_4}
\Short{0,0}{6,0}
\Short{0,6}{6,6}
\end{circuitikz}
```



# 3.3 Example 3: Three-Phase Circuit

```
\begin{circuitikz}
   % generator and line
   \triLine{1}{2,4}{4.5,4}{1.8}{\bar{Z}_L}{}{}
   % load A
   \triShort{4.5, 4}{9, 4}{1.8}
   \PLoad[P_A][Q_A]{2}{4.5}{9,4}
   % load B
  \triShort[*-][1.8]{6.5, 5.8}{6.5, 1}{1.8}
   \PLoad[P_B][Q_B]{4.5}{2}{6.5,1}
   % current and voltages
   I{8,5.8}{8.5,5.8}{\bar{I}_A}
   I{4.7,3.5}{4.7,3}{\bar{I}_B}
   V*{2,4}{2,5.8}{bar{V}_g}
   V{8.5,4}{8.5,5.8}{bar{V}}
\end{circuitikz}
```

