# **Filesystems**

#### /home is where the heart is

Bhuvy

Filesystems are important because they allow you to persist data after a computer is shut down, crashes, or has memory corruption. Back in the day, filesystems were expensive to use. Writing to the filesystem (FS) involved writing to magnetic tape and reading from that tape [1]. It was slow, heavy, and prone to errors.

Nowadays most of our files are stored on disk – though not all of them! The disk is still slower than memory by an order of magnitude at the least.

Some terminology before we begin this chapter. A **filesystem**, as we'll define more concretely later, is anything that satisfies the API of a filesystem. It may not be a hard disk. A disk is either a **hard disk drive (HDD)** which includes a spinning metallic platter and a head which can zap the platter to encode a 1 or a 0, or a **solid-state drive (SSD)** that can flip certain NAND gates on a chip or standalone drive to store a 1 or a 0. As of 2019, SSDs are an order of magnitude faster than the standard HDD. These are typical backings for a filesystem. A filesystem is implemented on top of this backing, meaning that we can either implement something like EXT, MinixFS, NTFS, FAT32, etc. on a commercially available hard disk. This filesystem tells the operating system how to organize the 1s and 0s to store file information as well as directory information, but more on that later.

The last piece of background is an important one. In this chapter, we will refer to sizes of files in the ISO-compliant KiB or Kibibyte. The \*iB family is short for power of two storage. That means the following:

Prefix	Byte Value	
KiB	1024B	
MiB	1024 * 1024 B	
GiB	10243̂ B	

The standard notational prefixes mean the following:

Prefix	Byte Value
KB	1000B
MB	1000 * 1000 B
GB	10003̂ B

We will do this in the book and in the Networking chapter for the sake of consistency and to not confuse anyone. What is confusing is that in the real world there is a different convention. That convention is that when a file is stored on a traditional file system, **KB** is the same as **KiB**. When we are talking about computer networks **KB** is not the same as **KiB** and is the ISO / Metric Definition above. This is a historical quirk was brought by a clash between network developers and memory/hard storage developers. Hard storage and memory developers found that if a bit could take one of two states, it would be natural to call a Kilo- prefix 1024 because it was about

1000. Network developers had to deal with bits, real-time signal processing, and various other factors, so they went with the already accepted convention that Kilo- means 1000 of something [1]. What you need to know is if you see KB in the wild, that it may be 1024 based on the context. If any time in this class (CS 241 @ Illinois) you see KB or any of the family refer to a filesystems question, you can safely infer that they are referring to 1024 as the base unit.

# What is a filesystem?

You may have encountered the old UNIX adage, "everything is a file". In most UNIX systems, file operations provide an interface to abstract many different operations. Network sockets, hardware devices, and data on the disk are all represented by file-like objects. A file-like object must follow the following conventions:

- 1. It must present itself to the filesystem.
- 2. It must support common filesystem operations, such as <u>open</u>, <u>read</u>, <u>write</u>. At a minimum, it needs to be opened and closed.

A filesystem is an implementation of the file interface. In this chapter, we will be exploring the various callbacks a filesystem provides, some typical functionality and associated implementation details. In this class, we will mostly talk about filesystems that serve to allow users to access data on disk, which are integral to modern computers.

Here are some common features of a filesystem:

- 1. They not only deal with storing local files, but handle special devices that allow for safe communication between the kernel and user space.
- 2. They deal with failures, scalability, indexing, encryption, compression, and performance.
- 3. They handle the abstraction between a file that contains data and how exactly that data is stored on disk, partitioned, and protected.

Before we dive into the details of a filesystem, let's take a look at some examples. To clarify, a mount point is simply a mapping of a directory to a filesystem represented in the kernel.

- 1. <u>ext4</u> Usually mounted at / on Linux systems, this is the filesystem that usually provides disk access as you're used to.
- 2. procfs Usually mounted at /proc, provides information and control over processes.
- 3. <u>sysfs</u> Usually mounted at /sys, a more modern version of /proc that also allows control over various other hardware such as network sockets.
- 4. tmpfs Mounted at /tmp in some systems, an in-memory filesystem to hold temporary files.
- 5. <u>sshfs</u> This syncs files across the <u>ssh</u> protocol.

It tells you what filesystem directory-based system calls resolve to. For example,  $\underline{/}$  is resolved by the  $\underline{\texttt{ext4}}$  filesystem in our case, but  $\underline{/\texttt{proc/2}}$  is resolved by the  $\underline{\texttt{procfs}}$  system even though it contains  $\underline{/}$  as a subsystem.

As you may have noticed, some filesystems provide an interface to things that aren't "files". Filesystems such as <a href="mailto:procfs">procfs</a> are usually referred to as <a href="mailto:virtual">virtual</a> filesystems, since they don't provide data access in the same sense as a traditional filesystem would. Technically, all filesystems in the kernel are represented by virtual filesystems, but we will differentiate <a href="mailto:virtual">virtual</a> filesystems as filesystems that actually don't store anything on a hard disk.

#### The File API

A filesystem must provide callback functions to a variety of actions. Some of them are listed below:

- open Opens a file for IO
- read Read contents of a file
- write Write to a file
- close Close a file and free associated resources
- chmod Modify permissions of a file
- <u>ioctl</u> Interact with device parameters of character devices such as terminals

Not every filesystem supports all the possible callback functions. For example, many filesystems do not implement <u>ioctl</u> or <u>link</u>. Many filesystems aren't <u>seekable</u> meaning that they do not provide random access. A program cannot move to an arbitrary point in the file. This is analogous to <u>seekable streams</u>. In this chapter, we will not be examining each filesystem callback. If you would like to learn more about this interface, try looking at the documentation for Filesystems at the User Space Level (FUSE).

# Storing data on disk

To understand how a filesystem interacts with data on disk, there are three key terms we will be using.

- 1. <u>disk block</u> A disk block is a portion of the disk that is reserved for storing the contents of a file or a directory.
- 2. <u>inode</u> An inode *is* a file or directory. This means that an inode contains metadata about the file as well as pointers to disk blocks so that the file can actually be written to or read from.
- 3. <a href="mailto:superblock">superblock</a> A superblock contains metadata about the inodes and disk blocks. An example superblock can store how full each disk block is, which inodes are being used etc. Modern filesystems may actually contain multiple superblocks and a sort-of super-super block that keeps track of which sectors are governed by which superblocks. This tends to help with fragmentation.

It may seem overwhelming, but by the end of this chapter, we will be able to make sense of every part of the filesystem.

To reason about data on some form of storage – spinning disks, solid state drives, magnetic tape – it is common practice to first consider the medium of storage as a collection of *blocks*. A block can be thought of as a contiguous region on disk. While its size is sometimes determined by some property of the underlying hardware, it is more frequently determined based on the size of a page of memory for a given system, so that data from the disk can be cached in memory for faster access – a very important feature of many filesystems.

A filesystem has a special block denoted as a *superblock* that stores metadata about the filesystem such as a journal (which logs changes to the filesystem), a table of inodes, the location of the first inode on disk, etc. The important thing about a superblock is that it is in a known location on disk. If not, your computer may not be able to boot up! Consider a simple ROM programmed into your motherboard. If your processor can't tell the motherboard to start reading and decipher a disk block to start the boot sequence, you are out of luck.

The inode is the most important structure for our filesystem as it represents a file. Before we explore it in-depth, let's list out the key information we need to have a usable file.

- Name
- File size
- Time created, last modified, last accessed
- Permissions
- Filepath
- Checksum
- File data

#### **File Contents**

#### From Wikipedia:

In a Unix-style file system, an index node, informally referred to as an inode, is a data structure used to represent a filesystem object, which can be various things including a file or a directory. Each inode stores the attributes and disk block location(s) of the filesystem object's data. Filesystem object attributes may include manipulation metadata (e.g. change, access, modify time), as well as owner and permission data (e.g. group-id, user-id, permissions).

The superblock may store an array of inodes, each of which stores direct, and potentially several kinds of indirect pointers to disk blocks. Since inodes are stored in the superblock, most filesystems have a limit on how many inodes can exist. Since each inode corresponds to a file, this is also a limit on how many files that filesystem can have. Trying to overcome this problem by storing inodes in some other location greatly increases the complexity of the filesystem. Trying to reallocate space for the inode table is also infeasible since every byte following the end of the inode array would have to be shifted, a highly expensive operation. This isn't to say there aren't any solutions at all, although typically there is no need to increase the number of inodes since the number of inodes is usually sufficiently high.

Big idea: Forget names of files. The 'inode' is the file.

It is common to think of the file name as the 'actual' file. It's not! Instead, consider the inode as the file. The inode holds the meta-information (last accessed, ownership, size) and points to the disk blocks used to hold the file contents. However, the inode does not usually store a filename. Filenames are usually only stored in directories (see below).

For example, to read the first few bytes of the file, follow the first direct block pointer to the first direct block and read the first few bytes. Writing follows the same process. If a program wants to read the entire file, keep reading direct blocks until you've read several bytes equal to the size of the file. If the total size of the file is less than that of the number of direct blocks multiplied by the size of a block, then unused block pointers will be undefined. Similarly, if the size of a file is not a multiple of the size of a block, data past the end of the last byte in the last block will be garbage.

What if a file is bigger than the maximum space addressable by its direct blocks? To that, we present a motto programmers take too seriously.

"All problems in computer science can be solved by another level of indirection." - David Wheeler

Except for the problem of too many layers of indirection.

To solve this problem, we introduce <u>indirect blocks</u>. A single indirect block is a block that stores pointers to more data blocks. Similarly, a double indirect block stores pointers to single indirect blocks, and the concept

can be generalized to arbitrary levels of indirection. This is a very important concept, as inodes are stored in the superblock, or some other structure in a well known location with a constant amount of space, indirection allows exponential increases in the amount of space an inode can keep track of.

As a worked example, suppose we divide the disk into 4KiB blocks and we want to address up to  $2^{32}$  blocks. The maximum disk size is  $4KiB*2^{32}=16TiB$  remember  $2^{10}=1024$ . A disk block can store  $\frac{4KiB}{4B}$  possible pointers or 1024 pointers. Four byte wide pointers are needed because we want to address 32 bits worth of blocks. Each pointer refers to a 4KiB disk block, so you can refer up to 1024\*4KiB=4MiB of data. For the same disk configuration, a double indirect block stores 1024 pointers to 1024 indirection tables. Thus a double-indirect block can refer up to 1024\*4MiB=4GiB of data. Similarly, a triple indirect block can refer up to 4TiB of data. This is three times as slow for reading between blocks, due to increased levels of indirection. The actual intra-block reading times don't change.

### **Directory Implementation**

A directory is just a mapping of names to inode numbers. It is typically just a normal file, but with some special bits set in its inode and a very specific structure for its contents. POSIX provides a small set of functions to read the filename and inode number for each entry, which we will talk about in depth later in this chapter.

Let's think about what it looks like in the actual file system. Theoretically, directories are just like actual files. The disk blocks will contain *directory entries* or *dirents*. What that means is that our disk block can look like this

Each directory entry could either be a fixed size, or a variable length C-string. It depends on how the particular filesystem implements it at the lower level. To see a mapping of filenames to inode numbers on a POSIX system, from a shell, use  $\underline{1s}$  with the  $\underline{-i}$  option

```
# ls -i
12983989 dirlist.c 12984068 sandwich.c
```

You can see later that this is a powerful abstraction. One can have a file be multiple different names in a directory, or exist in multiple directories.

# **UNIX Directory Conventions**

In standard UNIX filesystems, the following entries are specially added on requests to read a directory.

- 1. <u>·</u> represents the current directory
- 2. .. represents the parent directory
- 3.  $\tilde{}$  is the name of the home directory usually

Counterintuitively,  $\underline{\dots}$  does not refer to the 'grandparent' directory (parent of the parent). Only the current directory and the parent directory have special aliases involving  $\underline{\dots}$  (namely,  $\underline{\dots}$  and  $\underline{\dots}$ ). However,  $\underline{\dots}$  could

however be the name of a file or directory on disk (You can try this with  $\underline{\mathtt{mkdir}\ \dots}$ ). Confusingly, the shell  $\underline{\mathtt{zsh}}$  does interpret  $\underline{\dots}$  as a handy shortcut to the grandparent directory (should it exist) while expanding shell commands.

Additional facts about name-related conventions:

- 1. Files that start with '.' (a period) on disk are conventionally considered 'hidden' and will not be listed by programs like <u>ls</u> without additional flags (<u>-a</u>). This is not a feature of the filesystem, and programs may choose to ignore this.
- Some files may also start with a NUL byte. These are usually abstract UNIX sockets and are used to prevent
  cluttering up the filesystem since they will be effectively hidden by any program not expecting them. They
  will, however, be listed by tools that detail information about sockets, so this is not a feature providing
  security.
- 3. If you want to annoy your neighbor, create a file with the terminal bell character. Every single time the file is listed (by calling 'ls', for example), an audible bell will be heard.

### **Directory API**

While interacting with a file in C is typically done by using <u>open</u> to open the file and then <u>read</u> or <u>write</u> to interact with the file before calling <u>close</u> to release resources, directories have special calls such as, <u>opendir</u>, <u>closedir</u> and <u>readdir</u>. There is no function <u>writedir</u> since typically that implies creating a file or link. The program would just use something like <u>open</u> or <u>mkdir</u>.

To explore these functions, let's write a program to search the contents of a directory for a particular file. The code below has a bug, try to spot it!

```
int exists(char *directory, char *name) {
   struct dirent *dp;
   DIR *dirp = opendir(directory);
   while ((dp = readdir(dirp)) != NULL) {
      puts(dp->d_name);
      if (!strcmp(dp->d_name, name)) {
        return 1; /* Found */
      }
   }
   closedir(dirp);
   return 0; /* Not Found */
}
```

Did you find the bug? It leaks resources! If a matching filename is found then 'closedir' is never called as part of the early return. Any file descriptors opened and any memory allocated by opendir are never released. This means eventually the process will run out of resources and an open or opendir call will fail.

The fix is to ensure we free up resources in every possible code path.

In the above code, this means calling <u>closedir</u> before <u>return 1</u>. Forgetting to release resources is a common C programming bug because there is no support in the C language to ensure resources are always released with all code paths.

Given an open directory, after a call to <u>fork()</u>, either (XOR), the parent or the child can use <u>readdir()</u>, rewinddir() or seekdir(). If both the parent and the child use the above, the behavior is undefined.

There are two main gotchas and one consideration. The <u>readdir</u> function returns "." (current directory) and ".." (parent directory). The other is programs need to explicitly exclude subdirectories from a search, otherwise the search may take a very long time.

For many applications, it's reasonable to check the current directory first before recursively searching subdirectories. This can be achieved by storing the results in a linked list, or resetting the directory struct to restart from the beginning.

The following code attempts to list all files in a directory recursively. As an exercise, try to identify the bugs it introduces.

```
void dirlist(char *path) {
   struct dirent *dp;
   DIR *dirp = opendir(path);
   while ((dp = readdir(dirp)) != NULL) {
      char newpath[strlen(path) + strlen(dp->d_name) + 1];
      sprintf(newpath, "%s/%s", newpath, dp->d_name);
      printf("%s\n", dp->d_name);
      dirlist(newpath);
   }
}
int main(int argc, char **argv) {
   dirlist(argv[1]);
   return 0;
}
```

Did you find all 5 bugs?

```
// Check opendir result (perhaps user gave us a path that can not
    be opened as a directory
if (!dirp) {perror("Could not open directory"); return; }

// +2 as we need space for the / and the terminating 0
char newpath[strlen(path) + strlen(dp->d_name) + 2];

// Correct parameter
sprintf(newpath, "%s/%s", path, dp->d_name);

// Perform stat test (and verify) before recursing
if (0 == stat(newpath, &s) && S_ISDIR(s.st_mode)) dirlist(newpath)

// Resource leak: the directory file handle is not closed after
    the while loop
closedir(dirp);
```

One final note of caution. <a href="readdir">readdir</a> is not thread-safe! You shouldn't use the re-entrant version of the function. Synchronizing the filesystem within a process is important, so use locks around <a href="readdir">readdir</a>.

See the man page of readdir for more details.

### Linking

Links are what force us to model a filesystem as a tree rather than a graph.

While modeling the filesystem as a tree would imply that every inode has a unique parent directory, links allow inodes to present themselves as files in multiple places, potentially with different names, thus leading to an inode having multiple parent directories. There are two kinds of links:

1. <u>Hard Links</u> A hard link is simply an entry in a directory assigning some name to an inode number that already has a different name and mapping in either the same directory or a different one. If we already have a file on a file system we can create another link to the same inode using the 'ln' command:

```
$ ln file1.txt blip.txt
```

However, blip.txt *is* the same file. If we edit blip, I'm editing the same file as 'file1.txt!'. We can prove this by showing that both file names refer to the same inode.

```
$ ls -i file1.txt blip.txt
134235 file1.txt
134235 blip.txt
```

The equivalent C call is link

```
// Function Prototype
int link(const char *path1, const char *path2);
link("file1.txt", "blip.txt");
```

For simplicity, the above examples made hard links inside the same directory. Hard links can be created anywhere inside the same filesystem.

2. <u>Soft Links</u> The second kind of link is called a soft link, symbolic link, or symlink. A symbolic link is different because it does not deal with inode numbers directly. Instead, a symbolic link is a file on disk with a special bit set and stores a path to another file. Quite simply, without the special bit, it is nothing more than a text file with a file path inside. Note when people generally talk about a link without specifying hard or soft, they are referring to a hard link.

To create a symbolic link in the shell, use  $\underline{\tt ln -s}$ . To read the contents of the link as just a file, use  $\underline{\tt readlink}$ . These are both demonstrated below.

```
$ ln -s file1.txt file2.txt
$ ls -i file1.txt blip.txt
134235 file1.txt
134236 file2.txt
134235 blip.txt
$ cat file1.txt
file1!
$ cat file2.txt
file1!
$ cat blip.txt
file1!
$ echo edited file2 >> file2.txt # >> is bash syntax for append to file
$ cat file1.txt
file1!
edited file2
$ cat file2.txt
I'm file1!
edited file2
$ cat blip.txt
file1!
edited file2
$ readlink myfile.txt
file2.txt
```

Note that <u>file2.txt</u> and <u>file1.txt</u> have different inode numbers, unlike the hard link, <u>blip.txt</u>. There is a C library call to create symlinks which is similar to link.

```
symlink(const char *target, const char *symlink);
```

Some advantages of symbolic links are

- Can refer to files that don't exist yet
- Unlike hard links, can refer to directories as well as regular files
- Can refer to files (and directories) that exist outside of the current file system

However, symlinks have a key disadvantage, they as slower than regular files and directories. When the link's contents are read, they must be interpreted as a new path to the target file, resulting in an additional call to open and read since the real file must be opened and read. Another disadvantage is that POSIX will not let you hard link directories whereas soft links are allowed. The  $\underline{ln}$  command will only allow root to do this and only if you provide the  $\underline{-d}$  option. However, even root may not be able to perform this because most filesystems prevent it!

The integrity of the file system assumes the directory structure is an acyclic tree that is reachable from the root directory. It becomes expensive to enforce or verify this constraint if directory linking is allowed. Breaking these assumptions can cause file integrity tools to not be able to repair the file system. Recursive searches potentially never terminate and directories can have more than one parent but ".." can only refer to a single parent. All in all, a bad idea. Soft links are merely ignored, which is why we can use them to reference directories.

When you remove a file using  $\underline{rm}$  or  $\underline{unlink}$ , you are removing an inode reference from a directory. However, the inode may still be referenced from other directories. To determine if the contents of the file are still required, each inode keeps a reference count that is updated whenever a new link is created or destroyed. This count only tracks hard links, symlinks are allowed to refer to a non-existent file and thus, do not matter.

An example use of hard links is to efficiently create multiple archives of a file system at different points in time. Once the archive area has a copy of a particular file, then future archives can re-use these archive files rather than creating a duplicate file. This is called an incremental backup. Apple's "Time Machine" software does this.

### **Pathing**

Now that we have definitions, and have talked about directories, we come across the concept of a path. A path is a sequence of directories that provide one with a "path" in the graph that is a filesystem. However, there are some nuances. It is possible to have a path called a/b/../c/./. Since ... and . are special entries in directories, this is a valid path that actually refers to a/c. Most filesystem functions will allow uncompressed paths to be passed in. The C library provides a function realpath to compress the path or get the absolute path. To simplify by hand, remember that ... means 'parent folder' and that . means 'current folder'. Below is an example that illustrates the simplification of the a/b/../c/. by using cd in a shell to navigate a filesystem.

```
    cd a (in a)
    cd b (in a/b)
    cd . (in a, because .. represents 'parent folder')
    cd c (in a/c)
    cd . (in a/c, because . represents 'current folder')
    Thus, this path can be simplified to a/c.
```

#### Metadata

How can we distinguish between a regular file and a directory? For that matter, there are many other attributes that files also might contain. We distinguish a file type – different from the file extension i.e. png, svg, pdf – using fields inside the inode. How does the system know what type the file is?

This information is stored within an inode. To access it, use the stat calls. For example, to find out when my 'notes.txt' file was last accessed.

```
struct stat s;
stat("notes.txt", &s);
printf("Last accessed %s", ctime(&s.st_atime));
```

There are actually three versions of stat;

```
int stat(const char *path, struct stat *buf);
int fstat(int fd, struct stat *buf);
```

```
int lstat(const char *path, struct stat *buf);
```

For example, a program can use <u>fstat</u> to learn about file metadata if it already has a file descriptor associated with that file.

```
FILE *file = fopen("notes.txt", "r");
int fd = fileno(file); /* Just for fun - extract the file
    descriptor from a C FILE struct */
struct stat s;
fstat(fd, & s);
printf("Last accessed %s", ctime(&s.st_atime));
```

<u>lstat</u> is almost the same as <u>stat</u> but handles symbolic links differently. From the <u>stat</u> man page.

lstat() is identical to stat(), except that if pathname is a symbolic link, then it returns information about the link itself, not the file that it refers to.

The stat functions make use of struct stat. From the stat man page:

The  $\underline{\mathtt{st\_mode}}$  field can be used to distinguish between regular files and directories. To accomplish this, use the macros,  $\underline{\mathtt{S\_ISDIR}}$  and  $\underline{\mathtt{S\_ISREG}}$ .

```
struct stat s;
if (0 == stat(name, &s)) {
  printf("%s ", name);
  if (S_ISDIR( s.st_mode)) puts("is a directory");
  if (S_ISREG( s.st_mode)) puts("is a regular file");
```

```
} else {
  perror("stat failed - are you sure we can read this file's
         metadata?");
}
```

### Permissions and bits

Permissions are a key part of the way UNIX systems provide security in a filesystem. You may have noticed that the <a href="mode">st\_mode</a> field in <a href="mode">struct stat</a> contains more than just the file type. It also contains the mode, a description detailing what a user can and can't do with a given file. There are usually three sets of permissions for any file. Permissions for the <a href="mode">user</a>, the <a href="mode">group</a> and <a href="mode">other</a> (everyone not covered by the first two categories). For each of the three categories, we need to keep track of whether or not the user is allowed to read the file, write to the file, and execute the file. Since there are three categories and three permissions, permissions are usually represented as a 3-digit octal number. For each digit, the least significant byte corresponds to read privileges, the middle one to write privileges and the final byte to execute privileges. They are always presented as <a href="mode">User</a>, <a href="mode">Group</a>, <a href="mode">Other</a> (UGO)</a>. Below are some common examples. Here are the bit conventions:

- 1.  $\underline{\mathbf{r}}$  means that the set of people can read
- 2. w means that the set of people can write
- 3.  $\underline{\mathbf{x}}$  means that the set of people can execute

Octal Code	User	Group	Others
755	rwx	<u>r-x</u>	<u>r-x</u>
644	rw-	r-	r-

It is worth noting that the <u>rwx</u> bits have a slightly different meaning for directories. Write access to a directory that will allow a program to create or delete new files or directories inside. You can think about this as just having write access to the directory entry (dirent) mappings. Read-access to a directory will allow a program to list a directory's contents. This is just read access to the directory entry (dirent) mapping. Execute will allow a program to enter the directory using cd. Without the execute bit, it is not possible to create or remove files or directories since you cannot access them. You can, however, list the contents of the directory.

There are several command line utilities for interacting with a file's mode. <a href="mailto:mknod">mknod</a> changes the type of the file. <a href="mailto:chmod">chmod</a> takes a number and a file and changes the permission bits. However, before we can discuss chmod in detail, we must also understand the user ID (uid) and group id (gid) as well.

# User ID / Group ID

Every user in a UNIX system has a user ID. This is a unique number that can identify a user. Similarly, users can be added to collections called groups, and every group also has a unique identifying number. Groups have a variety of uses on UNIX systems. They can be assigned capabilities - a way of describing the level of control a user has over a system. For example, a group you may have run into is the <a href="mailto:sudoers">sudoers</a> group, a set of trusted users who are allowed to use the command <a href="mailto:sudoens">sudo</a> to temporarily gain higher privileges. We'll talk more about how <a href="mailto:sudoens">sudo</a> works in this chapter. Every file, upon creation, an owner, the creator of the file. This owner's user ID (<a href="mailto:uid">uid</a>) can be found inside the <a href="mailto:stat">stat</a> with a call to <a href="mailto:stat">stat</a>. Similarly, the group ID (<a href="mailto:gid">gid</a>) is set as well.

Every process can determine its <u>uid</u> and <u>gid</u> with <u>getuid</u> and <u>getgid</u>. When a process tries to open a file with a specific mode, it's <u>uid</u> and <u>gid</u> are compared with the <u>uid</u> and <u>gid</u> of the file. If the <u>uid</u>s match, then the process's request to open the file will be compared with the bits on the user field of the file's permissions. If the <u>gid</u>s match, then the process's request will be compared with the group field of the permissions. If none of the IDs match, then the other field will apply.

### Reading / Changing file permissions

Before we discuss how to change permission bits, we should be able to read them. In C, the <u>stat</u> family of library calls can be used. To read permission bits from the command line, use  $\underline{ls} -\underline{l}$ . Note, the permissions will output in the format 'trwxrwxrwx'. The first character indicates the type of file type. Possible values for the first character include but aren't limited to.

- 1. (-) regular file
- 2. (d) directory
- 3. (c) character device file
- 4. (l) symbolic link
- 5. (p) named pipe (also called FIFO)
- 6. (b) block device
- 7. (s) socket

Alternatively, use the program  $\underline{\mathtt{stat}}$  which presents all the information that one could retrieve from the  $\underline{\mathtt{stat}}$  library call.

To change the permission bits, there is a system call, <u>int chmod(const char \*path, mode\_t mode)</u>;. To simplify our examples, we will be using the command line utility of the same name <u>chmod</u> short of "change mode". There are two common ways to use chmod, with either an octal value or with a symbolic string.

```
$ chmod 644 file1
$ chmod 755 file2
$ chmod 700 file3
$ chmod ugo-w file4
$ chmod o-rx file4
```

The base-8 ('octal') digits describe the permissions for each role: The user who owns the file, the group and everyone else. The octal number is the sum of three values given to the three types of permission: read(4), write(2), execute(1)

Example: chmod 755 myfile

- 1. r + w + x = digit \* user has 4+2+1, full permission
- 2. group has 4+0+1, read and execute permission
- 3. all users have 4+0+1, read and execute permission

### Understanding the 'umask'

The umask *subtracts* (reduces) permission bits from <u>777</u> and is used when new files and new directories are created by open, mkdir etc. By default, the umask is set to <u>022</u> (octal), which means that group and other privileges will not include the writable bit. Each process has a current umask value. When forking, the child inherits the parent's umask value.

For example, by setting the umask to  $\underline{077}$  in the shell, ensures that future file and directory creation will only be accessible to the current user,

```
$ umask 077
$ mkdir secretdir
```

As a code example, suppose a new file is created with <u>open()</u> and mode bits <u>666</u> (write and read bits for user, group and other):

```
open("myfile", O_CREAT, S_IRUSR | S_IWUSR | S_IRGRP | S_IWOTH | S_IWOTH);
```

If umask is octal 022, then the permissions of the created file will be 0666 &  $\sim$ 022 for example.

```
S_IRUSR | S_IWUSR | S_IRGRP | S_IROTH
```

#### The 'setuid' bit

You may have noticed an additional bit that files with execute permission may have set. This bit is the <u>setuid</u> bit. It indicated that when run, the program will set the uid of the user to that of the owner of the file. Similar, there is a <u>setgid</u> bit which sets the gid of the executor to the gid of the owner. The canonical example of a program with setuid set is sudo.

<u>sudo</u> is usually a program that is owned by the root user - a user that has all capabilities. By using <u>sudo</u>, an otherwise unprivileged user can gain access to most parts of the system. This is useful for running programs that may require elevated privileges, such as using <u>chown</u> to change ownership of a file, or to use <u>mount</u> to mount or unmount filesystems (an action we will discuss later in this chapter). Here are some examples:

```
$ sudo mount /dev/sda2 /stuff/mydisk
$ sudo adduser fred
$ ls -l /usr/bin/sudo
-r-s--x-x 1 root wheel 327920 Oct 24 09:04 /usr/bin/sudo
```

When executing a process with the setuid bit, it is still possible to determine a user's original uid with <u>getuid</u>. The real action of the <u>setuid</u> bit is to set the effective user ID (<u>euid</u>) which can be determined with <u>geteuid</u>. The actions of getuid and geteuid are described below.

- getuid returns the real user id (zero if logged in as root)
- geteuid returns the effective user id (zero if acting as root, e.g. due to the setuid flag set on a program)

These functions can allow one to write a program that can only be run by a privileged user by checking geteuid or go a step further and ensure that the only user who can run the code is root by using getuid.

### The 'sticky' bit

Sticky bits as we use them today do not serve the same purpose as their initial introduction. Sticky bits were a bit that could be set on an executable file that would allow a program's text segment to remain in swap even after the end of the program's execution. This made subsequent executions of the same program faster. Today, this behavior is no longer supported and the sticky bit only holds meaning when set on a directory,

When a directory's sticky bit is set only the file's owner, the directory's owner, and the root user can rename or delete the file. This is useful when multiple users have write access to a common directory. A common use of the sticky bit is for the shared and writable /tmp directory where many user's files may be stored, but users should not be able to access files belonging to other users.

To set the sticky bit, use chmod +t.

```
aneesh$ mkdir sticky
aneesh$ chmod +t sticky
aneesh$ ls -1
drwxr-xr-x 7 aneesh aneesh 4096 Nov 1 14:19 .
drwxr-xr-x 53 aneesh aneesh 4096 Nov 1 14:19 ..
drwxr-xr-t 2 aneesh aneesh 4096 Nov 1 14:19 sticky
aneesh$ su newuser
newuser$ rm -rf sticky
rm: cannot remove 'sticky': Permission denied
newuser$ exit
aneesh$ rm -rf sticky
aneesh$ ls -1
drwxr-xr-x 7 aneesh aneesh 4096 Nov 1 14:19 .
drwxr-xr-x 53 aneesh aneesh 4096 Nov 1 14:19 ..
```

Note that in the example above, the username is prepended to the prompt, and the command  $\underline{su}$  is used to switch users.

# Virtual filesystems and other filesystems

POSIX systems, such as Linux and Mac OS X (which is based on BSD) include several virtual filesystems that are mounted (available) as part of the file-system. Files inside these virtual filesystems do not exist on the disk. They are generated dynamically by the kernel when a process requests a directory listing. Linux provides 3 main virtual filesystems:

Device	Use Case
/dev	A list of physical and virtual devices (for example network card, cdrom, random number generator
/proc	A list of resources used by each process and (by tradition) set of system information
/sys	An organized list of internal kernel entities

If we want a continuous stream of 0s, we can run cat /dev/zero.

Another example is the file <u>/dev/null</u>, a great place to store bits that you never need to read. Bytes sent to <u>/dev/null/</u> are never stored and simply discarded. A common use of <u>/dev/null</u> is to discard standard output. For example,

```
$ ls . >/dev/null
```

### Managing files and filesystems

Given the multitude of operations that are available to you from the filesystem, let's explore some tools and techniques that can be used to manage files and filesystems.

One example is creating a secure directory. Suppose you created your own directory in /tmp and then set the permissions so that only you can use the directory (see below). Is this secure?

```
$ mkdir /tmp/mystuff
$ chmod 700 /tmp/mystuff
```

There is a window of opportunity between when the directory is created and when it's permissions are changed. This leads to several vulnerabilities that are based on a race condition.

Another user replaces  $\underline{\texttt{mystuff}}$  with a hard link to an existing file or directory owned by the second user, then they would be able to read and control the contents of the  $\underline{\texttt{mystuff}}$  directory. Oh no - our secrets are no longer secret!

However in this specific example, the <u>/tmp</u> directory has the sticky bit set, so other users may not delete the <u>mystuff</u> directory, and the simple attack scenario described above is impossible. This does not mean that creating the directory and then later making the directory private is secure! A better version is to atomically create the directory with the correct permissions from its inception.

```
$ mkdir -m 700 /tmp/mystuff
```

### **Obtaining Random Data**

<u>/dev/random</u> is a file that contains a random number generator where the entropy is determined from environmental noise. Random will block/wait until enough entropy is collected from the environment.

<u>/dev/urandom</u> is like random, but differs in the fact that it allows for repetition (lower entropy threshold), thus won't block.

One can think of both of these as streams of characters from which a program can read as opposed to files with a start and end. To touch on a misconception, most of the time one should be using <a href="https://dev/urandom">/dev/urandom</a>. The only specific use case of <a href="https://dev/random">/dev/random</a> is when one needs cryptographically secure data on bootup and the system should block. Otherwise, there are the following reasons.

- 1. Empirically, they both produce numbers that look random enough.
- 2. <a href="//dev/random">/dev/random</a> may block at an inconvenient time. If one is programming a service for high scalability and relies on <a href=//dev/random</a>, an attacker can reliably exhaust the entropy pool and cause the service to block.
- 3. Manual page authors pose a hypothetical attack where an attacker exhausts the entropy pool and guesses the seeding bits, but that attack has yet to be implemented.
- 4. Some operating system don't have a true /dev/random like MacOS.
- 5. Security experts will talk about Computational Security vs Information Theoretic security, more on this article Urandom Myths. Most encryption is computationally secure, which means <a href="//dev/urandom">/dev/urandom</a> is as well.

### **Copying Files**

Use the versatile <u>dd</u> command. For example, the following command copies 1 MiB of data from the file <u>/dev/urandom</u> to the file <u>/dev/null</u>. The data is copied as 1024 blocks of block size 1024 bytes.

```
$ dd if=/dev/urandom of=/dev/null bs=1k count=1024
```

Both the input and output files in the example above are virtual - they don't exist on a disk. This means the speed of the transfer is unaffected by hardware power.

<u>dd</u> is also commonly used to make a copy of a disk or an entire filesystem to create images that can either be burned on to other disks or to distribute data to other users.

# **Updating Modification Time**

The <u>touch</u> executable creates a file if it does not exist and also updates the file's last modified time to be the current time. For example, we can make a new private file with the current time:

```
$ umask 077  # all future new files will mask out all r,w,x
bits for group and other access
```

An example use of touch is to force make to recompile a file that is unchanged after modifying the compiler options inside the makefile. Remember that make is 'lazy' - it will compare the modified time of the source file with the corresponding output file to see if the file needs to be recompiled.

```
$ touch myprogram.c # force my source file to be recompiled
$ make
```

### **Managing Filesystems**

To manage filesystems on your machine, use <u>mount</u>. Using mount without any options generates a list (one filesystem per line) of mounted filesystems including networked, virtual and local (spinning disk / SSD-based) filesystems. Here is a typical output of mount

```
$ mount
/dev/mapper/cs241--server_sys-root on / type ext4 (rw)
proc on /proc type proc (rw)
sysfs on /sys type sysfs (rw)
devpts on /dev/pts type devpts (rw,gid=5,mode=620)
tmpfs on /dev/shm type tmpfs
   (rw,rootcontext="system_u:object_r:tmpfs_t:s0")
/dev/sda1 on /boot type ext3 (rw)
/dev/mapper/cs241--server_sys-srv on /srv type ext4 (rw)
/dev/mapper/cs241--server_sys-tmp on /tmp type ext4 (rw)
/dev/mapper/cs241--server_sys-var on /var type ext4 (rw)rw,bind)
/srv/software/Mathematica-8.0 on /software/Mathematica-8.0 type
   none (rw, bind)
engr-ews-homes.engr.illinois.edu:/fs1-homes/angrave/linux on
   /home/angrave type nfs
   (rw,soft,intr,tcp,noacl,acregmin=30,vers=3,sec=sys,sloppy,addr=128.174.252.102)
```

Notice that each line includes the filesystem type source of the filesystem and mount point. To reduce this output, we can pipe it into <u>grep</u> and only see lines that match a regular expression.

```
>mount | grep proc # only see lines that contain 'proc'
proc on /proc type proc (rw)
none on /proc/sys/fs/binfmt_misc type binfmt_misc (rw)
```

#### **Filesystem Mounting**

Suppose you had downloaded a bootable Linux disk image from the arch linux download page

```
$ wget $URL
```

Before putting the filesystem on a CD, we can mount the file as a filesystem and explore its contents. Note: mount requires root access, so let's run it using sudo

```
$ mkdir arch
$ sudo mount -o loop archlinux-2015.04.01-dual.iso ./arch
$ cd arch
```

Before the mount command, the arch directory is new and obviously empty. After mounting, the contents of <a href="mailto:arch/">arch/</a> will be drawn from the files and directories stored in the filesystem stored inside the <a href="mailto:archlinux-2014.11.01-dual.iso">archlinux-2014.11.01-dual.iso</a> file. The <a href="mailto:100p">100p</a> option is required because we want to mount a regular file, not a block device such as a physical disk.

The loop option wraps the original file as a block device. In this example, we will find out below that the file system is provided under <a href="//dev/loop0">/dev/loop0</a>. We can check the filesystem type and mount options by running the mount command without any parameters. We will pipe the output into <a href="mailto:grep">grep</a> so that we only see the relevant output line(s) that contain 'arch'.

```
$ mount | grep arch
/home/demo/archlinux-2014.11.01-dual.iso on /home/demo/arch type
   iso9660 (rw,loop=/dev/loop0)
```

The iso9660 filesystem is a read-only filesystem originally designed for optical storage media (i.e. CDRoms). Attempting to change the contents of the filesystem will fail

```
$ touch arch/nocando
```

```
touch: cannot touch '/home/demo/arch/nocando': Read-only file
   system
```

# **Memory Mapped IO**

While we traditionally think of reading and writing from a file as an operation that happens by using the <u>read</u> and <u>write</u> calls, there is an alternative, mapping a file into memory using <u>mmap</u>. <u>mmap</u> can also be used for IPC, and you can see more about <u>mmap</u> as a system call that enables shared memory in the IPC chapter. In this chapter, we'll briefly explore mmap as a filesystem operation.

<u>mmap</u> takes a file and maps its contents into memory. This allows a user to treat the entire file as a buffer in memory for easier semantics while programming, and to avoid having to read a file as discrete chunks explicitly.

Not all filesystems support using <u>mmap</u> for IO, but amongst those that do, not all have the same behavior. Some will simply implement <u>mmap</u> as a wrapper around <u>read</u> and <u>write</u>. Others will add additional optimizations by taking advantage of the kernel's page cache. Of course, such optimization can be used in the implementation of read and write as well, so often using mmap does not impact performance.

<u>mmap</u> is used to perform some operations such as loading libraries and processes into memory. If many programs only need read-access to the same file, then the same physical memory can be shared between multiple processes. This is used for common libraries like the C standard library.

The process to map a file into memory is as follows.

- 1. mmap requires a file descriptor, so we need to open the file first
- 2. We seek to our desired size and write one byte to ensure that the file is sufficient length
- 3. When finished call munmap to unmap the file from memory.

Here is a quick example.

```
#define QUIT fail(__FILE__, __LINE__ )
int main() {
 // We want a file big enough to hold 10 integers
 int size = sizeof(int) * 10;
 int fd = open("data", O_RDWR | O_CREAT | O_TRUNC, 0600); //6 =
     read+write for me!
 lseek(fd, size, SEEK_SET);
 write(fd, "A", 1);
 void *addr = mmap(0, size, PROT_READ | PROT_WRITE, MAP_SHARED,
     fd, 0);
 printf("Mapped at %p\n", addr);
 if (addr == (void*) -1 ) QUIT;
 int *array = addr;
 array[0] = 0x12345678;
 array[1] = 0xdeadc0de;
 munmap(addr,size);
 return 0;
}
```

The careful reader may notice that our integers were written in least-significant-byte format because that is the endianness of the CPU that we ran this example on. We also allocated a file that is one byte too many! The <a href="PROT\_READ">PROT\_WRITE</a> options specify the virtual memory protection. The option <a href="PROT\_EXEC">PROT\_WRITE</a> options specify the virtual memory protection. The option <a href="PROT\_EXEC">PROT\_EXEC</a> (not used here) can be set to allow CPU execution of instructions in memory.

# **Reliable Single Disk Filesystems**

Most filesystems cache significant amounts of disk data in physical memory. Linux, in this respect, is extreme. All unused memory is used as a giant disk cache. The disk cache can have a significant impact on overall system performance because disk I/O is slow. This is especially true for random access requests on spinning disks where the disk read-write latency is dominated by the seek time required to move the read-write disk head to the correct position.

For efficiency, the kernel caches recently used disk blocks. For writing, we have to choose a trade-off between performance and reliability. Disk writes can also be cached ("Write-back cache") where modified disk blocks are stored in memory until evicted. Alternatively, a 'write-through cache' policy can be employed where disk writes are sent immediately to the disk. The latter is safer as filesystem modifications are quickly stored to persistent

media but slower than a write-back cache. If writes are cached then they can be delayed and efficiently scheduled based on the physical position of each disk block. Note, this is a simplified description because solid state drives (SSDs) can be used as a secondary write-back cache.

Both solid state disks (SSD) and spinning disks have improved performance when reading or writing sequential data. Thus, operating systems can often use a read-ahead strategy to amortize the read-request costs and request several contiguous disk blocks per request. By issuing an I/O request for the next disk block before the user application requires the next disk block, the apparent disk I/O latency can be reduced.

If your data is important and needs to be force written to disk, call <u>sync</u> to request that a filesystem's changes be written (flushed) to disk. However, not all operating systems honor this request. Even if the data is evicted from the kernel buffers, the disk firmware may use an internal on-disk cache or may not yet have finished changing the physical media. Note, you can also request that all changes associated with a particular file descriptor are flushed to disk using fsync(int fd).

If your operating system fails in the middle of an operation, most modern file systems do something called **journaling** to work around this. What the file system does is before it completes a potentially expensive operation, is that it writes what it is going to do down in a journal. In the case of a crash or failure, one can step through the journal and see which files are corrupt and fix them. This is a way to salvage hard disks in cases there is critical data and there is no apparent backup.

Even though it is unlikely for your computer, programming for data centers means that disks fail every few seconds. Disk failures are measured using "Mean-Time-To-Failure (MTTF)". For large arrays, the mean failure time can be surprisingly short. If the MTTF(single disk) = 30,000 hours, then the MTTF(1000 disks)= 30000/1000=30 hours or about a day and a half! That's also assuming that the failures between the disks are independent, which they often aren't.

### **RAID - Redundant Array of Inexpensive Disks**

One way to protect against this is to store the data twice! This is the main principle of a "RAID-1" disk array. By duplicating the writes to a disk with writes to another backup disk, there are exactly two copies of the data. If one disk fails, the other disk serves as the only copy until it can be re-cloned. Reading data is faster since data can be requested from either disk, but writes are potentially twice as slow because now two write commands need to be issued for every disk block write. Compared to using a single disk, the cost of storage per byte has doubled.

Another common RAID scheme is RAID-0, meaning that a file could be split up among two disks, but if any disk fails then the files are irrecoverable. This has the benefit of halving write times because one part of the file could be writing to hard disk one and another part to hard disk two.

It is also common to combine these systems. If you have a lot of hard disks, consider RAID-10. This is where you have two systems of RAID-1, but the systems are hooked up in RAID-0 to each other. This means you would get roughly the same speed from the slowdowns but now any one disk can fail and you can recover that disk. If two disks from opposing raid partitions fail, there is a chance that you can recover though we don't could on it most of the time.

# **Higher Levels of RAID**

RAID-3 uses parity codes instead of mirroring the data. For each N-bits written, we will write one extra bit, the 'Parity bit' that ensures the total number of 1s written is even. The parity bit is written to an additional disk. If any disk including the parity disk is lost, then its contents can still be computed using the contents of the other disks.

One disadvantage of RAID-3 is that whenever a disk block is written, the parity block will always be written

too. This means that there is effectively a bottleneck in a separate disk. In practice, this is more likely to cause a failure because one disk is being used 100% of the time and once that disk fails then the other disks are more prone to failure.

A single disk failure will not result in data loss because there is sufficient data to rebuild the array from the remaining disks. Data-loss will occur when two disks are unusable because there is no longer sufficient data to rebuild the array. We can calculate the probability of a two disk failure based on the repair time which includes not just the time to insert a new disk but the time required to rebuild the entire contents of the array.

```
MTTF = mean time to failure
MTTR = mean time to repair
N = number of original disks
p = MTTR / (MTTF-one-disk / (N-1))
```

Using typical numbers (MTTR=1day, MTTF=1000days, N-1 = 9, p=0.009)

There is a 1% chance that another drive will fail during the rebuild process (at that point you had better hope you still have an accessible backup of your original data. In practice, the probability of a second failure during the repair process is likely higher because rebuilding the array is I/O-intensive (and on top of normal I/O request activity). This higher I/O load will also stress the disk array.

RAID-5 is similar to RAID-3 except that the check block (parity information) is assigned to different disks for different blocks. The check-block is 'rotated' through the disk array. RAID-5 provides better read and write performance than RAID-3 because there is no longer the bottleneck of the single parity disk. The one drawback is that you need more disks to have this setup, and there are more complicated algorithms that need to be used.

Failure is common. Google reports 2-10% of disks fail per year. Multiplying that by 60,000+ disks in a single warehouse. Services must survive failure of not just a disk, but a rack of servers or even a whole data center.

#### **Solutions**

Simple redundancy (2 or 3 copies of each file) e.g., Google GFS (2001). More efficient redundancy (analogous to RAID 3++) e.g., Google Colossus filesystem (~2010): customizable replication including Reed-Solomon codes with 1.5x redundancy

# Simple Filesystem Model

Software developers need to implement filesystems all the time. If that is surprising to you, we encourage you to take a look at Hadoop, GlusterFS, Qumulo, etc. Filesystems are hot areas of research as of 2018 because people have realized that the software models that we have devised don't take full advantage of our current hardware. Additionally, the hardware that we use for storing information is getting better all the time. As such, you may end up designing a filesystem yourself someday. In this section, we will go over one of a fake filesystems and "walk through" some examples of how things work.

So, what does our hypothetical filesystem look like? We will base it off of the minixfs, a very simple filesystem that happens to be the first filesystem that Linux ran on. It is laid out sequentially on disk, and the first section is the superblock. The superblock stores important metadata about the entire filesystem. Since we want to be able to read this block before we know anything else about the data on disk, this needs to be in a well-known location so the very start of the disk is a good choice. After the superblock, we'll keep a map of which inodes

are being used. The nth bit is set if the nth inode – 0 being the inode root – is being used. Similarly, we store a map recording which data blocks are used. Finally, we have an array of inodes followed by the rest of the disk implicitly partitioned into data blocks. It's important to note that there may not be any real distinction from one data block to the next from the perspective of the hardware components of the disk. Thinking about the disk as an array of data blocks is simply something we do so that we have a way to describe where files live on disk.

Below, we have an example of how an inode that describes a file may look. Note that for the sake of simplicity, we have drawn arrows mapping data block numbers in the inode to their locations on disk. These aren't pointers so much as indices into an array.




Figure 10.1: Sample file filling up

We will assume that a data block is 4 KiB.

Note that a file will fill up each of its data blocks completely before requesting an additional data block. We will refer to this property as the file being *compact*. The file presented above is interesting since it uses all of its direct blocks, one of the entries for its indirect block and partially uses another indirect block.

The following subsections will all refer to the file presented above.

# How big is our file?

The size of a file is not something that we can compute by staring at its structure. We need additional information that is typically stored in the inode. This is because the filesystem isn't aware of the actual contents of what is in a file - that data is considered the user's and should only be manipulated by the user. However, we can compute upper and lower bounds on the filesize by only looking at how many blocks the file uses.

There are two full direct blocks, which together store  $2*sizeof(data\ block) = 2*4KiB = 8KiB$ .

There are two used blocks referenced by the indirect block, which can store up to 8KiB as calculated above. We can now add these values to get an upper bound on the file size of 16KiB.

What about a lower bound? We know that we must use the two direct blocks, one block referenced by the indirect block and at least 1 byte of a second block referenced by the indirect block. With this information, we can work out the lower bound to be 2\*4KiB+4KiB+1=12KiB+1B.

Note that our calculations so far have been to determine how much data the user is storing on disk. We have not considered the *overhead* of storing this data incurred while using this filesystem. You'll notice that we use an indirect block to store the disk block numbers of blocks used beyond the two direct blocks. While doing our above calculations, we did not take this block into account while computing the file size. This would instead be counted as the overhead of the file, and thus the total overhead of storing this file on disk is  $sizeof(indirect\_block) = 4KiB$ ).

Now that we're thinking about overhead, a related calculation could be to determine the max/min disk usage per file in this filesystem.

Trivially a file of size 0 has no associated data blocks and takes up no space on disk (ignoring the space required for the inode since these are located in a fixed size array somewhere on disk). How about the disk usage of the smallest non-empty file? That is, consider a file of size 1B. Note that when a user writes the first byte, a data block will be allocated. Since each data block is 4KiB, we find that 4KiB is the minimum disk usage for a non-empty file. Here, we observe that the file size will only be 1B, despite that 4KiB of the disk is used – there is a distinction between file size and disk usage because of overhead!

Finding maximum is slightly more involved. As we saw earlier in this chapter, a filesystem with this structure can have 1024 data block numbers in one indirect block. This implies that the maximum filesize can be 2\*4KiB + 1024\*4KiB = 4MiB + 8KiB (after accounting for the direct blocks as well). However, on disk we also store the indirect block itself. This means that an additional 4KiB of overhead will be used to account for the indirect block, so the total disk usage will be 4MiB + 12KiB.

Note that when only using direct blocks, completely filling up a direct block implies that our filesize and our disk usage are the same thing! While it would seem like we always want this ideal scenario, it puts a very restrictive limit on the maximum filesize. Attempting to remedy this by increasing the number of direct blocks seems promising, but note that this requires increasing the size of an inode and reducing the amount of space available to store user data – a tradeoff you will have to evaluate for yourself. Alternatively always trying to split your data up into chunks that never use indirect blocks is also not necessarily wise since it could exhaust the limited pool of available inodes.

# **Performing Reads**

Performing reads tend to be pretty easy in our filesystem because our files are compact. Let's say that we want to read the entirety of this particular file. What we'd start by doing is go to the inode's direct struct and find the first direct data block number. In our case, it is #7. Then we find the 7th data block from the *start* of all data blocks. Then we read all of those bytes. We do the same thing for all of the direct nodes. What do we do after? We go to the indirect block and read the indirect block. We know that every 4 bytes of the indirect block is either a sentinel node (-1) or the number of *another* data block. In our particular example, the first four bytes evaluate to the integer 5, meaning that our data continues on the 5th data block from the beginning. We do the same for data block #4 and we stop after because we exceed the size of the inode

Now, let's think about the edge cases. How would a program start the read starting at an arbitrary offset of n bytes given that block sizes are 4KiBs. How many indirect blocks should there be if the filesystem is correct? (Hint: think about using the size of the inode)

### **Performing Writes**

#### Writing to files

Performing writes fall into two categories, writes to files and writes to directories. First we'll focus on files and assume that we are writing a byte to the 6th KiB of our file. To perform a write on a file at a particular offset, first the filesystem must go to the data block would start at that offset. For this particular example we would have to go to the 2nd or indexed number 1 inode to perform our write. We would once again fetch this number from the inode, go to the root of the data blocks, go to the 5th data block and perform our write at the 2KiB offset from this block because we skipped the first four kibibytes of the file in block 7. We perform our write and go on our merry way.

Some questions to consider.

- How would a program perform a write go across data block boundaries?
- How would a program perform a write after adding the offset would extend the length of the file?
- How would a program perform a write where the offset is greater than the length of the original file?

#### Writing to directories

Performing a write to a directory implies that an inode needs to be added to a directory. If we pretend that the example above is a directory. We know that we will be adding at most one directory entry at a time. Meaning that we have to have enough space for one directory entry in our data blocks. Luckily the last data block that we have has enough free space. This means we just need to find the number of the last data block as we did above, go to where the data ends, and write one directory entry. Don't forget to update the size of the directory so that the next creation doesn't overwrite your file!

Some more questions:

- How would would a program perform a write when the last data block is already full?
- How about when all the direct blocks have just been filled up and the inode doesn't have an indirect block?
- What about when the first indirect entry (#4) is full?

# **Adding Deletes**

If the inode is a file, then remove the directory entry in the parent directory by marking it as invalid (maybe making it point to inode -1) and skip it in your reads. A filesystem decreases the hard link count of the inode and if the count reaches zero, free the inode in the inode map and free all associated data blocks so they are reclaimed by the filesystem. In many operating systems, several fields in the inode get overwritten.

If the inode is a directory, the filesystem checks if it is empty. If not, then the kernel will most likely just mark an error.

# Extra: Modern Filesystems

While the API for most filesystems have stayed the same on POSIX over the years, the actual filesystems themselves provide lots of important aspects.

- Data Integrity. File systems use journaling and sometimes checksums to ensure that the data written to is valid. Journalling is a simple invention where the file system writes an operation in a journal. If the filesystem crashes before the operation is complete, it can resume the operation when booted up again using the partial journal.
- Caching. Linux does a very good job of caching file system operations like finding inodes. This makes disk
  operations seem nearly instant. If you want to see a slow system, look at Windows with FAT/NTFS. Disk
  operations need to be cached by the application, or it will burn through the CPU.
- Speed. On spinning disk machines, data that is toward the end of a metallic platter will spin faster (angular velocity is farther from the center). Programs used this to reduce time loading large files like movies in a video editing piece of software. SSDs don't have this problem because there is no spinning disk, but they will portion off a section of their space to be used as "swap space" for fiels.
- Parallelism. Filesystems with multiple heads (for physical hard disks) or multiple controllers (for SSDs)
  can utilize parallelism by multiplexing the PCIe slot with data, always serving some data to the application
  whenever possible.
- Encryption. Data can be encrypted with one or more keys. A good example of this is Apple's APFS file systems.
- Redundancy. Sometimes data can be replicated to blocks to ensure that the data is always available.
- Efficient Backups. Many of us have data that we can't store on the cloud for one reason or another. It is useful that when a filesystems is either being used as a backup medium or is the source to the backup that it is able to calculate what has changed efficiently, compress files, and sync between the external drive.
- Integriy and Bootability. File systems need to be resillient to bit flipping. Most readers have their operating system installed on the same paritition as the file system that they used to do different operations. The file system needs to make sure a stray read or write doesn't destroy the boot sector meaning your computer can't start up again.
- Fragmentation. Just like a memory allocator, allocating space for a file leads to both internal and external fragmentation. The same caching benefit occurs when disk blocks for a single file are located next to each other. File systems need to perform well under low, high, and possible fragmentation usage.
- Distributed. Sometimes, the filesystem should be single machine fault tolerant. Hadoop and other distributed file system allow you to do just that.

### **Extra: Cutting Edge File systems**

There are a few filesystem hardware nowadays that are truly cutting edge. The one we'd briefly like to touch on is AMD's StoreMI. We aren't trying to sell AMD chipsets, but the featureset of StoreMI warrants a mention.

StoreMI is a hardware microcontroller that analyzes how the operating system accesses files and moves files/blocks around to speed up the load time. A common usage can be imagined as having a fast, but small

capacity SSD and a slower, large capcity HDD. To make it seem like all the files are on an SSD, the StoreMI matches the pattern of file access. If you are starting up Windows, Windows will often access many files in the same order. StoreMI takes note of that and when the microcontroller notices it is starting the boot, it will move files from the HDD drive to the SSD before they are requested by the operating system. By the time the operating system needs then, they are already on the SSD. StoreMI also does this with other applications as well. The technology still has a lot to be desired for, but it is an interesting intersection of data and pattern matching with filesystems.

# **Topics**

- Superblock
- Data Block
- Inode
- Relative Path
- File Metadata
- · Hard and Soft Links
- · Permission Bits
- Mode bits
- Working with Directories
- Virtual File System
- Reliable File Systems
- RAID

# Questions

- How big can files be on a file system with 15 Direct blocks, 2 double, 3 triple indirect, 4kb blocks and 4byte entries? (Assume enough infinite blocks)
- What is a superblock? Inode? Data block?
- How do we simplify /./proc/../dev/./random/
- In ext2, what is stored in an inode, and what is stored in a directory entry?
- What are /sys, /proc, /dev/random, and /dev/urandom?
- What are the permission bits?
- How does one use chmod to set user/group/owner read/write/execute permissions?
- What does the "dd" command do?
- What is the difference between a hard link and a symbolic link? Does the file need to exist?
- "Is -1" shows the size of each file in a directory. Is the size stored in the directory or in the file's inode?

BIBLIOGRAPHY 319

# Bibliography

 $[1] \ International. \ URL \ https://www.iec.ch/si/binary.htm.$