FU BAPI BUS2002 ACTELEM CHANGE M

Short Text

List: Change Activity Elements

Functionality

Change one or more activity elements (subobject of the BOR object type BUS2002001). Each time this BAPI is called, only the activity elements for one network can be changed.

Example

- Parameter I NUMBER
 - Specify the network for which the activity elements are to be changed in parameter I_NUMBER. The network can already exist in the database or have been created previously in the current processing unit via BAPI_BUS2002_CREATE. In the second case, use the temporary network number for internal assignment of the network number for parameter I_NUMBER.
- Tables IT_ACT_ELEMENT and IT_UPDATE_ACT_ELEMENT
 Transfer a row for each activity element to be changed in the tables IT_ACT_ELEMENT and IT_UPDATE_ACT_ELEMENT. The mapping of both table entries takes place via the activity element number field (ELEMENT).

Fill the table entry in IT_ACT_ELEMENT with the data of the activity element that is to be changed. In the table entry in IT_UPDATE_ACT_ELEMENT, flag all fields that are to be updated with the values from IT_ACT_ELEMENT with an "X".

All other fields remain unchanged, even if new values have been assigned to them in IT_ACT_ELEMENT. This BAPI therefore works according to the "change by flagging" principle (refer also to the programming guide in transaction BAPI).

Entries in table IT_UPDATE_ACT_ELEMENT that do not have a corresponding record in table IT_ACT_ELEMENT are ignored.

Entries in table IT_ACT_ELEMENT that do not have a corresponding record in table IT_UPDATE_ACT_ELEMENT generate an error.

If the tables IT_ACT_ELEMENT and/or IT_UPDATE_ACT_ELEMENT each contain several entries with the same key ELEMENT, system behaviour is undefined because unique mapping is not possible.

- Temporary activity element
 - An activity element to be changed can already exist in the database or have been created previously in the current processing unit via BAPI_BUS2002_ACTELEM_CREATE_M. You can change an activity element several times within a processing unit via BAPI_BUS2002_ACTELEM_CHANGE_M.
- Field NOT MRP APPLICABLE

With this field you control the 'Res/PurcRq' field in the network header, activity, or activity element. Possible values are:

- o '1' or 'X': Never relevant to materials planning
- '2': Relevant to materials planning after release
- o '3': Relevant to materials planning immediately
- o For the default value ' ' (SPACE) the following applies:

In create mode: The default is specified for the field analogous to the dialog in Customizing or inherited from the higher-level object.

In change mode: The value '' acts like the value '3' (Relevant to materials planning immediately).

SPACE is a selective value here, since you must set the parameter additionally in the I_NETWORK_UPD structure. This is not the case in create mode.

- o Anything else you enter generates the error CNIF PI088.
- Messages from the application and a success or error message are returned to the caller by the BAPI in the
 return table ET_RETURN. In ET_RETURN, the messages are grouped together in blocks per activity element.
 Each message block refers therefore to an activity element and starts with a summarized success or error
 message.

Notes

1. Definition "Processing Unit"

In the following, the term "processing unit" refers to a series of related processing steps.

The first step in a processing unit is initialization, which is done by calling the BAPI **BAPI_PS_INITIALIZATION**. Afterwards, the individual BAPIs listed below can be used several times, if required. The processing unit ends when the final precommit (call BAPI **BAPI_PS_PRECOMMIT**) is executed with a subsequent **COMMIT WORK** (for example, the statement COMMIT WORK, the BAPI "BAPI_TRANSACTION_COMMIT" or the BapiService.TransactionCommit method).

After the final COMMIT WORK, the next initialization opens a new processing unit via the BAPI "BAPI PS INITIALIZATION".

In principal, the following applies to each individual processing unit.

2. Creation of a Processing Unit

Each processing unit must be initialized by calling the BAPI "BAPI_PS_INITIALIZATION" once.

Afterwards, the following individual BAPIs can be used within a processing unit - they can also be used more than once, taking into account the "One-Project-Principle" explained below. This also means that an object created in the current processing unit by a CREATE-BAPI can be changed by a CHANGE-BAPI or STATUS-BAPI.

Except for the BAPIs explicitly named below, you can only call up BAPIs that execute GET methods or READ methods only. In particular, the BAPIs for confirming a network may **not** be used with the individual BAPIs named below!

Business Object ProjectDefinitionPI

BAPI	Method
BAPI_BUS2001_CREATE	ProjectDefinitionPI.CreateSingle
BAPI_BUS2001_CHANGE	ProjectDefinitionPI.Change
BAPI_BUS2001_DELETE	ProjectDefinitionPI.Delete
BAPI_BUS2001_SET_STATUS	ProjectDefinitionPI.SetStatus
BAPI_BUS2001_PARTNER_CREATE_M	ProjectDefinitionPI.PartnerCreateMultiple
BAPI_BUS2001_PARTNER_CHANGE_M	ProjectDefinitionPI.PartnerChangeMultiple
BAPI_BUS2001_PARTNER_REMOVE_M	$\label{projectDefinitionPI.PartnerRemoveMultiple} ProjectDefinitionPI.PartnerRemoveMultiple$

Business Object WBSPI

BAPI Method

BAPI_BUS2054_CREATE_MULTI WBSPI.CreateMultiple BAPI_BUS2054_CHANGE_MULTI WBSPI.ChangeMultiple BAPI_BUS2054_DELETE_MULTI WBSPI.DeleteMultiple BAPI_BUS2001_SET_STATUS WBSPI.SetStatus

Business Object NetworkPI

BAPI Method

BAPI BUS2002 CREATE NetworkPI.CreateFromData

BAPI_BUS2002_CHANGE NetworkPI.Change BAPI_BUS2002_DELETE NetworkPI.Delete

BAPI_BUS2002_ACT_CREATE_MULTI NetworkPI.ActCreateMultiple
BAPI_BUS2002_ACT_CHANGE_MULTI NetworkPI.ActChangeMultiple
BAPI_BUS2002_ACT_DELETE_MULTI NetworkPI.ActDeleteMultiple
BAPI_BUS2002_ACTELEM_CREATE_M NetworkPI.ActElemCreateMultiple
BAPI_BUS2002_ACTELEM_CHANGE_M NetworkPI.ActElemChangeMultiple
BAPI_BUS2002_ACTELEM_DELETE_M NetworkPI.ActElemDeleteMultiple
BAPI_BUS2002_SET_STATUS NetworkPI.SetStatus

The processing unit must be finished by calling the BAPIs BAPI_PS_PRECOMMIT and BAPI_TRANSACTION_COMMIT (in that order).

3. One-Project Principle

For technical reasons, only the project definition and the WBS elements of one project can be processed in a processing unit.

More than one project is used, for example, if

- You create or change more than one project
- You have changed a project and want to change a network to which WBS elements from a different project are assigned
- You want to change various networks to which WBS elements from different projects are assigned
- You create or change a WBS assignment in a network so that a WBS element from a second project is used
- WBS elements from different projects are already assigned to a network (note: this type of network cannot be processed with the network BAPIs named above).

If you define a report for calling BAPIs, this means that:

The report may use a maximum of one project per processing unit. The individual BAPI calls must be distributed between more than one processing unit, which use a maximum of one project per processing unit.

4. All-Or-Nothing Principle

If an error occurs in a processing unit in an individual BAPI or in the BAPI "BAPI_PS_PRECOMMIT" (that is, the return table ET_RETURN contains at least one message of the type "E" (error), "A" (abnormal end) or "X" (exit), posting is not possible.

If an error occurs in an individual BAPI and despite this you call the BAPI "BAPI_PS_PRECOMMIT", message CNIF_PI 056 is issued with message type I (information).

If an error occurs in an individual BAPI or in the BAPI "BAPI_PS_PRECOMMIT", but despite this you execute a COMMIT WORK, the program that is currently in process is terminated and message CNIF_PI 056 is issued with message type X.

This is to ensure data consistency for all objects created, changed, and/or deleted in the processing unit.

Note that the processing unit to which this happens can no longer be successfully closed and therefore, no new processing unit can be started.

However, you can set the current processing unit back to an initialized status by using a rollback work (for example, statement ROLLBACK WORK, the BAPI "BAPI_TRANSACTION_ROLLBACK" or the method BapiService.TransactionRollback). Technically speaking, this means that the previous LUW is terminated and a new

LUW is started in the current processing unit.

Note that in this case, the current processing unit does not have to be re-initialized.

Also note that the rollback also takes place according to the "all-or-nothing" principle, that therefore **all** individual BAPIs carried out up to the rollback are discarded. After a rollback, you can, therefore, no longer refer to an object that was previously created in the current processing unit using a CREATE-BAPI.

However, you can close the processing unit again after a rollback, using a PRECOMMIT and COMMIT WORK, as long as all individual BAPIs, and the precommit carried out after the rollback, finish without errors.

You can carry out several rollbacks in a processing unit (technically: start a new LUW several times).

5. Procedure in the Case of Errors

As soon as an error occurs in an individual BAPI or in the BAPI "BAPI_PS_PRECOMMIT", you have the following options:

- Exit the report or the program that calls the BAPIs, the PRECOMMIT and the COMMIT WORK.
- Execute a rollback in the current processing unit.

6. Rules for Posting

After you have successfully called the individual BAPIs of a processing unit, you must call the PRECOMMIT "BAPI_PS_PRECOMMIT".

If the PRECOMMIT is also successful, the COMMIT WORK must take place directly afterwards.

In particular, note that after the PRECOMMIT, you cannot call other individual BAPIs again in the current processing unit.

It is also not permitted to call the PRECOMMIT more than once in a processing unit.

7. Recommendation "COMMIT WORK AND WAIT"

If an object created in a processing unit is to be used in a subsequent processing unit (for example, as an account assignment object in a G/L account posting) it is recommended to call the commit work with the supplement "AND WAIT" or to set the parameters for the BAPI "BAPI_TRANSACTION_COMMIT" accordingly.

8. Field Selection

The field selection is a tool for influencing the user interface (that is, for the dialog). In the BAPIs, the settings from the field selection (for example, fields that are not ready for input or required-entry) are not taken into account.

9. Using a date in the BAPI interface

The BAPI must be provided with the date in the internal format YYYYMMDD (year month day). No special characters

may be used.

As a BAPI must work independent of user, the date cannot and should not be converted to the date format specified in the user-specific settings.

10. Customer Enhancements of the BAPIs

For the BAPIs used to create and change project definitions, WBS elements, networks, activities, and activity elements, you can automatically fill the fields of the tables PROJ, PRPS, AUFK, and AFVU that have been defined for customer enhancements in the standard system.

For this purpose, help structures that contain the respective key fields, as well as the CI include of the table are supplied. The BAPIs contain the parameter ExtensionIN in which the enhancement fields can be entered and also provide BAdIs in which the entered values can be checked and, if required, processed further.

CI Include Help Structure Key

CI PROJ BAPI TE PROJECT DEFINITION PROJECT DEFINITION

CI_PRPS BAPI_TE_WBS_ELEMENT WBS_ELEMENT

CI_AUFK BAPI_TE_NETWORK NETWORK

CI AFVU BAPI TE NETWORK ACTIVITY NETWORK ACTIVITY

CI_AFVU BAPI_TE_NETWORK_ACT_ELEMENT NETWORK ACTIVITY ELEMENT

Procedure for Filling Standard Enhancements

Before you call the BAPI for each object that is to be created or changed, for which you want to enter customerspecific table enhancement fields, add a data record to the container **ExtensionIn**:

- STRUCTURE: Name of the corresponding help structure
- VALUEPART1: Key of the object + start of the data part
- VALUEPART2-4: If required, the continuation of the data part

VALUPART1 to VALUPART4 are therefore filled consecutively, first with the keys that identify the table rows and then with the values of the customer-specific fields. By structuring the container in this way, it is possible to transfer its content with one MOVE command to the structure of the BAPI table extension.

Note that when objects are changed, **all** fields of the enhancements are overwritten (as opposed to the standard fields, where only those fields for which the respective update indicator is set are changed). Therefore, even if you only want to change one field, all the fields that you transfer in ExtensionIn must be filled.

Checks and Further Processing

Using the methods ...CREATE_EXIT1 or. ...CHANGE_EXIT1 of the BAdI BAPIEXT_BUS2001, BAPIEXT_BUS2002, and BAPIEXT_BUS2054, you can check the entered values (and/or carry out other checks).

In the BAdI's second method, you can program that the data transferred to the BAPI is processed further (if you only want to transfer the fields of the CI includes, **no** more action is required here).

For more information, refer to the SAP Library under Cross-Application Components -> Business Framework Architecture -> Enhancements, Modifications ... -> Customer Enhancement and Modification of BAPIs -> Customer Enhancement of BAPIs (CA-BFA).

Parameters

I_NUMBER
IT_ACT_ELEMENT
IT_UPDATE_ACT_ELEMENT
ET_RETURN
EXTENSIONIN
EXTENSIONOUT

Exceptions

Function Group

CN2002_ACT