
Installation OKD 4.7.x

okd:

- https://www.okd.io/
- Installation ist beispielhaft für 8 Nodes
 - o 1 x Infra
 - o 1 x Bootstrap
 - o 3 x Master
 - o 3 x Worker
- Anzahl der Master/Worker kann individuell angepasst werden

Architektur für UPI / OKD



Dokumentation

Releaseinfo:

- https://origin-release.apps.ci.l2s4.p1.openshiftapps.com/

Installation:

- https://docs.okd.io/latest/installing/installing_bare_metal/installing-bare-metal.html

Requirements:

- https://docs.okd.io/latest/installing/installing-bare-metal/installing-bare-metal/

Network Infrastruktur:

- https://docs.okd.io/latest/installing/installing-bare-metal/installing-bare-metal/ metal.html#installation-network-user-infra installing-bare-metal

Virtualisierung

Virtualbox 6.1.x:

- https://www.virtualbox.org/wiki/Downloads

Nodes

Hostname / FQDN	uname -a	CPU/MEM	Nutzung
infra / okd-infra.hs.local	CentOS 7.8	2/8	Administration
			DNS
			DHCP
			Firewall
			HaProxy
okd-m1 / okd-m1.lab.hs.local		4/16	okd-Master
okd-m2 / okd-m2.lab.hs.local	CoreOS Fedora release 33		
okd-m3 / okd-m3.lab.hs.local			
okd-n1 / okd-n1.lab.hs.local		2/8	okd-Worker
okd-n2 / okd-n2.lab.hs.local	CoreOS Fedora release 33		
okd-n3 / okd-n3.lab.hs.local			
okd-bootstrap / okd-bootstrap.lab.hs.local	CoreOS Fedora release 33	4/16	okd-Bootstrapper

Download

Stable Fedora CoreOS für PXE der Master/Worker/Bootstrapper

- https://getfedora.org/en/coreos?stream=stable

CentOS 7.x/8.x für das Infrastruktursystem

- https://www.centos.org/download/

Installtools OKD:

- https://github.com/openshift/okd/releases

Setup Infrastruktur-Node

ToDo's:

- Centos 7/8 VM als Infrastruktursystem
 - o 2 Netzwerke
 - **1**92.168.56.0/24
 - Public mit Zugang zum Internet
- -> Virtualbox HostOnly/Private
- -> Bridged
- Setup Firewalld/IP-Masquerading
- Setup Apache
- o Setup DHCP
 - Konfig im Anhang
 - Korring IIII 7 II II II II
- Setup DNS
 - Konfig im Anhang
- Setup HAProxy
 - Konfig im Anhang
- o Setup NFS
 - Konfig im Anhang
- Setup PXE/TFTP
 - Konfig im Anhang
- Setup chrony

- -> für Installation FCOS
- -> für Installation FCOS
- -> für OKD4/OpenShift
- -> für das LB zu den API-Endpoints
- -> für PV's etc.
- -> für Installation FCOS

• Installationvorbereitung

Im Weiteren als root@CentOS 7 (ginge auch als jeder andere User via sudo usw.)

Konfig-Files für dhcp/haproxy usw. sind exemplarisch im Git Repo enthalten

```
# mkdir -p /data/okd4
# cd /data/okd4
# git clone https://github.com/git67/okd4.git ./local
```

Setup Firewall/IP-Forwarding/Masquerading:

- Kann ggf. feiner granuliert werden
 - o Further use ...
- enp0s3 -> 192.168.56.0/24
- enp0s8 -> www

```
# sysctl -w net.ipv4.ip forward=1
# nmcli c mod enp0s3 connection.zone internal
# nmcli c mod enp0s8 connection.zone external
 firewall-cmd --get-active-zone
 firewall-cmd --zone=external --add-masquerade --permanent
 firewall-cmd --zone=external --query-masquerade
 firewall-cmd --reload
 firewall-cmd --permanent --direct --add-rule ipv4 nat POSTROUTING 0 -o enp0s8 -j MASQUERADE
 firewall-cmd --permanent --direct --add-rule ipv4 filter FORWARD 0 \
  -i enp0s3 -o enp0s8 -j ACCEPT
 firewall-cmd --permanent --direct --add-rule ipv4 filter FORWARD 0 \
  -i enp0s8 -o enp0s3 -m state --state RELATED, ESTABLISHED -j ACCEPT
 firewall-cmd --reload
 firewall-cmd --add-service http --permanent --zone=internal
 firewall-cmd --add-service https --permanent --zone=internal
 firewall-cmd --add-service ssh --permanent --zone=internal
 firewall-cmd --add-service dns --permanent --zone=internal
 firewall-cmd --add-service dhcp --permanent --zone=internal firewall-cmd --add-service tftp --permanent --zone=internal
 firewall-cmd --permanent --zone=public --add-service mountd
 firewall-cmd --permanent --zone=public --add-service rpc-bind
 firewall-cmd --permanent --zone=public --add-service nfs
 firewall-cmd --add-port 8080/tcp --permanent --zone=internal firewall-cmd --add-port 6443/tcp --permanent --zone=internal
 firewall-cmd --add-port 9000/tcp --permanent --zone=internal firewall-cmd --add-port 22623/tcp --permanent --zone=internal
  firewall-cmd --add-port 9000-9999/tcp --permanent --zone=internal
 firewall-cmd --add-port 10250-10259/tcp --permanent --zone=internal
 firewall-cmd --add-port 4789/udp --permanent --zone=internal
 firewall-cmd --add-port 6081/udp --permanent --zone=internal
 firewall-cmd --add-port 9000-9999/udp --permanent --zone=internal
 firewall-cmd --add-port 30000-32767/tcp --permanent --zone=internal
 firewall-cmd --add-port 30000-32767/udp --permanent --zone=internal
 firewall-cmd --add-port 2379-2380/tcp --permanent --zone=internal
 firewall-cmd --add-port 443/tcp --permanent --zone=internal
 firewall-cmd --permanent --zone=internal --add-service mountd firewall-cmd --permanent --zone=internal --add-service rpc-bind
# firewall-cmd --permanent --zone=internal --add-service nfs
# firewall-cmd --add-service http --permanent --zone=external
 firewall-cmd --add-service https --permanent --zone=external
 firewall-cmd --add-service ssh --permanent --zone=external
 firewall-cmd --add-service dns --permanent --zone=external
 firewall-cmd --add-service dhcp --permanent --zone=external
 firewall-cmd --add-port 8080/tcp --permanent --zone=external
 firewall-cmd --add-port 6443/tcp --permanent --zone=external
 firewall-cmd --add-port 9000/tcp --permanent --zone=external
 firewall-cmd --add-port 22623/tcp --permanent --zone=external
 firewall-cmd --add-port 9000-9999/tcp --permanent --zone=external
 firewall-cmd --add-port 10250-10259/tcp --permanent --zone=external
 firewall-cmd --add-port 443/tcp --permanent --zone=external
 firewall-cmd --add-port 4789/udp --permanent --zone=external
 firewall-cmd --add-port 6081/udp --permanent --zone=external
  firewall-cmd --add-port 9000-9999/udp --permanent --zone=external
 firewall-cmd --add-port 30000-32767/tcp --permanent --zone=external
  firewall-cmd --add-port 30000-32767/udp --permanent --zone=external
 firewall-cmd --add-port 2379-2380/tcp --permanent --zone=external
```

```
# firewall-cmd --reload
# firewall-cmd --list-all --zone=internal
# firewall-cmd --list-all --zone=external
# firewall-cmd --direct --get-all-rules
```

Setup Apache:

```
# yum install httpd -y

# sudo sed -i 's/Listen 80/Listen 8080/' /etc/httpd/conf/httpd.conf

# mkdir -p /var/www/html/okd4/
# chown -R apache: /var/www/html/
# chmod -R 755 /var/www/html/
# setsebool -P httpd_read_user_content 1

# systemctl enable httpd
# systemctl start --now httpd
```

Setup DNS:

- IP/Domain anpassen falls gewünscht
 - o Achtung, taucht auch in der OpenShift Installations Konfig auf!!
 - install-config.yaml

```
# yum install bind bind-utils -y
# vi /etc/named.conf (siehe Anhang)
...
# vi /var/named/hs.local.db (siehe Anhang)
...
# vi /var/named/192.168.56 (siehe Anhang)
...
# vi /etc/resolv.conf
...
# systemctl enable named
# systemctl start --now named
```

Setup DHCP:


- MAC-Adressen usw. anpassen ...
- Falls DNS angepasst worden ist, hier auch nacharbeiten ...

```
# yum install dhcp -y

# vi /etc/dhcp/dhcpd.conf (siehe Anhang)
...

# systemctl enable dhcpd
# systemctl start --now dhcpd
```

Setup HAProxy:



- Falls DNS angepasst worden ist, hier auch nacharbeiten ...

```
# yum install haproxy -y

# vi /etc/haproxy/haproxy.cfg (siehe Anhang)
...

# setsebool -P haproxy_connect_any 1
# systemctl enable haproxy
# systemctl start --now haproxy
```

Setup NFS-Server:

- /nfs/data
 - OpenShift erwartet für das Registry-PV 100GB, das wird nicht(!) überprüft, also ginge auch weniger

```
# yum install -y nfs-utils
# systemctl enable nfs-server rpcbind

# mkdir -p /nfs/datal/vol /nfs/datal/registry
# chmod -R 777 /nfs
# chown -R nobody:nobody /nfs

# vi /etc/exports
/nfs/datal/vol
192.168.56.0/24(rw,sync,no_root_squash,no_all_squash,no_wdelay)
/nfs/datal/registry
192.168.56.0/24(rw,sync,no_root_squash,no_all_squash,no_wdelay)

# setsebool -P nfs_export_all_rw 1
# systemctl start --now nfs-server rpcbind
```

Setup TFTP/PXE:

```
# yum install -y syslinux tftp-server

# mkdir /var/lib/tftpboot/pxelinux.cfg /var/lib/tftpboot/okd4

# setsebool -P tftp_anon_write 1

# systemctl enable tftp
# systemctl start --now tftp
```

Setup chrony:

- Standard ...

Vorbereitung der Installation:

- Falls noch nicht passiert ...

```
# mkdir -p /data/okd4
# cd /data/okd4
# git clone https://github.com/git67/okd4.git ./local
# cd ./local
```

Installations-Konfig:

- https://docs.okd.io/latest/installing/installing-bare-metal/installing-bare-metal/installing-bare-metal/
- Benötigt:
 - o Public SSH-Key für die Nodes
 - ~/.ssh/id_rsa.pub (z.b.)
 - o Pull Secret
 - https://cloud.redhat.com/openshift/install/pull-secret
 - Oder der "Fake"
 - {"auths":{"fake":{"auth": "bar"}}}

```
# cd /data/okd4/local
# cp install-config.yaml2edit install-config.yaml
# vi install-config.yaml
apiVersion: v1
baseDomain: hs.local
metadata:
 name: lab
compute:
- hyperthreading: Enabled
 name: worker
  replicas: 0
controlPlane:
 hyperthreading: Enabled
  name: master
 replicas: 3
networking:
 clusterNetwork:
  - cidr: 10.128.0.0/14
   hostPrefix: 23
  networkType: OVNKubernetes
  serviceNetwork:
  - 172.30.0.0/16
platform:
 none: {}
fips: false
pullSecret: 'HIER das PULL Secret eintragen'
sshKey: 'HIER den PUBLIC SSH-Key eintragen'
```

Download und Installation OpenShift-Installer/-Client und Download und Vorbereitung FCOS:

- Download und Installation OpenShift-Installer/-Client
- Download und Vorbereitung FCOS
- Erstellung Installations-Manifests
- Anpassung Konfig, das App-Pods nicht auf die Master deployed werden
- Erstellung Ignition-Files
- Sicherung intiale Auth's
 - Initiales Passwort kubeadmin
 - Initiales CA
 - export KUBECONFIG=/data/okd4/install/auth/kubeconfig
- Vorbereitung Webserver für FCOS-Installation:

```
# cd /data/okd4/local
# ./mk_inst.sh
```

Vorbereitung FCOS-Installation:

- 7 Files
 - o 1 Bootstrap
 - o 3 Master
 - o 3 Worker
- Pro Node 1 File
 - Siehe Files in /data/okd4/local
 - 01-bootstrap
 - 01-master
 - 01-worker
 - o 01-<mac adresse dash separiert>
 - Z.b. 01-08-00-27-0e-8b-0d
- Pro Node jeweils das "richtige" Ignition File" eintragen
 - Bootstrap -> bootstrap.ign
 - Master -> master.ign
 - Worker -> worker.ign
- Im Folgenden ein Beispiel für den Bootstrap-Node

```
# cd /var/lib/tftpboot/pxelinux.cfg/

# vi 01-<mac bootstrap>
default menu.c32
prompt 0
timeout 50
menu title **** OpenShift 4 Bootstrap PXE Boot Menu ****

label Install CoreOS 4.5.4 Bootstrap Node
    kernel /okd4/fcos-kernel
    append ip=dhcp rd.neednet=1 coreos.inst.install_dev=sda coreos.inst=yes
    coreos.inst.image_url=http://192.168.56.30:8080/okd4/fcos.raw.xz
    coreos.inst.ignition_url=http://192.168.56.30:8080/okd4/bootstrap.ign
    initrd=/okd4/fcos-initramfs,/okd4/fcos-live-rootfs

# vi ...
```

Setup OKD

Virtualbox:

- Einschalten Bootstrap-Node
 - o F12
 - Netzwerkboot
- System installiert automatisch und startet neu



Installation tracken:

```
# cd /data/okd4

# openshift-install --dir=install/ wait-for bootstrap-complete --log-level=debug
```

Warten bis Setup des Bootstrap-Node abschlossen ist:

```
DEBUG OpenShift Installer 4.7.0-0.okd-2021-02-25-144700
DEBUG Built from commit a005bb9eddcbc97e4cac2cdf4436fe2d524cc75e
INFO Waiting up to 20m0s for the Kubernetes API at
https://api.lab.hs.local:6443...
INFO API v1.20.0-1046+5fbfd197c16d3c-dirty up
INFO Waiting up to 30m0s for bootstrapping to complete...

DEBUG OpenShift Installer 4.7.0-0.okd-2021-02-25-144700
DEBUG Built from commit a005bb9eddcbc97e4cac2cdf4436fe2d524cc75e
INFO Waiting up to 20m0s for the Kubernetes API at
https://api.lab.hs.local:6443...
INFO API v1.20.0-1046+5fbfd197c16d3c-dirty up
...
```

Jetzt die restlichen Nodes (Master/Worker) via Netboot anstarten

Warten bis Setup des Bootstrap-Node abschlossen ist:

```
...
INFO Waiting up to 30m0s for bootstrapping to complete...

DEBUG Bootstrap status: complete

INFO It is now safe to remove the bootstrap resources
INFO Time elapsed: 0s
...
```

Jetzt den Bootstrap-Node in /etc/haproxy auskommentieren:

```
# sed '/ okd-bootstrap /s/^/#/' /etc/haproxy/haproxy.cfg
#systemctl reload haproxy
```

Erster Login:

```
# export KUBECONFIG=/data/okd4/local/auth/kubeconfig
# oc get nodes
```

CSR's freigeben:

```
# oc get csr -ojson | jq -r '.items[] | select(.status == {} ) |
.metadata.name' | xargs oc adm certificate approve
# oc get nodes
```

Weitere Schritte:

- Authentifications Provider (htpasswd, ldap, ...) einrichten
 - User anlegen
- Project Templates anlegen
 - o Quotas etc.
- PV für Registry anlegen
 - o Siehe NFS-Server ...

/etc/dhcp/dhcpd.conf:

```
ddns-update-style none;
default-lease-time 600;
max-lease-time 7200;
deny unknown-clients;
option domain-search "hs.local, lab.hs.local"; option domain-name-servers 192.168.56.30;
 authorative;
log-facility local7;
subnet 192.168.56.0 netmask 255.255.255.0 {
    option subnet-mask 255.255.255.0;
    option domain-search "hs.local lab.hs.local";
    option domain-name-servers 192.168.56.30;
    option routers 192.168.56.30;
    get-lease-hostnames true;
    use-host-decl_names true;
         yet lease institutes true;
use-host-decl-names true;
default-lease-time 600;
max-lease-time 7200;
filename "pxelinux.0";
next-server 192.168.56.30;
  host okd-bootstrap {
  option host-name "okd-bootstrap.lab.hs.local";
  fixed-address 192.168.56.64;
  hardware ethernet 08:00:27:36:5B:BE;
  host okd-m1 {
  option host-name "okd-m1.lab.hs.local";
  fixed-address 192.168.56.51;
  hardware ethernet 08:00:27;BE:3D:8B;
  host okd-m2 {
          option host-name "okd-m2.lab.hs.local";
fixed-address 192.168.56.52;
hardware ethernet 08:00:27:C4:91:C6;
  host okd-m3 {
   option host-name "okd-m3.lab.hs.local";
          fixed-address 192.168.56.53;
hardware ethernet 08:00:27:0E:8B:0D;
  host okd-n1 {
          option host-name "okd-n1.lab.hs.local";
fixed-address 192.168.56.61;
hardware ethernet 08:00:27:B8:3B:48;
          option host-name "okd-n2.lab.hs.local";
          fixed-address 192.168.56.62;
hardware ethernet 08:00:27:D0:C9:B3;
          option host-name "okd-n3.lab.hs.local"; fixed-address 192.168.56.63;
          hardware ethernet 08:00:27:FB:0F:54;
```

/etc/named.conf:

```
// named.conf
 //
///
// Provided by Red Hat bind package to configure the ISC BIND named(8) DNS
// server as a caching only nameserver (as a localhost DNS resolver only).
//
// See /usr/share/doc/bind*/sample/ for example named configuration files.
//
// See the BIND Administrator's Reference Manual (ARM) for details about the
 // configuration located in /usr/share/doc/bind-{version}/Bv9ARM.html
- If you are building an AUTHORITATIVE DNS server, do NOT enable recursion. - If you are building a RECURSIVE (caching) DNS server, you need to enable
                recursion.
             recursion.

If your recursive DNS server has a public IP address, you MUST enable access control to limit queries to your legitimate users. Failing to do so will cause your server to become part of large scale DNS amplification attacks. Implementing BCP38 within your network would greatly
                reduce such attack surface
            recursion yes;
            dnssec-enable yes;
            dnssec-validation yes;
            /* Path to ISC DLV key */
bindkeys-file "/etc/named.root.key";
            managed-keys-directory "/var/named/dynamic";
            pid-file "/run/named/named.pid";
session-keyfile "/run/named/session.key";
       forwarders {
            8.8.8.8;
8.8.4.4;
 };
 logging {
            channel default_debug {
    file "data/named.run";
                       severity dynamic;
 };
 zone "." IN {
            type hint;
file "named.ca";
 };
zone "hs.local" IN {
             file "/var/named/hs.local.db";
             allow-update { none; };
 };
 zone "56.168.192.in-addr.arpa" IN {
              type master;
              file "/var/named/192.168.56.db";
              allow-update { none; };
 include "/etc/named.rfc1912.zones";
include "/etc/named.root.key";;
```

/var/named/hs.local.db:

```
okd-infra.hs.local. admin.hs.local. (
                   IN SOA
                                                        ; Serial
; Refresh
                              604800
                           86400
241964
                                                        ; Retry
                                                   , Metry
; Expire
                                                      ; Negative Cache TTL
                              604800
; name servers - NS records
IN NS okd-infra
     name servers - A records
                                                                IN
                                                                                   A
                                                                                                   192.168.56.30
okd-infra.hs.local.
; OpenShift Container Platform Cluster - A records okd-bootstrap.lab.hs.local. IN A 192.168.56.51 okd-ml.lab.hs.local. IN A 192.168.56.55 okd-m3.lab.hs.local. IN A 192.168.56.55 okd-m3.lab.hs.local. IN A 192.168.56.55 okd-m1.lab.hs.local. IN A 192.168.56.65 okd-n1.lab.hs.local. IN A 192.168.56.62 okd-n3.lab.hs.local. IN A 192.168.56.62 okd-n3.lab.hs.local. IN A 192.168.56.63
                                                                                                                  192.168.56.64
                                                                                                 192.168.56.52
192.168.56.53
; OpenShift internal cluster IPs - A records api.lab.hs.local. IN A 192.168.56.30 api-int.lab.hs.local. IN A 192.168.56.30 *.apps.lab.hs.local. IN A 192.168.56.30 etcd-0.lab.hs.local. IN A 192.168.56.61 etcd-1.lab.hs.local. IN A 192.168.56.62 etcd-2.lab.hs.local. IN A 192.168.56.63
etca-2.1ab.ns.10ca1. IN A 192.console-openshift-console.apps.lab.hs.local. IN A 192.coauth-openshift.apps.lab.hs.local. IN A 192.168.56.30
                                                                                                                                              192.168.56.30
 ; OpenShift internal cluster IPs - SRV records
 _etcd-server-ssl._tcp.lab.hs.local.
_etcd-server-ssl._tcp.lab.hs.local.
_etcd-server-ssl._tcp.lab.hs.local.
                                                                                                                                                                                             etcd-0.lab
                                                                                                                                                                          2380
                                                                                                                 IN
                                                                                                                               SRV
                                                                                                                                                                                             etcd-1.lab
                                                                                                                               SRV
```

/var/named/192.168.56.db:

```
IN
                    SOA
                               okd-infra.hs.local. admin.hs.local. (
                               ; Serial
; Refresh
                6
604800
               86400
2419200
                               ; Retry
                               ; Expire
                 604800
                              ; Negative Cache TTL
; name servers - NS records
IN NS okd-inf
                       okd-infra.hs.local.
; name servers - PTR records
              PTR
                       okd-infra.hs.local.
; OpenShift Container Platform Cluster - PTR records
64
51
      IN
IN
               PTR okd-bootstrap.lab.hs.local.
PTR okd-m1.lab.hs.local.
               PTR
PTR
                        okd-m2.lab.hs.local.okd-m3.lab.hs.local.
52
        IN
                        okd-n1.lab.hs.local.
okd-n2.lab.hs.local.
61
        IN
               PTR
               PTR
PTR
63
        IN
                        okd-n3.lab.hs.local.
30
                     api.lab.hs.local.
api-int.lab.hs.local.
console-openshift-console.apps.lab.hs.local.
30
```

/etc/haproxy/haproxy.cfg:

```
# Global settings
global
                    20000
    maxconn
     log
chroot
                    /dev/log local0 info
/var/lib/haproxy
     pidfile
                    /var/run/haproxy.pid
     aroup
                   haproxy
     # turn on stats unix socket
stats socket /var/lib/haproxy/stats
# common defaults that all the 'listen' and 'backend' sections will
# use if not designated in their block
#-----
defaults
     mode
                                   global
     log
                                   httplog
                                   dontlognull
     option
     option http-server-close option forwardfor
                                except 127.0.0.0/8
     option
retries
                                   redispatch
     timeout http-request
                                   10s
     timeout queue
timeout connect
                                   1m
10s
     timeout client
timeout server
                                   300s
     timeout http-keep-alive 10s
timeout check 10s
                                   20000
     maxconn
listen stats
    bind :9000
     mode http
stats enable
     stats uri /
frontend okd4_k8s_api_fe
    bind :6443
     default backend okd4 k8s api be
    option tcplog
backend okd4 k8s api be
     balance source mode tcp
                    okd-bootstrap.lab.hs.local 192.168.56.64:6443 check
     server
                   okd-m1.lab.hs.local 192.168.56.51:6443 check okd-m2.lab.hs.local 192.168.56.52:6443 check
     server
                    okd-m3.lab.hs.local 192.168.56.53:6443 check
frontend okd4 machine config server fe
     bind :22623
     default_backend okd4_machine_config_server_be
     option tcplog
backend okd4_machine_config_server_be
     balance source
     mode tcp
     server
server
                   okd-bootstrap.lab.hs.local 192.168.56.64:22623 check
                   okd-m1.lab.hs.local 192.168.56.51:22623 check okd-m2.lab.hs.local 192.168.56.52:22623 check
     server
     server
                   okd-m3.lab.hs.local 192.168.56.53:22623 check
frontend\ okd4\_http\_ingress\_traffic\_fe
    bind:80

default_backend okd4_http_ingress_traffic_be
    mode tcp
option tcplog
backend okd4_http_ingress_traffic_be
    balance source
     mode tcp
                    okd-n1.lab.hs.local 192.168.56.61:80 check
     server
                   okd-n2.lab.hs.local 192.168.56.62:80 check okd-n3.lab.hs.local 192.168.56.63:80 check
     server
frontend okd4_https_ingress_traffic_fe
    bind *:443
     default_backend okd4_https_ingress_traffic_be
     mode tcp
     option tcplog
{\tt backend\ okd4\_https\_ingress\_traffic\_be}
     balance source
     mode tcp
                   okd-n1.lab.hs.local 192.168.56.61:443 check
okd-n2.lab.hs.local 192.168.56.62:443 check
okd-n3.lab.hs.local 192.168.56.63:443 check
     server
     server
```