CMP320 Operating Systems

Non-Contiguous Memory Allocation

Muhammad Adeel Nisar

Note: Slides Courtesy

- Dr Mansoor Sarwar
- Mr Arif Butt
- Silberschatz, Galvin, and Gagne

Today's Agenda

- · Review of Previous Lecture
- Introduction to Paging
 - Address Translation in Paging
 - Implementation of Page Table
 - In CPU Registers
 - In Associative Memory
 - In main memory
 - Structure of Page Table
 - · Hierarchical
 - Inverted
 - Hashed
- Introduction to Segmentation
- Introduction to Paged Segmentation
- Intel 80386 Address Translation




INTRODUCTION TO PAGING

- Paging is like reading a book. At any time we do not need all pages except ones
 we are reading. The analogy suggest that pages we are reading are in the main
 memory and the rest can be in the secondary memory
- Logical/Virtual address space is the set of addresses that programs use for load and store operations on disk. Logical address space is divided into pages
- Physical address space is the set of addresses used to reference locations in the main memory. Physical address space is divided into frames
- Pages and frames must be of same size
- Typical page sizes range from 1KB to 64 KB. (different for different architectures)
- Pages that have been loaded into the main memory form disk are said to have been mapped into the main memory
- A program / process is loaded by loading its pages into available not necessarily contiguous frames
- To run a program having n pages, find n free frames and load the pages into these frames. These frames need not to be contiguous. For example a program comprising of 10 pages need 10 free frames in main memory, which need not to be contiguous. For this to work, we need to store the mapping information of which page is loaded in which frame, in some data structure called "Page Table"
- No external fragmentation. Internal Fragmentation in paging is half a page per process

PAGE TABLES

- Page Tables are used to keep track of how logical addresses map to physical addresses. Page table entries generally contain the frame number where the particular page is loaded, a valid bit and a dirty bit
- Page table size depends on the maximum number of pages of a process that a CPU support. E.g. if a system support a process of maximum 8 pages then the page table will contain 8 rows (length is debatable). So the address of page table will consist of 3 bits
- Dirty bit records whether or not the page has been written since it was brought into the main memory
- Valid bit describes whether this particular page is loaded into memory or not



111

USE OF PAGE TABLES


page 0

page 1

page 2

page 3

logical memory



physical memory

page 3

7

page 0

page 2

page 1

LOGICAL & PHYSICAL ADDRESS FORMAT IN PAGING

Logical Address format (p, d)


- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory.
 - Page offset (d) combined with base address of frame to define the physical memory address that is sent to the memory unit.

Physical Address format (f, d)

- Physical address translated from the L.A is divided into:
 - Frame number (f) kept in the page table against the page number.
 - Frame offset (d) is the same as the page offset


ADDRESS TRANSLATION ARCHITECTURE IN PAGING

 Address translation means conversion of logical address into the equivalent physical address.



PAGING EXAMPLE

- Page size = 4 bytes
- Process address space = 4pages
- Physical address space = 8frames (p,d)
- Logical address: (1,3) = 0111
 (f,d)
- Physical address: (6,3) = 11011



SAMPLE PROBLEMS

Problem 12

- Consider a logical address space of 16 pages each of 1024 words (each word of 2 Bytes) mapped into a physical memory of 32 frames
- Give the Logical and Physical address format
- Also give the total Logical and Physical address space
- Compute the required page table size for this situation

Problem 13

A system has 48 bit L.A & a main memory of 64 GBs. Page size is 4096 bytes.
 Compute the number of pages and frames that exist in the system. Also give L.A & P.A format.

Problem 14

- Consider a system with
 - L.A = 32 bits; Page Size = 4 K; Main memory = 512 MB.
- Compute the total process address space and maximum number of pages in a process address space. Also give the logical and physical address format. Also give the page table size for this situation.

Problem 15

- Consider a LA space of 8 pages of 1024 words mapped into memory of 32 frames.
 - How many bits are there in the LA?
 - How many bits are there in PA?

SAMPLE PROBLEMS

Problem 16

- For each of the following logical addresses (given in decimal), compute the page number and offset within the page; if the page size is 4 KB
 - _ 20000
 - 32768
 - 60000
- Repeat for an 8 KB page

Problem 17

• A machine has a 32 bit address space and an 8 KB page. The page table is entirely in hardware, with one 32 bit word per entry. When a process starts, the page table is copied to the hardware from memory, at one word every 100 nsec. If each process runs for 100 msec (including the time to load the page table), what fraction of the CPU time is devoted to loading the page tables?

Problem 18

A machine has a 48 bit virtual addresses and 32 bit physical addresses.
 Pages are 8 KB. How many entries are needed for the page table?

PAGED ARCHITECTURES

<u>Paging Parameters in Intel P4</u>

- 32 bit linear address. (Intel used the term linear instead of logical)
- 4 K page size
- Maximum pages in a process address space = 2^{32} / 2^{12} = 1 M
- No of bits for **d** = 12
- No of bits for p = 32 12 = 20
- What about the physical address format? / What about no of bits for f?

Paging Parameters in PDP 11

- 16 bit Logical address.
- 8 K page size.
- Maximum pages in a process address space = 2^{16} / 2^{13} = 8
- No of bits for d = 13
- No of bits for p = 16 13 = 3
- What about the physical address format? / What about no of bits for f?

IMPLEMENTATION OF PAGE TABLE

IMPLEMENTATION OF PAGE TABLES

IN CPU REGISTERS

- Design CPU in such a way that page table can be kept / maintained within the CPU, using its registers. (costly affair)
- Feasible for small process address space with less number of pages which may be of large size
- Effective Memory Access Time (time to convert L.A to P.A) is almost the same as the Physical memory access time
- Example is PDP-11, which has eight pages each of size 8 KB

IN MAIN MEMORY

- Page table is kept in main memory
- Page-table base register (PTBR) points to the starting address of page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses.
 One for the page table (that resides inside the main memory) and one for the data / instruction.

$$T_{EFFECTIVE} = 2 T_{MEM}$$


IMPLEMENTATION OF PAGE TABLES (cont...)

IN ASSOCIATIVE CACHE / TLB

- Use a Cache / Translation Look Aside Buffer (TLB)
- Place references of some of the recently used pages in TLB, i.e. a
 portion of page table resides in TLB and the rest in main memory
- On a context switch, the TLB is flushed and loaded with values for the scheduled processes. (Normally TLB contains the page numbers of the currently running process)
- If mapping is found page hit else page fault

IMPLEMENTATION OF PAGE TABLE (cont...)

PAGING HARDWARE



IMPLEMENTATION OF PAGE TABLE (cont...)

Performance In Paging

Effective Memory Access Time (Page hit) = Time to access TLB + Time to access memory

Effective memory Access Time (Page Fault) = Time to access TLB + 2×1 Time to access memory

If HR is the hit ratio and MR is the miss ratio then

$$T_{EFFECTIVE} = HR (T_{TLB} + T_{MEM}) + MR (T_{TLB} + 2 T_{MEM})$$

IMPLEMENTATION OF PAGE TABLE (cont...)

Problem 19

Consider a system with memory access time of 100 nsec. Page table is implemented using
associative memory. The TLB access time is 20 ns. Hit ratio is 80%. Calculate the
Effective memory access time. Calculate the Effective memory access time if there is no
TLB, i.e. the entire page table is kept in memory.

Problem 20

Repeat above example with a hit ratio of 95% and compare

Problem 21

Consider a paging system with the page table stored in memory.

- a. If a memory reference takes 200 nanoseconds, how long does a paged memory reference take?
- b. If we add associative registers, and 75 percent of all page-table references are found in the associative registers, what is the effective memory reference time? (Assume that finding a page-table entry in the associative registers takes zero time, if the entry is there.)

Problem 22

- Consider a system with 80% hit ratio, 50 nsec time to search the associative registers,
 750 nsec time to access main memory. Find the time to access a page:
 - a. When the page number is found in associative memory
 - b. When the page number is not found in associative memory
 - c. Find the effective memory access time

STRUCTURE OF PAGE TABLE

STRUCTURE OF PAGE TABLE


- L.A space increases day by day due to the large size of processes, thus increasing the size of the Page Table
- Thus there is a dire need to structure Page Table in a better way especially in situation where the Page Table becomes larger in size than a single page size, i.e. a page table cannot be contained by a single page
- We can use following techniques for the structure of our page tables:
 - a. Multi level / Hierarchical Page Table
 - b. Hashed Page Table
 - c. Inverted Page Table

Multi level / Hierarchical Page Tables


- Consider a system with a logical address of 32 bits, and page size of 4K and each page entry of 4 Bytes
- Maximum pages in a process address space = 1M
- Page Table size = 4 M (because each entry in page table is of 4 Bytes).
 Since total no of pages are 2²⁰ i.e. 1MB, so there will be 2²⁰ rows/tupples /entries, each tupple of 4 Bytes. So page table size will be 4MB
- Since the system has a page size of 4K, therefore, the page table of 4M can't be accommodated in a single page of 4K. Thus we have to make pages of the page table
- We keep two page tables:
 - Outer page table / page directory (which keep track of the pages of the inner page table)
 - Inner Page Table which actually maps the frames
- No of pages in the outer page table = 4M/4K = 1K
- So size of outer page table = 1K entries of 4 bytes each = 4K
- This outer page table will now fit in one page

Multi level / Hierarchical Page Tables (cont...)

- A logical address (on 32-bit machine with 4K page size) is divided into:
 - a page number consisting of 20 bits.
 - a page offset consisting of 12 bits.
- Since the page table is paged, the page number is further divided into:
 - a 10-bit page number
 - a 10-bit page offset
- Thus, a logical address is as follows:




where p1 is an index into the outer page table, and p2 is the displacement within the page of the outer page table.



Two-Level Page Table Scheme


Outer page table is used to get hold of various pages inside the inner page table.



disk as needed.

Two-Level Page Table Scheme (cont...)

Address-translation scheme for a two-level 32-bit paging architecture



Since address translation works from the outer page table inwards, this scheme is also known as forward mapped page table. Pentium II uses this architecture

Multi level / Hierarchical Page Tables (cont...)


- Some other examples are:
 - 32 bit Sun SPARC support 3 Level Paging
 - 32 bit Motorola 68030 support 4 Level Paging
 - 64 bit Sun Ultra SPARC support 7 Level Paging
- Since each level is stored as a separate table in memory, converting a logical address to a physical one may take more than three memory accesses
- As the no of levels increases, too many memory references needed for address translation
- But at times this is required to support large process
 address space, so that larger processes can be executed in
 larger applications

Inverted Page Tables

- A Page Table has one entry for each Page in the Logical Address space of process
- An Inverted Page Table has one entry for each Frame in the Physical Address space (Physical Memory)
- Entries of a Page Table contains Frame numbers
- Entries of a Inverted Page Table contains Page numbers and pid (information about the process that owns that page)
- Page Table is indexed with page number, p
- Inverted Page Table is indexed with Frame number, f
- Inverted Page Tables are used to reduce the size of page table
- Only one page table is required in the system. (All processes will have / share a single Inverted Page Table)
- Page table size is limited by the number of frames (i.e. the physical / main memory) and not Process Address Space
- Each entry in the Page Table contains pid and p#. There is a possibility that
 there are two processes executing at a time and each process has a page no 3.
 So to avoid this confusion we have to keep pid as well
- 64 bit Ultra SPARC and IBM Power PC uses this technique

Inverted Page Tables (cont...)


This scheme decreases the amount of memory needed to store each page table but increases the time needed to search the table. It is because inverted page table is sorted by Physical address, but looks up occur on Virtual address. So the whole table might need to be searched for a match.



Hashed Page Tables

- Another common approach to handle address spaces larger than 32 bits is Hashed Page Table
- Hashing. A key is given, you pass it through a function that returns an integer value known as hash value, which is used to index a table / array (hash value must be within that array) where the required record will be lying or may contain a pointer to the record (link list)
- Hash Function. A function used to manipulate the key of an element in a list to identify its location in the list

Hashed Page Tables (cont...)



- Hashing can be combined with Inverted Page Tables, to overcome its limitation of complex / time consuming search.
- For 64 bit address space Clustered Page Tables are used.

SAMPLE PROBLEMS

Problem 23

A computer with a 32 bit address uses a two level page table. Virtual addresses are split
into a 9 bit top level page table field, an 11 bit second level page table field and an offset.
How large are the pages and how many are there in the address space?

Problem 24

• Suppose that a 32 bit virtual address is broken up into four fields: a, b, c and d. The first three are used for a three level page table system. The fourth field, d, is the offset. Does the number of pages depend on the sizes of all four fields? If not, which ones matter and which ones do not?

Problem 25

- A computer has 32 bit logical addresses and 4 KB pages. How many entries are needed in the page table if traditional (one level) paging is used?
- How many page table entries are needed for two level paging, with 10 bits in each part?

Problem 27

• In a 64 bit machine, with 256 MB RAM and a 4 KB page size, how many entries will there be in the page table if it is inverted?

SHARED PAGES


Shared Code

- One copy of read-only (reentrant) code shared among processes e.g.
 text editors
- Shared code must appear in same location in the logical address space of all processes
- Multiple invocations of vi editor or gcc; when multiple users invoke vim the code part can be shared by multiple processes, while data can be private for each process

Private Code and Data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space


Shared Pages Example



INTRODUCTION TO SEGMENTATION

INTRODUCTION TO SEGMENTATION


- A segment is a set of logically related instructions or data elements associated with a given name
- A segment is a logical unit such as: Main program, procedure, function, local & global variables, stack, symbol table, arrays
- A program is a collection of segments. Each program is divided into a number of segments which can be of different lengths, however, there is a maximum segment length
- A program is loaded by loading all of its segments into dynamic partitions that need not to be contiguous
- Memory-management scheme that supports programmer's view of memory
- Private Code and Data
 - Each process keeps a separate copy of the code and data
 - The pages for the private code and data can appear anywhere in the logical address space



The user does not think of memory as a linear array of words. Rather the user prefers to view memory as a collection of variable sized segments, with no necessary ordering among segments.

1/23/2011

LOGICAL VIEW OF SEGMENTATION



- Physical memory space
- · In paging we store the pages in frames and keep the mapping in page table
- · In segmentation instead of pages we have segments that are kept in the frames and we keep the mapping in segmentation table
- · Unlike pages segments can be of variable size


SEGMENTATION ARCHITECTURE

- Logical address consists of a two tuple:
- <segment-number, offset>,
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;

Ensure that s < STLR. If yes then adds STBR to itand then index the Segment table.


Each segment table entry has:


- Base contains the starting physical address where the segment resides in memory.
- **Limit** specifies the length of the segment.



Base contains the

SEGMENTATION EXAMPLE





EXAMPLES

Problem 28

Consider the given segment table, What are the Physical addresses for the following logical addresses:

- (2,399)
- (4,0)
- (4,1000)
- (3,1300)
- (6,297)

Segment Table

	limit	base
0	1000	1400
1	400	6300
2	400	4300
3	1100	3200
4	1000	4700

Problem 29

Consider the given segment table, What are the Physical addresses for the following logical addresses:

•	0,43	0
	0,73	L

- 1,10
- · 2,500
- 3,400
- 4,112

<u>Seg</u>	<u>Base</u>	<u>Len</u>		
0	219	600		
1	2300	14		
2	90	100		
3	1327	580		
4	1952	96		

EXTERNAL FRAGMENTATION IN SEGMENATION

- External fragmentation exist in segmentation
- Holes can be adjusted by compaction, i.e. shuffle segments to place free memory together in one block
- Compaction is possible only if relocation is dynamic and is done at execution time
- So in segmentation we need run time address binding, i.e.
 dynamically a segment of process can be shifted to another
 location within the process address space within the main
 memory

PROTECTION IN SEGMENATION

- With each entry in segment table we associate specific bits for protection like we do in page table, i.e. valid bit, read-write, read only and execute bits.
- Protection information can be included in the segment table or segment register of the memory management hardware.
- Format of a typical segment descriptor is

Base address	Length	Protection
--------------	--------	------------

The protection field in a segment descriptor specifies the *Access Rights* to the particular segment


- Access Rights:

Full read and write privileges
Read only (write protection)
Execute only (program protection)
System only (O.S. Protection)

SHARING OF SEGMENTS


- Sharing can be implemented at segment level
- Segment table of multiple processes point to the same segment
- Consider two processes P1 and P2 each correspond to an editor
- In the main memory both will load the editor code at a single location and will share its code
- P1 and P2 will both have their private data/buffers as shown on next slide

SHARING OF SEGMENTS



	limit	base
О	25286	43062
1	4425	68348

segment table process P₁



limit base 0 25286 43062 1 8850 90003


segment table process P_2

INTRODUCTION TO PAGED SEGMENTATION

PAGED SEGMENTATION

- When the segments size become too large the larger is the External Fragmentation
- To prevent it, we page the segments (like we paged the Page Table)
- In paging, against every process we had a Page Table which used to map the pages of that particular process with the frames in the Physical memory where those pages were loaded
- Here every segment will be further divided into pages and their mapping information is kept in the Page Table
- So every segment will have a Page Table. This way there will be no External fragmentation

PAGED SEGMENTATION EXAMPLE




Here we have divided segment 4 into four pages and kept that information in page table.


PAGED SEGMENTATION EXAMPLE

- Logical address is still <s,d>, with s used to index the segment table
- Each segment table entry consist of the tupple <seg-length, pagetable-base>
- The logical address is legal if d < seg-length.
- Segment offset, d, is partitioned into two parts: p and d'
- p is used to index the page table associated with segment s
- d' is used as offset within a page.

p indexes the page table to retrieve frame, f, and physical address (f,d')



TRANSLATION (LA - PA) IN PAGED SEGMENTATION



SAMPLE PROBLEM

Problem

- Consider MULTICS on a GE 345 processor, with Logical Address of 34 bits and page size of 1 KB. s is of 18 bits and d is of 16 bits.
- What is the largest segment size?
- What is the maximum number of segments per process?
- Give maximum number of pages per segment.
- Give the LA format including the no of bits for p and d'

SAMPLE PROBLEM

Problem

- Consider a process in MULTICS with its segment # 15
 having 5096 bytes. The page size is 1 KB. The process
 generates a Logical Address of (15, 3921).
 - Is it a legal address? If yes why?
 - How many pages does the segment have?
 - What page does the logical address refer to, and what is its offset?
 - What is the P.A if page#3 (i.e. fourth page) is in frame 12?

REAL MODE AND PROTECTED MODE ADDRESSING

- Earlier PCs like i8086 having an address bus of 20 bits and support only 1
 MB of memory
- i80286 has an address bus of 24 bits and can support 16 MB of memory
- i80386 has an address bus of 32 bits and can support 4 GB of memory
- Higher PCs (PCs with address bus greater than 20 bits) can operate in two modes:

Real Mode

- Only first 1 MB of RAM can be accessed in Real Mode
- The Real Mode Address is a 20 bit address, stored and represented in the form of **segment:offset** (as a 20 bit addr can't be stored in memory). Give a 4 bit left shift to seg register and add offset in it to get 20 bits address

Protected Mode

- In Protected Mode whole of the RAM is accessible that includes the Conventional RAM (640 KB), System RAM (384 KB) and Extended memory (Memory higher than 1 MB)
- PCs initially boots up in Real Mode. It may be shifted to protected mode during the booting process using drivers like HIMEM.SYS.

REAL MODE ADDRESSING IN DOS

- DOS uses the conventional memory's first 640 KB for its memory management
- Additional 64 KB (expanded memory) can be utilized by installing EMM386.EXE
- Smallest allocatable unit in DOS is a paragraph, not a Byte(which is smallest addressable unit)

· Paragraph

- Whenever memory is to be allocated, DOS allocates memory in form of a paragraph
- Minimum difference between two segments can be 10(h) or 16(d). This sixteen Bytes makes a paragraph
- Address Translation from 16 bits LA to 20 bits PA is done as: Seg * 16 + offset

OS Data Structures for Memory Management

- MCB / Arena Header. Memory Control Block is used to control an allocated block in memory. Every allocated block will have a MCB before start of block. It is a 16 Byte large structure. It contains information like block is free or allocated, contains segment address of PSP, number of paragraphs controlled by MCB
- EB. Environment Block contains environment information like environment variables and the file paths for that program.
- PSP. Program Segment Prefix contains control information like Disk Transfer Area and command line parameters. It is situated before the start of a process. It is a 100 Byte structure.

PROTECTED MODE ADDRESSING IN WINDOWS


- Real Mode supports only contiguous allocation
- Protected mode support non-contiguous allocation
- i80286 and higher processors support non-contiguous allocation
- i80286 support segmentation in Protected Mode
- i80386 and higher processors also support paging
- We must give credit to Pentium designers, as they have designed
 it to support pure paging, pure segmentation and paged segments,
 while at the same time being compatible with the i80286
- The key to such non contiguous allocation systems is the Addressing Technique, that is supported only in Protected mode

LA TO PA TRANSLATION IN PROTECTED MODE

The heart of Pentium Virtual Memory consists of two tables: the LDT (Local Descriptor Table) and the GDT (Global Descriptor Table). Each program has its own LDT, but there is a single GDT, shared by all the programs on the computer. The LDT describes segments local to each program, including its code, data, stack, where as the GDT describes system segments

Selectors

- In protected mode the segment registers are used as selectors
- As the name suggest they are used to select descriptor entry from some descriptor table
- To access a segment, a Pentium program first loads a 16 bit selector for that segment into one of the machine's six segment registers
- During execution, the CS register holds the selector for the code segment and the DS register holds the selector for the data segment
 i. 13 bits selector index selects a



13 bits selector index selects a descriptor table entry out of 8K entries of LDT or GDT (each entry of 8 bytes, so a total of 64 KB) g = 0 means GDT, g = 1 means LDT.

ii. g = 0 means 601, g = 1 means 60 iii. p is 2bit privilege level with 00 as highest privilege

<u>LA TO PA TRANSLATION IN PROTECTED MODE</u>


Descriptor

- A descriptor describes a memory segment by storing attributes related to a memory segment. For every segment there is a descriptor
- Significant attributes of a memory segment can be its base address, its length and its access rights
- For address of 80286 we need 24 bit, while for 80386 we need 32 bits. But in both cases the descriptor size is 8 Bytes

Base 24 - 31	G D O	Limit 16 - 19	Р	DPL	S	Туре	Base 16 - 23
Base 0 - 15			Limit 0 - 15				

Intel 80386 ADDRESS TRANSLATION

- IBM OS/2, MS Windows, Linux are the most famous operating systems that run on i386
- It uses paged segmentation with two level paging and a TLB with 32 entries.
- I. A = 48 bits
- Page size = 4K. (each page table entry is of 4 Bytes)
- Each entry of TLB can refer to a page. So 32 entries of TLB can address to a memory of 32 X 4K = 128 K (which is also known as TLB reach)
- A bigger picture of V.A / L.A in Intel 80386 is given below:




Intel 80386 ADDRESS TRANSLATION (cont...)


- We have 48 bit Logical address, which in Intel literature is also called Virtual Address
- Linear Address Space = 232 Bytes (max size of a segment)
- Max Segment size = 4 GB
- Maximum number of segments per process = 16 K (13 bits selector and one bit for the selection of LDT or GDT)
- At any one time the Intel CPU can access six segments out of these because of six segment registers (CS, DS, SS, ES,)
- Selector is used to index a segment descriptor table to obtain an 8 byte segment descriptor entry. Base address and offset are added to get a 32 bit linear address, which is partitioned into p1, p2 and d for supporting two level paging.
 - p1 is used to index the page directory / outer page table (having 1K entries), which gives us the appropriate page table base address
 - p2 is used to index this selected inner page table (having 1K entries)
 from where we get the frame number of the page of the given L.A
 - This frame number is appended with d part of the Linear Address to get the Physical address

Intel 80386 ADDRESS TRANSLATION (cont...)


- Supports both segmentation and segmentation with paging
- CPU generates 48 bits Logical Address
 - Given to segmentation unit:
 - » Which produces 32 bits Linear Address
 - Linear address given to two level paging unit:
 - » Which generates Physical Address



Intel 80386 ADDRESS TRANSLATION (cont...)



We're done for now, but Todo's for you after this lecture...



- Go through the slides and Book Sections: 8.4 8.8
- Solve all the sample problems given in slides to understand the concepts discussed in class