

FUJITSU Software Enterprise Service Catalog Manager V17.10



VMware vSphere Integration

Trademarks

LINUX is a registered trademark of Linus Torvalds.

Open Service Catalog Manager is a registered trademark of FUJITSU LIMITED.

The OpenStack Word Mark and OpenStack logo are registered trademarks/service marks or trademarks/ service marks of the OpenStack Foundation in the United States and other countries.

Apache Tomcat, Tomcat, and Apache are trademarks of The Apache Software Foundation.

Java is a registered trademark of Oracle and/or its affiliates.

UNIX is a registered trademark of the Open Group in the United States and in other countries.

Other company names and product names are trademarks or registered trademarks of their respective owners.

Copyright FUJITSU ENABLING SOFTWARE TECHNOLOGY GMBH 2019 All rights reserved, including those of translation into other languages. No part of this manual may be reproduced in any form whatsoever without the written permission of FUJITSU ENABLING SOFTWARE TECHNOLOGY GMBH.

High Risk Activity

The Customer acknowledges and agrees that the Product is designed, developed and manufactured as contemplated for general use, including without limitation, general office use, personal use, household use, and ordinary industrial use, but is not designed, developed and manufactured as contemplated for use accompanying fatal risks or dangers that, unless extremely high safety is secured, could lead directly to death, personal injury, severe physical damage or other loss (hereinafter "High Safety Required Use"), including without limitation, nuclear reaction control in nuclear facility, aircraft flight control, air traffic control, mass transport control, medical life support system, missile launch control in weapon system. The Customer shall not use the Product without securing the sufficient safety required for the High Safety Required Use. In addition, FUJITSU (or other affiliate's name) shall not be liable against the Customer and/or any third party for any claims or damages arising in connection with the High Safety Required Use of the Product.

Export Restrictions

Exportation/release of this document may require necessary procedures in accordance with the regulations of your resident country and/or US export control laws.

Contents

	About this Manual	4
1	Introduction	7
1.1	Components Involved in the vSphere Integration	8
1.2	Usage Scenarios	8
2	Configuring the vSphere Integration Software	. 10
3	Creating and Publishing Services	. 12
3.1	Prerequisites and Preparation	12
3.2	Creating Technical Services	12
3.3	Creating and Publishing Marketable Services	13
4	Using vSphere Services in ESCM	.14
4.1	Subscribing to Services	14
4.2	Modifying Subscription Parameters	14
4.3	Executing Service Operations	15
4.4	Terminating Subscriptions	15
5	Administrating the vSphere Integration	. 16
5.1	Controlling the Provisioning Process	16
5.2	Handling Problems in the Provisioning Process	16
5.3	Updating Service Controller Settings in the Database	17
5.4	Changing the Responsible Organization	18
Appendix A	Controller Configuration Settings	.20
Appendix B	vSphere Configuration	. 22
B.1	Configuring Load Balancing	26
Appendix C	Service Parameters and Operations	. 28
Glossary		. 37

About this Manual

This manual describes the integration of VMware vSphere with) FUJITSU Software Enterprise Service Catalog Manager, hereafter referred to as ESCM.

This manual is structured as follows:

Chapter	Description
Introduction on page 7	Provides an overview of the ESCM vSphere integration, the components involved, and the supported usage scenarios.
Configuring the vSphere Integration Software on page 10	Describes how to configure the vSphere integration so that it matches your environment.
Creating and Publishing Services on page 12	Describes how to create and publish services for vSphere in ESCM.
Using vSphere Services in ESCM on page 14	Describes how to provision, modify, and deprovision virtual machines in vSphere through services in ESCM.
Administrating the vSphere Integration on page 16	Describes administration tasks related to the ESCM vSphere integration.
Controller Configuration Settings on page 20	Describes the configuration settings for the vSphere integration software.
vSphere Configuration on page 22	Describes the configuration settings for the vSphere server.
Service Parameters and Operations on page 28	Describes the technical service parameters and service operations which are supported by the vSphere service controller.

Readers of this Manual

This manual is intended for operators who want to offer virtual machines controlled by vSphere through services on a marketplace provided by ESCM. It assumes that you have access to an existing ESCM installation and to a vSphere virtualization platform. In addition, you should have basic knowledge of vSphere and you should be familiar with the concepts and administration of ESCM.

Notational Conventions

This manual uses the following notational conventions:

Add	Names of graphical user interface elements.	
init	System names, for example command names and text that is entered from the keyboard.	
<variable></variable>	Variables for which values must be entered.	

[option]	Optional items, for example optional command parameters.	
one two	Alternative entries.	
{one two} Mandatory entries with alternatives.		

Abbreviations

This manual uses the following abbreviations:

APP Asynchronous Provisioning Platform

ESCM Enterprise Service Catalog Manager

DBMS Database Management System

laaS Infrastructure as a Service

IdP SAML Identity Provider

SAML Security Assertion Markup Language

STS Security Token Service

VM Virtual Machine

WSDL Web Services Description Language

WSIT Web Services Interoperability Technologies

Available Documentation

The following documentation on ESCM is available:

- Overview: A PDF manual introducing ESCM. It is written for everybody interested in ESCM and does not require any special knowledge.
- Operator's Guide: A PDF manual for operators describing how to administrate and maintain ESCM.
- *Technology Provider's Guide:* A PDF manual for technology providers describing how to prepare applications for usage in a SaaS model and how to integrate them with ESCM.
- Supplier's Guide: A PDF manual for suppliers describing how to define and manage service offerings for applications that have been integrated with ESCM.
- Reseller's Guide: A PDF manual for resellers describing how to prepare, offer, and sell services defined by suppliers.
- Broker's Guide: A PDF manual for brokers describing how to support suppliers in establishing relationships to customers by offering their services on a marketplace.
- *Marketplace Owner's Guide:* A PDF manual for marketplace owners describing how to administrate and customize marketplaces in ESCM.
- *Microsoft Azure Integration:* A PDF manual for operators describing how to offer and use virtual systems controlled by Microsoft Azure through services in ESCM.
- Amazon Web Services Integration: A PDF manual for operators describing how to offer and
 use virtual servers controlled by the Amazon Elastic Compute Cloud Web service through
 services in ESCM.

- OpenStack Integration: A PDF manual for operators describing how to offer and use virtual systems controlled by OpenStack through services in ESCM.
- *VMware vSphere Integration:* A PDF manual for operators describing how to offer and use virtual machines provisioned on a VMware vSphere server through services in ESCM.
- Shell Integration: A PDF manual for operators describing how to use Shell scripts through services in ESCM.
- Online Help: Online help pages describing how to work with the administration portal of ESCM.
 The online help is intended for and available to everybody working with the administration
 portal.

1 Introduction

Enterprise Service Catalog Manager (ESCM) is a set of services which provide all business-related functions and features required for turning on-premise applications and tools into 'as a Service' (aaS) offerings and using them in the Cloud. This includes ready-to-use account and subscription management, online service provisioning, billing and payment services, and reporting facilities.

VMware vSphere is a server and infrastructure virtualization platform that allows for running multiple operating systems and applications on a single server, the vSphere server. It gives you on-demand access to fully configured virtual machines (VMs) that are provisioned by cloning VM templates provided in vSphere. The provisioning of computing resources in the Cloud allows you to rapidly scale and flex your infrastructure to support new business initiatives or roll out services.

When integrating applications with ESCM, the instance provisioning can be done in two provisioning modes: synchronous or asynchronous mode.

Asynchronous provisioning is required if provisioning operations take a long time because long-running processes or manual steps are involved. This is the case, for example, when provisioning virtual machines on a virtual machine server. ESCM supports the integration of such applications with its asynchronous provisioning platform (APP). This is a framework which provides a provisioning service as well as functions, data persistence, and notification features which are always required for integrating applications in asynchronous mode.


The integration of ESCM and vSphere provides for an Infrastructure as a Service (laaS) solution that leverages the features of both products: Through services, which are published on a marketplace in ESCM, users can request and use VMs on a vSphere server. The usage costs can be calculated and charged by means of the ESCM billing and payment services.

When deploying the <code>oscm-app</code> container provided with ESCM, a VMware service controller is preconfigured and registered with the asynchronous provisioning platform (APP). This service controller can be used for integrating vSphere services with ESCM.

The VMware service controller includes all components required for connecting an existing ESCM installation with a vSphere server. This manual describes how to offer and use virtual machines provisioned on a VMware vSphere server through services on an ESCM marketplace.

1.1 Components Involved in the vSphere Integration

The following picture provides an overview of the main components involved in the integration of ESCM and vSphere:



In ESCM, customer subscriptions are managed by means of the **Subscription service**. When a customer creates, modifies, or terminates a subscription for a VM in vSphere, the Subscription service asynchronously triggers the corresponding actions in vSphere through the **Asynchronous Provisioning Platform (APP)** and the **VMware service controller**: VMs are created, modified, or deleted in vSphere.

APP is a framework which provides a provisioning service, an operation service, as well as functions, data persistence, and notification features which are required for integrating applications with ESCM in asynchronous mode. The actual communication with the applications is carried out by service controllers.

In vSphere, the basic configuration of VMs for typical usage scenarios is defined by the vSphere administrators in so-called **VM templates**. A template defines, for example, the operating system used by the VM to be provisioned. For every template, any number of technical services can be created in ESCM. On the other hand, a technical service can reference several templates, and a user may choose a template when subscribing to a corresponding service. The technology provider organization is responsible for knowing and providing the correct VM template names. The vSphere API is contacted by the VMware service controller for triggering actions in vSphere.

When APP is deployed, a VMware service controller is also deployed, registered, and initialized.

1.2 Usage Scenarios

The ESCM vSphere integration supports the following usage scenarios:

- **Provisioning of a VM**: When a customer subscribes to a corresponding service on an ESCM marketplace, vSphere is triggered to create a VM based on a specific VM template.
- **Vertical scale-up and scale-down**: By changing the corresponding parameters at an existing subscription, customers can trigger vSphere to add resources (disks, CPU, RAM, etc.) to a provisioned VM. In the same way, they can request vSphere to remove resources from a VM.
- **Starting and stopping a VM**: A customer can explicitly start and stop a VM on vSphere by executing a service operation at the corresponding subscription.

- Creating a snapshot and restoring a VM: A customer can explicitly create a snapshot
 of a VM on vSphere and restore it by executing a service operation at the corresponding
 subscription.
- **Deletion of a VM**: When a customer terminates a subscription for a VM, vSphere is triggered to delete it. The subscription is terminated independent of whether the deletion is successful.

In vSphere, the VMs created for ESCM subscriptions are managed in the same way as other VMs. They can be viewed and monitored with the standard vSphere management tools.

For more details on the usage scenarios, refer to *Using vSphere Services in ESCM* on page 14.

2 Configuring the vSphere Integration Software

The vSphere integration software requires and stores its data in the bssapp relational database. Another relational database, vmware, is used to store the vSphere configuration. The initial setup used when deploying the oscm-app container configures at least the following:

- VCENTER NAME: The name of the vCenter running on the vSphere server.
- DATACENTER NAME: The name of data center managed by the vCenter specified above.
- CLUSTER NAME: The name of the cluster where VMs are to be provisioned.
- LOADBALANCER_NAME: The name of the load balancer used by vSphere. Usually, you can use the name of the VM Network in vSphere: VM Network.

In addition, you can upload .csv files containing an entire vSphere configuration matching your environment, for example, if you want to use several databases or clusters for the provisioning of VMs, into the vmware database. Usually, you do not need to change these settings once they have been imported into the database.

There are the following types of .csv files:

- vCenter: Defines the URL and user credentials for accessing the vSphere server. For security reasons, it is recommended to delete the file as soon as you have successfully installed and configured the vSphere integration software.
- DataCenter: Defines one or several data centers of the vSphere installation.
- Cluster: Defines one or several clusters managed by a data center. For each vSphere cluster, a load balancing algorithm must be defined.
- VLAN: Defines one or more VLANs for a cluster.
- IPPool: Defines the list of IP addresses associated with a VLAN.

You find samples of the above files <u>here</u>. Refer to *vSphere Configuration* on page 22 for details on the content of the files.

To import the vSphere configuration settings into the vmware database:

- 1. Prepare the .csv files so that the configuration matches your environment.
- 2. Invoke the instance status interface of APP for the VMware service controller by opening its URL in a Web browser.

The access URL has the following format:

https://<hostname.fqdn>:<port>/oscm-app-vmware

<hostname.fqdn> is the name and the fully qualified domain name of the machine where the
oscm-app container has been deployed, <port> is the port to address the machine (default:
8881), oscm-app-vmware is the default context root of the service controller and cannot be
changed.

- 3. Log in with the ID and password of the user specified in the configuration settings for the VMware service controller by the platform operator in the BSS_USER_ID and BSS_USER_PWD configuration settings, or as another technology manager registered for the same organization.
- 4. Set the following vSphere-specific settings:
 - Connection URL: The URL for accessing the vSphere API.
 - · User ID: The ID of the technical user in vSphere for accessing the vSphere API.
 - Password: The password of the technical user in vSphere for accessing the vSphere API.
- 5. Upload the prepared .csv files into the database.

6. Save the settings.

3 Creating and Publishing Services

The following sections describe how to create and publish services in ESCM by means of which customers can request and use VMs on a vSphere server.

3.1 Prerequisites and Preparation

The following prerequisites must be fulfilled before you can create and publish services in ESCM:

- To create technical services for the vSphere integration in ESCM, you must have access
 to ESCM as a technology manager. You must be a member of the technology provider
 organization responsible for the VMware service controller as specified in the configuration
 settings for the installation.
- In vSphere, appropriate templates for the provisioning of VMs must exist, to which the technical services in ESCM can be mapped. The vSphere user specified in the configuration settings for the installation must have the necessary permissions to create and configure VMs based on these templates.
- To create marketable services for the vSphere integration in ESCM, you must have access to ESCM as a service manager of an organization with the supplier role. This may be the same organization as the technology provider organization or a different one.
- To publish your marketable services, you must have access to an appropriate marketplace in ESCM in your service manager role.

3.2 Creating Technical Services

The first step in providing ESCM services for vSphere is to create one or more technical services. Proceed as follows:

1. Define one or more technical services in an XML file.

As a basis, you can use the technical services samples provided on https://github.com/servicecatalog/oscm/tree/master/oscm-app-vmware/resources.

In the technical service definition, be sure to specify:

- · The asynchronous provisioning type
- The direct access type
- Service parameters which represent the VM templates defined in vSphere as well as the naming, location, and sizing parameters for the VMs to be provisioned. Service parameters also define the network setup in vSphere and the configuration of the VMs. For details on the supported service parameters, refer to Service Parameters and Operations on page 28.
- 2. Log in to the ESCM administration portal with your technology manager account.
- 3. Import the technical services you created and appoint one or more supplier organizations for them.

For details on these steps, refer to the *Technology Provider's Guide* and to the online help of ESCM.

3.3 Creating and Publishing Marketable Services

As soon as the technical services for the vSphere integration exist in ESCM, you can define and publish marketable services based on them. Your cost calculation for the services should include any external costs for operating the VMs.

Proceed as follows:

- 1. Log in to the ESCM administration portal with your service manager account.
- 2. Define one or more marketable services based on the technical services you created for vSphere.
- 3. Define price models for your marketable services.
- 4. Publish the services to a marketplace.

For details on these steps, refer to the Supplier's Guide and to the online help of ESCM.

4 Using vSphere Services in ESCM

The following sections describe how users can subscribe to and work with the services you have created for vSphere in ESCM. You will find details of the supported usage scenarios outlined in *Usage Scenarios* on page 8.

4.1 Subscribing to Services

Users of customer organizations can subscribe to the services you have created for vSphere on the marketplace where you have published them. This results in the provisioning of a VM in vSphere, as defined in the underlying technical service.

Depending on the definition of the service, the name of the VM is either generated automatically, or the customer can enter a name for it. The technical service may specify a prefix which is prepended to this name, as well as a pattern against which the name is checked before the provisioning operation is started. The name is used as the host name of the provisioned VM.

Depending on the parameters defined for the technical service, the customer can select or enter the number of CPUs, amount of RAM, disk size, additional data disks, and network settings for the VM as well as the vCenter, data center, and cluster in which the VM is to be provisioned.

The provisioning operations are carried out in asynchronous mode. As long as the provisioning is not complete, the status of the subscription is **pending**. The status changes to **ready** as soon as the provisioning has been finished successfully.

As soon as the provisioning is complete, the users assigned to the subscription can access the VM provided by vSphere using the IP address and initial password indicated in the subscription details on the marketplace in ESCM. The initial user ID for accessing the VM is Administrator for Microsoft Windows systems, root for Linux systems. It is strongly recommended that the initial password is changed after the first login.

4.2 Modifying Subscription Parameters

By modifying the corresponding service parameters at their subscriptions, customers can change the VMs provisioned in vSphere.

The following scenario is supported by the vSphere integration software:

Vertical scale-up and scale-down. By changing the corresponding service parameters, customers can trigger vSphere to add resources (disks, RAM, CPUs) to a VM. In the same way, they can request vSphere to remove resources from the VM.

The modifications are carried out in asynchronous mode. As long as the update is not complete, the status of the corresponding subscription is **pending update**. The status changes to **ready** as soon as the modification has been finished successfully.

Note: If the subscription was **suspended** before starting the modification, its status changes to **suspended update** as long as the operation is not complete.

In the technical service definition, you can specify an address to which emails are to be sent that notify service users or administrators of customer organizations about a successful modification of a VM.

4.3 Executing Service Operations

Customers can explicitly start and stop a VM in vSphere from ESCM as well as create and restore snapshots. To do this, they execute the appropriate service operation from the subscription for the VM:

- Start: Starts the VM if it was stopped.
- · Stop: Stops the VM if it was started.
- Restart: Shuts down the VM in vSphere and starts it again.
- **Snapshot**: Creates a snapshot of the VM. Be aware that no snapshot versions are stored. When a new snapshot is created, the previous one is overwritten.
- Restore: Resets the VM to a previously created snapshot.

4.4 Terminating Subscriptions

A customer can at any time terminate a subscription for a VM in vSphere.

vSphere is triggered to delete the VM. The subscription is terminated independent of whether the deletion is successful. Note, however, that the VM name cannot be re-used before the deletion has been completed in vSphere.

5 Administrating the vSphere Integration

The following sections describe administration tasks you may need to perform in your role as an operator of the vSphere integration software.

5.1 Controlling the Provisioning Process

The vSphere integration provides you with the following feature for controlling the provisioning, modification, and deprovisioning of VMs:

In the definition of the technical services for vSphere, you can specify the MAIL_FOR_COMPLETION parameter. This is an address to which emails are to be sent in case manual steps are required to complete an operation.

If you specify this parameter, the VMware service controller interrupts the processing of each operation before its completion and waits for a notification about the execution of a manual action. This notification consists in opening the link given in the email.

Omit the MAIL FOR COMPLETION parameter if you do not want to interrupt the processing.

5.2 Handling Problems in the Provisioning Process

If the provisioning of a VM fails on the vSphere side or if there are problems in the communication between the participating systems, the corresponding subscription in ESCM remains pending. The VMware service controller informs the technology managers of its responsible technology provider organization by email of any incomplete operation in vSphere.

You can then take the appropriate actions to solve the problem in vSphere or in the communication. For example, you could remove an incomplete VM, or you could restore a missing connection.

After solving the problem, the vSphere integration components and ESCM need to be synchronized accordingly. You do this by triggering a corresponding action in the APP component. Proceed as follows:

- 1. Work as a technology manager of the technology provider organization responsible for the VMware service controller.
- 2. Invoke the instance status interface of APP for the service controller of the application by opening its URL in a Web browser.

The access URL has the following format:

https://<hostname.fqdn>:<port>/oscm-app/controller/?controllerid=ess.vmware <hostname.fqdn> is the name and the fully qualified domain name of the machine where the oscm-app container has been deployed, <port> is the port to address the machine (default: 8881), oscm-app/controller/?controllerid=ess.vmware is the default context root of the service controller and cannot be changed.

The Web page shows all subscriptions for the application, including detailed information such as the customer organization, the ID of the related application instance, and the provisioning status.

3. Find the subscription for which you solved the problem in the most recent provisioning, modification, or delete operation.

- 4. In the **Action** column, select the action for the vSphere integration components to execute next. Possible actions are the following:
 - RESUME to resume the processing of a provisioning operation in APP which was suspended.
 - SUSPEND to suspend the processing of a provisioning operation in APP, for example when vSphere does not respond.
 - UNLOCK to remove the lock for a VM instance in APP.
 - DELETE to terminate the subscription in ESCM and remove the instance in APP, but keep the VM in vSphere for later use. The service manager role is required for this action.
 - DEPROVISION to terminate the subscription in ESCM, remove the instance in APP, and delete the VM in vSphere. The service manager role is required for this action.
 - ABORT_PENDING to abort a pending provisioning or modification operation in ESCM. ESCM
 is notified to roll back the changes made for the subscription and return it to its previous
 state. In vSphere, no actions are carried out.
 - COMPLETE_PENDING to complete a pending provisioning or modification operation in ESCM.
 ESCM is notified to complete the changes for the subscription and set the subscription
 status to ready (or suspended if it was suspended before). This is possible only if the
 operations of the service controller are already completed.
- 5. Click **Execute** to invoke the selected action.

The instance status interface provides the following additional functionality that is useful for problem-solving purposes:

You can display service instance details for each subscription by clicking the corresponding
entry in the table. This displays all subscription-related information that is stored in the bssapp
database.

5.3 Updating Service Controller Settings in the Database

During deployment, several configuration settings are written to the bssapp and vmware databases. This configuration is used for the initial setup of the VMware service controller and its registration with APP. It is up to the platform operator for taking care that the initial settings are correct. Refer to the *Operator's Guide* for details on the initial configuration using a var.env file. In addition, you can to upload .csv files containing an entire vSphere configuration matching your environment, for example, if you want to use several databases or clusters for the provisioning of VMs, into the vmware database. Refer to *Configuring the vSphere Integration Software* on page 10 for details.

A technology provider can define service parameters in the technical service definition. If such a parameter has the same ID as a controller configuration setting stored in the database, it overrules the configuration setting in the database when the marketable service based on such a technical service is subscribed to. By default the values in the controller configuration settings are used. Refer to the *Technology Provider's Guide* for details on defining technical services.

In addition, a supplier can define custom attributes for subscriptions and for customers. If such an attribute has the same ID as a controller configuration setting stored in the APP database as well as a corresponding technical service parameter, it overrules the technical service parameter as well as the configuration setting in the database when the marketable service based on such a technical service is subscribed to.

The controller configuration settings are evaluated as follows:

1. Configuration setting as stored in the APP database.

- 2. Technical service parameter. If defined, it overrules 1.
- 3. Custom attribute for customer. If defined, it overrules 1. and 2.
- 4. Custom attribute for subscription. If defined, it overrules 1. and 2. and 3.

To update the controller settings in the APP database:

1. Invoke the instance status interface of APP for the VMware service controller of the application by opening it's URL in a Web browser.

The access URL has the following format:

https://<hostname.fqdn>:<port>/oscm-app-vmware

<hostname.fqdn> is the name and the fully qualified domain name of the machine where the
oscm-app container has been deployed, <port> is the port to address the machine (default:
8881), oscm-app-vmware is the default context root of the service controller and cannot be
changed.

- 2. Log in with the ID and password of the user specified in the configuration settings for the VMware service controller by the platform operator in the BSS_USER_ID and BSS_USER_PWD configuration settings, or as another technology manager registered for the same organization.
- 3. The following **general controller settings** can be changed:
 - User ID: The identifier of the user responsible for the VMware service controller.
 - User Key: The user key for accessing ESCM. You receive this key with the confirmation email for your user account. The user must have the technology manager role in ESCM and belong to the technology provider organization responsible for the service controller.
 It is recommended that the user account is used only for carrying out actions on behalf of the service controller in ESCM.
 - Password: The password of the user for accessing ESCM.
- 4. The following **VMware controller-specific settings** can be changed:
 - Connection URL: The URL for accessing the vSphere API.
 - · User ID: The ID of the technical user in vSphere for accessing the vSphere API.
 - Password: The password of the technical user in vSphere for accessing the vSphere API.

You can also change the vSphere configuration by updating the respective .csv files and uploading them again to the vmware database. Refer to vSphere Configuration on page 22 for details.

5. Save the settings.

5.4 Changing the Responsible Organization

You can change the technology provider organization responsible for the VMware service controller using the Web interface of APP:

1. In a Web browser, access the Web interface (base URL) of APP.

The access URL has the following format:

https://<hostname.fqdn>:<port>/oscm-app

<hostname.fqdn> is the name and the fully qualified domain name of the machine where the
oscm-app container has been deployed, <port> is the port to address the machine (default:
8881), oscm-app is the default context root of APP and cannot be changed.

2. Log in with the ID and password of the user specified for BSS_USER_KEY in the configuration settings for APP or as another administrator of the same organization.

- 3. Specify the technology provider organization for the VMware service controller, ess.vmware.
- 4. Save the settings.
- 5. Make sure that the configuration settings for the VMware service controller are updated. Any technology manager registered for the technology provider organization you specified can log in to the graphical user interface for updating the controller configuration settings (see above). At least the ID and password of the user to be used for accessing ESCM must be changed in the controller configuration settings.

Appendix A: Controller Configuration Settings

This appendix describes the controller configuration settings as stored in the bssapp database. For details on how to update them, refer to *Updating Service Controller Settings in the Database* on page 17 and *Changing the Responsible Organization* on page 18.

CONTROLLER_ID

CONTROLLER ID=ess.vmware

The identifier of the service controller.

BSS_ORGANIZATION_ID

BSS ORGANIZATION ID=<organizationID>

The ID of the organization in ESCM which is responsible for the service controller. The organization must have the technology provider role. It is created and initially assigned to the VMware service controller by the platform operator.

BSS_USER_ID

BSS USER ID=<userId>

The identifier of the user specified in <code>BSS_USER_KEY</code> for accessing ESCM.

BSS USER KEY

BSS_USER_KEY=<userKey>

The user key for accessing ESCM. You receive this key with the confirmation email for your user account. The user must have the technology manager role in ESCM and belong to the technology provider organization responsible for the service controller.

BSS_USER_PWD

BSS USER PWD= crypt:<password>

The password of the user for accessing ESCM.

READY_TIMEOUT

READY_TIMOUT=<organizationID>

The time interval in milliseconds the VMware service controller waits for the VM instance to accept the next command in the provisioning process. When the specified timeout value is reached, the provisioning is aborted.

Allowed values: Any value between 0 and 4924967296

Default: 300000

USERID_<organizationId>

USERID <organizationId>=<userId>

Optional. The identifier of a service manager of a supplier organization providing a service on an ESCM marketplace for provisioning VMs. This identifier must be specified in case a shell script with service parameter placeholders is to be executed during the provisioning process.

Replace <organizationId> and the <userId> with the corresponding IDs.

USERKEY < organizationId>

USERKEY_<organizationId>=<userKey>

Optional. The user key of the service manager specified in <code>USERID_<organizationID></code>. This key must be specified in case a shell script with service parameter placeholders is to be executed during the provisioning process.

Replace <organizationId> and the <userKey> with the organization ID and user key, respectively.

USERPWD_<organizationId>

USERPWD_<organizationId>=_crypt:<userPwd>

Optional. The password of the service manager specified in <code>USERID_<organizationID></code>. This password must be specified in case a shell script with service parameter placeholders is to be executed during the provisioning process.


Replace corganizationId> and the cuserPwd> with the organization ID and password,
respectively. The crypt: prefix ensures that the password will be encrypted before it is stored.

Appendix B: vSphere Configuration

The vSphere integration software requires and stores its data in the bssapp relational database. Another relational database, vmware, is used to store the vSphere configuration. The initial setup used when deploying the oscm-app container configures at least the following:

- VCENTER NAME: The name of the vCenter running on the vSphere server.
- DATACENTER NAME: The name of data center managed by the vCenter specified above.
- CLUSTER NAME: The name of the cluster where VMs are to be provisioned.
- LOADBALANCER_NAME: The name of the load balancer used by vSphere. Usually, you can use the name of the VM Network in vSphere: VM Network.

In vSphere, several entities are distinguished. They form the following hierarchy:



One vCenter can manage many data centers. Each data center may contain any number of clusters. One cluster may use several VLANs (Virtual Local Area Networks), each having assigned several IP addresses.

You need to specify the vSphere configuration in the .csv files so that the correct entities are used for the provisioning of VMs in vSphere.

There are the following types of .csv files. They map the hierarchy depicted above:

- vCenter: Defines the URL and user credentials for accessing the vSphere server. For security reasons, it is recommended to delete the file as soon as you have successfully installed and configured the vSphere integration software.
- DataCenter: Defines one or several data centers of the vSphere installation.
- cluster: Defines one or several clusters managed by a data center. For each vSphere cluster, a load balancing algorithm must be defined. Refer to *Configuring Load Balancing* on page 26 for details.
- VLAN: Defines one or more VLANs for a cluster.
- IPPool: Defines the list of IP addresses associated with a VLAN.

You find samples of the above files *here*.

You can upload the files to the vmware database using the instance status interface of APP for the VMware service controller:

https://<hostname.fqdn>:<port>/oscm-app-vmware

The files must be UTF-8 encoded.

Below you find a description of the headers in the individual files below which you need to enter the appropriate information. The individual entries must be separated by commas, and be placed into one line without line breaks. If the entries contain a comma or blanks, you need to enclose them in double quotes.

vCenter

vCenter represents the vSphere installation. The vcenter.csv file contains the following headers:

Header	Description
TKey	The technical identifier of the vCenter in the VMware service controller database. It is used internally for identifying the vCenter. The key must be unique and consist of integers only.
Name	The name of the vCenter running on the vSphere server.
Identifier	The unique identifier of the vCenter. If specified, this identifier can be used as a placeholder in the naming scheme of the VMs to be provisioned (INSTANCENAME service parameter).
URL	The URL for accessing the vSphere API.
UserId	The ID of the technical user in vSphere for accessing the vSphere API.
Password	The password of the technical user in vSphere for accessing the vSphere API.

Example:

TKey, Name, Identifier, URL, UserId, Password
1, myvc1, 1, https://myvc1.com/sdk/vimService?wsdl, user, pw123

Data Center

Data centers are managed by a vCenter. For each vCenter, the datacenter.csv file may contain several entries for several data centers with the following headers:

Header	Description
VCenter	The name of the vCenter managing the data center.
Datacenter	The name of the data center.
DatacenterID	The unique identifier of the data center. The \${DC} placeholder in the INSTANCENAME service parameter of a technical service definition is replaced by this ID when vSphere instance names are generated.

Example:

```
VCenter, Datacenter, DatacenterID myvc1, datacenter1, 1 myvc1, datacenter2, 2
```

Clusters

One data center can contain many clusters. Each VM is provisioned in a cluster. For one vCenter and each data center managed by this vCenter, the <code>cluster.csv</code> may contain several entries for several clusters with the following headers:

Header	Description
VCenter	The name of the vCenter managing the data center where the cluster is located.
Datacenter	The name of the data center the cluster is associated with.
Clustername	The name of the cluster.
Load_balancer	Load balancer configuration in XML format without line breaks. You find a sample configuration on <i>GitHub</i> .

Example:

```
VCenter, Datacenter, Clustername, Load balancer
myvc1, datacenter1, cluster1,
 <?xml version="1.0" encoding="UTF-8" standalone="no"?>
 <ess:essvcenter xmlns:ess="http://oscm.org/xsd"</pre>
     xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
     xsi:schemaLocation="http://oscm.org/xsd
  ../../oscm-app-vmware\\resources\\XSD\\Loadbalancer schema.xsd">
 <balancer class=</pre>
     "org.oscm.app.vmware.business.balancer.EquipartitionHostBalancer"
     cpuWeight="0.5" memoryWeight="1" vmWeight="1"/>
 <host enabled="true" name="my.host1.com">
 <balancer class=</pre>
 "org.oscm.app.vmware.business.balancer.EquipartitionStorageBalancer"
     storage="VMdev0, VMdev1"/> </host>
 <host enabled="true" name="my.host2.com">
 <balancer class=</pre>
 "org.oscm.app.vmware.business.balancer.EquipartitionStorageBalancer"
     storage="VMdev0, VMdev1"/> </host>
 <storage enabled="true" limit="85%" name="VMdev0"/>
<storage enabled="true" limit="85%" name="VMdev1"/></ess:essvcenter>
```

The above example is not complete, and it contains line breaks due to text formatting reasons. If you want to use several clusters, you need to specify additional values for each of them. A sample cluster.csv file is also available on *GitHub*.

Refer to Configuring Load Balancing on page 26 for more details.

VLAN

VLANs (Virtual Local Area Networks) enable a single physical LAN segment to be further subdivided so that groups of ports are isolated from one another as if they were on physically separated segments. VLANs are associated with clusters. The vlan.csv file contains the following headers for defining VLANs:

Header	Description
VCenter	The name of the vCenter managing the data center where the cluster is located.
Datacenter	The name of the data center the cluster is associated with.
Cluster	The name of the cluster this VLAN is assigned to.
Name	The name of this VLAN.
Gateway	The IP address of the gateway of this VLAN.
SubnetMask	The subnet mask.
DNSServer	The DNS server for the VLAN.
DNSSuffix	The DNS suffix for the VLAN. The suffix is used in DNS name registration and resolution.
Enabled	In order to associate a VLAN with a VM and to activate the VLAN, you need to set this parameter to true.

Example:

```
VCenter, Datacenter, Cluster, Name, Gateway, SubnetMask,
DNSServer, DNSSuffix, Enabled
myvc1, datacenter1, cluster1, VLAN1, 10.10.1.1, 255.255.251.0,
10.10.1.11, mycompany1.com, true
myvc1, datacenter1, cluster1, VLAN2, 10.10.1.2, 255.255.252.0,
10.10.1.22, mycompany2.com, true
myvc1, datacenter1, cluster1, VM Network, 10.10.1.3, 255.255.253.0,
10.10.1.33, mycompany3.com, true
```

The above example is not complete, and it contains line breaks due to text formatting reasons. You need to specify additional values for all clusters defined in the cluster.csv file.

IP Pool

An IP pool is a list of IP addresses associated with a VLAN. The ippool.csv file contains the following headers for defining IP addresses:

Header	Description
VCenter	The name of the vCenter managing the data center where the cluster is located.
Datacenter	The name of the data center the cluster is associated with.

Header	Description
Cluster	The name of the cluster to which this IP address is assigned.
VLAN	The name of the VLAN this IP address is assigned to.
IPAddress	The IP address.

Example:

```
VCenter, Datacenter, Cluster, VLAN, IPAddress
myvc1, datacenter1, cluster1, VLAN1, 169.254.10.1
myvc1, datacenter1, cluster1, VLAN1, 169.254.10.2
myvc1, datacenter1, cluster1, VLAN1, 169.254.10.3
myvc1, datacenter1, cluster1, VLAN2, 169.255.10.1
myvc1, datacenter1, cluster1, VLAN2, 169.255.10.2
myvc1, datacenter1, cluster1, VLAN2, 169.255.10.3
```

The above example is not complete. You need to specify additional values for all VLANs defined in the vlan.csv file.

B.1 Configuring Load Balancing

When importing a <code>cluster.csv</code> file for defining one or several clusters managed by a data center, you need to configure a load balancing algorithm for allowing to automatically choose the vSphere host and storage for a new VM when it is provisioned, based on memory, CPUs, disk space, and number of VMs running on the vSphere host.

Load balancing is defined per vSphere cluster.

Note: The vSphere host as well as the storage can also be specified in technical service parameters: TARGET_HOST and TARGET_STORAGE. In this case, you do not make use of the vSphere load balancing. However, as soon as you import a cluster.csv file, these parameters are no longer evaluated.

The cluster.csv file must contain the load balancing configuration in XML format. The load balancing algorithm can take on the following options:

Distribute VMs equally over all hosts (dynamically):

The hosts and storages are read from vSphere. The target host will be the one with the least VMs running on it. The target storage will be the one with the highest amount of available disk space.

Example:

The above example contains line breaks due to text formatting reasons.

· Distribute VMs equally over all hosts (static configuration):

The target host and the target storage are determined by the criteria that you specify:

- 1. Define the criteria for determining the host (memory, CPUs, and number of VMs that may be provisioned on the host). The weight determines the importance of a criterion in the calculation of the target host. The weight number is in the range of 0 to 1. A value of 0 turns off the evaluation of the parameter.
- 2. For each host, define which storages are available and which criteria are used to determine the storage for a VM. You can select one of the following storage balancing algorithms:
 - Distribute VMs in the order of the configured storages
 - · Distribute VMs equally over all storages
- 3. For each storage, define the upper limit of disk space that can be used. When this limit is reached, another storage is selected as target storage.

Example:

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<essvcenter>
    <balancer class="org.oscm.app.vmware.business.balancer.</pre>
              EquipartitionHostBalancer"
              cpuWeight="0.5" memoryWeight="1" vmWeight="1"/>
    <host enabled="true" name="vmwdev1.my.host.com">
        <balancer class="org.oscm.app.vmware.business.balancer.</pre>
              EquipartitionStorageBalancer" storage="VMdev0,VMdev1"/>
    </host>
    <host enabled="true" name="vmwdev2.my.host.com">
        <balancer class="org.oscm.app.vmware.business.balancer.</pre>
              EquipartitionStorageBalancer" storage="VMdev0,VMdev1"/>
    </host>
    <storage enabled="true" limit="85%" name="VMdev0"/>
    <storage enabled="true" limit="85%" name="VMdev1"/>
</essvcenter>
```

The above example contains line breaks due to text formatting reasons.

Appendix C: Service Parameters and Operations

The following sections describe the technical service parameters and service operations which are supported by the VMware service controller.

You find a sample service on GitHub:

https://github.com/servicecatalog/oscm/tree/master/oscm-app-vmware/resources.

Note: All parameters defined in the technical service definition must be one-time parameters, since the modification of parameters is not supported. Be sure to set their modificationType to ONE TIME.

General Parameters

The following parameters are required for provisioning a VM:

TEMPLATENAME

Mandatory. The name of the VM template to be used for the provisioning of a new VM instance. The template is a master copy of a VM that can be used to create many clones. When you provision a VM, you create a copy of the template, including its settings, configured virtual devices, installed software, and other contents of its disks.

Once specified, the template name can no longer be changed. Be aware that template names are case-sensitive.

Example: centos52-template

ACCESS_INFO

Optional. A pattern for the access information for a VM after it has been provisioned. The access information is sent by email to the subscribing user as well as all users assigned to the subscription. It is displayed in the details of the subscription.

The instance-specific values of this parameter contain the actual access information for the VM as soon as the subscription has been created.

The pattern may contain any textual expression. In addition, the following placeholders are supported:

- \${IP}: IP address of the VM.
- \${HOST}: Host name of the VM.
- \${CPU}: CPU count.
- \${MEM}: Main memory.
- \${DISK}: System and data disk size(s).

Example: \${HOST}(IP:\${IP})
CPUS, \${MEM} RAM, \${DISK} HDD

Default: \${HOST}, \${IP}

MAIL_FOR_COMPLETION

Optional. The address to which emails are to be sent in case manual steps are required to complete an operation. If you specify this parameter, the service controller interrupts the provisioning of the VM and waits for a notification about the execution of a manual action. Omit this parameter if you do not want to interrupt the provisioning process.

Example: info@company.com

VM Naming Rule Parameters

The following parameters define the naming rules for the VMs to be provisioned:

INSTANCENAME

Mandatory. The name of the VM instance to be provisioned. This name is either generated automatically, or must be specified by customers when they subscribe to a corresponding service. The instance name is used as the host name of the VM in the network configuration. The permitted length of host names depends on the operating system.

The string given in Instancename_PREFIX is prepended to the name. The name including the prefix must match the pattern given in Instancename Pattern.

For the automatic generation of instance names, the following placeholders are supported. They are filled with the corresponding data from the VMware service controller database when the VM is provisioned. Refer to *vSphere Configuration* on page 22 for details.

- \${VC}: Unique ID of the vCenter derived from the vcenter database table. Specifies the vSphere server on which the VM is provisioned.
- \${DC}: Unique ID of the data center derived from the vcenter database table.
- \${ID3}: Unique sequential number of 3 digits.
- \${ID6}: Unique sequential number of 6 digits.
- \${ID8}: Unique sequential number of 8 digits.
- \${ID10}: Unique sequential number of 10 digits.
- \${ID12}: Unique sequential number of 12 digits.
- \${IP3}: The last octet (eight bit) of the VM's IP address, for example, 152 of the 192.16.20.152 IP address.

It is helpful to add some hint about the naming rules as default value.

Example: Hostname ([a-z0-9]) {6,8}

INSTANCENAME_PATTERN

Optional. A regular expression specifying a pattern for the VM instance names entered by the users when they subscribe to a corresponding service. This parameter is useful if the INSTANCENAME parameter is configurable by the user subscribing to the service, i.e. the instance names are not generated automatically. If the names do not match the pattern, the subscription is rejected. Special characters must not be used.

Default: ^[a-zA-Z0-9][a-zA-Z0-9-]{0,61}[a-zA-Z0-9]\$

The pattern may contain any textual expression.

Example: IT([a-z0-9]) {6,8}

INSTANCENAME PREFIX

Optional. A string to be prepended to the VM instance names when they are generated or entered by the users when they subscribe to a corresponding service. The combination of prefix and instance name must match the INSTANCENAME PATTERN parameter.

Example: IT

VM Location Parameters

The following parameters can be specified for defining where on the vSphere server the VMs are to be provisioned. The parameters can be used by suppliers for offering a list of options to the customers subscribing to a corresponding service.

TARGET_VCENTER_SERVER

Mandatory. The site where vSphere is installed. vCenter is the centralized management tool for the vSphere suite. Together with the TARGET_DATACENTER and TARGET_CLUSTER parameters, this parameter is used to specify the location of the provisioned VM instances. The vCenter must be contained in the vmware database.

TARGET_DATACENTER

Mandatory. The data center where the VM instances will be provisioned. Together with the <code>TARGET_VCENTER_SERVER</code> and <code>TARGET_CLUSTER</code> parameters, this parameter is used to determine the location of the provisioned VM instances. The data center must be contained in the <code>vmware</code> database.

TARGET CLUSTER

Mandatory. The cluster where the VM instances will be provisioned. A cluster is a group of hosts. Together with the <code>TARGET_VCENTER_SERVER</code> and <code>TARGET_DATACENTER</code> parameters, this parameter is used to determine the location of the provisoned VM instances. The cluster must be contained in the <code>vmware</code> database.

TARGET_HOST

Optional. The name of the host on which the VM instances will be provisioned. If not specified, the default vSphere load balancing mechanism will determine the host machine to be used. In this case, the target host will be the one with the least VMs running on it.

TARGET_STORAGE

Optional. The name of the disk where the files of the VM instances are to be stored. If not specified, the vSphere load balancing mechanism will determine the target storage. In this case, the target storage will be the one with the highest amount of available disk space.

Example: vmwdev1

TARGET FOLDER

Optional. The name of the virtual folder where the VM instances will be provisioned. If not specified, the VMs are placed into the folder where the VM template from which they were cloned is located.

Example: folder \${ORGID}

\${ORGID} is a placeholder for the organization of the subscribing user.

The actual value will be, for example, folder 83d79a.

VM Sizing Parameters

The following parameters define the size of the VMs to be provisioned. Make sure that users can only specify numbers that are supported by the VM template and the configuration in vSphere. This can be done, for example, by presenting the supported numbers as different parameter options for selection.

NUMBER_OF_CPU

Mandatory. The number of virtual CPUs the VM instance to be provisioned will use. The number of licensed CPUs on the host, the number of CPUs that the guest operating system supports, and the VM hardware version determine the number of virtual CPUs that you can use.

Default: 1

AMOUNT_OF_RAM

Mandatory. The amout of memory in MB allocated to each VM.

Default: 1024

DISK_SIZE

Mandatory. The operating system disk size in GB. This parameter can be used to adjust the system disk size. If the parameter is not specified, the same disk size as specified in the VM template is used.

Currently, only one virtual device is supported. If multiple disks are defined in the VM template, the first one only will be configured.

Default: 40

DATA_DISK_SIZE_#

Optional. Up to 4 additional data disks can be defined: Replace the hash sign (#) with a digit between 1 and 4. For each disk, this parameter is used for specifying the disk size in GB. Make sure that when a user modifies subscription parameters, the value for the disk size can only be increased.

When adding data disks, additional actions are required on the operating system where the VMs are provisioned: To enable disk usage, you need to format and mount them. To do so, you could use a script and provide the script's URL in the SCRIPT URL service parameter.

Example: DATA_DISK_SIZE_1="40"

DATA_DISK_TARGET_#

Optional. The mount point of the data disk with the given number (Linux), or the disk drive (Microsoft Windows).

Example: DATA_DISK_TARGET_1="D"

DATA_DISK_TARGET_VALIDATION_#

Optional. A regular expression specifying a fixed part of the mount point or disk drive where the additional data disk is to be mounted. This parameter must not be configurable by the user subscribing to the service.

Example: ~/home/datadisk/

VM Network Parameters

The following parameters define the network for the VM instances to be provisioned:

NUMBER_OF_NICS

Mandatory. The number of network interface cards (NICs) which are to be used for new VMs. The number must match the number defined in the VM template. You can configure up to 4 networks for a VM.

Default: 1

NIC#_NETWORK_ADAPTER

Optional. The network adapter with the given number (#) which is to be used when a VM is provisioned. If specified, it replaces the network adapter defined in the VM template.

Example: NIC1 NETWORK ADAPTER="VLAN1"

NIC#_NETWORK_SETTINGS

Optional. Determines how the IP address for the NIC with the given number (#) is set. The following options can be specified:

- DHCP: The DHCP protocol defines the IP address.
- MANUAL: The IP address is specified manually using the NIC#_* service parameters described below.
- DATABASE: The IP address is retrieved from the vmware database. The first free address
 is taken. The available IP addresses must have been defined in and imported from the
 ippool.csv configuration file.

Example: NIC1 NETWORK SETTINGS="DHCP"

NIC# IP ADDRESS

Optional. The IP address for the NIC with the given number (#). Only useful when the NIC# NETWORK SETTINGS parameter is set to MANUAL.

Example: NIC1 IP ADDRESS="172.16.254.1"

NIC#_SUBNET_MASK

Optional. The subnet mask for the NIC with the given number (#). Only useful when the NIC# NETWORK SETTINGS parameter is set to MANUAL.

Example: NIC1 SUBNET MASK="255.255.252.0"

NIC#_GATEWAY

Optional. The gateway for the NIC with the given number (#). Only useful when the NIC# NETWORK SETTINGS parameter is set to MANUAL.

Example: NIC1_GATEWAY="192.0.2.254"

NIC#_DNS_SERVER

Optional. The DNS server for the NIC with the given number (#). Only useful when the NIC# NETWORK SETTINGS parameter is set to MANUAL.

Example: NIC1_DNS_SERVER="208.67.222.222"

NIC#_DNS_SUFFIX

Optional. The DNS suffix for the NIC with the given number (#). The suffix is used in DNS name registration and resolution. This policy lets you specify a suffix for a group of VMs, and prevents users from changing it.

Example: NIC1_DNS_SUFFIX="example.com"

VM Configuration Parameters

The following parameters define the configuration of the VMs to be provisioned:

SCRIPT URL

Optional. The URL points to a shell script (Linux) or batch file (Microsoft Windows) that is downloaded from the given location, and uploaded and executed on a VM after the VM has been created and configured. You can use such a script or batch file, for example, for formatting and mounting additional data disks, or changing the root password. For security reasons, the SCRIPT_URL parameter must not be configurable by the user subscribing to the service.

Apart from the SCRIPT URL parameter, the following service parameters must be specified:

- SCRIPT USERID
- SCRIPT PWD

Scripts or batch files can be provided, for example, in the docroot directory of the app-domain domain.

A script or batch file can contain commands or placeholders for the following service parameters:

- LINUX ROOT PWD
- NIC# DNS SERVER (# being a digit between 1 and 4)
- NIC# DNS SUFFIX (# being a digit between 1 and 4)
- NIC# GATEWAY (# being a digit between 1 and 4)
- NIC# IP ADDRESS (# being a digit between 1 and 4)
- NIC# SUBNET MASK (# being a digit between 1 and 4)
- INSTANCENAME
- SCRIPT URL
- SCRIPT USERID
- SCRIPT PWD
- DOMAIN_NAME
- DATA DISK TARGET # (# being a digit between 1 and 4)
- DATA DISK SIZE # (# being a digit between 1 and 4)
- DATA DISK TARGET VALIDATION # (# being a digit between 1 and 4)

If the script or batch file contains a placeholder for a service parameter, you must insert the user credentials of a service manager of a supplier organization as VMware service controller settings:

- USERID_<organizationID>
- USERKEY <organizationID>
- USERPWD_<organizationID>

For details, refer to Controller Configuration Settingson page 20.

A sample script for changing the Linux root password is available in the <install_pack_dir>/ samples directory: changeRootPassword.sh.

Example: http://localhost:8080/changeNetworkSettings.sh

SCRIPT USERID

Optional. The user ID for executing the shell script (Linux) or batch file (Microsoft Windows) in the VM.

SCRIPT PWD

Optional. The password for executing the shell script (Linux) or batch file (Microsoft Windows) in the VM.

DOMAIN NAME

Optional. The domain part of the fully qualified domain name (FQDN) for Linux environments, or the Microsoft Windows domain that the VM will join if it is a Microsoft Windows system.

LINUX_ROOT_PWD

Optional. The root account password for Linux environments. Initially, a VM is provisioned with the user credentials derived from the VM template.

The root password can be changed only by executing a script using the <code>SCRIPT_URL</code> parameter. A sample of such a script is provided in the <code><install_pack_dir>/samples</code> directory: <code>changeRootPassword.sh</code>.

In the sample script, the LINUX_ROOT_PWD parameter contains the new Linux root password which is set when the script is executed. The sample script can be provided, for example, in the docroot directory of the app-domain domain.

WINDOWS_DOMAIN_JOIN

Optional. If set to true, the VM will join a Microsoft Windows domain, if set to false, the VM will be part of a Microsoft Windows Workgroup.

Default: false

WINDOWS DOMAIN ADMIN

Optional. The name of a Microsoft Windows domain administrator.

WINDOWS_DOMAIN_ADMIN_PWD

Optional. The password of the Microsoft Windows domain administrator.

WINDOWS_WORKGROUP

Optional. The Microsoft Windows Workgroup the VM will join, if specified by the WINDOWS DOMAIN JOIN parameter.

WINDOWS LOCAL ADMIN PWD

Optional. The local administrator password of the VM.

WINDOWS LICENSEKEY

Optional. The license key of the Microsoft Windows system.

SYSPREP_RUNONCE_COMMAND

Optional. The Microsoft Windows batch file that is executed by the Microsoft Windows system preparation script (sysprep) after the first boot.

Example: cmd /c CALL \\server\share\file.bat

Service Operations for VMs

The VMware service controller supports the service operations below for VMs.

The actionURL for each operation is:

https://oscm-app:8880/oscm-app/webservices/oscm-app/oscm-app/org.oscm.app.v2_0.service.AsynchronousOperationProxy?wsdl

<oscm-app> and <8880> are the server and port of the container where the VMware service
controller is deployed.

START_VM

Starts a VM in vSphere if it was stopped.

STOP_VM

Stops a VM in vSphere if it was started.

RESTART_VM

Shuts down a VM in vSphere and starts it again.

SNAPSHOT_VM

Creates a snapshot of the VM. Be aware that no snapshot versions are stored. When a new snapshot is created, the previous one is overwritten.

RESTORE_VM

Restores a previously created snapshot of the VM.

Glossary

Administrator

A privileged user role within an organization with the permission to manage the organization's account and subscriptions as well as its users and their roles. Each organization has at least one administrator.

Application

A software, including procedures and documentation, which performs productive tasks for users.

Billing System

A system responsible for calculating the charges for using a service.

Broker

An organization which supports suppliers in establishing relationships to customers by offering the suppliers' services on a marketplace, as well as a privileged user role within such an organization.

Cloud

A metaphor for the Internet and an abstraction of the underlying infrastructure it conceals.

Cloud Computing

The provisioning of dynamically scalable and often virtualized resources as a service over the Internet on a utility basis.

Customer

An organization which subscribes to one or more marketable services in ESCM in order to use the underlying applications in the Cloud.

Infrastructure as a Service (laaS)

The delivery of computer infrastructure (typically a platform virtualization environment) as a service.

Marketable Service

A service offering to customers in ESCM, based on a technical service. A marketable service defines prices, conditions, and restrictions for using the underlying application.

Marketplace

A virtual platform for suppliers, brokers, and resellers in ESCM to provide their services to customers.

Marketplace Owner

An organization which holds a marketplace in ESCM, where one or more suppliers, brokers, or resellers can offer their marketable services.

Marketplace Manager

A privileged user role within a marketplace owner organization.

Operator

An organization or person responsible for maintaining and operating ESCM.

Organization

An organization typically represents a company, but it may also stand for a department of a company or a single person. An organization has a unique account and ID, and is assigned one or more of the following roles: technology provider, supplier, customer, broker, reseller, marketplace owner, operator.

Organizational Unit

A set of one or more users within an organization representing, for example, a department in a company, an individual project, a cost center, or a single person. A user may be assigned to one or more organizational units.

OU Administrator

A privileged user role within an organization allowing a user to manage the organizational units for which he has been appointed as an administrator, and to create, modify, and terminate subscriptions for these units.

Payment Type

A specification of how a customer may pay for the usage of his subscriptions. The operator defines the payment types available in ESCM; the supplier or reseller determines which payment types are offered to his customers, for example payment on receipt of invoice, direct debit, or credit card.

Platform as a Service (PaaS)

The delivery of a computing platform and solution stack as a service.

Price Model

A specification for a marketable service defining whether and how much customers subscribing to the service will be charged for the subscription as such, each user assigned to the subscription, specific events, or parameters and their options.

Reseller

An organization which offers services defined by suppliers to customers applying its own terms and conditions, as well as a privileged user role within such an organization.

Role

A collection of authorities that control which actions can be carried out by an organization or user to whom the role is assigned.

Seller

Collective term for supplier, broker, and reseller organizations.

Service

Generally, a discretely defined set of contiguous or autonomous business or technical functionality, for example an infrastructure or Web service. ESCM distinguishes between technical services and marketable services, and uses the term "service" as a synonym for "marketable service".

Service Manager

A privileged user role within a supplier organization.

Standard User

A non-privileged user role within an organization.

Software as a Service (SaaS)

A model of software deployment where a provider licenses an application to customers for use as a service on demand.

Subscription

An agreement registered by a customer for a marketable service in ESCM. By subscribing to a service, the customer is given access to the underlying application under the conditions defined in the marketable service.

Subscription Manager

A privileged user role within an organization with the permission to create and manage his own subscriptions.

Supplier

An organization which defines marketable services in ESCM for offering applications provisioned by technology providers to customers.

Technical Service

The representation of an application in ESCM. A technical service describes parameters and interfaces of the underlying application and is the basis for one or more marketable services.

Technology Manager

A privileged user role within a technology provider organization.

Technology Provider

An organization which provisions applications as technical services in ESCM.