# Molecular Assays

#### Version 1.9

Gleb Ebert

2025-04-29

#### **PCR**

Protocol adapted Macarena Toll-Riera and Promega

- 1. Harvest bacterial cells to run PCR on
  - Liquid culture:
    - 1. Transfer 20 μL of bacterial culture into a centrifuge tube containing 80 μL of sterile MilliQ
    - 2. Centrifuge at maximum speed for 3 minutes
    - 3. Discard supernatant and resuspend pellets in 50 µL sterile MilliQ
  - Colonies: Barely touch the colony with a pipette tip, place in  $50~\mu L$  of sterile MilliQ and pipette up and down a few times
- 2. Incubate at 95°C for 10 minutes in heating block
- 3. Centrifuge at maximum speed for 5 minutes
- 4. Store at 4°C
- 5. Perform PCR using Promega's GoTaq reagents
  - 1. Prepare a master mix for n + 1 reactions of 25  $\mu$ L each. This master mix will have a final primer concentration of 200 nM. Primer and water volume can be adjusted if necessary, also to accommodate more DNA template volume
    - 5.00 µL 5X GoTaq Green Buffer
    - 0.50 μL dNTP Mix (10 μM)
    - 0.125 μL GoTaq G2 Polymerase
    - 0.50 μL forward primer (10 μM)
    - 0.50 μL reverse primer (10 μM)
    - 18.00 µL nuclease-free water
  - 2. Add 24.00  $\mu$ L of master mix to PCR tubes and add 1.00  $\mu$ L DNA template to each
  - 3. Gently vortex and then briefly centrifuge reactions
  - 4. Start PCR program (cycle through steps 2-4 30 times; this will take just under 2 hours)
    - 1. Initial Denaturation for 2 min at 95°C
    - 2. Denaturation for 30 s at 95°C
    - 3. Annealing for 30 s at  $T_m 5$ °C
      - Use lower T<sub>m</sub> of each primer pair to calculate annealing temperature
      - Higher temperatures make annealing more specific
    - 4. Elongation for 1 min/kb at 72°C
    - 5. Final Elongation for 5 min at 72°C
    - 6. Hold at 4°C
- 6. Run gel as a control that amplification worked
  - 1. Prepare 1% agarose gel
    - 1. Add 1g of agarose to 100 mL 1x TAE buffer inside erlenmeyer flask and microwave at standard settings for 1 minute
    - 2. Add 10  $\mu$ L of SYBR Safe to the gel chamber
    - 3. Pour gel in small gel chamber with the comb appropriate for the number of samples. Use the comb to ensure SYBR Safe is properly mixed with the liquid
  - 2. Load 10 µL of a 1 kb ladder and PCR reaction directly into the gel (or 5 µL if using small wells)
  - 3. Run gel at 120V for 30 minutes and image it
  - 4. If PCR did not work, the DNA might have been too concentrated. Retry after dilluting the sample

#### 16S rRNA Sequencing

- 1. Perform PCR according to PCR
  - Use one of the following primer pairs. Melting temperatures according to the Promega calculator specifically for use with GoTaq G2 Green Master Mix and 200 nM primers

Primer Pair	r Specificity		Source		
16s_fw + 1	6s_rv PhTAC125 & I	E. coli	Toll-Riera et al	. 2022	
F27 + R152	5 universal, two	universal, two bands for $Ph$ TAC125		Lane et al. 1991, Stackebrandt et al. 1993	
Primer Pair	r	Annealing [°C]		Elongation [s]	
16s_fw + 1	6s_rv	60	1008	60	
F27 + R152	5	57	1528	90	
Primer S	Sequence	$T_m$ [°C]			
16s_fw C	GATCATGGCTCAGATTG	AACGC 65			
16s_rv A	AGGCACCAAACCATCTC	TGG 65			
F27 A	AGAGTTTGATCCTGGCT	CAG 62			
R1525 A	AAGGAGGTGATCCAGCC	CGCA 69			

- 2. PCR cleanup according to one of the following options:
  - Use the Promega Wizard SV Gel and PCR Cleanup System or the Qiagen QIAquick PCR Purification Kit according to the respective manufacturer protocols. Elute with 30  $\mu$ L of nuclease free water
  - According to protocol adapted from Macarena Toll-Riera
    - 1. Mix PCR cleanup reaction
      - 17 μL PCR product
      - ► 0.3 µL Exonuclease I
      - 0.3 μL Antarctic Phosphatase
      - 2.4 μL sterile MilliQ (to fill up volume)
      - Prepare a master mix for multiple reactions (n + 1) and add 3  $\mu$ L to each tube
    - 2. Incubate samples in thermocycler or waterbath
      - 1. 15 minutes at 37°C
      - 2. 15 minutes at 80-85°C
      - 3. Hold at 4°C
- 3. Measure DNA concentration and purity using the GDC's NanoDrop. 260/280 (protein purity) and 260/230 (salt purity) should both be between 1.8 and 2.0. The latter often tends to be as small as 1.2, even after using a PCR cleanup kit
- 4. Calculate the necessary dilution factor to reach a final DNA concentration of 1.5  $ng/\mu L$  per 100 bp of PCR product after adding primers. Taking this into account, the target DNA concentration before addition of primers should be:

$${\rm target~concentration} = \frac{{\rm product~length}~bp}{100~bp}*1.5\frac{ng}{\mu L}*\frac{15~\mu L}{12~\mu L}$$

E.g. for a 1.5 kb product the target concentration should 28.125  $ng/\mu L$ 

- 5. Prepare samples for sequencing by adding to each shipping tube
  - 12 μL purified PCR reaction at the appropriate DNA concentration
  - 3 μL 20 μM primer (just one, either forward or reverse)
- 6. Add Microsynth label to tube and register samples online. Print out order summary and package it in a clear plastic bag together with the samples
- 7. Bring samples to Microsynth pickup point at the main entrance of the LFV building

## **Additional Primers**

Melting temperatures according to the Promega calculator specifically for use with GoTaq G2 Green Master Mix and 200 nM primers

Primer Pair		Specificity	Source		
398078_fw + 398078_rv		PhTAC125	Macarena Toll-Riera		
Ml_rpoB_fw + Ml_rpoB_rv		Micrococcus spp.	Huang et al. 2019		
Primer Pair		Annealing [°C]	Product [bp]	Elongation [s]	
398078_fw + 398078_rv			58	346	30
$Ml\_rpoB\_fw + Ml\_rpoB\_rv$			58	891	60
Primer	Sequence		T <sub>m</sub> [°C]		
398078_fw	CATTTACTTACAGGGGCTCTGG		GG 62.1		
398078_rv	GCTCCGTGATTTCATCTCGC		60.5		
Ml_rpoB_fw	ATGAACGC	GACGAGGAGGTT	67		

## References

Ml\_rpoB\_rv GTTCTTCGGCACCTC**S**C

• Huang, C.-H. et al. Reclassification of Micrococcus aloeverae and Micrococcus yunnanensis as later heterotypic synonyms of Micrococcus luteus. *Int J Syst Evol Microbiol* 69, 3512–3518 (2019).

63-64