CS5760: Topics in Cryptanalysis

2025

Scribe: Gautam Singh

Lecture 1: 14 January 2025

Instructors: Maria Francis and M. V. Panduranga Rao

1.1 Differential Cryptanalysis

In differential cryptanalysis, we exploit the XOR between plaintext pairs in a chosen plaintext attack to find the secret key bits used in the cryptosystem. Per DES round, the XOR of a pair of inputs remains invariant.

- 1. Expansion E to get Si_E .
- 2. XOR with subkey K to get $Si_I = Si_E \oplus Si_K$.
- 3. Permutation after S boxes to get Si_O .




Figure 1.1: The F function of DES

The authors want to carry out a probabilistic analysis on the S boxes; this will estimate the number of plaintexts to be used for cryptanalysis. Immediately, they abstract out the key schedule by assuming all round subkeys are independent of each other.

1.2 Probability Analysis of S Boxes

We now focus on the S boxes. Suppose $Si'_I = Si_I \oplus Si^*_I$ is the input XOR and $Si'_O = Si_O \oplus Si^*_O$ is the output XOR. The authors compute the joint probability distribution function (PDF) of the input-output XOR pair (Si'_I, Si'_O) . This results in a 64-by-16 table of frequency distributions, since S boxes take 6-bit inputs to 4-bit outputs. This is called the *pairs XOR distribution table*.

For cryptanalysis, we can now talk about the conditional probability $Pr(Si'_I \mid Si'_O)$. At each round of DES, we know $Si'_I = Si'_E$ and we observe Si'_O . Using the pairs XOR distribution of that S box, we can get more

information about Si_I and Si_I^* , which can then be used to compute $Si_K = Si_I \oplus Si_E = Si_I^* \oplus Si_E^*$. It is trivial to now extend this pairs XOR probability to the entire F-function used in the Feistel network, since the only nonlinearlity in the input XOR is provided by the S boxes.

S box Si. Then, $S_I' \to S_O'$ with probability $P = \prod_{i=1}^8 p_i$ by the F function of that particular round. That is, the probabilities are *multiplicative*. Further, the P_j 's across the rounds j will also multiply, thereby reducing the chances of a particular input-output XOR pair of the entire iterated cryptosystem. The aim is to keep the total $P = \prod_{i=1}^n P_i$ over the n rounds of this cryptosystem high enough to be able to perform cryptanalysis quickly.

1.3 Characteristic

To formalize the cryptanalysis of iterated cryptosystems, we are introduced to the notion of a *characteristic*. This is a tuple $\Omega = (\Omega_P, \Omega_\Lambda, \Omega_T)$ which characterizes the XOR of a pair of plaintexts as they go through the same cryptosystem. The authors write $\Omega_\Lambda = (\Lambda_1, \dots, \Lambda_n)$ such that $\Lambda_i = (\lambda_I^i, \lambda_O^i)$ where λ_I^i is the input to the F function in the i-th round and λ_O^i is the corresponding output. For intermediate rounds, we have




Figure 1.2: An example of an n = 2 round characteristic.

Call a pair of plaintexts right with respect to Ω and an independent key K if this pair generates the XORs using the key K over the n rounds of encryption, and wrong otherwise. The probability of a characteristic is then the fraction of such plaintext pairs which satisfy $P' = \Omega_P$. It is not hard to see that they can be concatenated and the probabilities are multiplicative.

When Ω_T is the swapped value of the halves of Ω_P , we get an iterative characteristic: one that we can concatenate with itself to get characteristics of arbitrary length. An example of an iterative characteristic is shown in Figure 1.3. The best iterative characteristic has probability about $\frac{1}{234}$, where $\psi = 19$ 60 00 00.

1.4 Signal-to-Noise Ratio

analyze a large enough number of plaintext pairs and find some bits of a subkey With the knowledge of characteristics and their probabilities, we need to (and thus the master key) entering certain S boxes. This is done with a simple counting approach, and intuitively the most frequently suggested subkey is likely to be the actual subkey used.




Figure 1.3: Example of an iterative characteristic where $\psi \to 0$.

approaches. To do this, we define the *signal-to-noise ratio* of a counting However, we did not account for the time and memory complexity of such counting scheme as the ratio of the number of right pairs to the average count, denoted by S/N. Suppose we want to find k subkey bits in a cryptosystem of block size m. Let α be the average count per counted pair and β be the fraction of counted pairs. Then, for a characteristic probability p,

$$S/N = \frac{mp}{\frac{m\alpha\beta}{2^k}} = \frac{2^k p}{\alpha\beta}.$$
 (1.2)

This shows that S/N is independent of the block size and the number of pairs used. A larger S/N implies fewer plaintext pairs are needed and conversely. To improve S/N, we consider fewer plaintexts that can pair up to form right pairs for various characteristics such as *quartet* (four plaintexts with two pairs each of two characteristics) and *octet* (eight plaintexts, four pairs each of three characteristics). This also saves memory since we can reuse the plaintexts for different characteristics.