# **PyAutoGUI Documentation**

**Al Sweigart** 

## Contents

2	FAQ:	FAQ: Frequently Asked Questions				
3	Fail-Safes					
	3.1	Installation				
	3.2	Cheat Sheet				
	3.3	Mouse Control Functions				
	3.4	Keyboard Control Functions				
	3.5	Message Box Functions				
	3.6	Screenshot Functions				
	3.7	Testing				
	3.8	Roadmap				
	3.9	pyautogui				
1	India	es and tables				

PyAutoGUI lets your Python scripts control the mouse and keyboard to automate interactions with other applications. The API is designed to be simple. PyAutoGUI works on Windows, macOS, and Linux, and runs on Python 2 and 3.

To install with pip, run pip install pyautogui. See the *Installation* page for more details.

The source code is available on: https://github.com/asweigart/pyautogui

PyAutoGUI has several features:

- Moving the mouse and clicking in the windows of other applications.
- Sending keystrokes to applications (for example, to fill out forms).
- Take screenshots, and given an image (for example, of a button or checkbox), and find it on the screen.
- · Locate an application's window, and move, resize, maximize, minimize, or close it (Windows-only, currently).
- Display alert and message boxes.

Here's a YouTube video of a bot automatically playing the game Sushi Go Round. The bot watches the game's application window and searches for images of sushi orders. When it finds one, it clicks the ingredient buttons to make the sushi. It also clicks the phone in the game to order more ingredients as needed. The bot is completely autonomous and can finish all seven days of the game. This is the kind of automation that PyAutoGUI is capable of.

Contents 1

2 Contents

## CHAPTER 1

### Examples

```
>>> import pyautogui
>>> screenWidth, screenHeight = pyautogui.size() # Get the size of the primary_
>>> screenWidth, screenHeight
(2560, 1440)
>>> currentMouseX, currentMouseY = pyautogui.position() # Get the XY position of the_
>>> currentMouseX, currentMouseY
(1314, 345)
>>> pyautogui.moveTo(100, 150) # Move the mouse to XY coordinates.
>>> pyautogui.click()
                               # Click the mouse.
>>> pyautogui.click(100, 200) # Move the mouse to XY coordinates and click it.
>>> pyautogui.click('button.png') # Find where button.png appears on the screen and_
\hookrightarrow click it.
>>> pyautogui.move(400, 0)
                                # Move the mouse 400 pixels to the right of its.
⇔current position.
>>> pyautogui.doubleClick()
                               # Double click the mouse.
>>> pyautogui.moveTo(500, 500, duration=2, tween=pyautogui.easeInOutQuad) # Use.
→tweening/easing function to move mouse over 2 seconds.
>>> pyautogui.write('Hello world!', interval=0.25) # type with quarter-second pause_
→in between each key
>>> pyautogui.press('esc')
                              # Press the Esc key. All key names are in pyautogui.
→ KEY_NAMES
>>> with pyautogui.hold('shift'): # Press the Shift key down and hold it.
        pyautogui.press(['left', 'left', 'left', 'left']) # Press the left arrow key_
\rightarrow4 times.
>>> # Shift key is released automatically.
```


(continues on next page)

(continued from previous page)

```
>>> pyautogui.hotkey('ctrl', 'c') # Press the Ctrl-C hotkey combination.
>>> pyautogui.alert('This is the message to display.') # Make an alert box appear and pause the program until OK is clicked.
```

This example drags the mouse in a square spiral shape in MS Paint (or any graphics drawing program):

```
>>> distance = 200
>>> while distance > 0:
    pyautogui.drag(distance, 0, duration=0.5) # move right
    distance -= 5
    pyautogui.drag(0, distance, duration=0.5) # move down
    pyautogui.drag(-distance, 0, duration=0.5) # move left
    distance -= 5
    pyautogui.drag(0, -distance, duration=0.5) # move up
```



The benefit of using PyAutoGUI, as opposed to a script that directly generates the image file, is that you can use the brush tools that MS Paint provides.

## CHAPTER 2

FAQ: Frequently Asked Questions

Send questions to al@inventwithpython.com

Q: Can PyAutoGUI work on Android, iOS, or tablet/smartphone apps.

A: Unfortunately no. PyAutoGUI only runs on Windows, macOS, and Linux.

Q: Does PyAutoGUI work on multi-monitor setups.

A: No, right now PyAutoGUI only handles the primary monitor.

Q: Does PyAutoGUI do OCR?

A: No, but this is a feature that's on the roadmap.

Q: Can PyAutoGUI do keylogging, or detect if a key is currently pressed down?

A: No, PyAutoGUI cannot do this currently.

## CHAPTER 3

### Fail-Safes



Like the enchanted brooms from the Sorcerer's Apprentice programmed to keep filling (and then overfilling) the bath with water, a bug in your program could make it go out of control. It's hard to use the mouse to close a program if the mouse cursor is moving around on its own.

As a safety feature, a fail-safe feature is enabled by default. When a PyAutoGUI function is called, if the mouse is in any of the four corners of the primary monitor, they will raise a pyautogui.FailSafeException. There is a one-tenth second delay after calling every PyAutoGUI functions to give the user time to slam the mouse into a corner to trigger the fail safe.

You can disable this failsafe by setting pyautogui.FAILSAFE = False. I HIGHLY RECOMMEND YOU DO NOT DISABLE THE FAILSAFE.

The tenth-second delay is set by the pyautogui.PAUSE setting, which is 0.1 by default. You can change this value. There is also a pyautogui.DARWIN\_CATCH\_UP\_TIME setting which adds an additional delay on macOS

after keyboard and mouse events, since the operating system appears to need a delay after PyAutoGUI issues these events. It is set to 0.01 by default, adding an additional hundredth-second delay.

Contents:

### 3.1 Installation

To install PyAutoGUI, install the pyautogui package from PyPI by running pip install pyautogui (on Windows) or pip3 install pyautogui (on macOS and Linux). (On macOS and Linux, pip refers to Python 2's pip tool.)

OS-specific instructions are below.

#### 3.1.1 Windows

On Windows, you can use the py.exe program to run the latest version of Python:

```
py -m pip install pyautogui
```

If you have multiple versions of Python installed, you can select which one with a command line argument to py. For example, for Python 3.8, run:

```
py -3.8 -m pip install pyautogui
```

(This is the same as running pip install pyautogui.)

### 3.1.2 macOS

On macOS and Linux, you need to run python3:

```
python3 -m pip install pyautogui
```

If you are running El Capitan and have problems installing pyobjc try:

```
MACOSX_DEPLOYMENT_TARGET=10.11 pip install pyobjc
```

#### 3.1.3 Linux

On macOS and Linux, you need to run python3:

```
python3 -m pip install pyautogui
```

On Linux, additionally you need to install the scrot application, as well as Tkinter:

```
sudo apt-get install scrot
sudo apt-get install python3-tk
sudo apt-get install python3-dev
```

PyAutoGUI install the modules it depends on, including PyTweening, PyScreeze, PyGetWindow, PymsgBox, and MouseInfo.

### 3.2 Cheat Sheet

This is a quickstart reference to using PyAutoGUI. PyAutoGUI is cross-platform GUI automation module that works on Python 2 & 3. You can control the mouse and keyboard as well as perform basic image recognition to automate tasks on your computer.

All the keyword arguments in the examples on this page are optional.

```
>>> import pyautogui
```

PyAutoGUI works on Windows/Mac/Linux and on Python 2 & 3. Install from PyPI with pip install pyautogui.

### 3.2.1 General Functions

```
>>> pyautogui.position() # current mouse x and y
(968, 56)
>>> pyautogui.size() # current screen resolution width and height
(1920, 1080)
>>> pyautogui.onScreen(x, y) # True if x & y are within the screen.
True
```

### 3.2.2 Fail-Safes

Set up a 2.5 second pause after each PyAutoGUI call:

```
>>> import pyautogui
>>> pyautogui.PAUSE = 2.5
```

When fail-safe mode is True, moving the mouse to the upper-left will raise a pyautogui. FailSafeException that can abort your program:

```
>>> import pyautogui
>>> pyautogui.FAILSAFE = True
```

#### 3.2.3 Mouse Functions

XY coordinates have 0, 0 origin at top left corner of the screen. X increases going right, Y increases going down.

If duration is 0 or unspecified, movement is immediate. Note: dragging on Mac can't be immediate.

Calling click() just clicks the mouse once with the left button at the mouse's current location, but the keyword arguments can change that:

3.2. Cheat Sheet 9

```
>>> pyautogui.click(x=moveToX, y=moveToY, clicks=num_of_clicks, interval=secs_between_

--clicks, button='left')
```

The button keyword argument can be 'left', 'middle', or 'right'.

All clicks can be done with click (), but these functions exist for readability. Keyword args are optional:

```
>>> pyautogui.rightClick(x=moveToX, y=moveToY)
>>> pyautogui.middleClick(x=moveToX, y=moveToY)
>>> pyautogui.doubleClick(x=moveToX, y=moveToY)
>>> pyautogui.tripleClick(x=moveToX, y=moveToY)
```

Positive scrolling will scroll up, negative scrolling will scroll down:

```
>>> pyautogui.scroll(amount_to_scroll, x=moveToX, y=moveToY)
```

Individual button down and up events can be called separately:

```
>>> pyautogui.mouseDown(x=moveToX, y=moveToY, button='left')
>>> pyautogui.mouseUp(x=moveToX, y=moveToY, button='left')
```

### 3.2.4 Keyboard Functions

Key presses go to wherever the keyboard cursor is at function-calling time.

```
>>> pyautogui.typewrite('Hello world!\n', interval=secs_between_keys) # useful for_ 

entering text, newline is Enter
```

A list of key names can be passed too:

```
>>> pyautogui.typewrite(['a', 'b', 'c', 'left', 'backspace', 'enter', 'f1'], __ 
interval=secs_between_keys)
```

The full list of key names is in pyautogui. KEYBOARD\_KEYS.

Keyboard hotkeys like Ctrl-S or Ctrl-Shift-1 can be done by passing a list of key names to hotkey ():

```
>>> pyautogui.hotkey('ctrl', 'c') # ctrl-c to copy
>>> pyautogui.hotkey('ctrl', 'v') # ctrl-v to paste
```

Individual button down and up events can be called separately:

```
>>> pyautogui.keyDown(key_name)
>>> pyautogui.keyUp(key_name)
```

### 3.2.5 Message Box Functions

If you need to pause the program until the user clicks OK on something, or want to display some information to the user, the message box functions have similar names that JavaScript has:

```
>>> pyautogui.alert('This displays some text with an OK button.')
>>> pyautogui.confirm('This displays text and has an OK and Cancel button.')
'OK'
>>> pyautogui.prompt('This lets the user type in a string and press OK.')
'This is what I typed in.'
```

The prompt () function will return None if the user clicked Cancel.

#### 3.2.6 Screenshot Functions

PyAutoGUI uses Pillow/PIL for its image-related data.

On Linux, you must run sudo apt-get install scrot to use the screenshot features.

If you have an image file of something you want to click on, you can find it on the screen with locateOnScreen().

```
>>> pyautogui.locateOnScreen('looksLikeThis.png') # returns (left, top, width, wheight) of first place it is found (863, 417, 70, 13)
```

The locateAllOnScreen () function will return a generator for all the locations it is found on the screen:

```
>>> for i in pyautogui.locateAllOnScreen('looksLikeThis.png')
...
(863, 117, 70, 13)
(623, 137, 70, 13)
(853, 577, 70, 13)
(883, 617, 70, 13)
(973, 657, 70, 13)
(933, 877, 70, 13)
```

```
>>> list(pyautogui.locateAllOnScreen('looksLikeThis.png'))
[(863, 117, 70, 13), (623, 137, 70, 13), (853, 577, 70, 13), (883, 617, 70, 13), (973, 4657, 70, 13), (933, 877, 70, 13)]
```

The locateCenterOnScreen() function just returns the XY coordinates of the middle of where the image is found on the screen:

```
>>> pyautogui.locateCenterOnScreen('looksLikeThis.png') # returns center x and y (898, 423)
```

These functions return None if the image couldn't be found on the screen.

Note: The locate functions are slow and can take a full second or two.

### 3.3 Mouse Control Functions

#### 3.3.1 The Screen and Mouse Position

Locations on your screen are referred to by X and Y Cartesian coordinates. The X coordinate starts at 0 on the left side and increases going right. Unlike in mathematics, the Y coordinate starts at 0 on the top and increases going down.

The pixel at the top-left corner is at coordinates 0, 0. If your screen's resolution is 1920 x 1080, the pixel in the lower right corner will be 1919, 1079 (since the coordinates begin at 0, not 1).

The screen resolution size is returned by the size() function as a tuple of two integers. The current X and Y coordinates of the mouse cursor are returned by the position() function.

For example:

```
>>> pyautogui.size()
(1920, 1080)
>>> pyautogui.position()
(187, 567)
```

Here is a short Python 3 program that will constantly print out the position of the mouse cursor:

```
#! python3
import pyautogui, sys
print('Press Ctrl-C to quit.')
try:
    while True:
        x, y = pyautogui.position()
        positionStr = 'X: ' + str(x).rjust(4) + ' Y: ' + str(y).rjust(4)
        print(positionStr, end='')
        print('\b' * len(positionStr), end='', flush=True)
except KeyboardInterrupt:
    print('\n')
```

Here is the Python 2 version:

```
#! python
import pyautogui, sys
print('Press Ctrl-C to quit.')
try:
    while True:
        x, y = pyautogui.position()
        positionStr = 'X: ' + str(x).rjust(4) + ' Y: ' + str(y).rjust(4)
        print positionStr,
        print '\b' * (len(positionStr) + 2),
        sys.stdout.flush()
except KeyboardInterrupt:
    print '\n'
```

To check if XY coordinates are on the screen, pass them (either as two integer arguments or a single tuple/list arguments with two integers) to the onScreen() function, which will return True if they are within the screen's boundaries and False if not. For example:

```
>>> pyautogui.onScreen(0, 0)
True
```

(continues on next page)

(continued from previous page)

```
>>> pyautogui.onScreen(0, -1)
False
>>> pyautogui.onScreen(0, 99999999)
False
>>> pyautogui.size()
(1920, 1080)
>>> pyautogui.onScreen(1920, 1080)
False
>>> pyautogui.onScreen(1919, 1079)
True
```

#### 3.3.2 Mouse Movement

The moveTo () function will move the mouse cursor to the X and Y integer coordinates you pass it. The None value can be passed for a coordinate to mean "the current mouse cursor position". For example:

```
>>> pyautogui.moveTo(100, 200)  # moves mouse to X of 100, Y of 200.
>>> pyautogui.moveTo(None, 500)  # moves mouse to X of 100, Y of 500.
>>> pyautogui.moveTo(600, None)  # moves mouse to X of 600, Y of 500.
```

Normally the mouse cursor will instantly move to the new coordinates. If you want the mouse to gradually move to the new location, pass a third argument for the duration (in seconds) the movement should take. For example:

```
>>> pyautogui.moveTo(100, 200, 2) # moves mouse to X of 100, Y of 200 over 2 seconds
```

(If the duration is less than pyautogui.MINIMUM\_DURATION the movement will be instant. By default, pyautogui.MINIMUM DURATION is 0.1.)

If you want to move the mouse cursor over a few pixels *relative* to its current position, use the move () function. This function has similar parameters as moveTo(). For example:

```
>>> pyautogui.moveTo(100, 200) # moves mouse to X of 100, Y of 200.
>>> pyautogui.move(0, 50) # move the mouse down 50 pixels.
>>> pyautogui.move(-30, 0) # move the mouse left 30 pixels.
>>> pyautogui.move(-30, None) # move the mouse left 30 pixels.
```

### 3.3.3 Mouse Drags

PyAutoGUI's dragTo() and drag() functions have similar parameters as the moveTo() and move() functions. In addition, they have a button keyword which can be set to 'left', 'middle', and 'right' for which mouse button to hold down while dragging. For example:

```
>>> pyautogui.dragTo(100, 200, button='left') # drag mouse to X of 100, Y of 200_

while holding down left mouse button
>>> pyautogui.dragTo(300, 400, 2, button='left') # drag mouse to X of 300, Y of 400_

while holding down left mouse button
>>> pyautogui.drag(30, 0, 2, button='right') # drag the mouse left 30 pixels over 2_

while holding down the right mouse button
```

### 3.3.4 Tween / Easing Functions

Tweening is an extra feature to make the mouse movements fancy. You can probably skip this section if you don't care about this.

A tween or easing function dictates the progress of the mouse as it moves to its destination. Normally when moving the mouse over a duration of time, the mouse moves directly towards the destination in a straight line at a constant speed. This is known as a *linear tween* or *linear easing* function.

PyAutoGUI has other tweening functions available in the pyautogui module. The pyautogui.easeInQuad function can be passed for the 4th argument to moveTo(), move(), dragTo(), and drag() functions to have the mouse cursor start off moving slowly and then speeding up towards the destination. The total duration is still the same as the argument passed to the function. The pyautogui.easeOutQuad is the reverse: the mouse cursor starts moving fast but slows down as it approaches the destination. The pyautogui.easeOutElastic will overshoot the destination and "rubber band" back and forth until it settles at the destination.

For example:

These tweening functions are copied from Al Sweigart's PyTweening module: https://pypi.python.org/pypi/PyTweening https://github.com/asweigart/pytweening This module does not have to be installed to use the tweening functions.

If you want to create your own tweening function, define a function that takes a single float argument between 0.0 (representing the start of the mouse travelling) and 1.0 (representing the end of the mouse travelling) and returns a float value between 0.0 and 1.0.

#### 3.3.5 Mouse Clicks

The click () function simulates a single, left-button mouse click at the mouse's current position. A "click" is defined as pushing the button down and then releasing it up. For example:

```
>>> pyautogui.click() # click the mouse
```

To combine a moveTo () call before the click, pass integers for the x and y keyword argument:

To specify a different mouse button to click, pass 'left', 'middle', or 'right' for the button keyword argument:

```
>>> pyautogui.click(button='right') # right-click the mouse
```

To do multiple clicks, pass an integer to the clicks keyword argument. Optionally, you can pass a float or integer to the interval keyword argument to specify the amount of pause between the clicks in seconds. For example:

(continued from previous page)

As a convenient shortcut, the doubleClick() function will perform a double click of the left mouse button. It also has the optional x, y, interval, and button keyword arguments. For example:

```
>>> pyautogui.doubleClick() # perform a left-button double click
```

There is also a tripleClick () function with similar optional keyword arguments.

The rightClick() function has optional x and y keyword arguments.

### 3.3.6 The mouseDown() and mouseUp() Functions

Mouse clicks and drags are composed of both pressing the mouse button down and releasing it back up. If you want to perform these actions separately, call the mouseDown() and mouseUp() functions. They have the same x, y, and button. For example:

### 3.3.7 Mouse Scrolling

The mouse scroll wheel can be simulated by calling the scroll () function and passing an integer number of "clicks" to scroll. The amount of scrolling in a "click" varies between platforms. Optionally, integers can be passed for the the x and y keyword arguments to move the mouse cursor before performing the scroll. For example:

On OS X and Linux platforms, PyAutoGUI can also perform horizontal scrolling by calling the hscroll() function. For example:

```
>>> pyautogui.hscroll(10)  # scroll right 10 "clicks"
>>> pyautogui.hscroll(-10)  # scroll left 10 "clicks"
```

The scroll () function is a wrapper for vscroll (), which performs vertical scrolling.

### 3.4 Keyboard Control Functions

### 3.4.1 The write() Function

The primary keyboard function is write(). This function will type the characters in the string that is passed. To add a delay interval in between pressing each character key, pass an int or float for the interval keyword argument.

For example:

```
>>> pyautogui.write('Hello world!') # prints out "Hello world!" 

\(\therefore\) instantly
>>> pyautogui.write('Hello world!', interval=0.25) # prints out "Hello world!" with \(\therefore\) \(\therefore\) quarter second delay after each character
```

You can only press single-character keys with write (), so you can't press the Shift or F1 keys, for example.

### 3.4.2 The press(), keyDown(), and keyUp() Functions

To press these keys, call the press () function and pass it a string from the pyautogui.KEYBOARD\_KEYS such as enter, esc, f1. See KEYBOARD\_KEYS.

For example:

```
>>> pyautogui.press('enter') # press the Enter key
>>> pyautogui.press('f1') # press the F1 key
>>> pyautogui.press('left') # press the left arrow key
```

The press () function is really just a wrapper for the keyDown () and keyUp() functions, which simulate pressing a key down and then releasing it up. These functions can be called by themselves. For example, to press the left arrow key three times while holding down the Shift key, call the following:

```
>>> pyautogui.keyDown('shift')  # hold down the shift key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.keyUp('shift')  # release the shift key
```

To press multiple keys similar to what write() does, pass a list of strings to press(). For example:

```
>>> pyautogui.press(['left', 'left', 'left'])
```

Or you can set how many presses left:

```
>>> pyautogui.press('left', presses=3)
```

To add a delay interval in between each press, pass an int or float for the interval keyword argument.

### 3.4.3 The hold() Context Manager

To make holding a key convenient, the hold() function can be used as a context manager and passed a string from the pyautogui.KEYBOARD\_KEYS such as shift, ctrl, alt, and this key will be held for the duration of the with context block. See *KEYBOARD\_KEYS*.

```
>>> with pyautogui.hold('shift'):
    pyautogui.press(['left', 'left'])
```

... is equivalent to this code:

```
>>> pyautogui.keyDown('shift')  # hold down the shift key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.press('left')  # press the left arrow key
>>> pyautogui.keyUp('shift')  # release the shift key
```

### 3.4.4 The hotkey() Function

To make pressing hotkeys or keyboard shortcuts convenient, the hotkey() can be passed several key strings which will be pressed down in order, and then released in reverse order. This code:

```
>>> pyautogui.hotkey('ctrl', 'shift', 'esc')
```

...is equivalent to this code:

```
>>> pyautogui.keyDown('ctrl')
>>> pyautogui.keyDown('shift')
>>> pyautogui.keyDown('esc')
>>> pyautogui.keyUp('esc')
>>> pyautogui.keyUp('shift')
>>> pyautogui.keyUp('ctrl')
```

To add a delay interval in between each press, pass an int or float for the interval keyword argument.

### 3.4.5 KEYBOARD\_KEYS

The following are the valid strings to pass to the press (), keyDown (), keyUp (), and hotkey () functions:

```
['\t', '\n', '\r', ' ', '!', '"', '#', '$', '%', '&', "'", '(',
')', '*', '+', ',', '-', '.', '/', '0', '1', '2', '3', '4', '5',
'8', '9', ':', ';', '<', '=', '>', '?', '@', '[', '\\', ']', '^', '_', '`,
'a', 'b', 'c', 'd', 'e','f', 'g', 'h', 'i', 'j', 'k', 'l', 'm', 'n', 'o',
'p', 'q', 'r', 's', 't', 'u', 'v', 'w', 'x', 'y', 'z', '{', '|', '}', '~',
'accept', 'add', 'alt', 'altleft', 'altright', 'apps', 'backspace',
'browserback', 'browserfavorites', 'browserforward', 'browserhome',
'browserrefresh', 'browsersearch', 'browserstop', 'capslock', 'clear',
'convert', 'ctrl', 'ctrlleft', 'ctrlright', 'decimal', 'del', 'delete',
'divide', 'down', 'end', 'enter', 'esc', 'escape', 'execute', 'f1', 'f10',
'f11', 'f12', 'f13', 'f14', 'f15', 'f16', 'f17', 'f18', 'f19', 'f2', 'f20',
'f21', 'f22', 'f23', 'f24', 'f3', 'f4', 'f5', 'f6', 'f7', 'f8', 'f9',
'final', 'fn', 'hanquel', 'hanquel', 'hanja', 'help', 'home', 'insert', 'junja',
'kana', 'kanji', 'launchapp1', 'launchapp2', 'launchmail',
'launchmediaselect', 'left', 'modechange', 'multiply', 'nexttrack',
'nonconvert', 'num0', 'num1', 'num2', 'num3', 'num4', 'num5', 'num6',
'num7', 'num8', 'num9', 'numlock', 'pagedown', 'pageup', 'pause', 'pgdn',
'pgup', 'playpause', 'prevtrack', 'print', 'printscreen', 'prntscrn',
'prtsc', 'prtscr', 'return', 'right', 'scrolllock', 'select', 'separator',
'shift', 'shiftleft', 'shiftright', 'sleep', 'space', 'stop', 'subtract', 'tab',
'up', 'volumedown', 'volumemute', 'volumeup', 'win', 'winleft', 'winright', 'yen',
'command', 'option', 'optionleft', 'optionright']
```

### 3.5 Message Box Functions

PyAutoGUI makes use of the message box functions in PyMsgBox to provide a cross-platform, pure Python way to display JavaScript-style message boxes. There are four message box functions provided:

### 3.5.1 The alert() Function

```
>>> alert(text='', title='', button='OK')
```

Displays a simple message box with text and a single OK button. Returns the text of the button clicked on.

### 3.5.2 The confirm() Function

```
>>> confirm(text='', title='', buttons=['OK', 'Cancel'])
```

Displays a message box with OK and Cancel buttons. Number and text of buttons can be customized. Returns the text of the button clicked on.

### 3.5.3 The prompt() Function

```
>>> prompt(text='', title='' , default='')
```

Displays a message box with text input, and OK & Cancel buttons. Returns the text entered, or None if Cancel was clicked.

### 3.5.4 The password() Function

```
>>> password(text='', title='', default='', mask='*')
```

Displays a message box with text input, and OK & Cancel buttons. Typed characters appear as \*. Returns the text entered, or None if Cancel was clicked.

### 3.6 Screenshot Functions

PyAutoGUI can take screenshots, save them to files, and locate images within the screen. This is useful if you have a small image of, say, a button that needs to be clicked and want to locate it on the screen. These features are provided by the PyScreeze module, which is installed with PyAutoGUI.

Screenshot functionality requires the Pillow module. OS X uses the screencapture command, which comes with the operating system. Linux uses the scrot command, which can be installed by running sudo apt-get install scrot.

### 3.6.1 The screenshot() Function

Calling screenshot () will return an Image object (see the Pillow or PIL module documentation for details). Passing a string of a filename will save the screenshot to a file as well as return it as an Image object.

```
>>> import pyautogui
>>> im1 = pyautogui.screenshot()
>>> im2 = pyautogui.screenshot('my_screenshot.png')
```

On a 1920 x 1080 screen, the screenshot () function takes roughly 100 milliseconds - it's not fast but it's not slow.


There is also an optional region keyword argument, if you do not want a screenshot of the entire screen. You can pass a four-integer tuple of the left, top, width, and height of the region to capture:

```
>>> import pyautogui
>>> im = pyautogui.screenshot(region=(0,0, 300, 400))
```

### 3.6.2 The Locate Functions

NOTE: As of version 0.9.41, if the locate functions can't find the provided image, they'll raise ImageNotFoundException instead of returning None.

You can visually locate something on the screen if you have an image file of it. For example, say the calculator app was running on your computer and looked like this:



You can't call the moveTo() and click() functions if you don't know the exact screen coordinates of where the calculator buttons are. The calculator can appear in a slightly different place each time it is launched, causing you to re-find the coordinates each time. However, if you have an image of the button, such as the image of the 7 button:



... you can call the locateOnScreen ('calc7key.png') function to get the screen coordinates. The return value is a 4-integer tuple: (left, top, width, height). This tuple can be passed to center() to get the X and Y coordinates at the center of this region. If the image can't be found on the screen, locateOnScreen() raises ImageNotFoundException.

```
>>> import pyautogui
>>> button7location = pyautogui.locateOnScreen('calc7key.png')
>>> button7location
Box(left=1416, top=562, width=50, height=41)
>>> button7location[0]
>>> button7location.left
1416
>>> button7point = pyautogui.center(button7location)
>>> button7point
Point (x=1441, y=582)
>>> button7point[0]
>>> button7point.x
1441
>>> button7x, button7y = button7point
>>> pyautogui.click(button7x, button7y) # clicks the center of where the 7 button,
⇔was found
>>> pyautoqui.click('calc7key.png') # a shortcut version to click on the center of,
→where the 7 button was found
```

The optional confidence keyword argument specifies the accuracy with which the function should locate the image on screen. This is helpful in case the function is not able to locate an image due to negligible pixel differences:

```
>>> import pyautogui
>>> button7location = pyautogui.locateOnScreen('calc7key.png', confidence=0.9)
>>> button7location
Box(left=1416, top=562, width=50, height=41)
```

Note: You need to have OpenCV installed for the confidence keyword to work.

The locateCenterOnScreen() function combines locateOnScreen() and center():

```
>>> import pyautogui
>>> x, y = pyautogui.locateCenterOnScreen('calc7key.png')
>>> pyautogui.click(x, y)
```

On a 1920 x 1080 screen, the locate function calls take about 1 or 2 seconds. This may be too slow for action video games, but works for most purposes and applications.

There are several "locate" functions. They all start looking at the top-left corner of the screen (or image) and look to the right and then down. The arguments can either be a

- locateOnScreen (image, grayscale=False) Returns (left, top, width, height) coordinate of first found instance of the image on the screen. Raises ImageNotFoundException if not found on the screen.
- locateCenterOnScreen(image, grayscale=False) Returns (x, y) coordinates of the center of the first found instance of the image on the screen. Raises ImageNotFoundException if not found on the screen.
- locateAllOnScreen (image, grayscale=False) Returns a generator that yields (left, top, width, height) tuples for where the image is found on the screen.
- locate(needleImage, haystackImage, grayscale=False) Returns (left, top, width, height) coordinate of first found instance of needleImage in haystackImage. Raises

ImageNotFoundException if not found on the screen.

• locateAll (needleImage, haystackImage, grayscale=False) - Returns a generator that yields (left, top, width, height) tuples for where needleImage is found in haystackImage.

The "locate all" functions can be used in for loops or passed to list():

```
>>> import pyautogui
>>> for pos in pyautogui.locateAllOnScreen('someButton.png')
... print(pos)
...
(1101, 252, 50, 50)
(59, 481, 50, 50)
(1395, 640, 50, 50)
(1838, 676, 50, 50)
>>> list(pyautogui.locateAllOnScreen('someButton.png'))
[(1101, 252, 50, 50), (59, 481, 50, 50), (1395, 640, 50, 50), (1838, 676, 50, 50)]
```

These "locate" functions are fairly expensive; they can take a full second to run. The best way to speed them up is to pass a region argument (a 4-integer tuple of (left, top, width, height)) to only search a smaller region of the screen instead of the full screen:

```
>>> import pyautogui
>>> pyautogui.locateOnScreen('someButton.png', region=(0,0, 300, 400))
```

### **Grayscale Matching**

Optionally, you can pass grayscale=True to the locate functions to give a slight speedup (about 30%-ish). This desaturates the color from the images and screenshots, speeding up the locating but potentially causing false-positive matches.

```
>>> import pyautogui
>>> button7location = pyautogui.locateOnScreen('calc7key.png', grayscale=True)
>>> button7location
(1416, 562, 50, 41)
```

### **Pixel Matching**

To obtain the RGB color of a pixel in a screenshot, use the Image object's getpixel() method:

```
>>> import pyautogui
>>> im = pyautogui.screenshot()
>>> im.getpixel((100, 200))
(130, 135, 144)
```

Or as a single function, call the pixel() PyAutoGUI function, which is a wrapper for the previous calls:

```
>>> import pyautogui
>>> pix = pyautogui.pixel(100, 200)
>>> pix
RGB(red=130, green=135, blue=144)
>>> pix[0]
130
>>> pix.red
130
```

If you just need to verify that a single pixel matches a given pixel, call the pixelMatchesColor() function, passing it the X coordinate, Y coordinate, and RGB tuple of the color it represents:

```
>>> import pyautogui
>>> pyautogui.pixelMatchesColor(100, 200, (130, 135, 144))
True
>>> pyautogui.pixelMatchesColor(100, 200, (0, 0, 0))
False
```

The optional tolerance keyword argument specifies how much each of the red, green, and blue values can vary while still matching:

```
>>> import pyautogui
>>> pyautogui.pixelMatchesColor(100, 200, (130, 135, 144))
True
>>> pyautogui.pixelMatchesColor(100, 200, (140, 125, 134))
False
>>> pyautogui.pixelMatchesColor(100, 200, (140, 125, 134), tolerance=10)
True
```

### 3.7 Testing

The unit tests for PyAutoGUI are currently not comprehensive. The tests (in basicTests.py) cover the following:

- onScreen()
- size()
- position()
- moveTo()
- moveRel()
- typewrite()
- PAUSE

### 3.7.1 Platforms Tested

- Python 3.4, 3.3, 3.2, 3.1, 2.7, 2.6, 2.5
- · Windows
- OS X
- · Raspberry Pi

(If you have run the unit tests successfully on other platforms, please tell al@inventwithpython.com.)

PyAutoGUI is not compatible with Python 2.4 or before.

The keyboard functions do not work on Ubuntu when run in VirtualBox on Windows.

### 3.8 Roadmap

PyAutoGUI is planned as a replacement for other Python GUI automation scripts, such as PyUserInput, PyKeyboard, PyMouse, pykey, etc. Eventually it would be great to offer the same type of features that Sikuli offers.

For now, the primary aim for PyAutoGUI is cross-platform mouse and keyboard control and a simple API.

Future features planned (specific versions not planned yet):

- A tool for determining why an image can't be found in a particular screenshot. (This is a common source of questions for users.)
- Full compatibility on Raspberry Pis.
- "Wave" function, which is used just to see where the mouse is by shaking the mouse cursor a bit. A small helper function.
- locateNear() function, which is like the other locate-related screen reading functions except it finds the first instance near an xy point on the screen.
- Find a list of all windows and their captions.
- Click coordinates relative to a window, instead of the entire screen.
- Make it easier to work on systems with multiple monitors.
- GetKeyState() type of function
- Ability to set global hotkey on all platforms so that there can be an easy "kill switch" for GUI automation programs.
- Optional nonblocking pyautogui calls.
- "strict" mode for keyboard passing an invalid keyboard key causes an exception instead of silently skipping it.
- rename keyboardMapping to KEYBOARD\_MAPPING
- Ability to convert png and other image files into a string that can be copy/pasted directly in the source code, so that they don't have to be shared separately with people's pyautogui scripts.
- Test to make sure pyautogui works in Windows/mac/linux VMs.
- A way to compare two images and highlight differences between them (good for pointing out when a UI changes, etc.)

#### Window handling features:

- pyautogui.getWindows() # returns a dict of window titles mapped to window IDs
- pyautogui.getWindow(str\_title\_or\_int\_id) # returns a "Win" object
- win.move(x, y)
- · win.resize(width, height)
- win.maximize()
- win.minimize()
- win.restore()
- win.close()
- win.position() # returns (x, y) of top-left corner
- win.moveRel(x=0, y=0) # moves relative to the x, y of top-left corner of the window

3.8. Roadmap 23

### **PyAutoGUI Documentation**

- win.clickRel(x=0, y=0, clicks=1, interval=0.0, button='left') # click relative to the x, y of top-left corner of the window
- Additions to screenshot functionality so that it can capture specific windows instead of full screen.

## 3.9 pyautogui

### 3.9.1 pyautogui package

**Submodules** 

pyautogui.keynames module

**Module contents** 

This documentation is still a work in progress.

## $\mathsf{CHAPTER}\, 4$

## Indices and tables

- genindex
- modindex
- search