Language Framework for Optimal Schedulers (LFOS)

Guideline for Users

Güner Orhan

December 28, 2016

1 Required Modules

In order to use LFOS frameowrk API, a programmer should import the required module:

```
from LFOS. Scheduler. Scheduler import Scheduler
from LFOS. Resource. Resource import *
from LFOS. Task. Task import *
from LFOS. Scheduling. Characteristic. Time import Time
from LFOS. macros import *
```

Listing 1: Importing required modules

2 Scheduler

Based on the selected instance, the scheduler instance, namely "sched", can be generated by following the following procedures one-by-one:

2.1 Resource Initialization for "cpu1"

Since some of the task specifications are based on the resources, in the framework, a programmer is expected to define the resources, initially. As explained in the article, some of the specifications are inevitable for a resource. Therefore, it should be defined for each resource. Based on the feature model, the following attributes are inevitable for a resource:

- CAPACITY (C): The capacity of the resource are required to determine the maximum amount of capacity which can be utilized per time unit.
- Type (\Re): This attribute categorize the resources based on *Abstractions* and *Identifier*.
- Mode (\mathcal{X}): The mode of a resource may be either *Shared* or *Exclusive*.

- POWER CONSUMPTION (\mathcal{V}): A resource consumes power based on this attribute. The resource is either *Scalable* or not.
- Objective (\mathcal{O}_{α}): This attribute is related with the resource-related objectives.

The only required specification for the instantiation is *Type* of the resource. The default values for all specification belonging to a resource are shown in Table 1.

Feature Name	Feature Name Variable Type	
Capacity (C)	float	0.0
Type (\Re)	LFOS.Resource.Type.ResourceTypeList::Enum	proc_t
$\boxed{ Mode\;(\mathcal{X}) }$	LFOS.Resource.Mode.ModeTypeList::Enum	CB_EXCLUSIVE
Power Consumption (\mathcal{V})	LFOS.Resource.Power	None
Objective (\mathcal{O}_{α})	LFOS.Objective	None

Table 1: Default instance variables of the *Resource* module and their default values.

For abstraction, ACTIVE is selected. Therefore, you can create the type object using the following code segment:

```
1 cpu1_t = Type(ResourceTypeList.ACTIVE, 'cpu1_t')
```

Listing 2: Active resource type object instantiation

According to the specification, a programmer can create the resource giving type object and a name of the resource as arguments to the class method of the ResourceFactory class shown in Listing 10. For active resources, an object belonging to TerminalResource class is instantiated using factory method pattern to handle the optional feature under Abstraction sub-feature.

```
1 cpu1 = ResourceFactory.create_instance(cpu1_t, 'cpu1')
```

Listing 3: Active resource instantiation using ResourceFactory class

2.1.1 Setting mode

There are three possible types for this attribute. These are:

- ModeTypeList.SHARED
- ModeTypeList.CB_EXCLUSIVE
- ModeTypeList.SB_EXCLUSIVE
- ModeTypeList.CB_AND_SB_EXCLUSIVE

The functionality of these modes are discussed in the article.

As shown in Table 1, the mode is initially set to ModeTypeList.CB_EXCLUSIVE. A programmer can change the mode of a resource by using the following code segment:

```
1 cpu1.set_mode(mode)
2 # mode ---> ResourceTypeList::Enum
```

Listing 4: Setting the mode of a resource after creating a resource.

In order to check the mode of the resource, you can use the functions depicted in Listing 12.

```
cpu1.is_mode(mode) # mode —> ResourceTypeList::Enum
# returns True if the argument matches with the mode of the resource.

cpu1.is_exclusive()
# returns True if the mode of the resource is any one of the exclusive mode
.
```

Listing 5: The functions for resource mode check.

According to your specification, you have selected at least CB_EXCLUSIVE mode for your resource "cpu1". Since the resource is set to this mode initially, you do not need to set it again.

In addition to the CB_EXCLUSIVE mode, you have selected the SB_EXCLUSIVE mode for your resource "cpu1". Therefore, you should manually set it after resource creation using the following code segment:

```
1 cpu1.set_mode(ModeTypeList.CB_AND_SB_EXCLUSIVE)
```

Listing 6: The resource is set to CB_AND_SB_EXCLUSIVE mode.

Due to semantic-based exclusive property of the resource, you can define exclusive resources by using the following formula:

```
cpul.add_exclusive_resource(resource)
# returns True if the SB\EXCLUSIVE mode is selected and the resource argument is not in the list of exclusive resources. Otherwise, it returns False.
```

Listing 7: A function for adding exclusive resources.

2.1.2 Setting Power Consumption

There are three possible types of power consumption:

- PowerTypeList.FIXED_STATE_POWER_CONSUMPTION
- PowerTypeList.DISCRETE_STATE_POWER_CONSUMPTION
- PowerTypeList.CONTINUOUS_STATE_POWER_CONSUMPTION

Each of these types have their corresponding classes inheriting Resource class. Therefore, we have utilized factory method design pattern.

You have selected continuous-state power consumption. Therefore, you can create your power consumption object with the code as follows:

```
1
   power_type = PowerTypeList.CONTINUOUS_STATE_POWER_CONSUMPTION
   cpu1_pc = PowerFactory.create_instance(power_type, scale, consumption)
   # create_instance(_type, min_scale, min_pow_cons, max_scale=None,
       max_pow_cons=None) -> FixedStatePowerConsumption |
       DiscreteStatePowerConsumption | ContinuousStatePowerConsumption
4
   |#
5
   #
              Returns the corresponding instance for given _type.
6
   #
7
   #
              :param _type:
8
                  PowerTypeList.FIXED_STATE_POWER_CONSUMPTION |
   #
9
                  PowerTypeList.DISCRETE_STATE_POWER_CONSUMPTION
   #
10
                  PowerTypeList.CONTINUOUS_STATE_POWER_CONSUMPTION
   #
11
   #
              :param min_scale: float -> minimum power scale
12
   #
              :param min_pow_cons: float -> minimum power consumption
13
   #
              :param max_scale: float -> maximum power scale
14
   #
              :param max_pow_cons: float -> maximum power consumption
15
              : return: FixedStatePowerConsumption |
       DiscreteStatePowerConsumption | ContinuousStatePowerConsumption
```

Listing 8: Power consumption object is created for Continuous-State Power Consumption type.

All other member functions for the class is shown in Listing 16

```
1
   ContinuousStatePowerConsumption.set_max_state(scale, pow_cons) -> boolean
   ContinuousStatePowerConsumption.max_range_check(scale) -> boolean
3
   ContinuousStatePowerConsumption.get_power_consumption_w_scale(scale) ->
       float
   Continuous State Power Consumption.\, get\_active\_power\_state\,() \,\, -\!\!\!> \,\, dict
4
    ContinuousStatePowerConsumption.get_max_power_state() -> list
5
   ContinuousStatePowerConsumption.get_min_power_state() -> list
    ContinuousStatePowerConsumption.get_power_states() -> Numpy.array
    ContinuousStatePowerConsumption.set_min_state(scale, pow_cons) -> boolean
   Continuous State Power Consumption.\,remove\_state\,(\,scale\,) \,\, -\! > \,\,boolean \,\,\,(\,Interface)
10
   ContinuousStatePowerConsumption.range_check(scale) -> boolean
    ContinuousStatePowerConsumption.get_power_consumption() -> float
11
12
   ContinuousStatePowerConsumption.set_power_scale_precision(precision) ->
   ContinuousStatePowerConsumption.set_power_mode(scale) -> list(scale, power
13
       consumption)
   ContinuousStatePowerConsumption.get_power_scale_precision() -> float
14
    ContinuousStatePowerConsumption.__calculate_power_consumption_slope()
15
   ContinuousStatePowerConsumption.add_state(self, scale, pow_cons) -> boolean
         (Interface Function)
17
   ContinuousStatePowerConsumption.get_power_scale() -> float
```

Listing 9: The member functions for ContinuousStatePowerConsumption module.

2.2 Resource Initialization for "cpu2"

For abstraction, ACTIVE is selected. Therefore, you can create the type object using the following code segment:

```
cpu2_t = Type(ResourceTypeList.ACTIVE, 'cpu2_t')
```

Listing 10: Active resource type object instantiation

According to the specification, a programmer can create the resource giving type object and a name of the resource as arguments to the class method of the ResourceFactory class shown in Listing 24. For active resources, an object belonging to TerminalResource class is instantiated using factory method pattern to handle the optional feature under Abstraction sub-feature.

```
1 cpu2 = ResourceFactory.create_instance(cpu2_t, 'cpu2')
```

Listing 11: Active resource instantiation using ResourceFactory class

2.2.1 Setting mode

There are three possible types for this attribute. These are:

- ModeTypeList.SHARED
- ModeTypeList.CB_EXCLUSIVE
- ModeTypeList.SB_EXCLUSIVE
- ModeTypeList.CB_AND_SB_EXCLUSIVE

The functionality of these modes are discussed in the article.

As shown in Table 1, the mode is initially set to ModeTypeList.CB_EXCLUSIVE. A programmer can change the mode of a resource by using the following code segment:

```
1 cpu2.set_mode(mode)
2 # mode ---> ResourceTypeList::Enum
```

Listing 12: Setting the mode of a resource after creating a resource.

In order to check the mode of the resource, you can use the functions depicted in Listing 26.

```
cpu2.is_mode(mode) # mode —> ResourceTypeList::Enum
# returns True if the argument matches with the mode of the resource.
cpu2.is_exclusive()
# returns True if the mode of the resource is any one of the exclusive mode
.
```

Listing 13: The functions for resource mode check.

According to your specification, you have selected at least CB_EXCLUSIVE mode for your resource "cpu2". Since the resource is set to this mode initially, you do not need to set it again.

2.2.2 Setting Power Consumption

There are three possible types of power consumption:

- PowerTypeList.FIXED_STATE_POWER_CONSUMPTION
- PowerTypeList.DISCRETE_STATE_POWER_CONSUMPTION
- PowerTypeList.CONTINUOUS_STATE_POWER_CONSUMPTION

Each of these types have their corresponding classes inheriting Resource class. Therefore, we have utilized factory method design pattern.

You have selected discrete-state power consumption. Therefore, you can create your power consumption object with the code as follows:

```
power_type = PowerTypeList.DISCRETE_STATE_POWER_CONSUMPTION
1
   cpu2-pc = PowerFactory.create_instance(power_type, scale, consumption)
   # create_instance(_type, min_scale, min_pow_cons, max_scale=None,
       max_pow_cons=None) -> FixedStatePowerConsumption |
       DiscreteStatePowerConsumption | ContinuousStatePowerConsumption
4
   #
5
   #
              Returns the corresponding instance for given _type.
6
   #
7
   #
              :param _type:
8
                  PowerTypeList.FIXED_STATE_POWER_CONSUMPTION
   #
9
                  PowerTypeList.DISCRETE_STATE_POWER_CONSUMPTION
   #
10
   #
                  PowerTypeList. CONTINUOUS\_STATE\_POWER\_CONSUMPTION
11
   #
              :param min_scale: float -> minimum power scale
12
              :param min_pow_cons: float -> minimum power consumption
   #
13
   #
              :param max_scale: float -> maximum power scale
14
   |#
              :param max_pow_cons: float -> maximum power consumption
15
              :return: FixedStatePowerConsumption
       DiscreteStatePowerConsumption | ContinuousStatePowerConsumption
```

Listing 14: Power consumption object is created for Discrete-State Power Consumption type.

All the other member functions for the object is shown in Listing 28:

```
DiscreteStatePowerConsumption.get_power_states() -> Numpy.array
1
    DiscreteStatePowerConsumption.set_power_mode(scale) -> list
    DiscreteStatePowerConsumption.range_check(scale) -> boolean
    DiscreteStatePowerConsumption.get_max_power_state() -> list
    DiscreteStatePowerConsumption.get_min_power_state() -> list
6
   DiscreteStatePowerConsumption.get_active_power_state() -> dict
7
    DiscreteStatePowerConsumption.remove_state(scale) -> float | None
8
    DiscreteStatePowerConsumption.max_range_check(scale) -> boolean
9
    Discrete State Power Consumption . \ get\_power\_consumption\_w\_scale (scale) \ -> \ float
    Discrete State Power Consumption.\, add\_state (\,scale\,\,,\,\,pow\_cons\,)\,\, -\! >\,\,boolean
10
    \label{localization} Discrete State Power Consumption.set\_max\_state (\, scale \,\,, \,\, pow\_cons \,) \,\, -\!\!\!> \,\, boolean
11
12
    DiscreteStatePowerConsumption.get_power_scale() -> float
    DiscreteStatePowerConsumption.get_power_consumption() -> float
13
    DiscreteStatePowerConsumption.set_min_state(scale, pow_cons) -> boolean
```

Listing 15: The member functions for DiscreteStatePowerConsumption module.

3 Task Initialization for t1

In order to create a task instance, a programmer first needs to specify the granularity of the task. A task can be specified as either *terminal* or *composite*. This information comes from the feature diagram. Secondly, she has to define each mandatory keyword that is inevitable to create task instance. The task model consists of many sub-feature models. It is necessary to explain these branches to make a programmar familiar with the terminology.

• Granularity (\mathcal{G}): The granularity of a task (terminal or composite) that is termed as TaskType in the implementation.

```
TaskTypeList .TERMINAL
TaskTypeList .COMPOSITE
```

Listing 16: The enumeration of the type of tasks.

- TIMING (T): This attribute includes all the relevant time-related task properties such as release time, execution time, deadline, and period information.
- REQUIREMENT (\mathcal{R}): The requirements of tasks that are Resource Requirement and Deadline Requirement.
- PRIORITY (ρ) : The priority information of a task.
- DEPENDENCY (Δ): The dependency relation with respect to other tasks, which is optional.
- Preemptable (\mathcal{P}_{τ}) : The preemptability property of a task, which is optional.
- OBJECTIVE (\mathcal{O}_{τ}) : This attribute holds the task-related objective information, which is optional.

In the second phase, a programmer should specify the values for each attribute in the feature model. The keywords and correlated information is represented in Table 2

3.1 Specifying the Granularity of task "t1"

There are two types of tasks, namely *Terminal* and *Composite*. These are enumerated within TaskTypeList as follows:

Since you have defined the task "t1" as Terminal, you should the following line:

```
1 task_type_t1 = TaskTypeList.TERMINAL
```

Listing 17: Terminal task type definition.

Keyword	Type	Default Value	Description
name	string	-	The name of a task
periodicity	LFOS.Task.Periodicity.PeriodicityTypeList	-	The periodicty type of a task
deadline_type	LFOS.Task.Requirement.DeadlineRequirementTypeList	DeadlineRequirementTypeList.HARD	The deadline satisfaction type of a task
priority	int	0	The priority of a task
deadline	LFOS.Scheduling.Characteristic.Time	-	The deadline of a task
token_number	$\operatorname{list}(\operatorname{int})$	[1]	The list of numbers of a specific token
			that would be fired. There exist
			one-to-one relation between the list and
			token_name list with respect to index.
phase	LFOS.Scheduling.Characteristic.Time	-	The first release time of a task
preemptability	LFOS.Task.Preemptability.PreemptionTypeList	PreemptionTypeList.FULLY_PREEMPTABLE	The preemptability of a task
type	string	-	The type of a task
token_name		list(" <name>"]</name>	The list of names of the token which
	list(str)		would be fired after completion of the
			task instance.

Table 2: Keywords to instantiate a task object.

3.1.1 Setting the time attributes

The time-related attributes for a task is kept under Timing class that inherits Periodicity class. Since the task class also inherits from the Timing class, a programmer can set and get the values directly from an intance of a task. The following member functions are utilized to interact with the task instance to access the timing attributes defined above:

```
Timing.set_deadline(new_deadline) -> None
Timing.str(object='') -> string
Timing.set_release_time(new_release_time) -> None
Timing.get_release_time() -> LFOS.Scheduling.Characteristic.Time
Timing.get_deadline() -> LFOS.Scheduling.Characteristic.Time
Timing.set_period(new_period) -> boolean
Timing.set_execution_time(new_exec_time) -> None
Timing.get_period_type() -> LFOS.Scheduling.Characteristic.Time
Timing.get_period() -> LFOS.Scheduling.Characteristic.Time
Timing.get_execution_time() -> LFOS.Scheduling.Characteristic.Time
Timing.get_execution_time() -> LFOS.Scheduling.Characteristic.Time
Timing.set_periodicity(_type) -> None
```

Listing 18: The member functions for Timing module.

The periodicity types are as follows:

```
PeriodicityTypeList .APERIODIC
PeriodicityTypeList .PERIODIC
PeriodicityTypeList .SPORADIC
```

Listing 19: The Periodicity type enumeration.

Since you have classified task "t1" as PERIODIC, you can set a parameter for this attribute as follows:

```
1 periodicity_t1 = PeriodictyTypeList.PERIODIC
```

Listing 20: Periodicity for parameter is stored in the variable to use it later in instantiation.

3.1.2 Setting the priority

The priority class is a compact small class consists of three class vairables:

- MIN_PRIORITY: the minimum value for priority value.
- MAX_PRIORITY: the maximum value for priority value.
- IMPORTANCE_RANKING: the importance criteria stating whether ascending or descending priority values have higher privilege for a task. PriorityRanking class includes this enumeration attributes as class variables:

```
Priority Ranking . ASCENDING
Priority Ranking . DESCENDING
```

Listing 21: The PriorityRanking enumeration.

This class also includes three functions, two of which setting and getting the priority value, and one of which is responsible for setting the class variables:

```
Priority.get_priority() -> int
Priority.set_class_vars(min_prio=None, max_prio=None, ranking=None) -> None
(class method)
Priority.set_priority(new_prio) -> boolean
```

Listing 22: The member functions for Priority module.

4 Task Initialization for t2

4.1 Specifying the Granularity of task "t1"

There are two types of tasks, namely *Terminal* and *Composite*. These are enumerated within TaskTypeList as follows:

Since you have defined the task "t1" as Terminal, you should the following line:

```
1 task_type_t1 = TaskTypeList.TERMINAL
```

Listing 23: Terminal task type definition.

4.1.1 Setting the time attributes

The time-related attributes for a task is kept under Timing class that inherits Periodicity class. Since the task class also inherits from the Timing class, a programmer can set and get the values directly from an intance of a task. The following member functions are utilized to interact with the task instance to access the timing attributes defined above:

```
Timing.set_deadline(new_deadline) -> None
Timing.str(object='') -> string
Timing.set_release_time(new_release_time) -> None
Timing.get_release_time() -> LFOS.Scheduling.Characteristic.Time
```

```
Timing.get_deadline() -> LFOS.Scheduling.Characteristic.Time
Timing.set_period(new_period) -> boolean
Timing.set_execution_time(new_exec_time) -> None
Timing.get_period_type() -> LFOS.Scheduling.Characteristic.Time
Timing.get_period() -> LFOS.Scheduling.Characteristic.Time
Timing.get_execution_time() -> LFOS.Scheduling.Characteristic.Time
Timing.set_execution_time() -> LFOS.Scheduling.Characteristic.Time
```

Listing 24: The member functions for Timing module.

The periodicity types are as follows:

```
PeriodicityTypeList .APERIODIC
PeriodicityTypeList .PERIODIC
PeriodicityTypeList .SPORADIC
```

Listing 25: The Periodicity type enumeration.

Since you have classified task "t1" as APERIODIC, you can set a parameter for this attribute as follows:

```
1 periodicity_t1 = PeriodictyTypeList.APERIODIC
```

Listing 26: Periodicity for parameter is stored in the variable to use it later in instantiation.

4.1.2 Setting the priority

The priority class is a compact small class consists of three class vairables:

- MIN_PRIORITY: the minimum value for priority value.
- MAX_PRIORITY: the maximum value for priority value.
- IMPORTANCE_RANKING: the importance criteria stating whether ascending or descending priority values have higher privilege for a task. PriorityRanking class includes this enumeration attributes as class variables:

```
PriorityRanking .ASCENDING
PriorityRanking .DESCENDING
```

Listing 27: The PriorityRanking enumeration.

This class also includes three functions, two of which setting and getting the priority value, and one of which is responsible for setting the class variables:

```
Priority.get_priority() -> int
Priority.set_class_vars(min_prio=None, max_prio=None, ranking=None) -> None
(class method)
Priority.set_priority(new_prio) -> boolean
```

Listing 28: The member functions for Priority module.