

# **Chapter** $\square$ **2** $\square$ **Describing Physical Memory**

Linux is available for a wide range of architectures so there needs to be an architecture-independent way of describing memory. This chapter describes the structures used to keep account of memory banks, pages and the flags that affect VM behaviour.

The first principal concept prevalent in the VM is *Non-Uniform Memory Access (NUMA)*. With large scale machines, memory may be arranged into banks that incur a different cost to access depending on the "distance" from the processor. For example, there might be a bank of memory assigned to each CPU or a bank of memory very suitable for DMA near device cards.

Each bank is called a *node* and the concept is represented under Linux by a struct pglist\_data even if the architecture is UMA. This struct is always referenced to by it's typedef pg\_data\_t. Every node in the system is kept on a NULL terminated list called pgdat\_list and each node is linked to the next with the field pg\_data\_t→node\_next. For UMA architectures like PC desktops, only one static pg data tstructure called contig page data is used. Nodes will be discussed further in Section 2.1.

Each node is divided up into a number of blocks called zones which represent ranges within memory. Zones should not be confused with zone based allocators as they are unrelated. A zone is described by a struct zone\_struct, typedeffed to zone\_t and each one is of type zone\_dma, zone\_normal or zone\_highmem. Each zone type suitable a different type of usage. zone\_dma is memory in the lower physical memory ranges which certain ISA devices require. Memory withinzone\_normal is directly mapped by the kernel into the upper region of the linear address space which is discussed further in Section 4.1. zone\_highmemis the remaining available memory in the system and is not directly mapped by the kernel.

With the x86 the zones are:

```
ZONE_DMA First 16MiB of memory
ZONE_NORMAL 16MiB - 896MiB
ZONE_HIGHMEM 896 MiB - End
```

It is important to note that many kernel operations can only take place using ZONE\_NORMAL so it is the most performance critical zone. Zones are discussed further in Section 2.2. Each physical page frame is represented by a struct page and all the structs are kept in a global mem\_map array which is usually stored at the beginning of ZONE\_NORMAL or just after the area reserved for the loaded kernel image in low memory machines. struct pages are discussed in detail in Section 2.4 and the global mem\_maparray is discussed in detail in Section 3.7. The basic relationship between all these structs is illustrated in Figure 2.1.




Figure 2.1: Relationship Between Nodes, Zones and Pages

As the amount of memory directly accessible by the kernel (ZONE\_NORMAL) is limited in size, Linux supports the concept of *High Memory* which is discussed further in Section <u>2.5</u>. This chapter will discuss how nodes, zones and pages are represented before introducing high memory management.

### **2.1** □ Nodes

As we have mentioned, each node in memory is described by <code>apg\_data\_t</code> which is a typedef for a <code>struct pglist\_data</code>. When allocating a page, Linux uses anode-local allocation policy to allocate memory from the node closest to the running CPU. As processes tend to run on the same CPU, it is likely the memory from the current node will be used. The struct is declared as follows in <code>sinux/mmzone.h></code>:

```
129 typedef struct pglist_data {
130
       zone t node zones[MAX NR ZONES];
       zonelist_t node_zonelists[GFP ZONEMASK+1];
131
132
      int nr zones;
133
      struct page *node mem map;
134
      unsigned long *valid addr bitmap;
135
       struct bootmem_data *bdata;
136
       unsigned long node_start_paddr;
137
       unsigned long node start mapnr;
138
       unsigned long node size;
139
       int node id;
140
       struct pglist_data *node_next;
141 } pg_data_t;
```

We now briefly describe each of these fields:

node\_zones The zones for this node, zone highmem, zone normal, zone dma;

**node\_zonelists** This is the order of zones that allocations are preferred from. build\_zonelists() in mm/page\_alloc.c sets up the order when called by free\_area\_init\_core(). A failed allocation in ZONE\_HIGHMEM may fall back to ZONE\_NORMAL or back to ZONE\_DMA;

**nr\_zones** Number of zones in this node, between 1 and 3. Not all nodes will have three. A CPU bank may not have ZONE\_DMA for example;

**node\_mem\_map** This is the first page of the struct page array representing each physical frame in the node. It will be placed somewhere within the global mem map array;

**valid\_addr\_bitmap** A bitmap which describes "holes" in the memory node that no memory exists for. In reality, this is only used by the Sparc and Sparc64 architectures and ignored by all others;

**bdata** This is only of interest to the boot memory allocator discussed in Chapter 5;

**node\_start\_paddr** The starting physical address of the node. An unsigned long does not work optimally as it breaks for ia32 with *Physical Address Extension (PAE)* for example. PAE is discussed further in Section 2.5. A more suitable solution would be to record this as a *Page Frame Number (PFN)*. A PFN is simply in index within physical memory that is counted in page-sized units. PFN for a physical address could be trivially defined as (page phys addr >> PAGE SHIFT);

node\_start\_mapnr This gives the page offset within the global mem\_map. It is calculated in free\_area\_init\_core() by calculating the number of pages between mem\_map and the local mem\_map for this node called lmem\_map;

**node\_size** The total number of pages in this zone;

**node\_id** The *Node ID (NID)* of the node, starts at 0;

node next Pointer to next node in a NULL terminated list.

All nodes in the system are maintained on a list calledpgdat\_list. The nodes are placed on this list as they are initialised by the init\_bootmem\_core() function, described later in Section 5.2.1. Up until late 2.4 kernels (> 2.4.18), blocks of code that traversed the list looked something like:

```
pg_data_t * pgdat;
pgdat = pgdat_list;
do {
     /* do something with pgdata_t */
     ...
} while ((pgdat = pgdat->node_next));
```

In more recent kernels, a macro for\_each\_pgdat(), which is trivially defined as a for loop, is provided to improve code readability.

## 2.2 □ Zones

Zones are described by a struct zone\_struct and is usually referred to by it's typedef zone\_t. It keeps track of information like page usage statistics, free area information and locks. It is declared as follows in linux/mmzone.h>:

```
37 typedef struct zone_struct {
    spinlock_t lock;
unsigned long free_pages;
unsigned long pages_min, pages_low, pages_high;
int need_balance;
41
42
43
44
45
      free_area_t
                            free_area[MAX_ORDER];
49
50
76 wait_queue_head_t * wait_table;
77 unsigned long wait_table_size;
78 unsigned long wait_table_shift;
79
     83
84
8.5
86
87
    char
91
                              *name;
       unsigned long
                              size;
93 } zone t;
```

This is a brief explanation of each field in the struct.

**lock** Spinlock to protect the zone from concurrent accesses;

**free pages** Total number of free pages in the zone;

pages\_min, pages\_low, pages\_high These are zone watermarks which are described in the next section;

**need\_balance** This flag that tells the pageout **kswapd** to balance the zone. A zone is said to need balance when the number of available pages reaches one of the *zone watermarks*. Watermarks is discussed in the next section;

**free** area Free area bitmaps used by the buddy allocator;

wait\_table A hash table of wait queues of processes waiting on a page to be freed. This is of importance to wait\_on\_page() and unlock\_page(). While processes could all wait on one queue, this would cause all waiting processes to race for pages still locked when woken up. A large group of processes contending for a shared resource like this is sometimes called a thundering herd. Wait tables are discussed further in Section 2.2.3;

wait\_table\_size Number of queues in the hash table which is a power of 2;

wait\_table\_shift Defined as the number of bits in a long minus the binary logarithm of the table size above;

```
zone_pgdat Points to the parent pg_data_t;
zone_mem_map The first page in the global mem_map this zone refers to;
zone_start_paddr Same principle as node_start_paddr;
zone_start_mapnr Same principle as node_start_mapnr;
name The string name of the zone, "DMA", "Normal" or "HighMem"
size The size of the zone in pages.
```

#### **2.2.1** □ **Zone Watermarks**

When available memory in the system is low, the pageout daemon**kswapd** is woken up to start freeing pages (see Chapter <u>10</u>). If the pressure is high, the process will free up memory synchronously, sometimes referred to as the *direct-reclaim* path. The parameters affecting pageout behaviour are similar to those by FreeBSD $\Box$ [*McK96*] and Solaris $\Box$ [*MM01*].

Each zone has three watermarks called <code>pages\_low,pages\_min</code> and <code>pages\_high</code> which help track how much pressure a zone is under. The relationship between them is illustrated in Figure 2.2. The number of pages for <code>pages\_min</code> is calculated in the function <code>free\_area\_init\_core()</code> during memory init and is based on a ratio to the size of the zone in pages. It is calculated initially as <code>ZoneSizeInPages/128</code>. The lowest value it will be is 20 pages (80K on a x86) and the highest possible value is 255 pages (1MiB on a x86).




Figure 2.2: Zone Watermarks

pages\_low When pages low number of free pages is reached, kswapd is woken up by the buddy allocator to start freeing pages. This is equivalent to when lotsfree is reached in Solaris and freemin in FreeBSD. The value is twice the value of pages min by default;

pages\_min When pages min is reached, the allocator will do the kswapd work in a synchronous fashion, sometimes referred to as the *direct-reclaim* path. There is no real equivalent in Solaris but the closest is the desfree or minfree which determine how often the pageout scanner is woken up;

pages\_high Once kswapd has been woken to start freeing pages it will not consider the zone to be "balanced" when pages high pages are free. Once the watermark has been reached, kswapd will go back to sleep. In Solaris, this is called lotsfree and in BSD, it is called free target. The default for pages high is three times the value of pages min.

Whatever the pageout parameters are called in each operating system, the meaning is the same, it helps determine how hard the pageout daemon or processes work to free up pages.

## **2.2.2** □ Calculating The Size of Zones




Figure 2.3: Call Graph: setup\_memory()

The PFN is an offset, counted in pages, within the physical memory map. The first PFN usable by the system, min\_low\_pfn is located at the beginning of the first page after \_end which is the end of the loaded kernel image. The value is stored as a file scope variable in mm/bootmem.c for use with the boot memory allocator.

How the last page frame in the system, <code>max\_pfn</code>, is calculated is quite architecture specific. In the x86 case, the functionfind\_<code>max\_pfn()</code> reads through the whole *e820* map for the highest page frame. The value is also stored as a file scope variable <code>inmm/bootmem.c.</code> The e820 is a table provided by the BIOS describing what physical memory is available, reserved or non-existent.

The value of <code>max\_low\_pfn</code> is calculated on the x86 with <code>find\_max\_low\_pfn</code>() and it marks the end of <code>ZONE\_NORMAL</code>. This is the physical memory directly accessible by the kernel and is related to the kernel/userspace split in the linear address space marked by <code>PAGE\_OFFSET</code>. The value, with the others, is stored in <code>mm/bootmem.c</code>. Note that in low memory machines, the <code>max\_pfn</code> will be the same as the <code>max\_low\_pfn</code>.

With the three variables min\_low\_pfn, max\_low\_pfnand max\_pfn, it is straightforward to calculate the start and end of high memory and place them as file scope variables in arch/i386/mm/init.c as highstart\_pfn andhighend\_pfn. The values are used later to initialise the high memory pages for the physical page allocator as we will much later in Section 5.5.

#### **2.2.3** □ Zone Wait Queue Table

When IO is being performed on a page, such are during page-in or page-out, it is locked to prevent accessing it with inconsistent data. Processes wishing to use it have to join a wait queue before it can be accessed by callingwait\_on\_page(). When the IO is completed, the page will be unlocked with UnlockPage() and any process waiting on the queue will be woken up. Each page could have a wait queue but it would be very expensive in terms of memory to have so many separate queues so instead, the wait queue is stored in the zone t.

It is possible to have just one wait queue in the zone but that would mean that all processes waiting on any page in a zone would be woken up when one was unlocked. This would cause a serious *thundering herd* problem. Instead, a hash table of wait queues is stored in zone\_t-wait\_table. In the event of a hash collision, processes may still be woken unnecessarily but collisions are not expected to occur frequently.




Figure 2.4: Sleeping On a Locked Page

The table is allocated during free\_area\_init\_core(). The size of the table is calculated by wait\_table\_size() and stored in thezone\_t-wait\_table\_size. The maximum size it will be is 4096 wait queues. For smaller tables, the size of the table is the minimum power of 2 required to store NoPages / PAGES\_PER\_WAITQUEUEnumber of queues, where NoPages is the number of pages in the zone and PAGE\_PER\_WAITQUEUE is defined to be 256. In other words, the size of the table is calculated as the integer component of the following equation:

```
wait table size = log2((NoPages * 2) / PAGES PER WAITQUEUE - 1)
```

The field <code>zone\_t→wait\_table\_shift</code> is calculated as the number of bits a page address must be shifted right to return an index within the table. The function <code>page\_waitqueue()</code> is responsible for returning which wait queue to use for a page in a zone. It uses a simple multiplicative hashing algorithm based on the virtual address of the <code>struct\_page</code> being hashed.

It works by simply multiplying the address by <code>GOLDEN\_RATIO\_PRIME</code> and shifting the result <code>zone\_t-wait\_table\_shift</code> bits right to index the result within the hash table. <code>GOLDEN\_RATIO\_PRIME</code> [Lev00] is the largest prime that is closest to the golden ratio [Knu68] of the largest integer that may be represented by the architecture.

## **2.3** □ **Zone Initialisation**

The zones are initialised after the kernel page tables have been fully setup by paging\_init(). Page table initialisation is covered in Section 3.6. Predictably, each architecture performs this task differently but the objective is always the same, to determine what parameters to send to either free\_area\_init() for UMA architectures or free\_area\_init\_node() for NUMA. The only parameter required for UMA is zones\_size. The full list of parameters:

**nid** is the Node ID which is the logical identifier of the node whose zones are being initialised;

**pgdat** is the node's pg\_data\_t that is being initialised. In UMA, this will simply be contig page data;

pmap is set later by free\_area\_init\_core() to point to the beginning of the local lmem\_map array allocated for the node. In NUMA, this is ignored as NUMA treats mem\_map as a virtual array starting at PAGE\_OFFSET. In UMA, this pointer is the global mem\_map variable which is now mem\_map gets initialised in UMA.

**zones\_sizes** is an array containing the size of each zone in pages;

**zone\_start\_paddr** is the starting physical address for the first zone;

**zone holes** is an array containing the total size of memory holes in the zones;

It is the core function free\_area\_init\_core() which is responsible for filling in each zone\_t with the relevant information and the allocation of the mem\_map array for the node. Note that information on what pages are free for the zones is not determined at this point. That information is not known until the boot memory allocator is being retired which will be discussed much later in Chapter 5.

## $2.3.1 \square \square$ Initialising mem\_map

The mem\_map area is created during system startup in one of two fashions. On NUMA systems, the global mem\_map is treated as a virtual array starting at PAGE\_OFFSET.free\_area\_init\_node() is called for each active node in the system which allocates the portion of this array for the node being initialised. On UMA systems, free\_area\_init() is uses contig\_page\_data as the node and the global mem\_map as the "local" mem\_map for this node. The callgraph for both functions is shown in Figure 2.5.




Figure 2.5: Call Graph: free\_area\_init()

The core function free\_area\_init\_core() allocates a locallmem\_map for the node being initialised. The memory for the array is allocated from the boot memory allocator with alloc\_bootmem\_node() (see Chapter 5). With UMA architectures, this newly allocated memory becomes the global mem\_map but it is slightly different for NUMA.

NUMA architectures allocate the memory for <code>lmem\_map</code> within their own memory node. The global <code>mem\_map</code> never gets explicitly allocated but instead is set to <code>PAGE\_OFFSET</code> where it is treated as a virtual array. The address of the local map is stored <code>inpg\_data\_t \rightarrow node\_mem\_map</code> which exists somewhere within the virtual <code>mem\_map</code>. For each zone that exists in the node, the address within the virtual <code>mem\_map</code> for the zone is stored in <code>zone\_t \rightarrow zone\_mem\_map</code>. All the rest of the code then treats <code>mem\_map</code> as a real array as only valid regions within it will be used by nodes.

## 2.4□ □ Pages

Every physical page frame in the system has an associated struct page which is used to keep track of its status. In the 2.2 kernel  $\Box$  [BC00], this structure resembled it's equivalent in System  $V\Box$  [GC94] but like the other UNIX variants, the structure changed considerably. It is declared as follows in  $\leq$  inux/mm.h $\geq$ :

```
152 typedef struct page {
153          struct list_head list;
154          struct address_space *mapping;
155          unsigned long index;
156          struct page *next_hash;
158          atomic_t count;
159          unsigned long flags;
```

Here is a brief description of each of the fields:

list Pages may belong to many lists and this field is used as the list head. For example, pages in a mapping will be in one of three circular linked links kept by the address\_space. These are clean\_pages, dirty\_pages and locked\_pages. In the slab allocator, this field is used to store pointers to the slab and cache the page belongs to. It is also used to link blocks of free pages together;

mapping When files or devices are memory mapped, their inode has an associated address\_space. This field will point to this address space if the page belongs to the file. If the page is anonymous and mapping is set, the address space is swapper space which manages the swap address space;

index This field has two uses and it depends on the state of the page what it means. If the page is part of a file mapping, it is the offset within the file. If the page is part of the swap cache this will be the offset within the address\_space for the swap address space (swapper\_space). Secondly, if a block of pages is being freed for a particular process, the order (power of two number of pages being freed) of the block being freed is stored in index. This is set in the function \_\_free\_pages\_ok();

**next\_hash** Pages that are part of a file mapping are hashed on the inode and offset. This field links pages together that share the same hash bucket;

**count** The reference count to the page. If it drops to 0, it may be freed. Any greater and it is in use by one or more processes or is in use by the kernel like when waiting for IO;

flags These are flags which describe the status of the page. All of them are declared in linux/mm.h> and are listed in Table 2.1. There are a number of macros defined for testing, clearing and setting the bits which are all listed in Table 2.2. The only really interesting one is SetPageUptodate() which calls an architecture specific function arch\_set\_page\_uptodate() if it is defined before setting the bit;

**Iru** For the page replacement policy, pages that may be swapped out will exist on either the active\_list or the inactive\_list declared in page\_alloc.c. This is the list head for these LRU lists. These two lists are discussed in detail in Chapter 10;

pprev\_hash This complement to next hash so that the hash can work as a doubly linked list;

**buffers** If a page has buffers for a block device associated with it, this field is used to keep track of the buffer\_head. An anonymous page mapped by a process may also have an associated buffer\_head if it is backed by a swap file. This is necessary as the page has to be synced with backing storage in block sized chunks defined by the underlying filesystem;

virtual Normally only pages from <code>zone\_normal</code> are directly mapped by the kernel. To address pages in <code>zone\_highmem</code>, <code>kmap()</code> is used to map the page for the kernel which is described further in Chapter 9. There are only a fixed number of pages that may be mapped. When it is mapped, this is its virtual address;

The type mem\_map\_t is a typedef for struct pageso it can be easily referred to within the mem\_map array.

Bit name	Description			
PG_active	This bit is set if a page is on the active_list LRU and cleared when it is removed. It marks a page as being hot			
PG_arch_1	Quoting directly from the code: PG_arch_1 is an architecture specific page state bit. The generic code guarantees that this bit is cleared for a page when it first is entered into the page cache. This allows an architecture to defer the			

	flushing of the D-Cache (See Section 3.9) until the page is mapped by a process			
PG_checked	Only used by the Ext2 filesystem			
PG_dirty	This indicates if a page needs to be flushed to disk. When a page is written to that is backed by disk, it is not flushed immediately, this bit is needed to ensure a dirty page is not freed before it is written out			
PG_error	If an error occurs during disk I/O, this bit is set			
PG_fs_1	Bit reserved for a filesystem to use for it's own purposes. Currently, only NFS uses it to indicate if a page is in sync with the remote server or not			
PG_highmem	Pages in high memory cannot be mapped permanently by the kernel. Pages that are in high memory are flagged with this bit during mem_init()			
PG_launder	This bit is important only to the page replacement policy. When the VM wants to swap out a page, it will set this bit and call the writepage() function. When scanning, if it encounters a page with this bit and PG_locked set, it will wait for the I/O to complete			
PG_locked	This bit is set when the page must be locked in memory for disk I/O. When I/O starts, this bit is set and released when it completes			
PG_lru	If a page is on either the active_list or the inactive_list, this bit will be set			
PG_referenced	If a page is mapped and it is referenced through the mapping, index hash table, this bit is set. It is used during page replacement for moving the page around the LRU lists			
PG_reserved	This is set for pages that can never be swapped out. It is set by the boot memory allocator (See Chapter 5) for pages allocated during system startup. Later it is used to flag empty pages or ones that do not even exist			
PG_slab	This will flag a page as being used by the slab allocator			
PG_skip	Used by some architectures to skip over parts of the address space with no backing physical memory			
PG_unused	This bit is literally unused			
PG_uptodate	When a page is read from disk without error, this bit will be set.			

Table 2.1: Flags Describing Page Status

Bit name	Set	Test	Clear
PG_active	SetPageActive()	PageActive()	ClearPageActive()
PG_arch_1	n/a	n/a	n/a
PG_checked	SetPageChecked()	PageChecked()	n/a
PG_dirty	SetPageDirty()	PageDirty()	ClearPageDirty()
PG_error	SetPageError()	PageError()	ClearPageError()
PG_highmem	n/a	PageHighMem()	n/a
PG_launder	SetPageLaunder()	PageLaunder()	ClearPageLaunder()
PG_locked	LockPage()	PageLocked()	UnlockPage()
PG_lru	TestSetPageLRU()	PageLRU()	TestClearPageLRU()
PG_referenced	SetPageReferenced()	PageReferenced()	ClearPageReferenced()
PG_reserved	SetPageReserved()	PageReserved()	ClearPageReserved()
PG_skip	n/a	n/a	n/a
PG_slab	PageSetSlab()	PageSlab()	PageClearSlab()
PG_unused	n/a	n/a	n/a
PG_uptodate	SetPageUptodate()	PageUptodate()	ClearPageUptodate()

Table 2.2: Macros For Testing, Setting and Clearing page→flags Status Bits

## 2.4.1 □ □ Mapping Pages to Zones

Up until as recently as kernel 2.4.18, a struct page stored a reference to its zone with page—zonewhich was later considered wasteful, as even such a small pointer consumes a lot of memory when thousands of struct pages exist. In more recent kernels, the zone field has been removed and instead the top ZONE\_SHIFT (8 in the x86) bits of the page—flags are used to determine the zone a page belongs to. First a zone table of zones is set up. It is declared inmm/page alloc.c as:

```
33 zone_t *zone_table[MAX_NR_ZONES*MAX_NR_NODES];
34 EXPORT SYMBOL(zone table);
```

MAX\_NR\_ZONES is the maximum number of zones that can be in a node, i.e. 3. MAX\_NR\_NODES is the maximum number of nodes that may exist. The function EXPORT\_SYMBOL() makes zone\_table accessible to loadable modules. This table is treated like a multi-dimensional array. During free area init core(), all the pages in a node are initialised. First it sets the value for the table

```
zone table[nid * MAX NR ZONES + j] = zone;
```

Where nid is the node ID, j is the zone index and zone is the zone\_t struct. For each page, the functionset\_page\_zone() is called as

```
set_page_zone(page, nid * MAX_NR_ZONES + j);
```

The parameter, page, is the page whose zone is being set. So, clearly the index in the zone\_table is stored in the page.

## 2.5□ □ High Memory

As the addresses space usable by the kernel (<code>ZONE\_NORMAL</code>) is limited in size, the kernel has support for the concept of High Memory. Two thresholds of high memory exist on 32-bit x86 systems, one at 4GiB and a second at 64GiB. The 4GiB limit is related to the amount of memory that may be addressed by a 32-bit physical address. To access memory between the range of 1GiB and 4GiB, the kernel temporarily maps pages from high memory into <code>ZONE\_NORMAL</code>with <code>kmap()</code>. This is discussed further in Chapter 9.

The second limit at 64GiB is related to *Physical Address Extension (PAE)* which is an Intel invention to allow more RAM to be used with 32 bit systems. It makes 4 extra bits available for the addressing of memory, allowing up to 2<sup>36</sup> bytes (64GiB) of memory to be addressed.

PAE allows a processor to address up to 64GiB in theory but, in practice, processes in Linux still cannot access that much RAM as the virtual address space is still only 4GiB. This has led to some disappointment from users who have tried to malloc() all their RAM with one process.

Secondly, PAE does not allow the kernel itself to have this much RAM available. The struct page used to describe each page frame still requires 44 bytes and this uses kernel virtual address space in ZONE\_NORMAL. That means that to describe 1GiB of memory, approximately 11MiB of kernel memory is required. Thus, with 16GiB, 176MiB of memory is consumed, putting significant pressure on ZONE\_NORMAL. This does not sound too bad until other structures are taken into account which use ZONE\_NORMAL. Even very small structures such as *Page Table Entries (PTEs)* require about 16MiB in the worst case. This makes 16GiB about the practical limit for available physical memory Linux on an x86. If more memory needs to be accessed, the advice given is simple and straightforward, buy a 64 bit machine.

## 2.6 □ □ What's New In 2.6

Nodes

At first glance, there has not been many changes made to how memory is described but the seemingly minor changes are wide reaching. The node descriptor pg\_data\_t has a few new fields which are as follows:

**node\_start\_pfn** replaces the node\_start\_paddr field. The only difference is that the new field is a PFN instead of a physical address. This was changed as PAE architectures can address more memory than 32 bits can address so nodes starting over 4GiB would be unreachable with the old field;

**kswapd\_wait** is a new wait queue for **kswapd**. In 2.4, there was a global wait queue for the page swapper daemon. In 2.6, there is one**kswapdN** for each node where N is the node identifier and each **kswapd** has its own wait queue with this field.

The node\_size field has been removed and replaced instead with two fields. The change was introduced to recognise the fact that nodes may have "holes" in them where there is no physical memory backing the address.

**node\_present\_pages** is the total number of physical pages that are present in the node.

**node\_spanned\_pages** is the total area that is addressed by the node, including any holes that may exist

#### Zones

Even at first glance, zones look very different. They are no longer called <code>zone\_t</code> but instead referred to as simplystruct <code>zone</code>. The second major difference is the LRU lists. As we'll see in Chapter 10, kernel 2.4 has a global list of pages that determine the order pages are freed or paged out. These lists are now stored in the <code>struct zone</code>. The relevant fields are:

**lru\_lock** is the spinlock for the LRU lists in this zone. In 2.4, this is a global lock called pagemap lru lock;

active\_list is the active list for this zone. This list is the same as described in Chapter <u>10</u> except it is now per-zone instead of global;

**inactive list** is the inactive list for this zone. In 2.4, it is global;

**refill\_counter** is the number of pages to remove from theactive\_list in one pass. Only of interest during page replacement;

**nr** active is the number of pages on the active list;

nr\_inactive is the number of pages on the inactive\_list;

**all\_unreclaimable** is set to 1 if the pageout daemon scans through all the pages in the zone twice and still fails to free enough pages;

**pages\_scanned** is the number of pages scanned since the last bulk amount of pages has been reclaimed. In 2.6, lists of pages are freed at once rather than freeing pages individually which is what 2.4 does;

**pressure** measures the scanning intensity for this zone. It is a decaying average which affects how hard a page scanner will work to reclaim pages.

Three other fields are new but they are related to the dimensions of the zone. They are:

**zone\_start\_pfn** is the starting PFN of the zone. It replaces the zone\_start\_paddr and zone\_start\_mapnr fields in 2.4;

**spanned\_pages** is the number of pages this zone spans, including holes in memory which exist with some architectures;

**present\_pages** is the number of real pages that exist in the zone. For many architectures, this will be the same value as spanned\_pages.

The next addition is struct per\_cpu\_pagesetwhich is used to maintain lists of pages for each CPU to reduce spinlock contention. The zone—pageset field is a NR\_CPUsized array of struct per\_cpu\_pageset where NR\_CPUs the compiled upper limit of number of CPUs in the system. The per-cpu struct is discussed further at the end of the section.

The last addition to struct zone is the inclusion of padding of zeros in the struct. Development of the 2.6 VM recognised that some spinlocks are very heavily contended and are frequently acquired. As it is known that some locks are almost always acquired in pairs, an effort should be made to ensure they use different cache lines which is a common cache programming trick [Sea00]. These padding in the struct zone are marked with the ZONE\_PADDING() macro and are used to ensure the zone—lock, zone—lru lockand zone—pageset fields use different cache lines.

#### **Pages**

The first noticeable change is that the ordering of fields has been changed so that related items are likely to be in the same cache line. The fields are essentially the same except for two additions. The first is a new union used to create a PTE chain. PTE chains are are related to page table management so will be discussed at the end of Chapter 3. The second addition is ofpage—private field which contains private information specific to the mapping. For example, the field is used to store a pointer to a buffer\_head if the page is a buffer page. This means that the page—buffers field has also been removed. The last important change is that page—virtual is no longer necessary for high memory support and will only exist if the architecture specifically requests it. How high memory pages are supported is discussed further in Chapter 9.

#### Per-CPU Page Lists

In 2.4, only one subsystem actively tries to maintain per-cpu lists for any object and that is the Slab Allocator, discussed in Chapter 8. In 2.6, the concept is much more wide-spread and there is a formalised concept of hot and cold pages.

The struct per\_cpu\_pageset, declared in linux/mmzone.h> has one one field which is an array with two elements of type per\_cpu\_pages. The zeroth element of this array is for hot pages and the first element is for cold pages where hot and cold determines how "active" the page is currently in the cache. When it is known for a fact that the pages are not to be referenced soon, such as with IO readahead, they will be allocated as cold pages.

The struct per\_cpu\_pages maintains a count of the number of pages currently in the list, a high and low watermark which determine when the set should be refilled or pages freed in bulk, a variable which determines how many pages should be allocated in one block and finally, the actual list head of pages.

To build upon the per-cpu page lists, there is also a per-cpu page accounting mechanism. There is a struct page\_state that holds a number of accounting variables such as the pgalloc field which tracks the number of pages allocated to this CPU and pswpinwhich tracks the number of swap readins. The struct is heavily commented in linux/page-flags.h>. A single function mod\_page\_state() is provided for updating fields in the page\_state for the running CPU and three helper macros are provided called inc page state(), dec page state() and sub page state().

