Modern Beamer Presentations with the **NUS** package

Matthias Vogelgesang matthias.vogelgesang@gmail.com

v1.2 - 2017/01/23

Contents

1	Intro	roduction										
2	Gett	Getting Started										
	2.1	Install	ling from CTAN	4								
	2.2	Install	ling from GitHub	4								
	2.3		mal Example	5								
	2.4		ndencies	6								
	2.5		oc	6								
3	Cust	Customization 6										
	3.1	Packag	ge options	6								
		3.1.1	Main theme	7								
		3.1.2	Inner theme	7								
		3.1.3	Outer theme	7								
		3.1.4	Color theme	8								
		3.1.5	Font theme	8								
	3.2	Color	Customization	8								
	3.3	Font C	Customization	9								
		3.3.1	Old style figures	9								
	3.4	Comm	nands	10								
		3.4.1	Standout frames	10								

4	pgf	plots	integration	10				
	4.1	Styles		10				
	4.2	Paul T	ol colors	11				
5	Tips	& Tricl		11				
	5.1	Backu	p Slides	11				
6	Known Issues							
	6.1		ormats	11				
	6.2	Intera	ctions with other color themes	12				
	6.3	Notes	on second screen	13				
	6.4	Stand	out frames with labels	13				
	6.5	Stand	out frames with Pandoc	14				
7	Lice	nse		14				
8	Imp	lement	ation	14				
	8.1	NUS p	arent theme	14				
		8.1.1	Package dependencies	15				
		8.1.2	Options	15				
		8.1.3	Component sub-packages	17				
		8.1.4	Custom commands	17				
		8.1.5	Process package options	18				
	8.2	NUS in	nner theme	18				
		8.2.1	Package dependencies	18				
		8.2.2	Options	18				
		8.2.3	Title page	19				
		8.2.4	Section page	22				
		8.2.5	Block environments	25				
		8.2.6	Lists and floats	27				
		8.2.7	Footnotes	27				
		8.2.8	Text and spacing settings	27				
		8.2.9	Standout frames					
		8.2.10	Secondary standout frames	29				
		8.2.11	Process package options					
	8.3	NUS o	outer theme					
		8.3.1	Package dependencies					
		8.3.2						

	8.3.3	Head and footline	32
	8.3.4	Frametitle	33
	8.3.5	Process package options	34
8.4	NUS font theme		35
	8.4.1	Package dependencies	35
	8.4.2	Load Fira fonts	35
	8.4.3	General font definitions	37
	8.4.4	Title format options	38
	8.4.5	Process package options	43
8.5	NUS color theme		43
	8.5.1	Package dependencies	43
	8.5.2	Options	44
	8.5.3	Base colors	44
	8.5.4	Base styles	44
	8.5.5	Derived colors	45
	8.5.6	Process package options	48
8.6	Tol pg	folots theme	48

1 Introduction

Beamer is an awesome way to make presentations with LaTeX, but its theme selection is surprisingly sparse. The stock themes share an aesthetic that can be a little cluttered, while the few distinctive custom themes available are often specialized for a particular corporate or institutional brand.

The goal of **NUS** is to provide a simple, modern Beamer theme suitable for anyone to use. It tries to minimize noise and maximize space for content; the only visual flourish it offers is an (optional) progress bar added to each slide or to the section slides.

By default, **NUS** uses Fira Sans, a gorgeous typeface commissioned by Mozilla and designed by Carrois. For best results, you will need the Fira typeface installed and use $X_{\underline{j}} \underline{\mathbb{M}}_{\underline{\mathsf{E}}} X$ to typeset your slides. However, **NUS** can also be used with other typefaces and $\underline{\mathbb{M}}_{\underline{\mathsf{E}}} X$ build systems.

NUS's codebase is maintained on GitHub. If you have issues, find mistakes in the manual or want to help make the theme even better, please get in touch there. The full list of contributors already contains over a dozen names!

2 Getting Started

2.1 Installing from CTAN

For most users, we recommend installing **NUS** from CTAN. If you keep your T_EX distribution up-to-date, chances are good that **NUS** is already installed. If it is not, you need to update your packages. If your distribution is T_EX Live (or MacT_EX on OS X), the following command updates all packages.

tlmgr update --all

If this results in an error, you may need to run it with administrative privileges:

sudo tlmgr update --all

 $\label{eq:macTex} \textit{MacTeX} \ on \ \textit{OS} \ \textit{X} \ also \ provides \ a \ graphical \ interface \ for \ \textbf{tlmgr} \ called \ \textit{TeX} \ Live \ \textbf{Utility}.$

For any other distribution please refer to its documentation on how to update your packages.

To get the most out of the theme you should also install the Fira fonts. However, this is not mandatory; **NUS** also works with the standard fonts.

2.2 Installing from GitHub

If you want to use the cutting-edge development version of **NUS**, you can install it manually. Like any धा_FX package, this involves four easy steps:

Download the source with a git clone of the NUS repository or as a zip archive of the latest development version.

Compile the style files by running make sty inside the downloaded directory. (Or run ETFX directly on source/NUStheme.ins.)

Move the resulting *.sty files to the folder containing your presentation. To use NUS with many presentations, run make install or move the *.sty files to a folder in your T_FX path instead.

Use the theme for your presentation by declaring \usetheme{NUS} in the preamble of your Beamer document.

NUS uses the Make build system to offer the following installation options for advanced users:

```
make sty builds the theme style files.
make doc builds this documentation manual.
make demo builds a demo presentation to test the features of NUS.
make all builds the theme and manual.
make clean removes the files generated by make all.
make install installs the theme into your local texmf folder.
make uninstall removes the theme from your local texmf folder.
```

2.3 A Minimal Example

The following code shows a minimal example of a Beamer presentation using **NUS**.

2.4 Dependencies

NUS depends on the beamer class and the following standard packages:

```
tikzpgfoptscalcifxetexifluatex
```

For best results, we recommend installing the fonts **Fira Sans** and **Fira Mono** and compiling with **NUS** using X₂M_EX or LuaT_EX. These are optional dependencies; **NUS** is compatible with (e.g.) pdfM_EX and will fall back to standard fonts if **Fira Sans** or **Fira Mono** is not installed.

The packaged name of **Fira Sans** is **Fira Sans OT** in some Linux distributions; this case is automatically handled by **NUS**.

2.5 Pandoc

To use this theme with Pandoc-based presentations, you can run the following command

```
$ pandoc -t beamer --latex-engine=xelatex -V theme:NUS -o
   output.pdf input.md
```

3 Customization

3.1 Package options

The theme provides a number of options, which can be set using a key=value interface. The primary way to set options is to provide a comma-separated list of option-value pairs when loading **NUS** in the preamble:

```
\usetheme[option1=value1, option2=value2, ...]{NUS}
```

Options can be changed at any time — even mid-presentation! — with the $\mbox{metroset}$ macro.

```
\metroset{option1=newvalue1, option2=newvalue2, ...}
```

	The list of options is structured as shown in the following example.
option key	list of possible values default
	A short description of the option.
	3.1.1 Main theme
titleformat	regular, smallcaps, allsmallcaps, allcaps regular
	Changes the format of titles, subtitles, section titles, frame titles, and the text on "standout" frames. The available options produce Regular, SMALLCAPS, ALLSMALLCAPS, or ALLCAPS titles. Please refer to Section 6.1 for known issues with these options.
titleformat plain	regular, smallcaps, allsmallcaps, allcaps regular
	Changes the format of "standout" frames (see titleformat, above).
	3.1.2 Inner theme
sectionpage	none, simple, progressbar progressbar
	Adds a slide at the start of each section (simple) with an optional thin progress bar below the section title (progressbar). The none option disables the section page.
subsectionpage	none, simple, progressbar none
	Optionally adds a slide at the start of each subsection. If enabled with the <code>simple</code> or <code>progressbar</code> options, the style of the <code>section</code> <code>page</code> will be updated to match the style of the <code>subsection</code> <code>page</code> . Note that section slides and subsection slides can appear consecutively if both are enabled; you may want to use this option together with <code>sectionpage=none</code> depending on the section structure of your presentation.
	3.1.3 Outer theme
numbering	none, counter, fraction
	Controls whether the frame number at the bottom right of each slide is omitted (none), shown (counter) or displayed as a fraction of the total number of frames (fraction).

titleformat title titleformat subtitle titleformat section titleformat frame regular, smallcaps, allsmallcaps, allcaps regular

Individually controls the format of titles, subtitles, section titles, and frame titles (see titleformat, above).

3.2 Color Customization

The included **NUS** color theme is used by default, but its colors can be easily changed to suit your tastes. All of the theme's styles are defined in terms of three beamer colors:

- normal text (dark fg, light bg)
- alerted text (colored fg, should be visible against dark or light)
- example text (colored fg, should be visible against dark or light)

An easy way to customize the theme is to redefine these colors using

\setbeamercolor{ ... }{ fg= ... , bg= ... }

in your preamble. For greater customization, you can redefine any of the other stock beamer colors. In addition to the stock colors the theme defines a number of **NUS** specific colors, which can also be redefined to your liking.

```
\setbeamercolor{progress bar}{ ... }
\setbeamercolor{title separator}{ ... }
\setbeamercolor{progress bar in head/foot}{ ... }
\setbeamercolor{progress bar in section page}{ ... }
```

3.3 Font Customization

The default font for **NUS** is **Fira**. This can be easily changed using the standard font selection commands of the **fontspec** package. So if you prefer, for example, the **Ubuntu** font family, just add the following two commands after loading the **NUS** theme.

```
\setsansfont{Ubuntu}
\setmonofont{Ubuntu Mono}
```

If you are expecting to present in a large room or with an underpowered projector, you may want to change the font to a heavier weight of Fira to maximize readability.

```
\setsansfont[BoldFont={Fira Sans SemiBold}]{Fira Sans Book}
```

3.3.1 Old style figures

The regular fontspec mechanism for changing glyph appearance applies also to this theme. If you want to have old style figures in the text but regular lined figures for math, you could add the following to your preamble:

3.4 Commands

3.4.1 Standout frames

The **NUS** inner theme offers a custom frame format with large, centered text and an inverted background — perfect for focusing attention on single sentence or image. To use it, add the key **standout** to the frame:

```
\begin{frame}[standout]
    Thank you!
\end{frame}
```

4 pgfplots integration

NUS comes with a set of pre-defined pgfplots styles and a color theme based on Paul Tol's color scheme.

4.1 Styles

Pass the following style keys to the axis environment to get the appropriate effect:

mlineplot Plot regular line charts with reduced axis frames, less intrusive legend and subdued grid.

mbarplot Plot vertical bar charts in a similar way as mlineplot but reduce grid usage.

horizontal mbarplot Plot horizontal bar charts.

disable thousands separator Helper style to remove thousands separator.

4.2 Paul Tol colors

A good presentation uses colors that are distinct from each other as much as possible as well as from black and white, can be discerned item under different lighting and display environments and by color-blind viewers, while matching well together.

In a technical note for SRON, Paul Tol proposed a palette of colors satisfying these constraints. The sub-package pgfplotsthemetol defines palettes for pgfplots charts based on Tol's work.

5 Tips & Tricks

5.1 Backup Slides

Speakers will often include extra slides at the end of their presentation to refer to during audience questions. One easy way to do this is to include the appendixnumberbeamer package in your preamble and call \appendix before your backup slides.

NUS will automatically turn off slide numbering and progress bars for slides in the appendix.

6 Known Issues

6.1 Title formats

Be aware that not every font supports small caps, so the **smallcaps** or **allsmallcaps** options may not work if you use a font other than **Fira Sans**. In particular, the Computer Modern sans-serif typeface, which is used when **NUS** is compiled with pdf@rX, does not have a small-caps variant.

The title format options allsmallcaps and allcaps are quite nice from an aesthetic point of view, but their use of \MakeLowercase and \MakeUppercase can cause unexpected problems. For example:

Some commands, like \\, do not work inside \MakeLowercase and \MakeUppercase. (See #125)

- Only alphabetic characters are affected by \MakeLowercase, so numerals
 and punctuation remain at full height. This can spoil some of the aesthetic
 benefits of allsmallcaps. (See #33)
- \MakeLowercase and \MakeUppercase apply to math mode and \scshape does not. This can easily introduce mathematical errors that are hard to catch
- It is impossible to typeset symbols which are encoded as uppercase letters in a different font. In particular, \mathbb and \mathcal letters will be replaced by other math glyphs. (See #153)

The **allsmallcaps** and **allcaps** options are safe to use if your titles contain only alphabetic characters and do not require the expansion of any macros.

6.2 Interactions with other color themes

NUS can be used along with any other Beamer color theme, such as **crane** or **seahorse**. If you wish to do this, it is usually best to include the **NUS** subpackages individually so the **NUS** color theme is never loaded. This will prevent conflicts between the **NUS** color theme and your preferred theme.

For example, overriding the color theme as follows may not work as expected because \usetheme{NUS} loads the NUS color theme, which defines a relationship between the frametitle background and the primary palette of the theme. Since seahorse assumes a different relationship between its palettes, the result is a grey, rather than periwinkle, frametitle background.

```
\usetheme{NUS}
\usecolortheme{seahorse}
```

The correct colors are chosen if the **NUS** outer, inner, and font themes are loaded seperately:

```
\useoutertheme{NUS}
\useinnertheme{NUS}
\usefonttheme{NUS}
\usecolortheme{seahorse} % or your preferred color theme
```

Please note that **NUS** may not use all the colors defined in your favourite Beamer color theme. In particular, **NUS** does not set a background color for the title; this will cause issues when using color themes like **whale** which set a white foreground for the title.

6.3 Notes on second screen

If you use the [show notes on second screen] option built in to Beamer and compile with XameX, text on slides following the first section slide may be rendered in white instead of the regular colour. This is due to a bug in Beamer or XameX itself. You can work around it either by compiling with LuaTeX or by adding the following code to your preamble to reset the text color on each slide.

```
\makeatletter
\def\beamer@framenotesbegin{% at beginning of slide
    \usebeamercolor[fg]{normal text}
    \gdef\beamer@noteitems{}%
    \gdef\beamer@notes{}%
}
\makeatother
```

6.4 Standout frames with labels

Because the **standout** frame option creates a group to restrict the colour change to a single slide, labels defined after calling **standout** will stay local to the group. In other words, the following may result in a "label undefined" error.

```
\begin{frame}[standout, label=conclusion]{Conclusion}
  Awesome slide
\end{frame}
```

To fix this problem, change the order of the keys in the frame.

```
\begin{frame}[label=conclusion, standout]{Conclusion}
    Awesome slide
\end{frame}
```

This error can be unwittingly triggered if you export your slides from Emacs Org mode, which automatically adds labels after frame options. Alex Branham offers the following solution for Org mode users, using org-set-property.

```
* Start of a frame
    :PROPERTIES:
    :BEAMER_opt: label=conclusion,standout
    :END:
```

6.5 Standout frames with Pandoc

With Pandoc versions prior 1.17.2 it was not possible to create standout frames because Pandoc only supported a specific list of frame attributes thus ignoring additional attributes such as {.standout}.

7 License

NUS is licensed under a Creative Commons Attribution-ShareAlike 4.0 International License. This means that if you change the theme and re-distribute it, you must retain the copyright notice header and license it under the same CC-BY-SA license. This does not affect any presentations that you create with the theme.

8 Implementation

8.1 NUS parent theme

The primary job of this package is to load the component sub-packages of the **NUS** theme and route the theme options accordingly. It also provides some custom commands and environments for the user.

8.1.1 Package dependencies

```
1\RequirePackage{etoolbox}
2\RequirePackage{pgfopts}
```

8.1.2 Options

Most options are passed off to the component sub-packages.

```
3\pgfkeys{/NUS/.cd,
4    .search also={
5     /NUS/inner,
6     /NUS/outer,
7     /NUS/color,
8     /NUS/font,
9  }
10}
```

titleformat plain Controls the formatting of the text on standout "plain" frames.

```
11 \pgfkeys{
   /NUS/titleformat plain/.cd,
12
      .is choice,
13
      regular/.code={%
        \let\NUS@plaintitleformat\@empty%
15
        \setbeamerfont{standout}{shape=\normalfont}%
16
      },
17
      smallcaps/.code={%
18
        \let\NUS@plaintitleformat\@empty%
        \setbeamerfont{standout}{shape=\scshape}%
20
      },
21
      allsmallcaps/.code={%
22
        \let\NUS@plaintitleformat\MakeLowercase%
23
        \setbeamerfont{standout}{shape=\scshape}%
24
        \PackageWarning{beamerthemeNUS}{%
25
          Be aware that titleformat plain=allsmallcaps can lead to problems%
26
        }
27
28
      },
      allcaps/.code={%
29
        \let\NUS@plaintitleformat\MakeUppercase%
30
        \setbeamerfont{standout}{shape=\normalfont}%
31
        \PackageWarning{beamerthemeNUS}{%
32
```

```
Be aware that titleformat plain=allcaps can lead to problems%
33
34
        }
      },
35
36 }
```

titleformat Sets a standard format for titles, subtitles, section titles, frame titles, and the text on standout "plain" frames.

```
37 \pgfkeys{
   /NUS/titleformat/.code=\pgfkeysalso{
        font/titleformat title=#1,
39
        font/titleformat subtitle=#1,
40
        font/titleformat section=#1,
41
        font/titleformat frame=#1,
42
        titleformat plain=#1,
43
      }
44
45 }
```

For backwards compatibility with earlier betas of the theme, we implement deprecated option names as aliases to the corresponding key=value options.

```
46 \pgfkeys{/NUS/.cd,
   usetitleprogressbar/.code=\pgfkeysalso{outer/progressbar=frametitle},
   noslidenumbers/.code=\pgfkeysalso{outer/numbering=none},
   usetotalslideindicator/.code=\pgfkeysalso{outer/numbering=fraction},
49
   nosectionslide/.code=\pgfkeysalso{inner/sectionpage=none},
50
   darkcolors/.code=\pgfkeysalso{color/background=dark},
52 blockbg/.code=\pgfkeysalso{color/block=fill, inner/block=fill},
53 }
```

Set default values for options.

```
54 \newcommand{\NUS@setdefaults}{
   \pgfkeys{/NUS/.cd,
      titleformat plain=regular,
56
   }
57
58 }
```

To avoid generating externalized figures of the progressbar we have to disable them with "tikzexternalenable" and "tikzexternaldisable". However, if the "external" libray is not loaded we would get undefined control sequence problems, hence we define them as no-ops if they are not defined yet.

```
59\providecommand{\tikzexternalenable}{}
60\providecommand{\tikzexternaldisable}{}
```

8.1.3 Component sub-packages

Having processed the options, we can now load the component sub-packages of the theme.

```
61\useinnertheme{NUS}
62\useoutertheme{NUS}
63\usecolortheme{NUS}
64\usefonttheme{NUS}
```

The tol theme for pgfplots is only loaded if pgfplots is used.

```
65 \AtEndPreamble{%
66 \@ifpackageloaded{pgfplots}{%
67 \RequirePackage{pgfplotsthemetol}
68 }{}
69 }
```

8.1.4 Custom commands

The parent theme defines custom commands as their proper usage may depend on multiple sub-packages.

\metroset Allows the user to change options midway through a presentation.

```
70 \newcommand{\metroset}[1]{\pgfkeys{/NUS/.cd,#1}}
```

\plain Creates a plain frame with dark background, suitable for displaying images or a few words. The format of the text can be set with the titleformat plain option.

```
71\def\NUS@plaintitleformat#1{#1}
72\newcommand{\plain}[2][]{%
73 \PackageWarning{beamerthemeNUS}{%
74 The syntax '\plain' may be deprecated in a future version of NUS.
75 Please use a frame with [standout] instead.
76 }
```

```
77 \begin{frame}[standout]{#1}
78 \NUS@plaintitleformat{#2}
79 \end{frame}
80 }
```

\mreducelistspacing

81 \newcommand{\mreducelistspacing}{\vspace{-\topsep}}

8.1.5 Process package options

```
82 \NUS@setdefaults
83 \ProcessPgfOptions{/NUS}
```

8.2 NUS inner theme

A **beamer** inner theme dictates the style of the frame elements traditionally set in the "body" of each slide. These include:

- · title, part, and section pages;
- · itemize, enumerate, and description environments;
- block environments including theorems and proofs;
- · figures and tables; and
- · footnotes and plain text.

8.2.1 Package dependencies

```
84 \RequirePackage{etoolbox}
85 \RequirePackage{keyval}
86 \RequirePackage{calc}
87 \RequirePackage{pgfopts}
88 \RequirePackage{tikz}
```

8.2.2 Options

sectionpage Optionally add a slide marking the beginning of each section.

```
89 \pgfkeys{
90  /NUS/inner/sectionpage/.cd,
91  .is choice,
92  none/.code=\NUS@disablesectionpage,
93  simple/.code={\NUS@enablesectionpage
```

```
\setbeamertemplate{section page}[simple]},
                          94
                          95
                                progressbar/.code={\NUS@enablesectionpage
                                                     \setbeamertemplate{section page}[progressbar]},
                          96
                          97 }
                          Optionally add a slide marking the beginning of each subsection.
        subsectionpage
                          98 \pgfkeys{
                              /NUS/inner/subsectionpage/.cd,
                                .is choice,
                         100
                                none/.code=\NUS@disablesubsectionpage,
                          101
                                simple/.code={\NUS@enablesubsectionpage
                          102
                                                \setbeamertemplate{section page}[simple]},
                          103
                                progressbar/.code={\NUS@enablesubsectionpage
                         104
                                                     \setbeamertemplate{section page}[progressbar]},
                         105
                         106 }
\NUS@inner@setdefaults Set default values for inner theme options.
                         107 \newcommand{\NUS@inner@setdefaults}{
                              \pgfkeys{/NUS/inner/.cd,
                                sectionpage=progressbar,
                         109
                                subsectionpage=none
                          110
                          111
                              }
                          112 }
                          8.2.3 Title page
             title page Template for the title page. Each element is only typset if it is defined by the
                          user. If \subtitle is empty, for example, it won't leave a blank space on the
                          title slide.
                          113 \setbeamertemplate{title page}{
                              \begin{minipage}[b][\paperheight]{\textwidth}
                          114
                                \ifx\inserttitlegraphic\@empty\else\usebeamertemplate*{title graphic}\fi
                          115
                                \vfill%
                          116
                                \ifx\inserttitle\@empty\else\usebeamertemplate*{title}\fi
                          117
                                \ifx\insertsubtitle\@empty\else\usebeamertemplate*{subtitle}\fi
                          118
                          119
                                \usebeamertemplate*{title separator}
```

Beamer's definition of \insertauthor is always nonempty, so we have to test another macro initialized by \author{...} to see if the user has defined an author. This solution was suggested by Enrico Gregorio in an answer to this Stack Exchange question.

```
\ifx\beamer@shortauthor\@empty\else\usebeamertemplate*{author}\fi
\ifx\insertdate\@empty\else\usebeamertemplate*{date}\fi
\ifx\insertinstitute\@empty\else\usebeamertemplate*{institute}\fi
\vfill
\vspace*{1mm}
\end{minipage}
```

Normal people should use \maketitle or \titlepage instead of using the title page beamer template directly. Beamer already defines these macros, but we patch them here to make the title page [plain] by default, remove \alphathanks, and ensure the title frame number doesn't count.

\maketitle Inserts the title frame, or causes the current frame to use the title page tem-\titlepage plate.

```
127 \def\maketitle{%
128  \ifbeamer@inframe
129  \titlepage
130  \else
131  \frame[plain,noframenumbering]{\titlepage}
132  \fi
133 }
134 \def\titlepage{%
135  \usebeamertemplate{title page}
136 }
```

title graphic Set the title graphic in a zero-height box, so it doesn't change the position of other elements.

```
137 \setbeamertemplate{title graphic}{
138  \vbox to 0pt {
139   \vspace*{2em}
140   \inserttitlegraphic%
141  }%
```

```
\nointerlineskip%
                  143 }
          title Set the title on the title page.
                  144\setbeamertemplate{title}{
                     \raggedright%
                     \linespread{1.0}%
                  147 \inserttitle%
                  148 \par%
                  149 \vspace*{0.5em}
                  150 }
       subtitle Set the subtitle on the title page.
                  151 \setbeamertemplate{subtitle}{
                      \raggedright%
                     \insertsubtitle%
                      \par%
                  154
                     \vspace*{0.5em}
                  155
                  156 }
title separator Template to set the title graphic in a zero-height box. (It won't change the posi-
                  tion of other elements.)
                  157 \newlength{\NUS@titleseparator@linewidth}
                  158 \setlength{\NUS@titleseparator@linewidth}{0.4pt}
                  159 \setbeamertemplate{title separator}{
                      \tikzexternaldisable%
                      \begin{tikzpicture}
                  161
                        \fill[fg] (0,0) rectangle (\textwidth, \NUS@titleseparator@linewidth);
                  162
                      \end{tikzpicture}%
                  163
                      \tikzexternalenable%
                      \par%
                  166 }
         author Set the author on the title page.
                  167 \setbeamertemplate{author}{
                     \vspace*{2em}
                     \insertauthor%
```

```
\par%
                   \vspace*{0.25em}
               171
               172 }
        date Set the date on the title page.
               173 \setbeamertemplate{date}{
                   \insertdate%
                   \par%
               176 }
   institute Set the institute on the title page.
               177 \setbeamertemplate{institute}{
                   \vspace*{3mm}
                   \insertinstitute%
               179
                   \par%
               180
               181 }
               8.2.4 Section page
               Template for the section title slide at the beginning of each section.
section page
               182 \defbeamertemplate{section page}{simple}{
                    \begin{center}
               183
                      \usebeamercolor[fg]{section title}
               184
                      \usebeamerfont{section title}
               185
                      \insertsectionhead\par
               186
                      \ifx\insertsubsectionhead\@empty\else
               187
                        \usebeamercolor[fg]{subsection title}
               188
                        \usebeamerfont{subsection title}
               189
                        \insertsubsectionhead
               190
                      \fi
               191
                   \end{center}
               192
               193 }
               194 \defbeamertemplate{section page}{progressbar}{
                    \centering
               195
                   \begin{minipage}{22em}
               196
                      \raggedright
               197
                      \usebeamercolor[fg]{section title}
               198
                      \usebeamerfont{section title}
               199
```

```
\insertsectionhead\\[-1ex]
                  200
                         \usebeamertemplate*{progress bar in section page}
                  201
                         \par
                  202
                         \ifx\insertsubsectionhead\@empty\else%
                  203
                           \usebeamercolor[fg]{subsection title}%
                  204
                           \usebeamerfont{subsection title}%
                  205
                           \insertsubsectionhead
                  206
                         \fi
                  207
                       \end{minipage}
                  208
                       \par
                  209
                       \vspace{\baselineskip}
                  210
                  211 }
                  212 \newcommand{\NUS@disablesectionpage}{
                       \AtBeginSection{
                  213
                         % intentionally empty
                  214
                       }
                  215
                  216 }
                  217 \newcommand{\NUS@enablesectionpage}{
                       \AtBeginSection{
                  218
                         \ifbeamer@inframe
                  219
                           \sectionpage
                  220
                  221
                         \else
                           \frame[plain,c,noframenumbering]{\sectionpage}
                  222
                         \fi
                  223
                       }
                  224
                  225 }
subsection page
                  Template for the subsection title slide that can optionally be added to at the
                  beginning of each subsection.
                  226 \setbeamertemplate{subsection page}{%
                       \usebeamertemplate*{section page}
                  227
                  228 }
                  229 \newcommand{\NUS@disablesubsectionpage}{
                       \AtBeginSubsection{
                  230
                         % intentionally empty
                  231
                       }
                  232
```

234 \newcommand{\NUS@enablesubsectionpage}{

\AtBeginSubsection{

233 }

```
236  \ifbeamer@inframe
237   \subsectionpage
238  \else
239   \frame[plain,c,noframenumbering]{\subsectionpage}
240  \fi
241  }
242 }
```

rogress bar in section page

Template for the progress bar displayed by default on the section page. This code is duplicated in large part in the outer theme's template **progress** bar in head/foot.

```
243 \newlength{\NUS@progressonsectionpage}
244 \newlength{\NUS@progressonsectionpage@linewidth}
245\setlength{\NUS@progressonsectionpage@linewidth}{0.4pt}
246\setbeamertemplate{progress bar in section page}{
    \setlength{\NUS@progressonsectionpage}{%
      \textwidth * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}%
248
    }%
249
    \tikzexternaldisable%
250
    \begin{tikzpicture}
251
      \fill[bg] (0,0) rectangle (\textwidth, \NUS@progressonsectionpage@linewidth);
252
      \fill[fg] (0,0) rectangle (\NUS@progressonsectionpage, \NUS@progressonsectionpa
253
    \end{tikzpicture}%
254
    \tikzexternalenable%
255
256 }
```

The above code assumes that \insertframenumber is less than or equal to \inserttotalframenumber. However, this is not true on the first compile; in the absence of an .aux file, \inserttotalframenumber defaults to 1. This behaviour could cause fatal errors for long presentations, as \NUS@progressonsectionpage would exceed TeX's maximum length (16383.99999pt, roughly 5.75 metres or 18.9 feet). To avoid this, we increase the default value for \inserttotalframenumber; presentations with over 4000 slides will still break on first compile, but users in that situation likely have deeper problems to solve.

257 \def\inserttotalframenumber{100}

8.2.5 Block environments

block The three different block environments differ only in their colours. Rather than block alerted repeat the essentially the same template three times, we use the auxiliary macro block example \NUS@block to define all three templates.

```
258 \newlength{\NUS@blocksep}
259 \newlength{\NUS@blockadjust}
260 \setlength{\NUS@blocksep}{0.75ex}
261\setlength{\NUS@blockadjust}{0.25ex}
262 \providecommand{\NUS@strut}{%
    \vphantom{ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz()}%
263
264 }
265 \newcommand{\NUS@block}[1]{
    \par\vskip\medskipamount%
    \setlength{\parskip}{0pt}
```

If a background color is defined for the block title or body, we need to add a little bit of padding to the corresponding box. Ideally, this would be accomplished by setting colsep=0.75ex, which is intended to add "color separation space" only when the box has a colored background. Unfortunately, colsep also adds this separation if the background color is inherited, even if the inherited color is actually empty. (The technical reason for this boils down to the fact that the \ifx directive does not expand macros.)

To achieve the correct spacing for alertblocks and exampleblocks as well as for normal blocks, we have to begin the beamercolorbox differently based on whether block title has an empty background.

If the block title background is empty, or the user has explicitly removed the background from (e.g.) block title alerted, we just need to set a rightskip for a nice ragged-right block title.

\ifbeamercolorempty[bg]{block title#1}{%

268

```
\begin{beamercolorbox}[rightskip=0pt plus 4em]{block title#1}}{%
269
    \ifbeamercolorempty[bg]{block title}{%
270
      \begin{beamercolorbox}[rightskip=0pt plus 4em]{block title#1}%
271
272
273 %
      \end{macrocode}
274 %
      Otherwise, if the |block title| has a background, we set the padding based
275 %
```

```
on |\NUS@blockskip|. However, we have to visually compensate for
276 %
277 %
      the |\NUS@strut| added to the block title (see below) by
      subtracting |\NUS@blockadjust| from the top and bottom padding.
278 %
279 %
      \begin{macrocode}
280 %
    {%
281
      \begin{beamercolorbox}[
282
         sep=\dimexpr\NUS@blocksep-\NUS@blockadjust\relax,
283
         leftskip=\NUS@blockadjust,
284
         rightskip=\dimexpr\NUS@blockadjust plus 4em\relax
285
      ]{block title#1}%
286
    }}%
287
      \end{macrocode}
288 %
289 %
      We can now set the contents of the |block title|. The zero-width but
290 %
      positive-height box |\NUS@strut| ensures that the block title box
291 %
      has a consistent height, even if it lacks punctuation, ascenders, or
292 %
      descenders.
293 %
294 %
      \begin{macrocode}
295 %
         \usebeamerfont*{block title#1}%
296
         \NUS@strut%
297
         \insertblocktitle%
298
         \NUS@strut%
299
    \end{beamercolorbox}%
300
      \end{macrocode}
301 %
302 %
303 %
      Next, we typeset the |block body|. This the code is similar to, but simpler
      than, the |block title| code since we don't need to adjust for any struts.
304 %
305 %
306 %
      \begin{macrocode}
    \nointerlineskip%
307
    \ifbeamercolorempty[bg]{block body#1}{%
308
      \begin{beamercolorbox}[vmode]{block body#1}}{
309
    \ifbeamercolorempty[bg]{block body}{%
310
      \begin{beamercolorbox}[vmode]{block body#1}%
311
    }{%
312
      \begin{beamercolorbox}[sep=\NUS@blocksep, vmode]{block body#1}%
313
      \vspace{-\NUS@parskip}
314
    }}%
315
```

```
\usebeamerfont{block body#1}%
316
317
        \setlength{\parskip}{\NUS@parskip}%
318 }
This concludes the auxiliary macro \NUS@block. Finally, we define the block
beamer templates using this macro.
319 \setbeamertemplate{block begin}{\NUS@block{}}
320 \setbeamertemplate{block alerted begin}{\NUS@block{ alerted}}
321\setbeamertemplate{block example begin}{\NUS@block{ example}}
322\setbeamertemplate{block end}{\end{beamercolorbox}\vspace*{0.2ex}}
323\setbeamertemplate{block alerted end}{\end{beamercolorbox}\vspace*{0.2ex}}
324\setbeamertemplate{block example end}{\end{beamercolorbox}\vspace*{0.2ex}}
8.2.6 Lists and floats
325 %\setbeamertemplate{itemize items}{\textbullet}
326 \setbeamertemplate{itemize item}{$\bullet$}
327\setbeamertemplate{itemize subitem}{$\circ$}
328 \setbeamertemplate{caption label separator}{: }
329 \setbeamertemplate{caption}[numbered]
8.2.7 Footnotes
330 \setbeamertemplate{footnote}{%
    \parindent 0em\noindent%
    \raggedright
    \usebeamercolor{footnote}\hbox to 0.8em{\hfil\insertfootnotemark}\insertfootnotet
333
334 }
8.2.8 Text and spacing settings
```

```
335 \newlength{\NUS@parskip}
336 \setlength{\NUS@parskip}{0.5em}
337 \setlength{\parskip}{\NUS@parskip}
338 \linespread{1.15}
```

By default, Beamer frames offer the c option to almost vertically center the text, but the placement is a little too high. To fix this, we redefine the c option to equalize \beamer@frametopskip and \beamer@framebottomskip. This solution was suggested by Enrico Gregorio in an answer to this Stack Exchange question.

```
339 \define@key{beamerframe}{c}[true]{% centered
340 \beamer@frametopskip=0pt plus 1fill\relax%
341 \beamer@framebottomskip=0pt plus 1fill\relax%
342 \beamer@frametopskipautobreak=0pt plus .4\paperheight\relax%
343 \beamer@framebottomskipautobreak=0pt plus .6\paperheight\relax%
344 \def\beamer@initfirstlineunskip{}%
345}
```

8.2.9 Standout frames

NUS offers a custom frame format with large, centered text and an inverted background. To use it, add the key **standout** to the frame: \begin{frame}[standout] ... \end{fram

Standout Optional arguments to Beamer's frames are implemented using \define@key from the keyval package, which will execute code when the defined option is called. For the standout option, we begin a group, change the colors and

fonts, and set a alignment.

```
346 \providebool{NUS@standout}
347 \define@key{beamerframe}{standout}[true]{%
    \booltrue{NUS@standout}
348
    \begingroup
349
       \setkeys{beamerframe}{c}
350
       \setkeys{beamerframe}{noframenumbering}
351
       \ifbeamercolorempty[bg]{palette primary}{
352
         \setbeamercolor{background canvas}{
353
           use=palette primary,
354
           bg=-palette primary.fg
355
         }
356
       }{
357
         \setbeamercolor{background canvas}{
358
           use=palette primary,
359
           bg=palette primary.bg
360
         }
361
362
       \setbeamercolor{local structure}{
363
         fg=palette primary.fg
364
365
       \centering
366
       \usebeamercolor[fg]{palette primary}
367
       \usebeamerfont{standout}
368
```

369 }

Then we just have to close the group after the standout slide is finished in order to restore the colours and fonts for the rest of the presentation.

Unfortunately, we cannot use or this (see

http://tex.stackexchange.com/questions/226319/). Instead, we add the \endgroup to \beamer@reseteecodes, which is run exactly once at the end of each slide.

```
370 \apptocmd{\beamer@reseteecodes}{%
371 \ifbool{NUS@standout}{
372 \endgroup
373 \boolfalse{NUS@standout}
374 }{}
375 }{}{}
```

8.2.10 Secondary standout frames

NUS offers a custom frame format with large, centered text and an secondary inverted background. To use it, add the key **secondarystandout** to the frame: \begin{frame}[secondarystandout] ... \end{frame}.

secondarystandout

Optional arguments to Beamer's frames are implemented using \define@key from the keyval package, which will execute code when the defined option is called. For the secondarystandout option, we begin a group, change the colors and fonts, and set a alignment.

```
376 \providebool{NUS@secondarystandout}
377 \define@key{beamerframe}{secondarystandout}[true]{%
    \booltrue{NUS@secondarystandout}
378
379
    \begingroup
      \setkeys{beamerframe}{c}
380
      \setkeys{beamerframe}{noframenumbering}
381
      \ifbeamercolorempty[bg]{palette primary}{
382
         \setbeamercolor{background canvas}{
383
           use=palette primary,
384
           bg=-palette primary.fg
385
         }
386
      }{
387
         \setbeamercolor{background canvas}{
388
```

```
use=palette primary,
389
390
           bg=palette primary.bg
         }
391
392
       \setbeamercolor{local structure}{
393
         fg=palette primary.fg
394
395
       \centering
396
       \usebeamercolor[fg]{palette primary}
397
       \usebeamerfont{standout}
398
399 }
```

Then we just have to close the group after the secondarystandout slide is finished in order to restore the colours and fonts for the rest of the presentation. Unfortunately, we cannot use or this (see

http://tex.stackexchange.com/questions/226319/). Instead, we add the \endgroup to \beamer@reseteecodes, which is run exactly once at the end of each slide.

```
400 \apptocmd{\beamer@reseteecodes}{%
401 \ifbool{NUS@secondarystandout}{
402 \endgroup
403 \boolfalse{NUS@secondarystandout}
404 }{}
405 }{}{}
```

8.2.11 Process package options

```
406 \NUS@inner@setdefaults
407 \ProcessPgfPackageOptions{/NUS/inner}
```

8.3 NUS outer theme

A **beamer** outer theme dictates the style of the frame elements traditionally set outside the body of each slide: the head, footline, and frame title.

8.3.1 Package dependencies

```
408 \RequirePackage{etoolbox}
409 \RequirePackage{calc}
410 \RequirePackage{pgfopts}
```

8.3.2 Options

411 \pgfkeys{

numbering Adds slide numbers to the bottom right of each slide.

```
/NUS/outer/numbering/.cd,
                    .is choice,
              413
                    none/.code=\setbeamertemplate{frame numbering}[none],
              414
                    counter/.code=\setbeamertemplate{frame numbering}[counter],
              415
                    fraction/.code=\setbeamertemplate{frame numbering}[fraction],
              416
              417 }
             Adds a progress bar to the top, bottom, or frametitle of each slide.
progressbar
             418 \pgfkeys{
                  /NUS/outer/progressbar/.cd,
                    .is choice,
             420
                    none/.code={%
              421
                       \setbeamertemplate{headline}[plain]
             422
                      \setbeamertemplate{frametitle}[plain]
             423
                      \setbeamertemplate{footline}[plain]
             424
                    },
              425
                    head/.code={\pgfkeys{/NUS/outer/progressbar=none}
             426
                      \addtobeamertemplate{headline}{}{%
              427
                         \usebeamertemplate*{progress bar in head/foot}
             428
                      }
             429
                    },
             430
                    frametitle/.code={\pgfkeys{/NUS/outer/progressbar=none}
              431
                      \addtobeamertemplate{frametitle}{}{%
             432
                         \usebeamertemplate*{progress bar in head/foot}
             433
                      }
             434
             435
                    },
                    foot/.code={\pgfkeys{/NUS/outer/progressbar=none}
             436
                      \addtobeamertemplate{footline}{}{%
             437
                         \usebeamertemplate*{progress bar in head/foot}%
             438
                      }
             439
                    },
             440
              441 }
```

\NUS@outer@setdefaults Sets default values for outer theme options.

```
\pgfkeys{/NUS/outer/.cd,
                  443
                         numbering=counter,
                  444
                         progressbar=none,
                  445
                      }
                  446
                  447 }
                  8.3.3 Head and footline
                  All good beamer presentations should already remove the navigation symbols,
                  but NUS removes them automatically (just in case).
                  448 \setbeamertemplate{navigation symbols}{}
                 Templates for the frame number. Can be omitted, shown or displayed as a frac-
frame numbering
                  tion of the total frames.
                  449 \defbeamertemplate{frame footer}{none}{}
                  450 \defbeamertemplate{frame footer}{copyright}{\tiny \copyright{} Copyright National U
                     All rights reserved}
                  452 \defbeamertemplate{frame footer}{custom}[1]{ #1 }
                  453 \defbeamertemplate{frame numbering}{none}{}
                  454 \defbeamertemplate {frame numbering} {counter} {\insertframenumber}
                  455 \defbeamertemplate{frame numbering}{fraction}{
                      \insertframenumber/\inserttotalframenumber
                  457 }
                  Templates for the head- and footline at the top and bottom of each frame.
       headline
       footline
                  458 \defbeamertemplate{headline}{plain}{%
                      \begin{beamercolorbox}[wd=\textwidth,sep=0.3ex]{headline head}%
                  459
                         \hfill%
                  460
                      \end{beamercolorbox}%
                  461
                  462
```

442 \newcommand{\NUS@outer@setdefaults}{

463 }

465

466

467

468

\hfill%

\begin{beamercolorbox}[wd=\textwidth]{footline}%

\usebeamerfont{page number in head/foot}%

464 \defbeamertemplate{footline}{plain}{%

\usebeamertemplate*{frame footer}

```
469    \usebeamertemplate*{frame numbering}
470    \end{beamercolorbox}%
471    \begin{beamercolorbox}[wd=\textwidth,sep=0.3ex]{footline foot}%
472    \hfill%
473    \end{beamercolorbox}%
474 }
```

8.3.4 Frametitle

frametitle Templates for the frame title, which is optionally underlined with a progress bar.

```
475 \newlength{\NUS@frametitle@padding}
476 \setlength{\NUS@frametitle@padding}{2.2ex}
477 \newcommand{\NUS@frametitlestrut@start}{
    \rule{Opt}{\NUS@frametitle@padding +%
      \totalheightof{%
479
        \footnote{NUS@frametitleformat}{\NUS@frametitleformat X}{X}%
480
      }%
481
    }%
482
483 }
484 \newcommand{\NUS@frametitlestrut@end}{
    \rule[-\NUS@frametitle@padding]{Opt}{\NUS@frametitle@padding}
485
486 }
487 \defbeamertemplate{frametitle}{plain}{%
    \nointerlineskip%
488
    \begin{beamercolorbox}[%
489
        wd=\paperwidth,%
490
        sep=0pt,%
491
        leftskip=\NUS@frametitle@padding,%
492
        rightskip=\NUS@frametitle@padding,%
493
      ]{frametitle}%
494
    \NUS@frametitlestrut@start%
495
496
    \insertframetitle%
    \nolinebreak%
497
    \NUS@frametitlestrut@end%
498
    \end{beamercolorbox}%
499
500 }
501\setbeamertemplate{frametitle continuation}{%
    \usebeamerfont{frametitle}
502
    \romannumeral \insertcontinuationcount
503
```

504 }

progress bar in head/foot

Template for the progress bar optionally displayed below the frame title on each page. Much of this code is duplicated in the inner theme's template progress bar in section page.

```
505 \newlength{\NUS@progressinheadfoot}
506 \newlength{\NUS@progressinheadfoot@linewidth}
507\setlength{\NUS@progressinheadfoot@linewidth}{0.4pt}
508\setbeamertemplate{progress bar in head/foot}{
    \nointerlineskip
509
    \setlength{\NUS@progressinheadfoot}{%
510
      \paperwidth * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}%
511
512
    \begin{beamercolorbox}[wd=\paperwidth]{progress bar in head/foot}
513
      \tikzexternaldisable%
514
      \begin{tikzpicture}
515
        \fill[bg] (0,0) rectangle (\paperwidth, \NUS@progressinheadfoot@linewidth);
516
        \fill[fg] (0,0) rectangle (\NUS@progressinheadfoot, \NUS@progressinheadfoot@l
517
      \end{tikzpicture}%
518
      \tikzexternalenable%
519
    \end{beamercolorbox}
520
521 }
```

appendix Removes page numbering and per-slide progress bars when \appendix is called. This makes it easier to include additional "backup slides" at the end of the presentation, especially in conjunction with the package appendixnumber beamer.

```
522 \AtBeginDocument{%
    \apptocmd{\appendix}{%
523
       \pgfkeys{%
524
         /NUS/outer/.cd,
525
         numbering=none,
526
         progressbar=none}
527
       }{}{}
528
529 }
```

8.3.5 Process package options

```
530 \NUS@outer@setdefaults
531 \ProcessPgfPackageOptions{/NUS/outer}
```

8.4 NUS font theme

A beamer font theme sets the style of the font used in the document.

8.4.1 Package dependencies

```
532 \RequirePackage{etoolbox}
533 \RequirePackage{ifxetex}
534 \RequirePackage{ifluatex}
535 \RequirePackage{pgfopts}
```

8.4.2 Load Fira fonts

If the presentation is compiled with XeITFX or LuaITFX, the fontspec package is loaded and we search for the Fira fonts.

```
536\ifboolexpr{bool {xetex} or bool {luatex}}{
    \@ifpackageloaded{fontspec}{
      \PassOptionsToPackage{no-math}{fontspec}
538
539
      \RequirePackage[no-math]{fontspec}
540
    }
541
```

\checkfont Checks if a font is installed; if not, fontsnotfound is increased.

```
\newcounter{fontsnotfound}
542
    \newcommand{\checkfont}[1]{%
543
       \suppressfontnotfounderror=1%
544
       \int \int x = "#1" at 10pt
545
       \selectfont
546
       \ifx\x\nullfont%
547
         \stepcounter{fontsnotfound}%
548
549
       \suppressfontnotfounderror=0%
550
    }
551
552
```

\iffontsavailable Resets the fontsnotfound counter and calls \checkfont for each font in the comma separated list in the first argument.

```
\newcommand{\iffontsavailable}[3]{%
553
      \setcounter{fontsnotfound}{0}%
554
```

```
\expandafter\forcsvlist\expandafter%
555
       \checkfont\expandafter{#1}%
556
       \ifnum\value{fontsnotfound}=0%
557
         #2%
558
       \else%
559
         #3%
560
       \fi%
561
     }
562
```

We search for regular, italic, light, light italic, mono, and mono bold fonts under the default **Fira Sans** and **Fira Mono** names. If this fails, the suffix OT — used by some Linux distributions — will be tried. If this also fails, a warning will be displayed and the standard fonts will be used.

```
563 \iffontsavailable{Myriad Pro}%
564
       \setsansfont[]{Myriad Pro}%
565
       \usepackage{mdsymbol}
566
567
    }{%
         \PackageWarning{beamerthemeNUS}{%
568
           Could not find Myriad Pro fonts%
569
         }
570
       }
571
572 \iffontsavailable{DejaVu Sans Mono}%
573 {%
    \setmonofont[Mapping=tex-text,Scale=0.8]{DejaVu Sans Mono}%
574
    }{%
575
         \PackageWarning{beamerthemeNUS}{%
576
           Could not find DejaVu Sans Mono fonts%
577
         }
578
579
    \AtBeginEnvironment{tabular}{%
580
       \addfontfeature{Numbers={Monospaced}}%
581
    }
582
583 }{%
    \usepackage[T1]{fontenc}
584
    \usepackage[utf8]{inputenc}
585
    \usepackage[lf]{MyriadPro}
586
    \usepackage{mdsymbol}
587
    \usepackage[scaled=0.8]{beramono}
588
```

```
\PackageWarning{beamerthemeNUS}{%

You need to compile with XeLaTeX or LuaLaTeX to use the Myriad Pro fonts%

591 }

592 }
```

This concludes the portion of the code which is only run when compiled with XeMeX or LuaMeX. The remainder of this package applies regardless of the compiling engine.

8.4.3 General font definitions

```
593 \setbeamerfont{title}{size=\Large,%
                         series=\bfseries}
595 \setbeamerfont{author}{size=\small}
596 \setbeamerfont{date}{size=\small}
597\setbeamerfont{section title}{size=\Large,%
                                 series=\bfseries}
598
599 \setbeamerfont{block title}{size=\normalsize,%
                               series=\bfseries}
601\setbeamerfont{block title alerted}{size=\normalsize,%
                                        series=\bfseries}
602
603 \setbeamerfont*{subtitle}{size=\large}
604\setbeamerfont{frametitle}{size=\large,%
                              series=\bfseries}
606 \setbeamerfont{caption}{size=\small}
607\setbeamerfont{caption name}{series=\bfseries}
608 \setbeamerfont{description item}{series=\bfseries}
609 \setbeamerfont{page number in head/foot}{size=\scriptsize}
610 \setbeamerfont{bibliography entry author}{size=\normalsize,%
                                              series=\normalfont}
612 \setbeamerfont{bibliography entry title}{size=\normalsize,%
                                             series=\bfseries}
613
614\setbeamerfont{bibliography entry location}{size=\normalsize,%
                                                series=\normalfont}
616 \setbeamerfont{bibliography entry note}{size=\small,%
                                            series=\normalfont}
618 \setbeamerfont{standout}{size=\Large,%
                            series=\bfseries}
619
```

8.4.4 Title format options

titleformat title Controls the format of the title.

```
620 \pgfkeys{
    /NUS/font/titleformat title/.cd,
621
       .is choice,
622
      regular/.code={%
623
         \let\NUS@titleformat\@empty%
624
         \setbeamerfont{title}{shape=\normalfont}%
625
      },
626
      smallcaps/.code={%
627
         \let\NUS@titleformat\@empty%
628
         \setbeamerfont{title}{shape=\scshape}%
630
      },
      allsmallcaps/.code={%
631
         \let\NUS@titleformat\lowercase%
632
         \setbeamerfont{title}{shape=\scshape}%
633
         \PackageWarning{beamerthemeNUS}{%
           Be aware that titleformat title=allsmallcaps can lead to problems%
635
         }
636
      },
637
      allcaps/.code={%
638
         \let\NUS@titleformat\uppercase%
         \setbeamerfont{title}{shape=\normalfont}
640
         \PackageWarning{beamerthemeNUS}{%
641
           Be aware that titleformat title=allcaps can lead to problems%
642
         }
643
      },
644
645 }
```

titleformat subtitle Control the format of the subtitle.

```
646 \pgfkeys{
647  /NUS/font/titleformat subtitle/.cd,
648   .is choice,
649   regular/.code={%
650   \let\NUS@subtitleformat\@empty%
651   \setbeamerfont{subtitle}{shape=\normalfont}%
652  },
653  smallcaps/.code={%
```

```
\let\NUS@subtitleformat\@empty%
654
655
         \setbeamerfont{subtitle}{shape=\scshape}%
      },
656
      allsmallcaps/.code={%
657
         \let\NUS@subtitleformat\lowercase%
658
         \setbeamerfont{subtitle}{shape=\scshape}%
659
         \PackageWarning{beamerthemeNUS}{%
660
           Be aware that titleformat subtitle=allsmallcaps can lead to problems%
661
         }
662
      },
663
      allcaps/.code={%
664
         \let\NUS@subtitleformat\uppercase%
665
         \setbeamerfont{subtitle}{shape=\normalfont}%
666
         \PackageWarning{beamerthemeNUS}{%
667
           Be aware that titleformat subtitle=allcaps can lead to problems%
668
         }
669
      },
670
671 }
```

titleformat section Controls the format of the section title.

```
672 \pgfkeys{
    /NUS/font/titleformat section/.cd,
       .is choice,
674
      regular/.code={%
675
         \let\NUS@sectiontitleformat\@empty%
676
         \setbeamerfont{section title}{shape=\normalfont}%
677
      },
678
      smallcaps/.code={%
679
         \let\NUS@sectiontitleformat\@empty%
680
         \setbeamerfont{section title}{shape=\scshape}%
681
      },
682
      allsmallcaps/.code={%
683
         \let\NUS@sectiontitleformat\MakeLowercase%
684
         \setbeamerfont{section title}{shape=\scshape}%
685
         \PackageWarning{beamerthemeNUS}{%
686
           Be aware that titleformat section=allsmallcaps can lead to problems%
687
         }
688
      },
689
      allcaps/.code={%
690
```

```
\let\NUS@sectiontitleformat\MakeUppercase%
                      691
                      692
                               \setbeamerfont{section title}{shape=\normalfont}%
                               \PackageWarning{beamerthemeNUS}{%
                      693
                                 Be aware that titleformat section=allcaps can lead to problems%
                      694
                               }
                      695
                             },
                      696
                      697 }
   frametitleformat Control the format of the frame title.
                      698 \pgfkeys{
                           /NUS/font/titleformat frame/.cd,
                             .is choice,
                      700
                             regular/.code={%
                      701
                               \let\NUS@frametitleformat\@empty%
                      702
                               \setbeamerfont{frametitle}{shape=\normalfont}%
                      703
                             },
                      704
                             smallcaps/.code={%
                      705
                               \let\NUS@frametitleformat\@empty%
                      706
                               \setbeamerfont{frametitle}{shape=\scshape}%
                      707
                             },
                      708
                             allsmallcaps/.code={%
                      709
                               \let\NUS@frametitleformat\MakeLowercase%
                      710
                               \setbeamerfont{frametitle}{shape=\scshape}%
                      711
                               \PackageWarning{beamerthemeNUS}{%
                      712
                                 Be aware that titleformat frame=allsmallcaps can lead to problems%
                      713
                               }
                      714
                             },
                      715
                             allcaps/.code={%
                      716
                               \let\NUS@frametitleformat\MakeUppercase%
                      717
                               \setbeamerfont{frametitle}{shape=\normalfont}
                      718
                               \PackageWarning{beamerthemeNUS}{%
                      719
                                 Be aware that titleformat frame=allcaps can lead to problems%
                      720
                               }
                      721
                      722
                             },
                      723 }
titleformat aliases Allows titleformat title et al. to be used in the \usetheme declaration,
                      where ETFX automatically removes all spaces.
                      724 \pgfkeys{
```

```
/NUS/font/.cd,
   titleformattitle/.code=\pgfkeysalso{titleformat title=#1},
726
    titleformatsubtitle/.code=\pgfkeysalso{titleformat subtitle=#1},
727
    titleformatsection/.code=\pgfkeysalso{titleformat section=#1},
728
    titleformatframe/.code=\pgfkeysalso{titleformat frame=#1},
729
730 }
```

\NUS@font@setdefaults Sets default values for font theme options.

```
731 \newcommand{\NUS@font@setdefaults}{
    \pgfkeys{/NUS/font/.cd,
      titleformat title=regular,
733
      titleformat subtitle=regular,
734
      titleformat section=regular,
735
      titleformat frame=regular,
736
737
    }
738 }
```

We first define hooks to change the case format of the titles.

```
739 \def\NUS@titleformat#1{#1}
740 \def\NUS@subtitleformat#1{#1}
741 \def\NUS@sectiontitleformat#1{#1}
742 \def\NUS@frametitleformat#1{#1}
```

To make the uppercase and lowercase macros work in the title, subtitle, etc., we have to patch the appropriate beamer commands that set their values. This solution was suggested by Enrico Gregorio in an answer to this StackExchange question.

```
743 \patchcmd{\beamer@title}%
    {\def\inserttitle{#2}}%
    {\def\inserttitle{\NUS@titleformat{#2}}}%
745
    {}%
746
    {\PackageError{beamerfontthemeNUS}{Patching title failed}\@ehc}
747
748 \patchcmd{\beamer@subtitle}%
   {\def\insertsubtitle{#2}}%
750
   {\def\insertsubtitle{\NUS@subtitleformat{#2}}}%
    {}%
751
   {\PackageError{beamerfontthemeNUS}{Patching subtitle failed}\@ehc}
753 \patchcmd{\sectionentry}
```

```
{\def\insertsectionhead{#2}}
    {\def\insertsectionhead{\NUS@sectiontitleformat{#2}}}
755
756
    {\PackageError{beamerfontthemeNUS}{Patching section title failed}\@ehc}
757
758 \atempswafalse
759 \patchcmd{\beamer@section}
    {\edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\unexpanded{#
760
    {\edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{%
761
      \noexpand\NUS@sectiontitleformat{\unexpanded{#1}}}}
762
    {\@tempswatrue}
763
    {}
764
765 \patchcmd{\beamer@section}
    {\def\insertsectionhead{\hyperlink{Navigation\the\c@page}{#1}}}
766
    {\def\insertsectionhead{\hyperlink{Navigation\the\c@page}{%
767
      \NUS@sectiontitleformat{#1}}}
768
    {\@tempswatrue}
769
770
771 \patchcmd{\beamer@section}
    {\protected@edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{#1}
772
    {\protected@edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{%
773
      \noexpand\NUS@sectiontitleformat{#1}}}
774
    {\atempswatrue}
776
777 \if@tempswa\else
    \PackageError{beamerfontthemeNUS}{Patching section title failed}\@ehc
779 \fi
780 \atempswafalse
781 \patchcmd{\beamer@subsection}
    {\edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\unexpande
782
    {\edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{%
783
784
      \noexpand\NUS@sectiontitleformat{\unexpanded{#1}}}}}
    {\@tempswatrue}
785
    {}
786
787 \patchcmd{\beamer@subsection}
    {\def\insertsubsectionhead \hyperlink{Navigation \he\c@page}{\#1}}}
788
    {\def\insertsubsectionhead }\n \avigation \the \c@page} \
789
      \NUS@sectiontitleformat{#1}}}
790
    {\atempswatrue}
791
793 \patchcmd{\beamer@subsection}
```

```
{\protected@edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{
    {\protected@edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{
795
      \noexpand\NUS@sectiontitleformat{#1}}}
796
    {\atempswatrue}
797
    {}
798
799 \if@tempswa\else
    \PackageError{beamerfontthemeNUS}{Patching section title failed}\@ehc
801\fi
Similarly, to make the \MakeLowercase and \MakeUppercase macros work
in the frame title we have to patch \beamera@frametitle.
802 \patchcmd{\beamer@@frametitle}
    {{%
803
         \gdef\insertframetitle{{#2\ifnum\beamer@autobreakcount>0\relax{}\space%
804
        \usebeamertemplate*{frametitle continuation}\fi}}%
805
      \gdef\beamer@frametitle{#2}%
806
      \gdef\beamer@shortframetitle{#1}%
807
      }}
808
    {{%
809
        \gdef\insertframetitle{{\NUS@frametitleformat{#2}\ifnum%
810
        \beamer@autobreakcount>0\relax{}\space%
811
        \usebeamertemplate*{frametitle continuation}\fi}}%
812
      \gdef\beamer@frametitle{#2}%
813
      \gdef\beamer@shortframetitle{#1}%
      }}
815
816
    {\PackageError{beamerfontthemeNUS}{Patching frame title failed}\@ehc}
817
8.4.5 Process package options
818 \NUS@font@setdefaults
819 \ProcessPgfPackageOptions{/NUS/font}
8.5
     NUS color theme
8.5.1 Package dependencies
820 \RequirePackage{pgfopts}
```

8.5.2 Options

block Optionally adds a light grey background to block environments like **theorem** and **example**.

```
821 \pgfkeys{
822  /NUS/color/block/.cd,
823   .is choice,
824   transparent/.code=\NUS@block@transparent,
825  fill/.code=\NUS@block@fill,
826 }
```

colors Provides the option to have a dark background and light foreground instead of the reverse.

```
827 \pgfkeys{
828  /NUS/color/background/.cd,
829    .is choice,
830    dark/.code=\NUS@colors@dark,
831    light/.code=\NUS@colors@light,
832 }
```

\NUSacolorasetdefaults Sets default values for color theme options.

```
833 \newcommand{\NUS@color@setdefaults}{
834 \pgfkeys{/NUS/color/.cd,
835 background=light,
836 block=transparent,
837 }
838 }
```

8.5.3 Base colors

```
839 \definecolor{mDarkBrown}{HTML}{604c38}
840 \definecolor{NUSblue}{HTML}{003D7C}
841 \definecolor{NUSorange}{HTML}{EF7C00}
842 \definecolor{mLightGreen}{HTML}{14B03D}
```

8.5.4 Base styles

All colors in **NUS** are derived from the definitions of **normal text**, **alerted text**, and **example text**.

```
843 \newcommand{\NUS@colors@dark}{
    \setbeamercolor{normal text}{%
844
       fg=black!2,
845
       bg=NUSblue
846
    }
847
    \usebeamercolor[fg]{normal text}
848
849 }
850 \newcommand{\NUS@colors@light}{
    \setbeamercolor{normal text}{%
851
       fg=NUSblue,
852
       bg=black!2
853
    }
854
855 }
856 \setbeamercolor{alerted text}{%
    fg=NUSorange
858 }
859\setbeamercolor{example text}{%
    fg=mLightGreen
861 }
```

8.5.5 Derived colors

The titles and structural elements (e.g. itemize bullets) are set in the same color as normal text. This would ideally done by setting normal text as a parent style, which we do to set titlelike, but this doesn't work for structure as its foreground is set explicitly in beamercolorthemedefault.sty.

```
862\setbeamercolor{titlelike}{use=normal text, parent=normal text}
863\setbeamercolor{author}{use=normal text, parent=normal text}
864\setbeamercolor{date}{use=normal text, parent=normal text}
865\setbeamercolor{institute}{use=normal text, parent=normal text}
866\setbeamercolor{structure}{use=normal text, fg=normal text.fg}
```

The "primary" palette should be used for the most important navigational elements, and possibly of other elements. **NUS** uses it for frame titles and slides.

```
867 \setbeamercolor{palette primary}{%
868   use=normal text,
869   fg=normal text.bg,
870   bg=normal text.fg
871}
```

```
872
873 \setbeamercolor{palette secondary}{%
    use=normal text,
874
     fg=alerted text.fg,
875
    bg=normal text.fg
876
877 }
878
879 \setbeamercolor{frametitle}{%
     use=palette primary,
880
     parent=palette primary
881
882 }
```

The **NUS** inner or outer themes optionally display progress bars in various locations. Their color is set by **progress** bar but the two different kinds can be customized separately. The horizontal rule on the title page is also set based on the progress bar color and can be customized with title separator.

```
883 \setbeamercolor{progress bar}{%
    use=alerted text,
884
     fg=alerted text.fg,
885
    bg=alerted text.fg!50!black!30
886
887 }
888 \setbeamercolor{title separator}{
    use=progress bar,
889
     parent=progress bar
890
891 }
892 % \setbeamercolor{footline}{%
893 %
       use=palette primary,
       parent=palette primary
894 %
895 % }
896 \setbeamercolor{footline foot}{%
    bg=NUSorange
897
898 }
899 \setbeamercolor{headline head}{%
    bg=NUSorange
900
901 }
902
903
904\setbeamercolor{progress bar in head/foot}{%
    use=progress bar,
```

```
906 parent=progress bar
907 }
908 \setbeamercolor{progress bar in section page}{
909   use=progress bar,
910   parent=progress bar
911 }
```

Block environments such as **theorem** and **example** have no background color by default. The option **block=fill** sets a background color based on the background and foreground of **normal text**. The option **block=transparent** reverts the block environments to an empty background, which can be useful if changing colors mid-presentation.

```
912 \newcommand{\NUS@block@transparent}{
    \setbeamercolor{block title}{%
913
       use=normal text,
914
       fg=normal text.fg,
915
       bg=
916
917
    \setbeamercolor{block body}{
918
       bg=
919
    }
920
921 }
922 \newcommand{\NUS@block@fill}{
    \setbeamercolor{block title}{%
923
       use=normal text,
924
       fg=normal text.fg,
925
       bg=normal text.bg!80!fg
926
    }
927
    \setbeamercolor{block body}{
928
       use={block title, normal text},
929
       bg=block title.bg!50!normal text.bg
930
    }
931
932 }
933 \setbeamercolor{block title alerted}{%
       use={block title, alerted text},
934
       bg=block title.bg,
935
       fg=alerted text.fg
936
937 }
938 \setbeamercolor{block title example}{%
```

```
use={block title, example text},
bg=block title.bg,
fg=example text.fg

943 \setbeamercolor{block body alerted}{use=block body, parent=block body}

944 \setbeamercolor{block body example}{use=block body, parent=block body}

Footnotes

945 \setbeamercolor{footnote}{fg=normal text.fg!90}

946 \setbeamercolor{footnote mark}{fg=.}
```

We also reset the bibliography colors in order to pick up the surrounding colors at the time of use. This prevents us having to set the correct color in normal and standout mode.

```
947 \setbeamercolor{bibliography entry author}{fg=, bg=}
948 \setbeamercolor{bibliography entry title}{fg=, bg=}
949 \setbeamercolor{bibliography entry location}{fg=, bg=}
950 \setbeamercolor{bibliography entry note}{fg=, bg=}
```

8.5.6 Process package options

```
951 \NUS@color@setdefaults
952 \ProcessPgfPackageOptions{/NUS/color}
953 \mode<all>
```

8.6 Tolpgfplots theme

Paul Tol's 12-color palette¹ is as follows:

```
954 \definecolor{TolDarkPurple}{HTML}{332288}

955 \definecolor{TolDarkBlue}{HTML}{6699CC}

956 \definecolor{TolLightBlue}{HTML}{88CCEE}

957 \definecolor{TolLightGreen}{HTML}{44AA99}

958 \definecolor{TolDarkGreen}{HTML}{117733}

959 \definecolor{TolDarkBrown}{HTML}{999933}

960 \definecolor{TolLightBrown}{HTML}{DDCC77}

961 \definecolor{TolDarkRed}{HTML}{6661100}

962 \definecolor{TolLightRed}{HTML}{CC6677}
```

¹Tol actually describes several palettes; these colours are taken from the bottom row of Figure 3 in his technical note.

```
963 \definecolor{TolLightPink}{HTML}{AA4466}
964 \definecolor{TolDarkPink}{HTML}{882255}
965 \definecolor{TolLightPurple}{HTML}{AA4499}
```

To use these colors, we describe "cycle lists" from which PGF chooses styles for the different series in a chart.

mbarplot cycle Colors and styles intended for bar charts with up to 12 series.

```
966 \pgfplotscreateplotcyclelist{mbarplot cycle}{%
    {draw=TolDarkBlue,
                            fill=TolDarkBlue!70},
967
    {draw=TolLightBrown,
                            fill=TolLightBrown!70},
968
    {draw=TolLightGreen,
                            fill=TolLightGreen!70},
969
    {draw=TolDarkPink,
                            fill=TolDarkPink!70},
970
    {draw=TolDarkPurple,
                            fill=TolDarkPurple!70},
971
    {draw=TolDarkRed,
                            fill=TolDarkRed!70},
972
    {draw=TolDarkBrown,
                            fill=TolDarkBrown!70},
973
    {draw=TolLightRed,
                            fill=TolLightRed!70},
974
975
    {draw=TolLightPink,
                            fill=TolLightPink!70},
976
    {draw=TolLightPurple, fill=TolLightPurple!70},
    {draw=TolLightBlue,
                            fill=TolLightBlue!70},
977
    {draw=TolDarkGreen,
                            fill=TolDarkGreen!70},
978
979 }
```

mlineplot cycle Colors and styles intended for line charts with up to 4 series.

```
980 \pgfplotscreateplotcyclelist{mlineplot cycle}{%
981    {TolDarkBlue, mark=*, mark size=1.5pt},
982    {TolLightBrown, mark=square*, mark size=1.3pt},
983    {TolLightGreen, mark=triangle*, mark size=1.5pt},
984    {TolDarkBrown, mark=diamond*, mark size=1.5pt},
985}
```

However, the above cycle lists are not applied automatically. We still need to define styles — mlineplot and mbarplot — that the user can apply to the axis of a pgfplots chart to use the colors. We'll also take the opportunity to adjust the display of chart axes when these styles are used.

```
986 \pgfplotsset{
987 compat=1.9,
```

mlineplot A style to apply to the axis of a PGF line plot.

```
mlineplot/.style={
988
       mbaseplot,
989
       xmajorgrids=true,
990
       ymajorgrids=true,
991
       major grid style={dotted},
992
       axis x line=bottom,
993
       axis y line=left,
994
       legend style={
995
          cells={anchor=west},
996
          draw=none
997
998
       cycle list name=mlineplot cycle,
999
     },
1000
```

mbarplot A style to apply to the axis of a PGF bar chart. mbarplot uses vertical bars by horizontal mbarplot default, while horizontal mbarplot has horizontal bars as the name implies.

Their shared properties are factored out into the internal style mbarplot base.

```
mbarplot base/.style={
1001
        mbaseplot,
1002
        bar width=6pt,
1003
        axis y line*=none,
1004
1005
     },
     mbarplot/.style={
1006
        mbarplot base,
1007
        ybar,
1008
1009
        xmajorgrids=false,
        ymajorgrids=true,
1010
        area legend,
1011
        legend image code/.code={%
1012
          \draw[#1] (0cm,-0.1cm) rectangle (0.15cm,0.1cm);
1013
        },
1014
        cycle list name=mbarplot cycle,
1015
     },
1016
     horizontal mbarplot/.style={
1017
        mbarplot base,
1018
        xmajorgrids=true,
1019
        ymajorgrids=false,
1020
```

```
xbar stacked,
           1021
                   area legend,
           1022
                   legend image code/.code={%
           1023
                     \draw[#1] (0cm,-0.1cm) rectangle (0.15cm,0.1cm);
           1024
                   },
           1025
                   cycle list name=mbarplot cycle,
           1026
                 },
           1027
mbaseplot Adjusts the appearance of the axes in a PGF chart.
                 mbaseplot/.style={
           1028
                   legend style={
           1029
                     draw=none,
           1030
                     fill=none,
           1031
                     cells={anchor=west},
           1032
           1033
                   },
                   x tick label style={
           1034
                     font=\footnotesize
           1035
           1036
                   y tick label style={
           1037
                     font=\footnotesize
           1038
                   },
           1039
                   legend style={
           1040
                     font=\footnotesize
           1041
           1042
                   major grid style={
           1043
                     dotted,
           1044
                   },
           1045
                   axis x line*=bottom,
           1046
           1047
                 disable thousands separator/.style={
           1048
                   /pgf/number format/.cd,
           1049
           1050
                     1000 sep={}
                 },
           1051
           1052 }
```