Floating Point

15-213: Introduction to Computer Systems 4th Lecture, May 24, 2016

Instructor:

Brian Railing


Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

Fractional binary numbers

■ What is 1011.101₂?

Fractional Binary Numbers



- Bits to right of "binary point" represent fractional powers of 2
- Represents rational number:

$$\sum_{k=-j}^{i} b_k \times 2^k$$

Fractional Binary Numbers: Examples

Value

5 3/4 2 7/8

17/16

Representation

101.11₂ = 4 + 1 + 1/2 + 1/410.111₂ = 2 + 1/2 + 1/4 + 1/81.0111₂ = 1 + 1/4 + 1/8 + 1/16

Observations

- Divide by 2 by shifting right (unsigned)
- Multiply by 2 by shifting left
- Numbers of form 0.1111111...2 are just below 1.0

■
$$1/2 + 1/4 + 1/8 + ... + 1/2^i + ... \rightarrow 1.0$$

■ Use notation 1.0 – ε

Representable Numbers

Limitation #1

- Can only exactly represent numbers of the form x/2^k
 - Other rational numbers have repeating bit representations

```
    Value Representation
    1/3 0.01010101[01]...2
    1/5 0.001100110011[0011]...2
    1/10 0.0001100110011[0011]...2
```

■ Limitation #2

- Just one setting of binary point within the w bits
 - Limited range of numbers (very small values? very large?)

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

IEEE Floating Point

IEEE Standard 754

- Established in 1985 as uniform standard for floating point arithmetic
 - Before that, many idiosyncratic formats
- Supported by all major CPUs
- Some CPUs don't implement IEEE 754 in full e.g., early GPUs, Cell BE processor

Driven by numerical concerns

- Nice standards for rounding, overflow, underflow
- Hard to make fast in hardware
 - Numerical analysts predominated over hardware designers in defining standard

Floating Point Representation

Numerical Form:

Example: $15213_{10} = (-1)^0 \times 1.1101101101101_2 \times 2^{13}$

 $(-1)^{s} M 2^{E}$

- Sign bit s determines whether number is negative or positive
- Significand M normally a fractional value in range [1.0,2.0).
- **Exponent** *E* weights value by power of two

Encoding


- MSB s is sign bit s
- exp field encodes E (but is not equal to E)
- frac field encodes M (but is not equal to M)

| S | ехр | frac |
|---|-----|------|
| | | |

Precision options

Single precision: 32 bits

 \approx 7 decimal digits, $10^{\pm 38}$



Double precision: 64 bits

 \approx 16 decimal digits, $10^{\pm 308}$



Other formats: half precision, quad precision

"Normalized" Values

$$V = (-1)^s M 2^E$$

When: exp ≠ 000...0 and exp ≠ 111...1

Exponent coded as a biased value: E = Exp - Bias

- Exp: unsigned value of exp field
- $Bias = 2^{k-1} 1$, where k is number of exponent bits
 - Single precision: 127 (Exp: 1...254, E: -126...127)
 - Double precision: 1023 (Exp: 1...2046, E: -1022...1023)

■ Significand coded with implied leading 1: M = 1.xxx...x2

- xxx...x: bits of frac field
- Minimum when frac=000...0 (M = 1.0)
- Maximum when frac=111...1 (M = 2.0ε)
- Get extra leading bit for "free"

Normalized Encoding Example

$$V = (-1)^{S} M 2^{E}$$

 $E = Exp - Bias$

- Value: float F = 15213.0;
 - $15213_{10} = 11101101101101_2$ = $1.1101101101101_2 \times 2^{13}$

Significand

$$M = 1.101101101_2$$

frac= $101101101101_000000000_2$

Exponent

$$E = 13$$
 $Bias = 127$
 $Exp = 140 = 10001100_{2}$

Result:

0 10001100 1101101101101000000000

s exp frac

Denormalized Values

$$V = (-1)^{s} M 2^{E}$$

 $E = 1 - Bias$

- **Condition:** exp = 000...0
- **Exponent value:** E = 1 Bias (instead of E = 0 Bias)
- Significand coded with implied leading 0: *M* = 0.xxx...x₂
 - xxx...x: bits of frac
- Cases
 - exp = 000...0, frac = 000...0
 - Represents zero value
 - Note distinct values: +0 and -0 (why?)
 - $exp = 000...0, frac \neq 000...0$
 - Numbers closest to 0.0
 - Equispaced

Special Values

- **■** Condition: exp = 111...1
- Case: exp = 111...1, frac = 000...0
 - Represents value ∞ (infinity)
 - Operation that overflows
 - Both positive and negative
 - E.g., $1.0/0.0 = -1.0/-0.0 = +\infty$, $1.0/-0.0 = -\infty$
- Case: exp = 111...1, frac ≠ 000...0
 - Not-a-Number (NaN)
 - Represents case when no numeric value can be determined
 - E.g., sqrt(-1), $\infty \infty$, $\infty \times 0$


C float Decoding Example

float: 0xC0A00000

 $V = (-1)^s M 2^E$ E = Exp - Bias

$$Bias = 2^{k-1} - 1 = 127$$

binary:



1 8-bits

23-bits

(decimal)

$$M =$$

$$v = (-1)^s M 2^E =$$

Hex Decimanary

| 0 | 0 | 0000 |
|---|----|------|
| 1 | 1 | 0001 |
| 2 | 2 | 0010 |
| 3 | 3 | 0011 |
| 4 | 4 | 0100 |
| 5 | 5 | 0101 |
| 6 | 6 | 0110 |
| 7 | 7 | 0111 |
| 8 | 8 | 1000 |
| 9 | 9 | 1001 |
| A | 10 | 1010 |
| В | 11 | 1011 |
| С | 12 | 1100 |
| D | 13 | 1101 |
| E | 14 | 1110 |
| F | 15 | 1111 |

C float Decoding Example

 $V = (-1)^{s} M 2^{E}$ E = Exp - Bias

float: 0xC0A00000

1 1000 0001 010 0000 0000 0000 0000

1 8-bits 23-bits

E = -> Exp = (decimal)

S =

M = 1.

 $v = (-1)^s M 2^E =$

В C D E

C float Decoding Example

float: 0xC0A00000

$$V = (-1)^s M 2^E$$

 $E = Exp - Bias$

$$Bias = 2^{k-1} - 1 = 127$$

1 1000 0001 010 0000 0000 0000 0000

1 8-bits

23-bits

$$E = 129 -> Exp = 129 - 127 = 2$$
 (decimal)

S = **1** -> negative number


M = 1.010 0000 0000 0000 0000 0000= 1 + 1/4 = 1.25

$$v = (-1)^s M 2^E = (-1)^1 * 1.25 * 2^2 = -5$$

Hex Decimany

| 0 | 0 | 0000 |
|---|----|------|
| 1 | 1 | 0001 |
| 2 | 2 | 0010 |
| 3 | 3 | 0011 |
| 4 | 4 | 0100 |
| 5 | 5 | 0101 |
| 6 | 6 | 0110 |
| 7 | 7 | 0111 |
| 8 | 8 | 1000 |
| 9 | 9 | 1001 |
| A | 10 | 1010 |
| В | 11 | 1011 |
| C | 12 | 1100 |
| D | 13 | 1101 |
| E | 14 | 1110 |
| F | 15 | 1111 |


Visualization: Floating Point Encodings



Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- **■** Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

Tiny Floating Point Example



8-bit Floating Point Representation

- the sign bit is in the most significant bit
- the next four bits are the exponent, with a bias of 7
- the last three bits are the frac

Same general form as IEEE Format

- normalized, denormalized
- representation of 0, NaN, infinity

 $V = (-1)^s M 2^E$

n: E = Exp - Bias


Dynamic Range (Positive Only)

| _ | | | _ | _ | _ | 2 3 | II. L - LAP DIGS |
|--------------|-----|------|------|-----|----------|---------|--------------------------|
| | s | exp | frac | E | Value | | d: E = 1 - Bias |
| | 0 | 0000 | 000 | -6 | 0 | | |
| | 0 | 0000 | 001 | -6 | 1/8*1/64 | = 1/512 | closest to zero |
| Denormalized | 0 | 0000 | 010 | -6 | 2/8*1/64 | = 2/512 | $(-1)^{0}(0+1/4)*2^{-6}$ |
| numbers | ••• | | | | | | |
| | 0 | 0000 | 110 | -6 | 6/8*1/64 | = 6/512 | |
| | 0 | 0000 | 111 | -6 | 7/8*1/64 | = 7/512 | largest denorm |
| | 0 | 0001 | 000 | -6 | 8/8*1/64 | = 8/512 | smallest norm |
| | 0 | 0001 | 001 | -6 | 9/8*1/64 | = 9/512 | $(-1)^{0}(1+1/8)*2^{-6}$ |
| | ••• | | | | | | |
| | 0 | 0110 | 110 | -1 | 14/8*1/2 | = 14/16 | |
| | 0 | 0110 | 111 | -1 | 15/8*1/2 | = 15/16 | closest to 1 below |
| Normalized | 0 | 0111 | 000 | 0 | 8/8*1 | = 1 | |
| numbers | 0 | 0111 | 001 | 0 | 9/8*1 | = 9/8 | closest to 1 above |
| | 0 | 0111 | 010 | 0 | 10/8*1 | = 10/8 | |
| | | | | | | | |
| | 0 | 1110 | 110 | 7 | 14/8*128 | = 224 | |
| | 0 | 1110 | 111 | 7 | 15/8*128 | = 240 | largest norm |
| | 0 | 1111 | 000 | n/a | inf | | |
| | | | | | | | |


Distribution of Values

6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- Bias is $2^{3-1}-1=3$




■ Notice how the distribution gets denser toward zero.




Distribution of Values (close-up view)

6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- Bias is 3





Special Properties of the IEEE Encoding

- **FP Zero Same as Integer Zero**
 - All bits = 0

Can (Almost) Use Unsigned Integer Comparison

- Must first compare sign bits
- Must consider -0 = 0
- NaNs problematic
 - Will be greater than any other values
 - What should comparison yield? The answer is complicated.
- Otherwise OK
 - Denorm vs. normalized
 - Normalized vs. infinity

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

Floating Point Operations: Basic Idea

$$\mathbf{x} +_{\mathbf{f}} \mathbf{y} = \text{Round}(\mathbf{x} + \mathbf{y})$$

$$\mathbf{x} \times_{\mathbf{f}} \mathbf{y} = \text{Round}(\mathbf{x} \times \mathbf{y})$$

Basic idea

- First compute exact result
- Make it fit into desired precision
 - Possibly overflow if exponent too large
 - Possibly round to fit into frac

Rounding

Rounding Modes (illustrate with \$ rounding)

| | \$1.40 | \$1.60 | \$1.50 | \$2.50 | -\$1.50 |
|------------------------|--------|--------|--------|--------|-----------------------|
| Towards zero | \$1↓ | \$1↓ | \$1 ↓ | \$2 ↓ | -\$1 ↑ |
| Round down (-∞) | \$1 ₩ | \$1 ₩ | \$1 ↓ | \$2 ↓ | -\$2↓ |
| ■ Round up $(+\infty)$ | \$2 1 | \$2 1 | \$2 1 | \$3 1 | -\$1 ↑ |
| Nearest Even (default) | \$1↓ | \$2 1 | \$2 1 | \$2 ↓ | - \$2 ↓ |

Closer Look at Round-To-Even

Default Rounding Mode

- Hard to get any other kind without dropping into assembly
- C99 has support for rounding mode management
- All others are statistically biased
 - Sum of set of positive numbers will consistently be over- or underestimated

Applying to Other Decimal Places / Bit Positions

- When exactly halfway between two possible values
 - Round so that least significant digit is even
- E.g., round to nearest hundredth

| 7.8949999 | 7.89 | (Less than half way) |
|-----------|------|-------------------------|
| 7.8950001 | 7.90 | (Greater than half way) |
| 7.8950000 | 7.90 | (Half way—round up) |
| 7.8850000 | 7.88 | (Half way—round down) |

Rounding Binary Numbers

Binary Fractional Numbers

- "Even" when least significant bit is 0
- "Half way" when bits to right of rounding position = 100...2

Examples

Round to nearest 1/4 (2 bits right of binary point)

| Value | Binary | Rounded | Action | Rounded Value |
|--------|--------------------------|-----------------------|-------------|---------------|
| 2 3/32 | 10.000112 | 10.002 | (<1/2—down) | 2 |
| 2 3/16 | 10.00 <mark>110</mark> 2 | 10.012 | (>1/2—up) | 2 1/4 |
| 2 7/8 | 10.11 <mark>100</mark> 2 | 11.0 <mark>0</mark> 2 | (1/2—up) | 3 |
| 2 5/8 | 10.10 <mark>100</mark> 2 | 10.1 <mark>0</mark> 2 | (1/2—down) | 2 1/2 |

FP Multiplication

- \blacksquare $(-1)^{s1} M1 2^{E1} \times (-1)^{s2} M2 2^{E2}$
- Exact Result: $(-1)^s M 2^E$
 - Sign s: s1 ^ s2
 - Significand *M*: *M1* x *M2*
 - Exponent *E*: *E1* + *E2*

Fixing

- If $M \ge 2$, shift M right, increment E
- If E out of range, overflow
- Round M to fit frac precision

■ Implementation

Biggest chore is multiplying significands

```
4 bit mantissa: 1.010*2^2 \times 1.110*2^3 = 10.0011*2^5
= 1.00011*2^6 = 1.001*2^6
```


Floating Point Addition


- $\blacksquare (-1)^{s1} M1 2^{E1} + (-1)^{s2} M2 2^{E2}$
 - **A**ssume *E1* > *E2*
- Exact Result: $(-1)^s M 2^E$
 - ■Sign *s*, significand *M*:
 - Result of signed align & add
 - ■Exponent *E*: *E1*

Fixing

- ■If $M \ge 2$, shift M right, increment E
- •if M < 1, shift M left k positions, decrement E by k
- ■Overflow if *E* out of range
- Round *M* to fit **frac** precision

Get binary points lined up





 $1.010*2^{2} + 1.110*2^{3} = (1.010 + 11.100)*2^{2}$ = $100.110 * 2^{2} = 1.0011 * 2^{4} = 1.010 * 2^{4}$

Mathematical Properties of FP Add

Compare to those of Abelian Group

Closed under addition?

Yes

But may generate infinity or NaN

Commutative?

Yes

Associative?

No

Overflow and inexactness of rounding

-(3.14+1e10)-1e10 = 0, 3.14+(1e10-1e10) = 3.14

0 is additive identity?

Yes

Every element has additive inverse?

Almost

Yes, except for infinities & NaNs

Monotonicity

■ $a \ge b \Rightarrow a+c \ge b+c$?

Almost

Except for infinities & NaNs

Mathematical Properties of FP Mult

Compare to Commutative Ring

Closed under multiplication?

Yes

But may generate infinity or NaN

• Multiplication Commutative?

Yes

Multiplication is Associative?

No

Possibility of overflow, inexactness of rounding

Ex: (1e20*1e20) *1e-20= inf, 1e20* (1e20*1e-20) = 1e20

1 is multiplicative identity?

Yes

• Multiplication distributes over addition?

No

Possibility of overflow, inexactness of rounding

-1e20*(1e20-1e20)=0.0, 1e20*1e20 - 1e20*1e20 = NaN

Monotonicity

• $a \ge b \& c \ge 0 \Rightarrow a * c \ge b * c$?

Almost

Except for infinities & NaNs

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

Floating Point in C

C Guarantees Two Levels

- float single precision
- double double precision

Conversions/Casting

- Casting between int, float, and double changes bit representation
- double/float → int
 - Truncates fractional part
 - Like rounding toward zero
 - Not defined when out of range or NaN: Generally sets to TMin
- int → double
 - Exact conversion, as long as int has ≤ 53 bit word size
- int → float
 - Will round according to rounding mode

Floating Point Puzzles

■ For each of the following C expressions, either:

- Argue that it is true for all argument values
- Explain why not true

```
int x = ...;
float f = ...;
double d = ...;
```


Assume neither **d** nor **f** is NaN

```
• x == (int)(float) x
• x == (int) (double) x
f == (float) (double) f
• d == (double) (float) d
• f == -(-f);
• 2/3 == 2/3.0
• d < 0.0 \Rightarrow ((d*2) < 0.0)
• d > f \Rightarrow -f > -d
• d * d >= 0.0
• (d+f)-d == f
```

Summary

- IEEE Floating Point has clear mathematical properties
- Represents numbers of form M x 2^E
- One can reason about operations independent of implementation
 - As if computed with perfect precision and then rounded
- Not the same as real arithmetic
 - Violates associativity/distributivity
 - Makes life difficult for compilers & serious numerical applications

programmers



Additional Slides

Creating Floating Point Number

Steps

- Normalize to have leading 1
- Round to fit within fraction

- s exp frac

 1 4-bits 3-bits
- Postnormalize to deal with effects of rounding

Case Study

Convert 8-bit unsigned numbers to tiny floating point format

Example Numbers

| 128 | 1000000 |
|-----|----------|
| 15 | 00001101 |
| 33 | 00010001 |
| 35 | 00010011 |
| 138 | 10001010 |
| 63 | 0011111 |

Normalize

| | S | ехр | frac |
|---|---|--------|--------|
| - | 1 | 4-bits | 3-bits |

Requirement

- Set binary point so that numbers of form 1.xxxxx
- Adjust all to have leading one
 - Decrement exponent as shift left

| Value | Binary | Fraction | Exponent |
|-------|----------|-----------|----------|
| 128 | 1000000 | 1.0000000 | 7 |
| 15 | 00001101 | 1.1010000 | 3 |
| 17 | 00010001 | 1.0001000 | 4 |
| 19 | 00010011 | 1.0011000 | 4 |
| 138 | 10001010 | 1.0001010 | 7 |
| 63 | 00111111 | 1.1111100 | 5 |

Rounding

1.BBGRXXX

Guard bit: LSB of result

Round bit: 1st bit removed

Sticky bit: OR of remaining bits

Round up conditions

- Round = 1, Sticky = $1 \rightarrow > 0.5$
- Guard = 1, Round = 1, Sticky = 0 → Round to even

| Value | Fraction | GRS | Incr? | Rounded |
|-------|-----------|-----|-------|---------|
| 128 | 1.0000000 | 000 | N | 1.000 |
| 15 | 1.1010000 | 100 | N | 1.101 |
| 17 | 1.0001000 | 010 | N | 1.000 |
| 19 | 1.0011000 | 110 | Y | 1.010 |
| 138 | 1.0001010 | 011 | Y | 1.001 |
| 63 | 1.1111100 | 111 | Y | 10.000 |

Postnormalize

Issue

- Rounding may have caused overflow
- Handle by shifting right once & incrementing exponent

| Value | Rounded | Exp | Adjusted | Result |
|-------|---------|-----|----------|--------|
| 128 | 1.000 | 7 | | 128 |
| 15 | 1.101 | 3 | | 15 |
| 17 | 1.000 | 4 | | 16 |
| 19 | 1.010 | 4 | | 20 |
| 138 | 1.001 | 7 | | 134 |
| 63 | 10.000 | 5 | 1.000/6 | 64 |

Interesting Numbers

{single,double}

| Description | exp | frac | Numeric Value |
|-------------------------------------------------|----------|------|------------------------------------------------|
| Zero | 0000 | 0000 | 0.0 |
| Smallest Pos. Denorm. | 0000 | 0001 | $2^{-\{23,52\}} \times 2^{-\{126,1022\}}$ |
| ■ Single $\approx 1.4 \times 10^{-45}$ | | | |
| ■ Double $\approx 4.9 \times 10^{-324}$ | | | |
| Largest Denormalized | 0000 | 1111 | $(1.0 - \varepsilon) \times 2^{-\{126,1022\}}$ |
| ■ Single $\approx 1.18 \times 10^{-38}$ | | | |
| ■ Double $\approx 2.2 \times 10^{-308}$ | | | |
| Smallest Pos. Normalized | 0001 | 0000 | 1.0 x $2^{-\{126,1022\}}$ |
| Just larger than largest deno | rmalized | | |
| One | 0111 | 0000 | 1.0 |
| Largest Normalized | 1110 | 1111 | $(2.0 - \varepsilon) \times 2^{\{127,1023\}}$ |
| ■ Single $\approx 3.4 \times 10^{38}$ | | | |

■ Double $\approx 1.8 \times 10^{308}$