# CCNA – 200 – 301

(Lab # 2a)

## VLAN Configuration (Without Trunk)

(By Engr. Gul Raeez Gulshan)

**Objective:**

- Creating two virtual LANs named **VLAN 10 and VLAN 20**.
- Network IP is 192.168.1.0 and all PCs are configured with IP address in range (192.168.1.1 to 192.168.1.8).
- Configuring switchports of both switches for VLAN 10 & VLAN 20 in access mode.
- For switch (SW0) and switch (SW1), the ports **f0/1, f0/2 and f0/5** are configured to be accessed in **VLAN 10**, while the ports **f0/3, f0/4 and f0/6** are configured to be accessed in **VLAN 20**.
- Showing the results by pinging between the devices in both VLANs.
- *No trunk link/cable has been used between the two switches, instead we used two different links/cables for VLAN 10 and VLAN 20.*




### Logical Topology in Packet Tracer



## Configuring Switch (SW0) for VLAN 10 & 20

```
SW0>enable
SW0#configure terminal
SW0(config)#interface range fastEthernet 0/1-2
SW0(config-if-range)#switchport mode access
SW0(config-if-range)#switchport access vlan 10
SW0(config-if-range)#exit
SW0(config)#interface range fastEthernet 0/3-4
SW0(config-if-range)#switchport mode access
SW0(config-if-range)#switchport access vlan 20
SW0(config-if-range)#exit
SW0(config)#interface fastEthernet 0/5
SW0(config-if)#switchport mode access
SW0(config-if)#switchport access vlan 10
SW0(config-if)#exit
SW0(config)#interface fastEthernet 0/6
SW0(config-if)#switchport mode access
SW0(config-if)#switchport access vlan 20
SW0(config-if)#exit
SW0(config)#do show vlan
```

```
Switch(config)#do show vlan

VLAN Name                              Status    Ports
---- --------------------------------- --------- -------------------------------
1    default                           active    Fa0/7, Fa0/8, Fa0/9, Fa0/10
                                                 Fa0/11, Fa0/12, Fa0/13, Fa0/14
                                                 Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                 Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                 Fa0/23, Fa0/24, Gig0/1, Gig0/2
10   VLAN0010                          active    Fa0/1, Fa0/2, Fa0/5
20   VLAN0020                          active    Fa0/3, Fa0/4, Fa0/6
1002 fddi-default                      active
1003 token-ring-default                active
1004 fddinet-default                   active
1005 trnet-default                     active
```

## Configuring Switch (SW1) for VLAN 10 & 20

```
SW1>enable
SW1#configure terminal
SW1(config)#interface range fastEthernet 0/1-2
SW1(config-if-range)#switchport mode access
SW1(config-if-range)#switchport access vlan 10
SW1(config-if-range)#exit
SW1(config)#interface range fastEthernet 0/3-4
SW1(config-if-range)#switchport mode access
SW1(config-if-range)#switchport access vlan 20
SW1(config-if-range)#exit
SW1(config)#interface fastEthernet 0/5
SW1(config-if)#switchport mode access
SW1(config-if)#switchport access vlan 10
SW1(config-if)#exit
SW1(config)#interface fastEthernet 0/6
SW1(config-if)#switchport mode access
SW1(config-if)#switchport access vlan 20
SW1(config-if)#exit
SW1(config)#do show vlan
```

```
SW1(config-if)#do show vlan

VLAN Name                              Status    Ports
---- --------------------------------- --------- -------------------------------
1    default                           active    Fa0/7, Fa0/8, Fa0/9, Fa0/10
                                                 Fa0/11, Fa0/12, Fa0/13, Fa0/14
                                                 Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                 Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                 Fa0/23, Fa0/24, Gig0/1, Gig0/2
10   VLAN0010                          active    Fa0/1, Fa0/2, Fa0/5
20   VLAN0020                          active    Fa0/3, Fa0/4, Fa0/6
1002 fddi-default                      active
1003 token-ring-default                active
1004 fddinet-default                   active
1005 trnet-default                     active
```

*Pinging from PC0 (VLAN10) to PC0 (VLAN10): Successful*

```
C:\>ping 192.168.1.5

Pinging 192.168.1.5 with 32 bytes of data:

Reply from 192.168.1.5: bytes=32 time<1ms TTL=128
Reply from 192.168.1.5: bytes=32 time<1ms TTL=128
Reply from 192.168.1.5: bytes=32 time=4ms TTL=128
Reply from 192.168.1.5: bytes=32 time<1ms TTL=128

Ping statistics for 192.168.1.5:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 4ms, Average = 1ms
```

*Pinging from PC0 (**VLAN10**) to PC0 (**VLAN20**): Unsuccessful*

```
C:\>ping 192.168.1.7

Pinging 192.168.1.7 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 192.168.1.7:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```

*Pinging from PC4 (**VLAN20**) to PC7 (**VLAN20**): Successful*

```
C:\>ping 192.168.1.8

Pinging 192.168.1.8 with 32 bytes of data:

Reply from 192.168.1.8: bytes=32 time<1ms TTL=128
Reply from 192.168.1.8: bytes=32 time<1ms TTL=128
Reply from 192.168.1.8: bytes=32 time=1ms TTL=128
Reply from 192.168.1.8: bytes=32 time<1ms TTL=128

Ping statistics for 192.168.1.8:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
```

*Pinging from PC7 (**VLAN20**) to PC0 (**VLAN10**): Unsuccessful*