ECE459: Programming for Performance	Winter 2024		
Lecture 25 — Profiling and Scalability			
Jeff Zarnett	2024-07-13		

Profiling and Scalability

We've had a long look at the subject of observation – identifying areas in the execution of our program that are a potential issue. Most of our upcoming discussion will be around the idea of CPU profiling, which is to say, examining where CPU time is going. That's generally predicated on the idea that CPU time is limiting factor. But maybe it isn't, and before we go about focusing on how to improve this aspect, let's check that assumption and consider what else it could be.

While we're discussing this, we will also take some time to relate performance to scalability. Very early on in the course we mentioned the idea that what we want in scalability is to take our software from 1 user to 100 to 10 million. To scale up, we probably need to do some profiling to find out what's slow and make a decision about what to change. It's also useful in terms of making an estimate of our maximum number of users or transactions could be. That's not a hypothetical scenario either; I [JZ] was asked by a C-Level (company executive) whether a particular system could handle $10\times$ as many users – and that answer had to be supported with some numbers.

With that said, if you identify a problem in a production system and we want to experiment on it with a dev machine, or if we have an application developed and we want to estimate what its performance and limiting factors would be, there are a few things we need to worry about. So we should respect the following principles, as outlined in [Liu09].

Hardware Principle. Scalability testing is very different from QA testing (you test your code, right?) in that you will do development and QA on your local computer and all you really care about is whether the program produces the correct output "fast enough". That's fine, but it's no way to test if it scales. If you actually want to test for scalability and real world performance, you should be doing it on the machines that are going to run the program in the live/production environment. Why? Well, low-end systems have very different limiting factors. You might be limited by the 16GB of RAM in your laptop and that would go away in the 64GB of RAM server you're using. So you might spend a great deal of time worrying about RAM usage when it turns out it doesn't matter.

Reality Principle. It would be a good idea to use a "real" workload, as much as one can possibly simulate. Legal reasons might prevent you from using actual customer data, but you should be trying to use the best approximation of it that you have.

If you only generate some test data, it might not be representative of the actual data: you might say 1% of your customers are on the annual subscription but if it's really 10% that might make a difference in how long it takes to run an analysis. On the other hand, your test data might be much larger than in production because your tests create (and don't delete) entities in the test system database every time you run.

This isn't theoretical: I [JZ] have been the incident responder on an incident where an app doesn't start up because the database migration takes too long and gets killed. This issue wasn't caught in the test environment because the size of data there was much smaller than the live database. So of course the migration was finished well under the time limit during testing... and failed when going live. Oops.

Related to that, user behaviour is hard to simulate, too. If you are making threads that pretend to be users to simulate concurrent usage of the system, the scripts those threads run may not accurately represent the way the users really behave. Your test example scenario may assume that company managers want to run the report once a month... your users might run them every hour. That one really happened to me [JZ] as well. The manager was using the report to keep an eye on what his team members were doing all day!

Volume Principle. "More is the new more." It's okay to use lighter workloads for regression testing and things like that, but if you actually want to see how your system performs under pressure, you actually need to put it under pressure! You can simulate pressure by limiting RAM or running something very CPU-intensive concurrently, but it's not quite the same as having an actually-high workload.

Why not? The issue isn't so much the test as it is what you're not seeing. If I want to test the app on my laptop under CPU pressure I can just run the app while I repeatedly convert a lecture video just to consume CPU cycles. That does have the effect of limited CPU time available and we can see how the app performs when CPU time is maxed out. But that's not the same as what happens if you have 500 users concurrently, because you might not get to full CPU usage with 500 users due to other reasons, such as lock contention.

These tests, incidentally, are of great interest to the customers and C-Levels, who would like to know that you can deliver promised levels of performance or throughput, or what the current maximum is.

Reproducibility and Regression Testing. Your results will need to be reproducible. Remember that good programming practice says that tests should be run, and re-run to make sure it all works. The same is true in your performance tests. Just as we don't want to see old bugs cropping up again, old (solved) performance issues are not nice to see either. Or a new change that slows the whole program down is not a success either. So please, have regression testing and performance regression testing. Real-life example: https://arewefastyet.com tracks regressions/improvements in Firefox performance.

Characterizing Performance & Scalability Problems

It is a capital mistake to theorize before one has data. Insensibly one begins to twist facts to suit theories, instead of theories to suit facts.

- Sherlock Holmes (A Scandal in Bohemia; Sir Arthur Conan Doyle)

Keeping the wisdom of Mr. Holmes in mind, we need to collect evidence before reaching conclusions. At a high level we probably have five potential culprits to start with:

- 1. CPU
- 2. Memory
- 3. Disk
- 4. Network
- 5. Locks

These are, obviously, more categories than specific causes, but they are starting points for further investigation. They are listed in some numerical order, but there is no reason why one would have to investigate them in the order defined there.

CPU. CPU is probably the easiest of these to diagnose. Something like top or Task Manager will tell you pretty quickly if the CPU is busy. You can look at the %CPU columns and see where all your CPU is going. Still, that tells you about right now; what about the long term average? Checking with my machine "Loki", that used to donate its free CPU cycles to world community grid (I'm singlehandedly saving the world, you see.):


top - 07:28:19 up 151 days, 23:38, 8 users, load average: 0.87, 0.92, 0.91

Those last three numbers are the one, five, and fifteen minute averages of CPU load, respectively. Lower numbers mean less CPU usage and a less busy machine. A small guide on how to interpret this, from [And15].

Picture a single core of a CPU as a lane of traffic. You are a bridge operator and so you need to monitor how many cars are waiting to cross that bridge. If no cars are waiting, traffic is good and drivers are happy. If there is a backup of cars, then there will be delays. Our numbering scheme corresponds to this:

- 1. 0.00 means no traffic (and in fact anything between 0.00 and 0.99) means we're under capacity and there will be no delay.
- 2. 1.00 means we are exactly at capacity. Everything is okay, but if one more car shows up, there will be a delay.
- 3. Anything above 1.00 means there's a backup (delay). If we have 2.00 load, then the bridge is full and there's an equal number of cars waiting to get on the bridge.

Or, visually, also from [And15]:



Being at or above 1.00 isn't necessarily bad, but you should be concerned if there is consistent load of 1.00 or above. And if you are below 1.00 but getting close to it, you know how much room you have to scale things up – if load is 0.4 you can increase handily. If load is 0.9 you're pushing the limit already. If load is above 0.70 then it's probably time to investigate. If it's at 1.00 consistently we have a serious problem. If it's up to 5.00 then this is a red alert situation.

Now this is for a single CPU – if you have a load of 3.00 and a quad core CPU, this is okay. You have, in the traffic analogy, four lanes of traffic, of which 3 are being used to capacity. So we have a fourth lane free and it's as if we're at 75% utilization on a single CPU.

Memory and Disk. Next on the list is memory. One way to tell if memory is the limiting factor is actually to look at disk utilization. If there is not enough RAM in the box, there will be swapping and then performance goes out the window and scalability goes with. That is of course, the worst case. You can ask via top about how much swap is being used, but that's probably not the interesting value.

KiB Mem: 8167736 total, 6754408 used, 1413328 free, 172256 buffers KiB Swap: 8378364 total, 1313972 used, 7064392 free. 2084336 cached Mem

This can be misleading though, because memory being "full" does not necessarily mean anything bad. It means the resource is being used to its maximum potential, yes, but there is no benefit to keeping a block of memory open for no reason. Things will move into and out of memory as they need to, and nobody hands out medals to indicate that you did an awesome job of keeping free memory. It's not like going under budget in your department for the year. Also, memory is not like the CPU; if there's nothing for the CPU to do, it will just idle (or go to a low power state, which is nice for saving the planet). But memory won't "forget" data if it doesn't happen to be needed right now - data will hang around in memory until there is a reason to move or change it. So freaking out

about memory appearing as full is kind of like getting all in a knot about how "System Idle Process" is hammering the CPU^1 .

You can also ask about page faults, with the command ps -eo min_flt,maj_flt,cmd which will give you the major page faults (had to fetch from disk) and minor page faults (had to copy a page from another process). The output of this is too big even for the notes, but try it yourself (or I might be able to do a demo of it in class). But this is lifetime and you could have a trillion page faults at the beginning of your program and then after that everything is fine. What you really want is to ask Linux for a report on swapping:

```
jz@Loki:~$ vmstat 5
procs ------memory----- ---swap--
                                              ----io---- -system-- ----cpu--
                                                 bi
        baws
               free
                       buff
                             cache
                                      si
                                           S0
                                                       bo
                                                             in
                                                                  cs us sv id wa st
    0 1313972 1414600 172232 2084296
                                                     3
                                                          39
                                                                      1 27
                                                                            1 72
                                                                                   0
                                                                                      0
                                          0
                                               0
                                                                 1
    0 1313972 1414476 172232 2084296
                                          0
                                               0
                                                     0
                                                          21
                                                               359
                                                                    735 19
                                                                            0 80
                                                                                   0
                                                                                      0
    0 1313972 1414656 172236 2084228
                                          0
                                               0
                                                     0
                                                          102
                                                               388
                                                                    758 22
                                                                            0 78
                                                                                   0
                                                                                      0
 4
    0 1313972 1414592 172240 2084292
                                          0
                                               0
                                                     0
                                                           16
                                                               501
                                                                    847 33
                                                                            0 67
                                                                                   0
                                                                                      0
    0 1313972 1412028 172240 2084296
                                               0
                                                     0
                                                               459
                                                                    814 29
                                                                            0 71
                                                                                   0
                                          0
                                                                                      0
```

In particular, the columns "si" (swap in) and "so" (swap out) are the ones to pay attention to. In the above example, they are all zero. That is excellent and tends to indicate that we are not swapping to disk and that's not the performance limiting factor. Sometimes we don't get that situation. A little bit of swapping may be inevitable, but if we have lots of swapping, we have a very big problem. Here's a not-so-nice example, from [Tan05]:

	pro	cs				memor	Ъ	swa	р		io	system	cpu	
r	b	W	swpd	free	buff	cache	si	S0	bi	bo	in	cs us	sy	id
1	0	0	13344	1444	1308	19692	0	168	129	42	1505	713 20	11	69
1	0	0	13856	1640	1308	18524	64	516	379	129	4341	646 24	34	42
3	0	0	13856	1084	1308	18316	56	64	14	0	320	1022 84	9	8

If we're not doing significant swapping, then memory isn't holding us back, so we can conclude it is not the limiting factor in scaling the application up. On to disk.

Looking at disk might seem slightly redundant if memory is not the limiting factor. After all, if the data were in memory it would be unnecessary to go to disk in the first place. Still, sometimes we can take a look at the disk and see if that is our bottleneck.

```
jz@Loki:~$ iostat -dx /dev/sda 5
Linux 3.13.0-24-generic (Loki) 16-02-13
                                          _x86_64_ (4 CPU)
                         wrqm/s
                                                    rkB/s
                                                             wkB/s avgrq-sz avgqu-sz
                                                                                       await r_await w_await
                                                                                                              svctm
Device:
                rrqm/s
                                    r/s
                                            w/s
                                                                                                                      %util
sda
                                   0.45
                                           2.40
                                                            154.98
                  0.24
                                                   11.60
                                                                     116.91
                                                                                0.17
                                                                                       61.07
                                                                                               11.57
```

It's that last column, %util that tells us what we want to know. The device bandwidth here is barely being used at all. If you saw it up at 100% then you would know that the disk was being maxed out and that would be a pretty obvious indicator that it is the limiting factor. This does not tell you much about what is using the CPU, of course, and you can look at what processes are using the I/O subsystems with iotop which requires root privileges².

Network. That leaves us with networks. We can ask about the network with nload: which gives the current, average, min, max, and total values. And you get a nice little graph if there is anything to see. It's not so much fun if nothing is happening. But you'll get the summary, at least:

¹Yes, a tech journalist named John Dvorak really wrote an article about this, and I will never, ever forgive him for it.

²https://xkcd.com/149/

Curr: 3.32 kBit/s Avg: 2.95 kBit/s Min: 1.02 kBit/s Max: 12.60 kBit/s Ttl: 39.76 GByte

Locks. The last possibility we'll consider is that your code is slow because we're waiting for locks, either frequently or for lengthy periods of time. We've already discussed appropriate use of locks, so we won't repeat that. The discussion here is about how to tell if there is a locking problem in the first place.

We'll exclude the discussion of detecting deadlock, because we'll say that deadlock is a correctness problem more than a performance problem. In any case, a previous course (ECE 252, SE 350, MTE 241) very likely covered the idea of deadlock and how to avoid it. The Helgrind tool (Valgrind suite) is a good way to identify things like lock ordering problems that cause a deadlock. Onwards then.

Unexpectedly low CPU usage, that's not explained by I/O-waits, may be a good indicator of lock contention. If that's the case, when CPU usage is low we would see many threads are blocked.

Unlike some of the other things we've discussed, there's no magical locktrace tool that would tell us about critical section locks, and the POSIX pthread library does not have any locks tracing in its specification [Sit21]. One possibility is to introduce some logging or tracing ourselves, e.g., recording in the log that we want to enter a critical section A and then another entry once we're in it and a third entry when we leave A. That's not great, but it is something!

I did some reading about perf lock but the problem is, as above, that it doesn't really find user-space lock contention. You can ask tools to tell you about thread switches but that's not quite the same. Other commercial tools like the Intel VTune claim that they can find these sorts of problems. But those cost money and may be CPU-vendor-specific.

But it's probably CPU...

Most profiling tools, and most of our discussion, will be about CPU profiling. It's the most likely problem we'll face and something that we are hopefully able to do something about.

References

- [And15] Andre. Understanding Linux CPU load—when should you be worried?, 2015. Online; accessed 13-Feburary-2016. URL: http://blog.scoutapp.com/articles/2009/07/31/understanding-load-averages.
- [Liu09] Henry H. Liu. Software Performance and Scalability: A Quantitative Approach. John Wiley & Sons, 2009.
- [Sit21] Richard L. Sites. Understanding Software Dynamics. Addison-Wesley Professional, 2021.
- [Tan05] Brian K. Tanaka. Monitoring Virtual Memory with vmstat, 2005. Online; accessed 13-February-2016. URL: http://www.linuxjournal.com/article/8178.