

Lua command reference document

Version information: This document is based on the commands available in IRB SVN revision 122

Content

| Global LUA pre-defined functions (basicFunctions.lua) | 3 |
|---|----|
| internals | 3 |
| Global functions | 3 |
| Global Functions | 5 |
| Global variables creation | 5 |
| Lighting / ambiance commands | 5 |
| Background | 6 |
| Special FX post-process commands | 6 |
| Cameras commands | 7 |
| Cameras commands (continued) | 8 |
| Sound commands | 9 |
| Player affecting commands | 9 |
| Dialogs /GUI commands | 10 |
| Game Commands | 10 |
| Callbacks for the global function: | 10 |
| Misc Commands: | 10 |
| Dynamic objects functions: | 11 |
| Label management | 11 |
| Object type management | 11 |
| Position/rotation management | 11 |
| Position/rotation management (continued) | 12 |
| Getting information | 12 |
| Animation/AI specific functions | 12 |
| Default animation names | 13 |
| Dynamic objects: (properties and combat) | 14 |
| Current properties and combat commands: | 15 |
| Special Variables | 16 |
| Callhacks: | 16 |



Global LUA pre-defined functions (basicFunctions.lua)

Theses function they can be called from anywhere in IRB. They are global. But these have been written in LUA, so they could be modified by the user.

---- internals

IRBStoreGlobalParams() IRBRestoreGlobalParams()

---- Global functions

setObjectName(string 'name')

set the global name of the current object

chaseObject(string 'name', float speed, float near, float far)

chase the specified object speed = move speed

near = stop when reaching this distance (also IDLE state is triggered)

far = start walking from this position (also WALK state is triggered)

walkRandomly(float radius, float speed)

Walk randomly in a specified radius radius = random point to get there specified from a radius around the object speed = move speed

walkToObject(otherObj)

Walk to an object, current command doesn't account the animations

CustomDynamicObjectUpdate()

update the dynamic objects, work with the 'walkToObject' command Should be placed in the 'step' callback

programAction(time, action, parameter...)

Call a specified custom function at the specified time interval.

time = time interval in second
action = function name to call
parameters = parameter (up to 10 parameters)

Ex: programAction(10, print, 'hello world')

Will call: print "hello world" after 10 seconds.

CustomDynamicObjectUpdateProgrammedAction()

Update programmed action if it exist



action = hasActionProgrammed()

Will return the name of the action that is programmed. if any.

enableObject()

will enable the current object

disableObject()

Will disable the current object

decreasePlayerLife(points)

Remove 'point' from the current life of the player

increasePlayerLife(points)

Increase the current player life with 'points'

decreasePLayerMoney(points)

Remove 'points' from the current player money

increasePlayerMoney(points)

Increase the current money of the player with 'point'

playSound(soundName, looped)

Play a 2D sound

emitSound(soundName, looped)

Play a sound from the current position of the object (3D Sound)

sleep(time)

Will 'sleep' until the time is reached. 'time' is in seconds.



Global Functions

Theses function can be called from about anywhere in IRB. They are global. They have been coded directly in the engine and cannot be modified directly by the user.

Global variables creation

setGlobal(string 'name', value)

Create a global unique name

value = getGlobal(string 'name')

Retrieve the value of the global

deleteGlobal(string 'name')

Delete the specified global

Lighting / ambiance commands

setTimeOfDay(int time)

set the time of day

setAmbientLight(int *r*,int *q*, int *b***)**

Set the ambient light to the specified RGB colors

r,g,b = getAmbientColor()

Give back the ambient color

setFogColor(int *r*, int *q*, int *b***)**

Set the color of the fog to the specified RGB color

r,g,b = getFogColor()

Retrieve the current fog color in RGB color

setFogRange (float near, float far)

Define the range of the fog

near, far = getFogRange()

Retrieve the range of fog

String = getLanguage()

Return the current language for the game, the currently supported languages strings are:

"en-us" -> English, US

"pt-br" -> Portugese, Brazil

"fr-ca" -> French, Canada

"de-ge" -> Deutch, Germany



Background

setSkydomeTexture(string 'texturefilename')

Change the texture of the skydome

setSkydomeVisible(bool visible)

Set the visibility of the skydome

setBackgroundColor(int *r*, int *g*, int *b*)

Set the background rendering color

Special FX post-process commands

setPostFX(string 'name')

Create a postprocess FX, Theses can be useful in a lot of circonstances. Applied FX will change all of the display. The shader modify the rendered output.

name can be:

adaptive bloom blur color depth of field desaturate displacement dream vision embossed gray_scale invert motion blur none night_vision pencil posterize pulsing radial blur scratched sepia shake sharpen simple_bloom tiling vignette water

Theses FX are based on shaders and there might be modified in the future.



Cameras commands

setCameraTarget(float x, float y, float z)

Set a new position for the camera, use the specified coordinates

setCameraTarget(string 'objectname')

Set a new position for the camera, use the object name as reference

x,y,z = getCameraTarget()

Get the current camera target

x,y,z = getCameraPosition(string 'objectname')

Retrieve the position of the current camera

setCameraPosition(float x, float y, float z)

Set a new position for the camera, use the specified coordinates

setCameraPosition(string 'objectname')

Set a new position for the camera, use the object name as reference

setCameraRange(float start, float end)

Set the range of the ingame camera zoom (mouse wheel)

Default values are min=72, max=2000

setCameraZoom(float zoom)

Set distance for the camera zoom

Default value is 600

Start, end = getCameraRange()

Retrieve the current range limits of the camera zoom

setCameraAngleLimit(float low, float high)

Define the angle limit (up/down) limits of the game camera

The default values are -25, 89

low, high = getCameraAngleLimit()

Retrieve the current rotation information of the RTS camera

setCameraRTSRotation(float X, float Y)

Redefine the angle of the rotation of the RTS camera

The default values are 135.0, 45.0

Start, end = getCameraRTSRotation()

Retrieve the current rotation information of the RTS camera



Cameras commands (continued)

cutsceneMode()

switch the current camera to the cutscene camera

gameMode()

switch the current camera to the ingame camera

setRTSView()

switch the ingame camera view to a RTS game type view

setRTSFixedView()

switch the ingame camera view to a RTS game type view, rotation is locked

setRPGView()

switch the ingame camera view to third person view type view

Sound commands

playSound2D(string 'filename', boolean looped)

PLay the specified 2D sound, 'looped' is optional.

playSound3D(string 'filename',bool looped, float x, float y, float z)

Play the specified sound, at the specified coordinates. Looped is for a looping sound

setSoundListenerPosition(float x, int y, int z)

Define the position of the listener for a 3D sound

Note: is now updated directly by the engine to the player position. Will need to be overridden to change the position.

setSoundVolume (float volume)

Set the volume to a specified level

stopSounds()

Stop all sounds

Player affecting commands

setPlayerLife(int life)

Set the player life to the specified value.

A change in the value will rise a "injured state" on the player

A value of 0 will set the "die" state on the player

life = getPlayerLife()

Get the current player life

setPlayerMoney(int money)

Set the amount of money the player will have

money = getPlayerMoney()

Retrieve the current amount of money the player have

addPlayerItem(string 'item')

Set a custom global callback and define a new object to use in the inventory GUI

addPlayerLoot()

Add the current item to the player loot. Item must be a "loot type" object.

removePlayerItem(string 'item)

Remove the custom callback, and remove the name from the inventory GUI

usePlayerItem(string 'item')

use the specified defined item (global)

'item' is a custom defined callback (global)

count = getItemCount()

return the item count from the inventory of the player



Dialogs / GUI commands

showBlackScreen(string 'optional text')

Show a black screen with an optional text (mostly used when player is dead)

hideBlackScreen()

Remove the black screen

showDialogMessage(string 'message')

Show the specified message

answer = showDialogQuestion(string 'question')

Show the specified question. (note: this can only be called from within a dynamic object)

Bool = getAnswer()

Will return the answer of the dialog question. Used principally in the **OnAnswer()** callback to do an action based on the response of the Question Dialog.

Game Commands

saveGame()

save the game

loadGame()

load back the game

Callbacks for the global function:

These functions are for the internal use of the engine. They should not be tampered with unless you know what you are doing.

IRBStoreGlobalParams()

IRBRestoreGlobalParams()

Misc Commands:

x,y,z = getObjectPosition(string 'objectname')

Retrieve the position of the specified object



Dynamic objects functions:

These function can only be used inside the dynamic object, they will not work outside (ex: global scripts)

Label management

showObjectLabel()

Display the object label

hideObjectLabel()

Hide the object label

setObjectLabel(string 'newlabel')

Define the new object label Ex: setObjectLabel("baddie")

Object type management

setObjectType("type")

Allow the developper to override the dynamic object type from LUA.

Type is a string and can contain theses values:

"interactive"
"non-interactive"

Position/rotation management

setPosition(float x,float y,float z)

Move the object to this specified position

x,y,z = getPosition()

Give back the position of the object (x,y,z)

setRotation(float x,float y,float z)

Rotate the object to the specified angle

x,y,z = getRotation()

Give back the current angle rotation of the object (x,y,z)

turn(float degrees)

Turn relative of a specified degree angle

move(float speed)

Set the walk speed of the object Also activate the "walk" animation state



Position/rotation management (continued)

walkTo(float x,float y,float z)

Set the destination of the object and the object will walk there with the current speed defined in the XML file

Ex: walkTo(10,0,10)

true/false = hasReached()

Will tell if a walking character has reached the destination point

lookAt(float x,float y,float z)

The object turn to face the specified coordinates

Ex: lookAt(10,0,10)

lookToObject(string 'objectname')

The object turn to face the specified object name

Getting information

string 'objectname' = getName()

Return the defined name of the template used

distance = distanceFrom(float x, float y, float z)

Give back the specified distance from the specified coordinates to the object.

distance = distanceFrom(string 'object')

Give back the specified distance from the the object to the specified object.

setEnabled(boolean)

Set the state of the dynamic object (enabled/disabled)

Ex: setEnabled(false)

Note: Disabling a NPC will remove it from the map

Animation/AI specific functions

setFrameLoop(int start, int end)

Set the animation frameloop for the object

setAnimationSpeed(float speed)

set the animation speed to the specified value. (frame rate)

setAnimation(string 'animation name')

Set the current animation of the object to the specified animation name ex: setAnimation("attack")



Default animation names

Here are the default animation names for the specific animation states. The animation states are associated with the AI in the engine.

Using these names will trigger the proper animation state for the Al.

idle, set the state to OBJECT_ANIMATION_IDLE

❖ Special, must be there (xml) as this is the strict minimum for a NPC

walk, set the state to OBJECT_ANIMATION_WALK

Used by the animation system for walking

run, set the state to OBJECT_ANIMATION_RUN attack, set the state to OBJECT_ANIMATION_ATTACK

❖ Special, will trigger the attack if an attack event has been defined in the XML file

hurt, set the state to *OBJECT_ANIMATION_INJURED*

Used by the animation/combat system for the injured state in combat

knockback, set the state to *OBJECT_ANIMATION_KNOCKBACK* **die**, set the state to *OBJECT_ANIMATION_DIE*

Used by the animation system/combat to show the die state

die_knockback, set the state to OBJECT_ANIMATION_DIE_KNOCKBACK spawn, set the state to OBJECT_ANIMATION_SPAWN despawn, set the state to OBJECT_ANIMATION_DESPAWN despawn_knockback, set the state to OBJECT_ANIMATION_DESPAWN_KNOCKBACK

Dynamic objects: (properties and combat)

Current properties names:

| Property name | 2 | Description |
|---------------|---|--|
| life | > | Current life points |
| mana | > | Current mana points |
| maxlife | > | Maximum life points |
| regenlife | > | Points of life regeneration |
| regenmana | > | Points of mana regeneration |
| money | > | Current money |
| level | > | Current level |
| experience | > | Current experience (or given experience if NPC) |
| mindamage | > | minimum damage per hit |
| maxdamage | > | maximum damage per hit |
| armor | > | armor point |
| magic_armor | > | magic armor point |
| hurt_resist | > | hurt resistance probability |
| dotduration | > | duration for the dot (damage over time, poison) |
| hit_prob | > | probability of hitting the target |
| dodge_prob | > | probability of dodging the hit from the attacker |
| mindefense | > | minimum defense points |
| maxdefense | > | maximum defense points |

Current properties and combat commands:

setEnemy()

This object will become an enemy of the player

setObject()

This object will become an object (non-aggressive) (default)

setPropertie (string 'propertie name', float value)

This will set the named propertie to the value entered Ex: setPropertie("life",100)

float value getPropertie(string 'propertie name')

Give back the entered value from the named propertie entered Ex: value = getPropertie("life")

attack(string 'enemy name')

This will trigger the combat system to do a battle with the current object and the object entered. The combat system will check the properties of each opponent and do damages on the defender.

This will not check of the faction, nor the distance.

Ex: attack("player")

Special Variables

ObjName = NAME OF THE OBJECT

objType = *ENEMY* or *OBJECT*

Callbacks:

onLoad()

Called when the object is loading in the game

onRefresh() or step() -- old name

Called at each interval (default interval is 1/4 sec)

onClicked()

Called when the object as been clicked on with the mouse

onCollision()

Called when a collision occur with the object

onAnswer()

Called when the user respond to the Question Dialog. The answer return only to the dialog caller. *Ex:* If the player is invoking the question dialog, <u>only him</u> will receive the answer.

CustomDynamicObjectUpdate()

CustomDynamicObjectProgrammedAction()