Ocean: wind-driven circulation

ATM2016

Last time

- Ocean circulation
  - Hydrostatic balance
  - Geostrophic balance
    - Thermal wind relationship
- Sea level and isopycnal (lines with the same density)

Today

- Wind stress
- Wind-driven circulation
    - Ekman transport
    - Upwelling / Downwelling
    - Ekman pumping
    - Convergence / divergence

Averaged wind speed



Averaged wind stress



Wind and wind stress

Wind = wind stress ?

Weak stress

Wind and wind stress

Wind = wind stress ?

Moderate stress



Wind and wind stress

Wind = wind stress ?

Strong stress

Wind and wind stress

Crag coefficient

$$\text{Wind stress} = c_D \rho_{air} |u_{air} - u_{water}| (u_{air} - u_{water})$$

$$\text{Wind stress} \propto u_{air}^2$$

How does the ocean feel the wind stress?



$$F_x = \frac{1}{\rho_{ref}} \frac{\partial \tau_x}{\partial z}$$

$$F_y = \frac{1}{\rho_{ref}} \frac{\partial \tau_y}{\partial z}$$

How does the ocean feel the wind stress?



Ekman layer

Wind stress decreases rather rapidly with depth.

Dynamics in the Ekman layer

$$-fv + \frac{1}{\rho_{ref}} \frac{\partial p}{\partial x} = F_x$$

$$-fv + \frac{1}{\rho_{ref}} \frac{\partial p}{\partial x} = \frac{1}{\rho_{ref}} \frac{\partial \tau_x}{\partial z}$$

$$-f(v_g + v_a) + \frac{1}{\rho_{ref}} \frac{\partial p}{\partial x} = \frac{1}{\rho_{ref}} \frac{\partial \tau_x}{\partial z}$$

$$-fv_a = \frac{1}{\rho_{ref}} \frac{\partial \tau_x}{\partial z}$$

Dynamics in the Ekman layer

$$-fv_a = \frac{1}{\rho_{ref}}\frac{\partial \tau_x}{\partial z} \Rightarrow -f\rho_{ref}\int_{-\delta}^{0} v_a dz = \tau_{x,wind}$$

$$fu_a = \frac{1}{\rho_{ref}}\frac{\partial \tau_y}{\partial z} \Rightarrow f\rho_{ref}\int_{-\delta}^{0} u_a dz = \tau_{y,wind}$$

Dynamics in the Ekman layer

North hemisphere



$$-f\rho_{ref}\int_{-\delta}^{0} v_a dz = \tau_{x,wind}$$



$$f\rho_{ref}\int_{-\delta}^{0} u_a dz = \tau_{y,wind}$$

Dynamics in the Ekman layer

- Transport of the water in the Ekman layer is to the right of the wind stress direction in the northern hemisphere

- Transport of the water in the Ekman layer is to the left of the wind stress direction in the southern hemisphere.

- Ekman spiral



a

Ekman spiral



Wind stress structure



Wind stress structure

$$\frac{\partial \tau_x}{\partial y} < 0$$



- Northern H. : divergence
- Southern H. : convergence

$$\frac{\partial \tau_x}{\partial y} > 0$$



- Northern H. : convergence
- Southern H. : divergence

Wind stress structure

$$\frac{\partial \tau_y}{\partial x} < 0$$



- Northern H. : convergence
- Southern H. : divergence

$$\frac{\partial \tau_y}{\partial x} > 0$$



- Northern H. : divergence
- Southern H. : convergence

Wind stress structure

$$\frac{\partial \tau_y}{\partial x} - \frac{\partial \tau_x}{\partial y} < 0$$



- Northern H. : convergence
- Southern H. : divergence

$$\frac{\partial \tau_y}{\partial x} - \frac{\partial \tau_x}{\partial y} > 0$$



- Northern H. : divergence
- Southern H. : convergence

Wind stress structure



Sea level


Sea Surface Height
mean
90°N
60°N
30°N
0°
30°S
60°S
90°S
lat
120°E
150°E
180°
150°W
120°W
90°W
60°W
30°W
0°
30°E
60°E
90°E
120°E
150°E
lon
−140
−120
−100
−80
−60
−40
−20
0
20
40
60
80
100
120
140
(cm)

Ekman pumping / suction



Ekman pumping / suction



Ekman pumping at the equator



Ekman pumping / suction and temperature