# **DBM** Documentation

Release 1.2.1

Simon Lee

## **CONTENTS:**

	Class		3
		Matrix	
		Data Set	
		Parameters	
		Delta Boosting Machines	
	1.5	Delta Boosting Machines with Automatic BL Selection	8
2	Func	etions	11
Inc	dex		13

This is the document of the Python APIs of Delta Boosting Machine. Classes and functions are listed and described.

CONTENTS: 1

2 CONTENTS:

**CHAPTER** 

ONE

### **CLASSES**

### **Matrix**

\_\_init\_\_ (height=None, width=None, val=None, file\_name=None, sep=None, mat=None)

This is the class of Matrix used in DBM. To feed the training and prediction data to DBM, they should be converted to Matrix first of all. The Matrix interface provides four ways of initialization, i.e. initialization with random values in [-1, 1], initialization with a user-provided value, initialization from a file and initialization with a Float\_Matrix object. One may also initializing a matrix with any values and then use the method from\_np2darray to transfer the values from a numpy array of the same shape to it.

Initialization with random values in [-1, 1] :param height: height of the matrix :param width: width of the matrix

Initialization with a user-provided value :param val: a particular value for initialization

Initialization from a file :param file\_name: file name of the file where data comes from :param sep: seperator used in the file

Initialization with a Float\_Matrix object :param mat: a Float\_Matrix object

**Note:** 1. When initializing from a file, the format should be correct. One may first of all save a matrix to a file and look at the file and see how it looks like. 2. Avoid directly using Float\_Matrix. 3. Converting tools np2darray\_to\_float\_matrix and float\_matrix\_to\_np2darray are provided.

assign(i, j, val)

Assign a value to a particular element.

#### **Parameters**

- i height of the element
- **j** width of the element
- val value to be assigned

clear()

Set all elements to 0.

#### from np2darray(source)

Assign the data stored in a two-dimensional numpy array to this matrix.

Parameters source – a two-dimensional numpy array of the same shape as this matrix

get(i, j)

Access to a particular element in the matrix.

#### **Parameters**

- i height of the element
- **j** width of the element

**Returns** the element

Note: i and j should be in the correct ranges

```
save (file name, sep = \t^{\prime})
```

Save the data stored in it to a file.

#### **Parameters**

- file\_name a string
- sep a character

#### shape()

Return a list containing the shape of the matrix.

**Returns** [matrix height, matrix width]

#### show()

Print to screen the data stored in the matrix.

#### to np2darray()

Assign the data stored in this matrix to a two-dimensional numpy array and return it.

**Returns** a two-dimensional numpy array of the same shape as this matrix

## **Data Set**

```
class dbm_py .interface .Data_set (data_x, data_y, portion_for_validating, random_seed=-1)
```

\_\_init\_\_ (data\_x, data\_y, portion\_for\_validating, random\_seed=-1)

This is the class of Data\_set that provides an easy to tool for splitting all data into training and validating parts.

#### **Parameters**

- data\_x a Matrix object
- data\_y a Matrix object
- portion\_for\_validating percentage of the whole data used for validating
- random\_seed optional random seed (random if negative or fixed if non-negative)

### get\_train\_x()

Return the part of predictors for training.

Returns a Matrix object

### get\_train\_y()

Return the part of responses for training.

Returns a Matrix object

#### get\_validate\_x()

Return the part of predictors for validating.

Returns a Matrix object

## get\_validate\_y()

Return the part of responses for validating.

Returns a Matrix object

## **Parameters**

Parameter Name	Туре	Meaning
dbm_no_bunches_of_learners	int	number of boostraped BLs
dbm_no_candidate_feature	int	number of features for each BL (< total number of features)
dbm_portion_train_sample	double	percentage for training each BL
dbm_no_cores	int	number of BL in each bunch (number of cores used)
dbm_loss_function	char	(n)ormal, (b)ernoulli, (p)oisson or (t)weedie
dbm_display_training_progress	bool	whether to display training progress or not
dbm_record_every_tree	bool	whether to record trees in a file or not
dbm_freq_showing_loss_on_test	int	show loss on test after how many bunches of BLs
dbm_shrinkage	double	shrinkage for each BL
dbm_nonoverlapping_training	int	
_ 11 0- 0		whether to BLs in a bunch use nonoverlapping samples or not
dbm_remove_rows_containing_nans	int	whether to remove rows containing NaNs in training every BL
dbm_min_no_samples_per_bl	int	minimal number of samples for trainin every BL
dbm_portion_for_trees	double	percentage of BLs using trees
dbm_random_seed	int	random seed (random $< 0$ and fixed $>= 0$ )
dbm_portion_for_lr	double	percentage of BLs using linear regression
dbm_portion_for_s	double	percentage of BLs using splines
dbm_portion_for_k	double	percentage of BLs using k-means
dbm_portion_for_nn	double	should be 0
dbm_portion_for_d	double	percentage of BLs using dominating principal component stairs
dbm_accumulated_portion	double	1
_shrinkage_for_selected_b		unused
dbm_portion_shrinkage_for_unselected_bl	double	unused
tweedie_p	double	p of tweedie should in (1, 2)
splines_no_knot	int	number of knots of splines
splines_portion_of_pairs	double	percentage of pairs of perdictors considered
splines_regularization	double	ridge regression penalty
splines_hinge_coefficient	double	coefficient in splines
kmeans_no_centroids	int	number of centroids
kmeans_max_iteration	int	max number of iterations of training
kmeans_tolerance	double	max tolerated error
kmeans_fraction_of_pairs	double	percentage of pairs of predictors considered
nn_no_hidden_neurons	int	number of hidden neurons
		Continued on next page

1.3. Parameters 5

Table 1.1 – continued from previous page	d from previous page	Table 1.1 – continued
--	----------------------	-----------------------

		1 1 0
nn_step_size	double	stochastic gradient descent step size
nn_validate_portion	double	percentage of samples used for validating
nn_batch_size	int	number of samples in a batch
nn_max_iteration	int	maximal number of iterations of training
nn_no_rise_of_loss_on_validate	int	maximal number rises of loss on validation set
		maximal number rises of loss on validation set
cart_min_samples_in_a_node	int	minimal numbers in a node of a tree
cart_max_depth	int	maximal numbers of levels of a tree
cart_prune	int	whether to prune after training
lr_regularization	double	ridge regression penalty
dpcs_no_ticks	int	number of stairs in the direction of dominating principal component
		number of stairs in the direction of dominating principal component
dpcs_range_shrinkage_of_ticks	double	shrinkage of the range in the direction of dominating principal component
		shrinkage of the range in the direction of dominating principal component
dbm_do_perf	bool	whether to record performance on both training sets
		whether to record performance on both training sets
pdp_no_x_ticks	int	number of ticks in x-axis
pdp_no_resamplings	int	number of resamplings for bootstrapping
pdp_resampling_portion	double	percentage of samples in each bootstrap
pdp_ci_bandwidth	double	width of the confidence interval
pdp_save_files	int	whether to save the result
	•	•

class dbm\_py.interface.Params (params=None)

\_\_init\_\_(params=None)

This is class of Params storing parameters used in DBM.

Parameters params – a Params object

print\_all()

Print all parameters and their values to the screen.

set\_params (string, sep=' ')

Set values of parameters.

Usage: [sep] represents the character used as the separator

 $`parameter\_name[sep] parameter\_value' \cdot parameter\_name[sep] parameter\_value[sep] parameter\_value[sep] parameter\_value' \cdot parameter\_value[sep] parameter\_va$ 

#### **Parameters**

- **string** a string storing the parameters to be set
- **sep** separator used in the string

## **Delta Boosting Machines**

#### **Parameters** params – a Params object

calibrate\_plot (observation, prediction, resolution, file\_name='')

This is exactly the same as the one in GBM in R.

#### **Parameters**

- observation a Matrix object
- **prediction** a Matrix object
- resolution a scalar
- **file\_name** save the result if provided

#### **Returns** a Matrix object

interact (data, predictor\_ind, total\_no\_predictor)

This is exactly the same as the one in GBM in R.

#### **Parameters**

- data a Matrix object
- predictor\_ind a Matrix object
- total\_no\_predictor a scalar

#### Returns a scalar

load (file\_name)

Load from a file.

Parameters file\_name - a string

pdp (data\_x, feature\_index)

Calculate the data used in partial dependence plots.

#### **Parameters**

- data\_x a Matrix object used for calculating
- **feature\_index** the index of the predictor of interest (the No. of the column)

**Returns** a Matrix object storing the data used in partial dependence plots

predict (data\_x)

Predict if it has been trained or it has been loaded from a trained model.

Parameters data\_x - a Matrix object

#### Returns

save (file\_name)

Save the DBM after trained.

Parameters file\_name - a string

save\_performance (file\_name)

Save the training and validating losses.

**Parameters** file\_name - a string

 $ss(data_x)$ 

Calculate statistical signifiance of every predictor.

**Parameters** data\_x – a Matrix object used for calculating

**Returns** a Matrix object storing P-values for every predictor

```
train(data set)
```

Train the DBM.

Parameters data\_set - a Data\_set object

train\_with\_monotonic\_constraints (data\_set, monotonic\_constraints)

Train the DBM with monotonic constraints. Negative values indicate a decreasing relationship and positive values indicates an increasing relationship.

#### **Parameters**

- data\_set a Data\_set object
- monotonic\_constraints a Matrix object of the dimension p\*1

## **Delta Boosting Machines with Automatic BL Selection**

```
class dbm_py.interface.AUTO_DBM(params)
```

```
__init__ (params)
```

This is the class of DBM.

Parameters params – a Params object

calibrate\_plot (observation, prediction, resolution, file\_name)

This is exactly the same as the one in GBM in R.

#### **Parameters**

- observation a Matrix object
- prediction a Matrix object
- resolution a scalar
- **file\_name** save the result if provided

**Returns** a Matrix object

interact (data, predictor\_ind, total\_no\_predictor)

This is exactly the same as the one in GBM in R.

#### **Parameters**

- data a Matrix object
- predictor\_ind a Matrix object
- total\_no\_predictor a scalar

Returns a scalar

load(file name)

Load from a file.

Parameters file\_name - a string

pdp (data\_x, feature\_index)

Calculate the data used in partial dependence plots.

#### **Parameters**

• data\_x - a Matrix object used for calculating

• **feature\_index** – the index of the predictor of interest (the No. of the column)

**Returns** a Matrix object storing the data used in partial dependence plots

### predict (data\_x)

Predict if it has been trained or it has been loaded from a trained model.

**Parameters** data\_x – a Matrix object

**Returns** 

save (file\_name)

Save the DBM after trained.

**Parameters** file\_name - a string

save\_performance (file\_name)

Save the training and validating losses.

Parameters file\_name - a string

 $ss(data_x)$ 

Calculate statistical signifiance of every predictor.

**Parameters** data\_x – a Matrix object used for calculating

Returns a Matrix object storing P-values for every predictor

train(data\_set)

Train the DBM.

Parameters data\_set - a Data\_set object

train\_with\_monotonic\_constraints (data\_set, monotonic\_constraints)

Train the DBM with monotonic constraints. Negative values indicate a decreasing relationship, positive values indicates an increasing relationship and zero indicates no constraints.

#### **Parameters**

- data\_set a Data\_set object
- monotonic\_constraints a Matrix object of the dimension p\*1

### **CHAPTER**

## **TWO**

## **FUNCTIONS**

dbm\_py.interface.np2darray\_to\_float\_matrix(source)

Convert a two-dimensional numpy array to a Matrix.

**Parameters** source – a two-dimensional numpy array

**Returns** a Matrix object of the same shape as the numpy array

dbm\_py.interface.float\_matrix\_to\_np2darray(source)

Convert a Matrix to a two-dimensional numpy array.

Parameters source – a Matrix object

**Returns** a two-dimensional numpy array of the same shape as the Matrix

 $\verb|dbm_py.interface.string_to_params| (\textit{string}, \textit{sep='}')$ 

Directly transfer a string to a Params object.

#### **Parameters**

- string a string
- sep a character

Returns a Params object

## **INDEX**

Symbols	M		
init() (dbm_py.interface.AUTO_DBM method), 8	Matrix (class in dbm_py.interface), 3		
init() (dbm_py.interface.DBM method), 6 init() (dbm_py.interface.Data_set method), 4	N		
init() (dbm_py.interface.Matrix method), 3 init() (dbm_py.interface.Params method), 6	np2darray_to_float_matrix() (in module dbm_py.interface), 11		
A	P		
assign() (dbm_py.interface.Matrix method), 3 AUTO_DBM (class in dbm_py.interface), 8	Params (class in dbm_py.interface), 6 pdp() (dbm_py.interface.AUTO_DBM method), 8		
C	pdp() (dbm_py.interface.DBM method), 7 predict() (dbm_py.interface.AUTO_DBM method), 9		
calibrate_plot() (dbm_py.interface.AUTO_DBM method), 8	predict() (dbm_py.interface.DBM method), 7 print_all() (dbm_py.interface.Params method), 6		
calibrate_plot() (dbm_py.interface.DBM method), 7 clear() (dbm_py.interface.Matrix method), 3	S		
D	save() (dbm_py.interface.AUTO_DBM method), 9 save() (dbm_py.interface.DBM method), 7		
Data_set (class in dbm_py.interface), 4 DBM (class in dbm_py.interface), 6	save() (dbm_py.interface.Matrix method), 4 save_performance() (dbm_py.interface.AUTO_DBM		
F	method), 9 save_performance() (dbm_py.interface.DBM method), 7		
float_matrix_to_np2darray() (in module dbm_py.interface), 11	set_params() (dbm_py.interface.Params method), 6 shape() (dbm_py.interface.Matrix method), 4		
from_np2darray() (dbm_py.interface.Matrix method), 3	show() (dbm_py.interface.Matrix method), 4 ss() (dbm_py.interface.AUTO_DBM method), 9		
G	ss() (dbm_py.interface.DBM method), 7		
get() (dbm_py.interface.Matrix method), 3	string_to_params() (in module dbm_py.interface), 11		
get_train_x() (dbm_py.interface.Data_set method), 4 get_train_y() (dbm_py.interface.Data_set method), 4	Т		
get_validate_x() (dbm_py.interface.Data_set method), 4 get_validate_y() (dbm_py.interface.Data_set method), 4	to_np2darray() (dbm_py.interface.Matrix method), 4 train() (dbm_py.interface.AUTO_DBM method), 9 train() (dbm_py.interface.DBM method), 7		
1	train_with_monotonic_constraints()		
interact() (dbm_py.interface.AUTO_DBM method), 8 interact() (dbm_py.interface.DBM method), 7	(dbm_py.interface.AUTO_DBM method),		
1	train_with_monotonic_constraints() (dbm_py.interface.DBM method), 8		
load() (dbm_py.interface.AUTO_DBM method), 8 load() (dbm_py.interface.DBM method), 7			