Chapter 1

Thermoelasticity: Combining the Heat equation and non-linear Solid Mechanics




Figure 1.1 Undeformed configuration of an elastic block.

We consider the uniform steady thermal expansion of an elastic body that is differentially heated. The top surface is heated and the bottom surface is maintained at the reference temperature, which leads to a uniform temperature gradient throughout the material. The material expands more near the upper surface than near the lower surface, deforming the initially rectangular block into an curved configuration.




Figure 1.2 Deformed elastica when the top surface is heated and the lower surface is maintained at the reference temperature. The contours indicate the temperature of the body.

1.1 The driver code

The driver code for this example is given below:

```
//LIC// This file forms part of oomph-lib, the object-oriented,
//LIC// multi-physics finite-element library, available
//LIC// at http://www.oomph-lib.org.
//LIC//
//T.TC//
           Version 1.0; svn revision $LastChangedRevision$
//LIC// $LastChangedDate$
//LIC//
//LIC// Copyright (C) 2006-2016 Matthias Heil and Andrew Hazel
//LIC//
//LIC// This library is free software; you can redistribute it and/or
//LIC// modify it under the terms of the GNU Lesser General Public
//LIC// License as published by the Free Software Foundation; either
//LIC// version 2.1 of the License, or (at your option) any later version.
//LIC//
// {
m LIC} // {
m This} library is distributed in the hope that it will be useful,
//LIC// but WITHOUT ANY WARRANTY; without even the implied warranty of //LIC// MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
//LIC// Lesser General Public License for more details.
//LIC//
//LIC// You should have received a copy of the GNU Lesser General Public
//LIC// License along with this library; if not, write to the Free Software
//LIC// Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA
//LIC// 02110-1301 USA.
//LIC//
//LIC// The authors may be contacted at oomph-lib@maths.man.ac.uk.
//LIC//
//Driver for a multi-physics problem that couples the
//unsteady heat equation to the equations of large-displacement solid
//mechanics
//Oomph-lib headers, we require the generic, unsteady heat
//and and elements.
#include "generic.h"
#include "solid.h"
#include "unsteady_heat.h"
// The mesh is our standard rectangular guadmesh
#include "meshes/rectangular_quadmesh.h
// Use the oomph and std namespaces
using namespace oomph;
using namespace std;
/// A class that solves the equations of steady thermoelasticity by
/// combining the UnsteadyHeat and PVD equations into a single element.
/// A temperature-dependent growth term is added to the PVD equations by
/// overloading the member function get_istotropic_growth()
                   =====class definition==
template<unsigned DIM>
class QThermalPVDElement : public virtual QPVDElement<DIM, 3>,
                            public virtual QUnsteadyHeatElement<DIM, 3>
private:
 /// Pointer to a private data member, the thermal expansion coefficient
 double* Alpha_pt;
 /// The static default value of Alpha
 static double Default_Physical_Constant_Value;
 /// \short Constructor: call the underlying constructors and /// initialise the pointer to Alpha to point
 /// to the default value of 1.0.
 QThermalPVDElement() : QPVDElement<DIM, 3>(),
                         QUnsteadyHeatElement<DIM, 3>()
   Alpha_pt = &Default_Physical_Constant_Value;
 ///short The required number of values stored at the nodes is the sum of the
 ///required values of the two single-physics elements. Note that this step is
 ///generic for any multi-physics element of this type.
```

1.1 The driver code 3

```
unsigned required_nvalue(const unsigned &n) const
{return (QUnsteadyHeatElement<DIM, 3>::required_nvalue(n) +
          QPVDElement<DIM, 3>::required_nvalue(n));}
///Access function for the thermal expansion coefficient (const version)
const double &alpha() const {return *Alpha pt;}
///Access function for the pointer to the thermal expansion coefficientr
double* &alpha_pt() {return Alpha_pt;}
/// Overload the standard output function with the broken default
void output(ostream &outfile) {FiniteElement::output(outfile);}
/// \short Output function:
     Output x, y, u, v, p, theta at Nplot^DIM plot points
// Start of output function
void output (ostream &outfile, const unsigned &nplot)
  //vector of local coordinates
  Vector<double> s(DIM);
  Vector<double> xi(DIM);
  // Tecplot header info
  outfile << this->tecplot_zone_string(nplot);
  // Loop over plot points
  unsigned num_plot_points=this->nplot_points(nplot);
  for (unsigned iplot=0;iplot<num_plot_points;iplot++)</pre>
   {
    // Get local coordinates of plot point
    this->get_s_plot(iplot,nplot,s);
    // Get the Lagrangian coordinate
    this->interpolated_xi(s,xi);
    \ensuremath{//} Output the position of the plot point
    for (unsigned i=0;i<DIM;i++)</pre>
     {outfile << this->interpolated_x(s,i) << " ";}
    // Output the temperature (the advected variable) at the plot point
    outfile << this->interpolated_u_ust_heat(s) << std::endl;</pre>
  outfile << std::endl:
  // Write tecplot footer (e.g. FE connectivity lists)
  this->write_tecplot_zone_footer(outfile,nplot);
 } //End of output function
/// \short C-style output function: Broken default void output(FILE* file_pt)
 {FiniteElement::output(file_pt);}
/// \ short C-style output function: Broken default
void output(FILE* file_pt, const unsigned &n_plot)
{FiniteElement::output(file_pt,n_plot);}
/// \short Output function for an exact solution: Broken default
void output_fct(ostream &outfile, const unsigned &Nplot,
                 FiniteElement::SteadyExactSolutionFctPt
                 exact_soln_pt)
 {FiniteElement::output_fct(outfile,Nplot,exact_soln_pt);}
/// \short Output function for a time-dependent exact solution:
/// Broken default.
void output_fct(ostream &outfile, const unsigned &Nplot,
                 const double& time,
                 FiniteElement::UnsteadvExactSolutionFctPt
                 exact soln pt)
  FiniteElement::
   output_fct(outfile,Nplot,time,exact_soln_pt);
/// \ compute norm of solution: use the version in the unsteady heat
/// class
void compute_norm(double& el_norm)
 QUnsteadyHeatElement<DIM, 3>::compute_norm(el_norm);
/// \short Validate against exact solution at given time
/// Solution is provided via function pointer.
/// Plot at a given number of plot points and compute L2 error
/// and L2 norm of velocity solution over element
/// Call the broken default
void compute error(ostream &outfile,
```

```
FiniteElement::UnsteadyExactSolutionFctPt exact_soln_pt,
                                const double& time,
                                double& error, double& norm)
   {FiniteElement::compute_error(outfile,exact_soln_pt,
                                                  time, error, norm);}
 /// \short Validate against exact solution.
 /// Solution is provided via function pointer.
 /// Plot at a given number of plot points and compute L2 error
 /// and L2 norm of velocity solution over element
 /// Call the broken default
 void compute_error(ostream &outfile,
                                FiniteElement::SteadyExactSolutionFctPt exact_soln_pt,
                                double& error, double& norm)
   {FiniteElement::compute_error(outfile,exact_soln_pt,error,norm);}
 /// \ overload the growth function in the advection-diffusion equations.
 /// to be temperature-dependent.
 void get_isotropic_growth(const unsigned& ipt, const Vector<double> &s,
                                           const Vector<double>& xi, double &gamma) const
   //The growth is the undeformed coefficient plus linear thermal
   //expansion
  gamma = 1.0 + (*Alpha_pt)*this->interpolated_u_ust_heat(s);
 /// \ short Calculate the contribution to the residual vector.
 /// We assume that the vector has been initialised to zero
 /// before this function is called.
 void fill_in_contribution_to_residuals(Vector<double> &residuals)
     //Call the residuals of the advection-diffusion eqautions
    UnsteadyHeatEquations<DIM>::
      fill_in_contribution_to_residuals(residuals);
     //Call the residuals of the Navier-Stokes equations
    PVDEquations<DIM>::
      fill_in_contribution_to_residuals(residuals);
 ///\short Compute the element's residual Vector and the jacobian matrix
 /// We assume that the residuals vector and jacobian matrix have been
 ^{\prime\prime\prime} initialised to zero before calling this function
 \verb|void fill_in_contribution_to_jacobian (Vector < double > \&residuals, | leads to the contribution of th
                                                              DenseMatrix<double> &jacobian)
    //Just call standard finite difference for a SolidFiniteElement so
     //that variations in the nodal positions are taken into account
    {\tt SolidFiniteElement::fill\_in\_contribution\_to\_jacobian(residuals, jacobian);}
};
/// Set the default physical value to be one
//-----
template<>
double QThermalPVDElement<2>::Default_Physical_Constant_Value=1.0;
//=====start_of_namespace===================
/// Namespace for the physical parameters in the problem
namespace Global_Physical_Variables
{
 /// Thermal expansion coefficient
 double Alpha=0.0;
 /// Young's modulus for solid mechanics
 double E = 1.0; // ADJUST
 /// Poisson ratio for solid mechanics
 double Nu = 0.3; // ADJUST
 /// We need a constitutive law for the solid mechanics
 ConstitutiveLaw* Constitutive_law_pt;
} // end of namespace
//===== start_of_problem_class==============
/// 2D Thermoelasticity problem on rectangular domain, discretised
/// with refineable elements. The specific type
/// of element is specified via the template parameter.
template<class ELEMENT>
```

1.1 The driver code 5

```
class ThermalProblem : public Problem
public:
 ///Constructor
ThermalProblem();
 /// Destructor. Empty
 ~ThermalProblem() {}
 /// \short Update the problem specs before solve (empty)
void actions_before_newton_solve() {}
 /// Update the problem after solve (empty)
void actions_after_newton_solve(){}
 /// Actions before adapt: (empty)
void actions_before_adapt(){}
 /// \short Doc the solution.
void doc_solution();
 /// \short Overloaded version of the problem's access function to /// the mesh. Recasts the pointer to the base Mesh object to
 /// the actual mesh type.
 ElasticRectangularQuadMesh<ELEMENT>* mesh_pt()
   return dynamic_cast<ElasticRectangularQuadMesh<ELEMENT>*>(
   Problem::mesh_pt());
private:
 /// DocInfo object
DocInfo Doc_info;
}; // end of problem class
/// \short Constructor for Convection problem
template<class ELEMENT>
ThermalProblem<ELEMENT>::ThermalProblem()
 // Set output directory
Doc_info.set_directory("RESLT");
 // # of elements in x-direction
unsigned n x=8:
 // # of elements in y-direction
unsigned n_y=8;
 // Domain length in x-direction
double 1 x=3.0;
 // Domain length in y-direction
double l_y=1.0;
 // Build a standard rectangular quadmesh
Problem::mesh_pt() =
 new ElasticRectangularQuadMesh<ELEMENT>(n_x,n_y,l_x,l_y);
 // Set the boundary conditions for this problem: All nodes are
 // free by default -- only need to pin the ones that have Dirichlet
 // conditions here
  //The temperature is prescribed on the lower boundary
  unsigned n_boundary_node = mesh_pt()->nboundary_node(0);
  for(unsigned n=0;n<n_boundary_node;n++)</pre>
    //Get the pointer to the node
Node* nod_pt = mesh_pt()->boundary_node_pt(0,n);
    //Pin the temperature at the node
    nod_pt->pin(0);
    //Set the temperature to 0.0 (cooled)
    nod_pt->set_value(0,0.0);
  //The temperature is prescribed on the upper boundary
  n_boundary_node = mesh_pt()->nboundary_node(2);
  for(unsigned n=0;n<n_boundary_node;n++)</pre>
    Node* nod_pt = mesh_pt()->boundary_node_pt(2,n);
    //Pin the temperature at the node
    nod_pt->pin(0);
```

```
//Set the temperature to 1.0 (heated)
   nod_pt->set_value(0,1.0);
 //{
m The\ horizontal	ext{-}position} is fixed on the vertical boundary (symmetry)
 n_boundary_node = mesh_pt()->nboundary_node(1);
  for(unsigned n=0;n<n_boundary_node;n++)</pre>
   \verb|static_cast| < \verb|SolidNode*| (mesh_pt() -> boundary_node_pt(1,n)) -> pin_position(0); \\
 //We need to completely fix the lower-right corner of the block to
  //prevent vertical rigid-body motions
 static_cast<SolidNode*>(mesh_pt()->boundary_node_pt(1,0))->pin_position(1);
// Complete the build of all elements so they are fully functional
// Loop over the elements to set up element-specific
// things that cannot be handled by the (argument-free!) ELEMENT
// constructor.
unsigned n_element = mesh_pt()->nelement();
for(unsigned int i=0;i<n_element;i++)</pre>
   // Upcast from GeneralsedElement to the present element
  ELEMENT *el_pt = dynamic_cast<ELEMENT*>(mesh_pt()->element_pt(i));
   // Set the coefficient of thermal expansion
  el_pt->alpha_pt() = &Global_Physical_Variables::Alpha;
  // Set a constitutive law
  el_pt->constitutive_law_pt() =
   Global_Physical_Variables::Constitutive_law_pt;
// Setup equation numbering scheme
cout <<"Number of equations: " << assign_eqn_numbers() << endl;</pre>
} // end of constructor
/// Doc the solution
//----
template<class ELEMENT>
void ThermalProblem<ELEMENT>::doc_solution()
//Declare an output stream and filename
ofstream some_file;
char filename[100];
// Number of plot points: npts x npts
unsigned npts=5;
// Output solution
sprintf(filename, "%s/soln%i.dat", Doc_info.directory().c_str(),
        Doc_info.number());
some_file.open(filename);
mesh_pt()->output(some_file,npts);
some file.close();
Doc_info.number()++;
} // end of doc
/// Driver code for 2D Thermoelasticity problem
//-----
int main(int argc, char **argv)
// "Big G" Linear constitutive equations:
Global_Physical_Variables::Constitutive_law_pt = new GeneralisedHookean(&Global_Physical_Variables::Nu,
                        &Global_Physical_Variables::E);
//Construct our problem
ThermalProblem<QThermalPVDElement<2> > problem;
//Number of quasi-steady steps
unsigned n_steps = 11;
///If we have additional command line arguemnts, take fewer steps
if(argc > 1) {n_steps = 2;}
for(unsigned i=0;i<n_steps;i++)</pre>
  //Increase the thermal expansion coefficient
```

```
Global_Physical_Variables::Alpha = 0.1*i;
//Perform a single steady newton solve
problem.newton_solve();
//Document the solution
problem.doc_solution();
}
// end of main
```

1.2 Source files for this tutorial

• The source files for this tutorial are located in the directory:

```
demo_drivers/multi_physics/thermo/
```

• The driver code is:

```
demo_drivers/multi_physics/thermo/thermo.cc
```

1.3 PDF file

A pdf version of this document is available.