

Basic System Programming with the IBM Mainframe

Course code ESU03G ERC 1.0



August 2019 edition

Notices

This information was developed for products and services offered in the US.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 United States of America

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

© Copyright International Business Machines Corporation 2019.

This document may not be reproduced in whole or in part without the prior written permission of IBM.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Tradema	ırks		V
Exercise	1. Syste	m Familiarization	. 1-1
	Section 1:	Gathering information and accessing the lab image	1-2
	Section 2:	Exit ISPF	1-8
	Section 3:	Logoff	1-8
Exercise	2 Subm	it a job	2-1
=X010100		Create a data set	
		JCL and viewing help	
		Rename a data set member	
Evercise	3 101 6	xercises	3₋1
LACICISE		Copy a selected member of a PDS	
		Copy an entire data set	
		Copy and replace a selected member	
		Perform a secure compress	
		Compress a data set in place	
		Copy a PDS and a PDSE data set	
		Optional: Copy in-stream data to PS	
		Optional: Print a Sequential data set to SYSOUT	
		Optional: Print a PDS member	
	Section 10): Optional: Create a PDS member	3-8
Exercise	4. Proce	edures	. 4-1
	Section 1:	Override DD-statements of an in-stream procedure	4-2
		Run cataloged procedure	
		Create cataloged procedure	
		Use of DFSORT (ICEMAN)	
	Section 5:	Optional: Create PS from in-stream	4-8
	Section 6:	Optional: Conditional processing	4-9
	Section 7:	Optional: Route a job to INTRDR using IEBGENER	4-9
Exercise	5. z/OS I	Management Facility	. 5-1
		Accessing the z/OS Management Facility	
		z/OSMF interface layout	
		TSO interface	
	Section 4:	Links	5-6
		Setting up a z/OS console	
		Using the z/OS console	
		Entering z/OS commands and interpreting the output	
		Identifying the system configuration	
		The DEVSERV command	
Fyercise	6 ISHFI	LL and hierarchical file system	6-1
		ISHELL introduction	
		Introduction to the file system	
		Customize ISHELL	
		UNIX directory list	
		Optional: Create a hierarchical file system	
	200000000		· ·

Glossarv		X-1	7
	Section 8:	Optional: Introduction to the file system	0
	Section 7:	Optional: Additional UNIX activities	-9
	Section 6:	Optional: Managing files	-7

Trademarks

The reader should recognize that the following terms, which appear in the content of this training document, are official trademarks of IBM or other companies:

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide.

The following are trademarks of International Business Machines Corporation, registered in many jurisdictions worldwide:

Parallel Sysplex™

Hiperspace™ HyperSwap® IBM LinuxONE™ IBM Spectrum Control™ IBM z Systems®

IBM z® IBM z13® IMSTM

MVS™ Notes® Open Class® Operating System/400® OS/390® OS/400®

Parallel Sysplex® Power Architecture® Power Systems™
Power® PowerHA® POWER8®

RACF® Resource Measurement RMF™

Facility™

RS/6000® System p5® System Storage®

 System z10®
 Tivoli®
 VTAM®

 z Systems®
 z/Architecture®
 z/OS®

 z/VM®
 z/VSE®
 zEnterprise®

z10™ z13® z9®

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

UNIX is a registered trademark of The Open Group in the United States and other countries.

VMware is a registered trademark or trademark of VMware, Inc. or its subsidiaries in the United States and/or other jurisdictions.

Other product and service names might be trademarks of IBM or other companies.

Exercise 1. System Familiarization

Estimated time

00:15

Overview

The steps in this exercise are to guide you through accessing the Skytap environment to gain entry into the IBM mainframe system and exit ISPF and logoff TSO. These action items are to be performed on the actual live system.

Objectives

- Access the Skytap environment
- · Access the system image
- · Log on to TSO
- Logoff TSO

References

SC34-4823

Interactive System Productivity Facility (ISPF) User's Guide

Exercise instructions

Preface



Note

The Enter key on your keyboard may/may not be the Enter key.


On some keyboards, the Enter key for VM is the right CTRL key. Take care when entering your password. If you enter the password incorrectly four times, your user ID will be revoked. Contact the Help Desk for support.

Section 1: Gathering information and accessing the lab image

___ 1. Now that you are ready to perform the lab exercises, select the **Launch Lab** button to start.

You will use the IBM Remote Lab Platform (IRLP) to complete your lab session. Instructions: 1. Ensure that you have downloaded the relevant exercise guide. 2. Access the lab by clicking the 'Launch Lab' button below. 3. Log in with your IBM ID ², complete the labs and return to Coursera. Launch Lab

__ 2. Select **Course Lab Kit** on the top left of the screen, by clicking the link (highlighted in red below)



This will provide you with all of the information you will need to progress through this course.

The following is just an example. **Do not** use the information below to record your information. Ensure that you use the information in your **Course Lab Kit**.

Remote Access Information

Example Only

SKYTAP ON SOFTLAYER INFORMATION

Remote access to the lab environment is provided through virtual machine based desktops hosted in the Skytap on Softiayer cloud environment.

The following document is available which provides useful information about interacting with the desktops provided for the class: skytap_on_softlayer_usage_tips.pdf

Please use the credentials below for logging into the desktops. Note if only a student account is provided the same account credentials are usually used by the instructor when logging into their desktop as well.

List of credentials:

Login	Password	PC Image
IBM	Passw0rd\$\$	information
		IIII VI III U II VII

Lab Information

Z SYSTEMS BASIC INFORMATION

This class is hosted by our z Systems environment with a special setup due to the design of the course.

Please reference the lab materials for the steps to access the logon for this special setup environment as it may involve HMC's or PC3270 access, depending on the course code.

SYSTEM INFORMATION

This class is hosted on the following student system(s):

1. MVSCZ01

The Student TSO User IDs and passwords assigned to this class are:

Record your information here for reference:

1. TSOZA01 / B473404B

	,	
a.	a. PC Image Login:	
b.	o. PC Image Password:	
C.	c. System name:	
d.	d. TSO user ID:	
e.	e. TSO password:	
4.	. If the lab image is "suspended" or "powered off", then Click the session image (Click the Play button).	age to activate it.




__ 5. Click the **play button**.




Wait patiently while your image is being created. This may take a while.

6. **Left click** in the middle of the next screen:



The request for the password will now appear.


___ 7. Using the information you recorded in step 3, enter the assigned **password** on the following screen and **press the arrow** to the right of the entry to continue.




___ 8. Once the icons appear on the desktop, using the information you recorded in step 3, **double click the system name**.




__ 9. Using the information you recorded in step 3, enter the assigned **TSO user ID** and press the **Enter Key.**



__ 10. Using the information you recorded in step 3, enter the assigned **TSO password** and press the **Enter Key.**



___ 11. Once you have successfully logged on, the following screen will appear:




___ 12. When three asterisks (***) appear, press the **Enter Key** to continue.

You are now logged on to TSO.

When *** (three asterisks) appear on the screen, press the **Enter Key** to continue.

Section 2: Exit ISPF

- 13. To leave ISPF's Program Development Facility:
 - __ a. You can enter an **X** on the command line or press the **F3 Key**.



You now have ended the ISPF session and returned to the TSO command line mode. Your TSO session is still running.

Section 3: Logoff

14. To terminate your TSO session, enter the TSO command logoff on your terminal.



TSO then replies with a message like **IKJ56470I** *userid* **LOGGED OFF TSO AT 14:40:51 on July 16, 2019** to indicate that your TSO session has been terminated.

End of exercise

Exercise 2. Submit a job

Estimated time

01:00

Overview

This exercise provides an opportunity to allocate a partitioned data set, edit a member and execute an IEBCOPY program.

Objectives

- · Allocate a data set
- · Copy a member
- · Submit a job
- · View the job output

References

GC35-0033 Device Support Facilities User's Guide and Reference

GC28-1758 MVS JCL User's Guide

z/OS Introduction and Workshop Unit Job Control Language (JCL)

http://dtsc.dfw.ibm.com/MVSDS/'HTTPD2.APPS.ZOSCLASS.PDF(Z

CLASS06)'

Exercise instructions

Preface

- All action items followed by a * sign, include exercise hints, which are located at the end of this
 exercise.
- Example solutions for many of the following exercise parts can be found in data set (D80WW.ES10V15.SOLUTION). DO NOT MODIFY this data set. Attempt to resolve any editing and JCL errors using the course materials before referencing data set.

Section 1: Create a data set



Note

Remember not to put single quotation marks around the data set name for batch JCL DD statements.

- __ 1. Access the ISPF Primary Option Menu.
- ___ 2. If needed, allocate a partitioned data set named *userid*.ES10.CNTL with the following characteristics:
 - __ a. One cylinder primary and secondary space
 - b. 10 blocks directory space
 - __ c. Record format fixed blocked
 - __ d. Logical record size 80
 - e. Block size 0



Note

Data set *userid*.**ES10**.**CNTL** may already exist, and can be used as it is with no modifications to its allocation characteristics.

- __ 3. Use option **3.3** to copy member **LAB5#01** from data set **D80ww.ES10V15.CNTL** into data set **userid.ES10.CNTL**.
- 4. Edit member LAB5#01 in data set userid.ES10.CNTL.
- ___ 5. Enter your JOB statement with the following specifications:
 - __ a. Job name is useridA (Yes, your user ID with an A at the end).
 - __ b. Account #: See member JOBCARD in D80ww.ES10V15.CNTL.*
 - c. Programmer's name is your name.
 - __ d. Message class is: See member **JOBCARD** in **D80ww.ES10v15.CNTL**.
 - __ e. Message level is: 1,1.
 - __ f. You are to be informed when the job has completed execution.

h.	Run the job in Class A: See member JOBCARD in D80ww.ES10V15.CNTL . Instead of typing your own job card, why not copy your sample jobcard member
	userid.ES10.CNTL(JOBCARD) and modify it if needed.
	nplete the EXEC statement by calling the program IEBCOPY.
	nplete the DD statements as follows:
a.	SYSUT1 is D80WW.ES10V15.PROC .
	SYSUT2 is a new cataloged data set called userid.ES10.PROC to be allocated with the same characteristics as D80WW.ES10V15.PROC .
8. Sub	omit the job.
9. Vie	w its output with SDSF. Leave the output on the spool. *
Section 2: J	CL and viewing help
These instr	uctions are provided for those who might require additional assistance.
The following	ng is the correct syntax of the JCL for job LAB5#01:
Note: Repla	ace UUUUUUU with your TSO user ID and replace NNNNNNN with your name.
000001	//wwwwwwa job 3ES10G10000012, NNNNNNN', MSGCLASS=Q, MSGLEVEL=(1,1),
000002	// NOTIFY=&SYSUID, CLASS=A, REGION=0M //STEP1 EXEC PGM=IEBCOPY
	//SYSUT1 DD DSN=D80WW.ES10V15.PROC,DISP=SHR //SYSUT2 DD DISP=(,CATLG),DSN=UUUUUUUU ES10.PROC,
	// LIKE=D80WW.ES10V15.PROC //SYSPRINT DD SYSOUT=*
800008	//SYSIN DD DUMMY
How to viev	w the completion status for job LAB5#01 :
	er submitting the job, record the Job number.
10. Alte	s submitting the job, record the Job number.
	IKJ56250I JOB TSOFS21A(JOB01345) SUBMITTED
	*** _
11. Fro	m the ISPF Primary Option Menu, select S (SDSF), and press the Enter key .
12. Fro	m the SDSF Primary Option Menu, select ST (Status of jobs), and press the Enter key .
13. Loc	ate the Job number.

© Copyright IBM Corp. 2019

Note: You might need to press the F8 (Forward) key to advance to the next screen.

__ 14. Enter the letter **S** to the left of the Job ID, press the **Enter key**.

```
SDSF HELD OUTPUT DISPLAY ALL CLASSES LINES 190
                                                              LINE 1-3 (3)
COMMAND INPUT
                                                                      SCROLL ===> CSR
PREFIX=*
          DEST=(ALL)
                        OWNER=*
                                  SYSNAME =
                                    Prty C ODisp Dest
144 Q HOLD LOCA
     JOBNAME
                                                                          REC-Cnt
                                                                                    PAGE
               JobID
                          Owner
     TS0FS21A J0B01343
                         TS0FS21
                                                  LOCAL
                                                                                56
                                                                                67
     TS0FS21A J0B01345 TS0FS21
                                     144 Q HOLD
                                                  LOCAL
                                                                                67
```

___ 15. Using the F8 (Forward) key, ensure that the job completed without any errors.

A RC (Return Code) of **0** is a successful job completion status.

Note: The following output is three pages in length:

```
OUTPUT DISPLAY TSOFS21A JOB01345
                                                                              COLUMNS 02- 81
                                                DSID
                                                            2 LINE 0
                                                                             SCROLL ===> CSR
JES2 JOB
                                                       -- SYSTEM JC02
                                              L O G
                                                                                        -- N O
17.39.09 JOB01345 ---- TUESDAY
                                         23 JUL 2019 ---
                      IRR010I USERID TS0FS21 IS ASSIGNED TO THIS JOB.
ICH70001I TS0FS21 LAST ACCESS AT 17:30:28 ON TUESDAY, JULY 2
$HASP373 TS0FS21A STARTED - INIT 1 - CLASS A - SYS
17.39.09 JOB01345
17.39.09
          J0B01345
17.39.09
          J0B01345
                                                                      ----TIMINGS (MINS.)--
17.39.09
          J0B01345
                      -STEPNAME PROCSTEP
                                                       EXCP
                                                                CONN
                                                  RC
17.39.09 JOB01345
                                                                              TCB
                                                                                          SRB
17.39.09 JOB01345
                      -STEP1
                                                  ΘΘ
                                                                                           . 00
                                                                   10
                                                                               . 00
                      -TSOFS21A ENDED.
                                            NAME-GLADNEY
                                                                             TOTAL TCB CPU TIM
          J0B01345
                      $HASP395 TSOFS21A ENDED - RC=0000
17.39.09 JOB01345
        JES2 JOB STATISTICS
  23 JUL 2019 JOB EXECUTION DATE
             8 CARDS READ
71 SYSOUT PRINT RECORDS
              0 SYSOUT PUNCH RECORDS
         8 SYSOUT SPOOL KBYLES
0.00 MINUTES EXECUTION TIME
1 //TSOFS21A JOB 3ES10G10000012, 'GLADNEY', MSGCLASS=Q, MSGLEVEL=(1,1),
// NOTIFY=&SYSUID, CLASS=A, REGION=0M
/FECAS3I SUBSTITUTION JCL - 3ES10G10000012, 'GLADNEY', MSGCLASS=Q, MSGLEV
              8 SYSOUT SPOOL KBYTES
                         EXEC PGM=IEBCOPY
           //STEP1
         3 //SYSUT1
                         DD
                               DSN=D80WW.ES10V15.PROC,DISP=SHR
           //SYSUT2
                               DISP=(,CATLG),DSN=TS0FS21.ES10.PROC
                         DD
                  F2=SPLIT
  F1=HELP
                                  F3=END
                                                                                  F6=B00K
                                                 F4=RETURN
                                                                 F5=IFIND
  F7=UP
                  F8=DOWN
                                  F9=SWAP NEX F10=LEFT
                                                                F11=RIGHT
                                                                                F12=RETRIEVE
```

```
SDSF OUTPUT DISPLAY TSOFS21A JOB01345
                                                                    3 LINE 8
                                                                                         COLUMNS 02- 81
 COMMAND INPUT ===> __LIKE=DB0WW.ES10V15.PROC
           5 //SYSPRINT DD
             //SYSIN
                             DD
                                    DUMMY
ICH70001I TSOFS21 LAST ACCESS AT 17:30:28 ON TUESDAY, JULY 23
IEFA111I TSOFS21A IS USING THE FOLLOWING JOB RELATED SETTINGS:
SWA=BELOW,TIOT SIZE=32K,DSENQSHR=DISALLOW,GDGBIAS=JOB
IEF236I ALLOC. FOR TSOFS21A STEP1
                                                                            JULY 23, 2019
IGD103I SMS ALLOCATED TO DDNAME SYSUT1
IGD101I SMS ALLOCATED TO DDNAME (SYSUT2 )
                (TSOFS21.ES10.PROC
           STORCLAS (BASE) MGMTCLAS (STANDARD) DATACLAS (
          VOL SER NOS= SMS001
JES2 ALLOCATED TO SYSPRINT
DMY ALLOCATED TO SYSIN
IEF237I
IEF142I
           TSOFS21A STEP1 - STEP WAS EXECUTED - COND CODE 0000
          D80WW.ES10V15.PROC
TS0FS21.ES10.PROC
                                                                                         DDNAME=SYSUT1
IGD104I
                                                                         RETAINED.
                                                                                        DDNAME=SYSUT2
IGD104I
                                                                         RETAINED,
              TS0FS21.TS0FS21A.J0B01345.D0000101.?
          STEP/STEP1 /START 2019204.1739
STEP/STEP1 /STOP 2019204.1739
IEF373I
IEF032I
                     0 HR 00 MIN 00.00 SEC
1188K SYS: 240K EXT:
           CPU:
                                                            SRB:
                                                                         0 HR
                                                                                 00 MIN
                                                                                             00.00 SEC
                                                              280K
                                                                      SYS:
           VIRT:
                                                                                  10852K
           ATB- REAL:
VIRT- ALLOC:
                                                    44K
                                                           SLOTS:
                                                                                                 ΘK
                                           14M SHRD:
            JOB/TSOFS21A/START 2019204.1739
                                      2019204.1739
IEF033I
            JOB/TSOFS21A/STOP
  F1=HELP
                                                        F4=RETURN
                                                                          F5=IFIND
                                                                                             F6=B00K
                    F2=SPLIT
                                       F3=END
  F7=UP
                    F8=DOWN
                                      F9=SWAP NEX F10=LEFT
                                                                         F11=RIGHT
                                                                                           F12=RETRIEVE
```

```
SDSF OUTPUT DISPLAY TSOFS21A JOB01345
                                                        DSID
                                                                      4 LINE 24
                                                                                           COLUMNS 02-
 COMMAND INPUT =
                                                                                          SCROLL ===>
                        0 HR 00 MIN 00.00 SEC
                                                          SRB: 0 HR 00 MIN 00.00 SEC
IEBCOPY MESSAGES AND CONTROL STATEMENTS
           CPU:
                                                        LEVEL UA92265 DATED 20170618 DFSMS 02.0
IEB1135I IEBCOPY
                         FMID HDZ2230
                                             SERVICE
            TS0FS21A
IEB1035I
                          STEP1
                                        17:39:09
                                                    TUE
                          STEP1 17:39:09 TOE 20 GENERATED STATEMENT INDD=SYSUT1, OUTDD=SYSUT2 GENERATED STATEMENT OF PDS INDD=SYSUT1 VOL=SMS001 DSN=TS0FS21.ES10.PROC TO PDS OUTDD=SYSUT2 VOL=SMS001 DSN=TS0FS21.ES10.PROC
STEP1
            COPY
IEB1013I
            COPYING FROM PDS
IEB1014I
IEB167I
           FOLLOWING MEMBER(S) COPIED FROM INPUT DATA SET REFERENCED BY SYSUT1
                       HAS BEEN SUCCESSFULLY COPIED HAS BEEN SUCCESSFULLY COPIED
IEB154I
           COMP
           COMPARE
IEB154I
                                                       COPIED
IEB154I
           COMPO
                        HAS BEEN SUCCESSFULLY
EB154I
           COPY
                        HAS BEEN SUCCESSFULLY COPIED
IEB1098I 4 OF 4 MEMBERS COPIED FROM INPUT DATA SET REFERENCED BY SYSUT1
IEB144I THERE ARE 0 UNUSED TRACKS IN OUTPUT DATA SET REFERENCED BY SYSUT2
IEB149I THERE ARE 0 UNUSED DIRECTORY BLOCKS IN OUTPUT DIRECTORY
IEB147I END OF JOB - 0 WAS HIGHEST SEVERITY CODE
```

Section 3: Rename a data set member

In your data set userid.ES10.CNTL you should have a member called JOBCARD.


- 16. Verify it with ISPF 3.4, then m(ember) list, or with ISPF 1 view, or ISPF 2 edit.
- 17. You task is to rename this member to **JOBC**.

You have many ways to do that:

- You can use ISPF
 - a. option 3.4, 'm' or 'e', then r(ename)
 - b. Or option 3.1
- 2. You can use TSO command 'rename'
 - a. Goto ISPF option 6 and enter command:

```
RENAME 'TSOZAxx.ES10.CNTL(JOBCARD)' 'TSOZAxx.ES10.CNTL(JOBC)'
```

18. Once you have renamed the member, verify with ISPF 3.4 then 'm' or 'e', or with ISPF 1 or with ISPF 2.



```
        Menu
        Functions
        Confirm
        Utilities
        Help

        DSLIST
        TS0FS74.ES10.CNTL
        Row 000000

        Command
        ===>
        Size
        Created
        Changed

        Name
        Prompt
        Size
        Created
        Changed

        JOBC
        9
        2015/12/04
        2019/07/20
        19:3
```

End of exercise

Exercise hints

Section 1: Create a data set

Step 5b:

Step 9:

The completion message will not be sent to the TSO/E session asynchronously; it will be sent with the response to a command input (that is, pressing the Enter key), or, when you log off while the job is running, you will receive the message when you log on again. This is such a small job that you most likely will see the completion message when you press Enter in response to *** to clear the submission message.

Exercise 3. JCL exercises

Estimated time

01:00

Optional sections: 00:45

Overview

This exercise provides an opportunity to code an IEBCOPY job to copy a member from one data set to another. Also, IEBCOPY is used to perform a secure compress of a PDS, which reclaims unused spaces between members. There are optional exercises which include copying in-stream data to a PS, print a sequential data set and a PDS member, and creating an additional PDS member.

Objectives

- · Copy a member of a PDS
- Copy PDS and PDSE
- · Replace a member
- Perform a secure compress
- · Compress a data set in place

References

GC35-0033 Device Support Facilities User's Guide and Reference

GC28-1758 MVS JCL User's Guide

z/OS Introduction and Workshop Unit Job Control Language (JCL)

http://dtsc.dfw.ibm.com/MVSDS/'HTTPD2.APPS.ZOSCLASS.PDF(Z

CLASS06)'

Exercise instructions

Preface

- This exercise depends on the successful completion of the previous exercises.
- The answers to all questions are located at the end of this exercise.
- All action items followed by a * sign, include exercise hints, which are located at the end of this
 exercise.



Important

Section 7: Optional: Copy in-stream data to PS is expected to be successfully completed prior to advancing to the next exercise.

Section 1: Copy a selected member of a PDS

___1. Create member **LAB5#11** in data set *userid*.**ES10**.**CNTL**, and code an IEBCOPY job to copy member **JOBCARD** from data set **D80ww**.**ES10V15**.**CNTL** into data set *userid*.**ES10**.**CNTL**.

Here is a little help. Make sure you specify a disposition of 'share' (DISP=SHR) for the output dataset. Your job should look like the following:



Note

Do not create a job card; TSO creates a default job card for you.

- ___2. Submit the job, by entering 'sub' or 'submit' on the command line
- __ 3. You will be prompted to enter a one character that will be appended as a suffix character to your TSO userid to form your job name (ex: TSOZA059 if you entered **9** and your TSO userid is TSOZA05)

```
IKJ56700A ENTER JOBNAME CHARACTER(S) - 9
IKJ56250I JOB TSOZA059(JOB01360) SUBMITTED ***
```

4.	Check the results of your job using SDSF. *
	In case of errors, remove the cause of error and rerun the job.
5.	Now tailor the copied JOBCARD member so that this job card can be copied into each new JCL member.
	Your JOBCARD should look something like the following:
	//useridA
	//* JOB SUBMITTED FROM userid.ES10.CNTL(LAB5#XX) ***
	//* DOC: WRITE THE PURPOSE OF YOUR JOB RIGHT HERE
	The comment lines shown in the sample above are for documentation purposes so that you will be able to trace from where the JCL was submitted.
6.	Save the changes to the member.
Section 2	2: Copy an entire data set
7.	Create member LAB5#12 in data set userid.ES10.CNTL.
8.	Copy the member JOBCARD into it and create a job step that copies the (input) data set userid.ES10.CNTL into (output) data set userid.COPY.CNTL .
9.	Since the output data set does not exist, allocate it during the copy step. The characteristics are the same as for <code>userid.ES10.CNTL</code> . * (Use the <code>LIKE</code> parameter to allocate the new data set.)
10.	Submit the job.
11.	Check the results of your job. In case of errors, remove the cause of error and rerun the job.
Section 3	3: Copy and replace a selected member
12.	Create member LAB5#13 in data set userid.ES10.CNTL.
13.	Copy the member JOBCARD into it and create a job step that copies member JOBCARD from D80ww.ES10V15.CNTL into data set userid.COPY.CNTL with the REPLACE option of IEBCOPY. *

You may specify a disposition of 'share' (DISP=SHR) or DISP=OLD for the output dataset, because userid.COPY.CNTL is not detained or used by any other process or TSO user session. Your job should look like the following:

- __ 14. Submit the job.
- ___ 15. Check the results of your job. In case of errors, remove the cause of error and rerun the job.
- ___ 16. Remember to replace the existing member. Check this thoroughly.

Section 4: Perform a secure compress

After a PDS has been subjected to a high volume of activity such as replacing members, adding new member and deleting members there may be unusable gaps or spaces between members stored within the PDS. A compress function using IEBCOPY is provided to compress the members and consolidate all the gaps or spaces into a single area within the PDS.



Important

Do not compress a partitioned data set currently being used by more than one user. If you do, the other users will see the data set as damaged, even though it is not. If any of these other users update the partitioned data set after you compress it, then their update will actually damage the partitioned data set.

__ 17. Create member LAB5#14 in data set userid.ES10.CNTL. Copy the member JOBCARD into it and create job steps that do the following: *

Use the first step to allocate a data set named *userid*.COMPRESS.DATA like data set *userid*.COPY.CNTL. The second step should only run when the RC=0 in the previous step. Use the **IF/THEN/ELSE/ENDIF** clause for this purpose.

- ___ 18. Copy the entire data set *userid*.COPY.CNTL into *userid*.COMPRESS.DATA, thus creating a backup of *userid*.COPY.CNTL.
- __ 19. Submit the job.
- __ 20. Check that the above step was successful using the IF/THEN/ELSE/ENDIF clause, and verify with ISPF 3.4 data set list utility, or ISPF 3.2 data set utility that dataset userid.COMPRESS.DATA was actually created.

21. If the above steps were executed with RC=0, go on to LAB 5 #15, else delete userid. COMPRESS. DATA, remove the cause of the error, and rerun the job. *

Section 5: Compress a data set in place

- 22. Create member LAB5#15 in data set userid. ES10.CNTL.
- 23. Copy the member **JOBCARD** into it and create a job step that compresses the data set userid. COPY. CNTL in place.
- 24. Submit the job.



Note

IEBCOPY performs a compress when both the input and output are the same data set on the same volume.

- 25. Delete data set userid.COMPRESS.DATA, but only if previous step was executed with RC=0.
- ___ 26. Check the results of your job and verify with ISPF 3.4 data set list utility, or ISPF 3.2 data set utility that dataset userid. COMPRESS.DATA was actually deleted. In case of errors, remove the cause of error and rerun the job.
- 27. You should see the following message in the job output:

IGD105I TSOZA05.COMPRESS.DATA

DELETED, DDNAME=DD1

Section 6: Copy a PDS and a PDSE data set

_ 28.	First,	, create	data s	et <i>use</i> ı	rid.COP	C.PDS usin	g ISPF	option	3.2 with	the	follow	/ing
	chara	acteristi	cs:									

a. Space: One TRK primary and one TRK secondary allocation

b. DSORG: PDS

__ c. RECFM: FB

__ d. DIR: One directory block

e. LRECL: 80 f. BLKSIZE: 0

29. Second, create data set userid. COPY. PDSE using ISPF option 3.2 with the following characteristics:

__ a. Space: One TRK primary and one TRK secondary allocation

__ b. DSORG: LIBRARY

c. RECFM: FB

__ d. DIR: One directory block

e. LRECL: 80

__ f. BLKSIZE: 0

30. Create member LAB5#16 in data set <i>userid</i> . ES10.CNTL .				
31. Copy the member JOBCARD into it and create a job step that copies data set userid.ES10.CNTL into data set userid.COPY.PDS .				
Important				
Do not submit the job at this time.				
32. Create member LAB5#17 in data set <i>userid</i> . ES10.CNTL .				
33. Copy the member JOBCARD into it and create a job step that copies data set <pre>userid.ES10.CNTL</pre> into data set <pre>userid.COPY.PDSE</pre> .				
34. Save the member and submit both jobs.				
Questions				
Q1: Does member LAB5#16 complete successfully?				
Q2: Does member LAB5#17 complete successfully?				

End of exercise (Optional exercises follow)

Section 7: Optional: Copy in-stream data to PS



Important

The successful completion of this section is required to perform exercise 4, section 3: Create cataloged procedure.

35.	Create member LAB5#21 in data set <i>userid</i> . ES10.CNTL .
36.	Code an IEBGENER job to copy data from in-stream data set to the newly allocated data set userid .GENER.COPY#1.
37.	The characteristics for the new data set are as follows:
_ _ _ _	c. RECFM: FB
38.	The in-stream data could be like the following:
	TEST TEST TEST TEST TEST TEST TEST TEST
39.	After submitting the job, check the results of the job. Using ISPF 3.4 or ISPF 2 verify that dataset TSOZA05.GENER.COPY#1 has actually been created and that it contains the above data records. In the case of an error, fix the error(s), and rerun the job.
40.	Create member LAB5#22 in data set userid.ES10.CNTL.
41.	Copy the member JOBCARD into it and create a job step that copies the (input) data set <code>userid.GENER.COPY#1</code> into data set <code>userid.GENER.COPY#2</code> .
42.	Since the output data set does not yet exist, allocate it during the COPY step. The characteristics are the same as for <code>userid.GENER.COPY#1</code> . (Use the <code>LIKE</code> parameter to copy it.)
43.	After submitting the job, check the results of the job. Using ISPF 3.4 or ISPF 2 verify that dataset TSOZA05.GENER.COPY#2 has actually been created and that it is an exact copy of the contents of TSOZA05.GENER.COPY#1. In the case of an error, fix the error(s) and rerun the job

Section 8: Optional: Print a Sequential data set to SYSOUT

___ 44. Create member LAB5#23 in data set userid.ES10.CNTL.

45. C	opy the member	JOBCARD into it and create a job step t	hat does the following:
a.	Print data set <i>u</i>	userid.GENER.COPY#1 to a SYSOUT	dataset.
b.	TSOZA05.GEN	g the job, check the results of the job. Ve NER.COPY#1 has actually been copied in set. In the case of an error, fix the error(s	n the job's sysprint, as a
Section 9:	Optional: Pr	rint a PDS member	
46. C	reate member L	AB5#24 in data set userid.ES20.CNTI	ն .
	• •	JOBCARD into it and create a job step tserid.Es10.CNTL to SYSOUT=*.	hat prints the member
	fter submitting the	e job, check the results of the job. In the	case of an error, fix the error(s)
Section 10	:Optional: C	reate a PDS member	
49. C	reate member L A	\B5#25 in data set <i>userid</i> .ES10.CNTI	ப்.
	opy the member ata set <i>userid</i> .0	JOBCARD into it and create a job step t	hat creates member TEST into
The cont	ents of the memb	er TEST should look like:	
		TEST TEST TEST TEST TEST TEST TEST TEST	AA AAAA BB BBBB
m	ember TEST has	e job, check the results of the job. Using actually been created in data set userids) and rerun the job.	•
(Command ===>)5.COPY.CNTL(TEST) ***********************************	Line 000000
		rest test test test test test test	
		AAAA AAAA AAAA AAAA AAAA AAAA	
B	BBB BBBB BBBB I	BBBB BBBB BBBB BBBB BBBB BBBB	BBBB

End of optional exercises

© Copyright IBM Corp. 2019

****** Bottom of Data *********

Exercise answers

Section 6: Copy a PDS and a PDSE data set

Q1: Does member LAB5#16 complete successfully?

A1: No. Member LAB5#16 fails (or ABENDS) due to running out of directory space. This PDS was allocated with only one directory block.

Q2: Does member LAB5#17 complete successfully?

A2: Yes. LAB5#17 completed successfully because the output data set is a PDSE, and a PDSE dynamically creates more directory space as needed.

Exercise hints

Section 1: Copy a selected member of a PDS

Step 1: Make sure you specify a disposition of 'share' (DISP=SHR) for the output dataset.

Step 2: Ensure you complete the MSGCLASS in the example JOBCARD.

Section 2: Copy an entire data set

Step 7: Do not forget to code the LIKE and DISP parameters for the new data set name on the DD statement.

Section 3: Copy and replace a select member

Step 11: Do not forget to use correct format and positional characters of the selected member keyword.

Section 4: Perform a secure compress

Step 15: The first step should execute the IEFBR14 program.

Step 18: The IF statement should include RC not equal to 0 for both the IEFBR14 and IEBCOPY steps. To delete the userid.COMPRESS.DATA data set, execute the IEFBR14 program and include a DD statement with DISP=(OLD,DELETE).

Exercise 4. Procedures

Estimated time

00:30

Optional sections: 00:30

Overview

This exercise provides an opportunity modify JCL to override DD statements on an in-stream procedure. You will create and run cataloged procedures in a PDS. Using both DFSORT and IEBGENER, you will learn how to copy data sets. There are optional exercises, which provide the ability to invoke conditional processing and using IEBGENER to route a job to INTRDR, which defines a logical device for jobs entering the system through the internal reader facility.

Objectives

- Override DD statements
- · Create and run cataloged procedures
- Use DFSORT
- Use IEBGENER

References

GC35-0033	Device Support Facilities User's Guide and Reference
SC26-7527	DFSORT Getting Started
SG23-6878	DFSORT Application Programming Guide
GC28-1758	MVS JCL User's Guide

Exercise instructions

Preface

- This exercise depends on the successful completion of the previous exercises.
- All action items followed by a * sign, include exercise hints, which are located at the end of this
 exercise.

Section 1: Override DD-statements of an in-stream procedure

__ 1. Create member **LAB5#31** in data set **userid.ES10.CNTL** and copy the same member from data set **D80ww.ES10V15.CNTL** into it. It looks like:

```
//userid1 JOB (ACCOUNT), 'userid', MSGCLASS=X, MSGLEVEL=(1,1),
       NOTIFY=userid, CLASS=A, REGION=2M
//*********************
    JOB SUBMITTED FROM userid.ES10.CNTL(LAB5#31)
    DOC: Override DD-Statements on an Instream Procedure
//***********************
//COMP
       PROC
//***************
//***** MAKE BACKUP
//***************
//s1
   EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DISP=SHR, DSN=userid.ES10.CNTL
//SYSUT2 DD DISP=(,CATLG),DSN=userid.ES10.BACK,
//
    LIKE=userid.ES10.CNTL
//SYSIN DD
          DUMMY
//IFOK1 IF (S1.RC=0) THEN
//****************
//***** COMPRESS DATA SET
//*****************
//s2
       EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DISP=SHR, DSN=userid.ES10.CNTL
//SYSUT2 DD DISP=OLD, DSN=userid.ES10.CNTL
//SYSIN DD DUMMY
//IFOKEND1 ENDIF
//IFOK2
       IF
          (S2.RC=0) THEN
//***************
//***** COMPRESS SUCCESSFUL, DELETE BACKUP
//***************
//s3
       EXEC PGM=IEFBR14
       DD DISP=(OLD, DELETE), DSN=userid.ES10.BACK
//IFOKEND2 ENDIF
//
      PEND
//FINAL EXEC COMP
```

As you can see, this job has an in-stream procedure that makes a secure compress of data set *userid*.ES10.CNTL.

___ 2. Your task is now to execute the job so that the data set *userid*.COPY.CNTL will be compressed during the job's execution. *



Note

Do not change the in-stream procedure. Perform this task by overriding DD statements.

Section 2: Run cataloged procedure

<u>Note</u>: a cataloged procedure is a pre-written segment of code (which is stored as a member of PDS), which can be used as many times as needed in any job in the system. IBM supplies many utility programs to create catalog procedures in batch, one of them being IEBUPDTE to create source data records in a PDS member. This program places cataloged procedures into partitioned data sets. These procedures are typically placed inside a system library called **SYS1.PROCLIB**.

- __ 3. Create member **LAB5#32** in data set *userid*.**ES10**.**CNTL**, and copy member **JOBCARD** into it.
- ___ 4. Create a job step that runs a cataloged procedure stored in D80ww.ES10v15.PROC (COMP).

The procedure looks like:

```
PROC INDS=FORGOTTEN, BACK=FORGOTTEN
//*********************
   DOC: COMPRESS DATA SETS SPECIFIED WITH VARIABLES.
//*********************
//***************
//*****
        MAKE BACKUP
//**************
//S1
      EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DISP=SHR, DSN=&INDS.
//SYSUT2 DD DISP=(,CATLG),DSN=&BACK.,
//
     LIKE=&INDS
//SYSIN DD DUMMY
//IFOK1
      IF
          (S1.RC=0) THEN
//***************
//****** COMPRESS DATA SET
//***************
//s2
      EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DISP=SHR, DSN=&INDS.
//SYSUT2 DD DISP=OLD, DSN=&INDS.
//SYSIN DD DUMMY
//IFOKEND1 ENDIF
//IFOK2
      IF
         (S2,RC=0) THEN
//****************
//****** COMPRESS SUCCESSFUL, DELETE BACKUP
//***************
//s3
      EXEC PGM=IEFBR14
//DD1
      DD
         DISP=(OLD, DELETE), DSN=&BACK.
//IFOKEND2 ENDIF
```

As you can see, there are two variables needed to run this procedure without problems. Furthermore, you see that this is also a secure compress like the one you had as an in-stream procedure.

___ 5. Run this procedure to compress data set *userid*.ES10.CNTL and define *userid*.ES10.BACK as the backup of the secure compress.

Section 3: Create cataloged procedure



Important

This section is dependent on the successful completion of exercise 3, section 7: Optional: Copy in-stream data to PS.

During this exercise, you will code a cataloged procedure in your own data set and test it. It allows you to copy any kind of PDS or sequential data set to another PDS or PS data set.


- ___ 6. In exercise 2, Submit a job, Section 1 Create a data set, step 7, you should have allocated a PDS named userid.ES10.PROC with the same attributes as data set D80ww.ES10v15.PROC and you have copied some sample procedure members, including a PROC member named COPY.
- __ 7. Verify and validate member COPY (browse, view, edit) in your own PDS named userid.ES10.PROC, which holds the cataloged procedure. The procedure should do the following:

```
TSOZA05.ES10.PROC(COPY) - 01.01 Line 000000000 Col
BROWSE
                                                    Scroll ==
Command ===>
//COPY
       PROC PROG=IEBCOPY, DISPI=, INDS=, DISPO=, OUTDS=, LIKEDS=
//S1
        EXEC PGM=&PROG
//SYSUT1 DD DISP=&DISPI,DSN=&INDS
//SYSUT2 DD DISP=&DISPO, DSN=&OUTDS,
       LIKE=&LIKEDS.
//SYSPRINT DD SYSOUT=*
//SYSIN
         DD DUMMY
__ a. Depending on the input variable, it calls IEBCOPY or IEBGENER. Name the variable
```

- __ a. Depending on the input variable, it calls IEBCOPY or IEBGENER. Name the variable PROG. The default for this variable is IEBCOPY.
- __ b. The disposition of DD-statements SYSUT1 and SYSUT2 is defined as JCL symbols. Name the symbols DISPI for input and DISPO for output.
- __ c. The data set names should be variable so that they can vary from procedure call to procedure call. Name their JCL symbols INDS and OUTDS.
- _ d. The data set defined for SYSUT2 might be new. If this is the case, allocate it like the input data set. Use the JCL symbol &LIKEDS to do this.
- __ e. Do not specify any default values for the symbols except for PROG.
- ___ 8. Once you have validated your own cataloged procedure, test it.
 - __ a. Create member LAB5#33 in data set *userid*.Es10.CNTL and copy member JOBCARD into it.
 - b. Create job steps that call the new cataloged procedure to copy:
 - i. PDS Data set userid.ES10.CNTL to the new data set userid.ES10.XXXX.
 - ii. Sequential Data set *userid*.GENER.COPY#1 to the new data set *userid*.ES10.YYYY.
 - __ c. Verify with SDSF that your job has executed successfully, and with ISPF 3.4 that both PDS Data set userid.ES10.XXXX and sequential Data set userid.ES10.YYYY have been created and populated from their respective input dataset.
 - __ d. If the job fails, remove the cause of error and rerun the job.

Section 4: Use of DFSORT (ICEMAN)

ICEMAN is the program name for DFSORT. You can invoke DFSORT with PGM=ICEMAN. DFSORT is also shipped with an alias of SORT, so you can use PGM=SORT.



- Create member LAB5#34 in data set userid.ES10.CNTL.
- ___ 10. Copy member **JOBCARD** into it and create a job step that copies member SORTTEST from data set **D80ww.ES10V15.CNTL** into your **CNTL** data set using the 'SELECT MEMBER=(xxx)' function of IEBCOPY.
- ___ 11. Now create a job step that calls program ICEMAN which is the sort program DFSORT.

This program needs the following DD statements:

```
SYSOUT DD SYSOUT=

SORTIN DD DISP=...,DSN=....

SORTOUT DD DISP=...,DSN=....

SYSIN DD *
```

12. There are many input control statements, but you will need only the following ones: *

```
SORT FIELDS=(....)
OPTION SKIPREC=...
```

___ 13. Now that you have enough familiarity to create this sort step, do the following:

Sort member **SORTTEST** that you have copied in the previous step into dataset **userid.ES10.CNTL** and write the results to **userid.ES10.CNTL** (SORTOUT1).

- __ 14. Skip the first record.
- 15. Sort by the number of years in the company (columns 1-3).
 - __ a. Data type is character (сн)
 - __ b. Descending order (D)

As the second sort criteria:

- 16. Sort the records by employee name, starting in column 4 until column 16.
 - __ a. Data type: character (сн)
 - b. Ascending order (A)
- 17. Check the results of your job and edit member **SORTOUT1** for the sorted output. *
- 18. In case of errors, remove the cause of errors and rerun the job.

End of exercise (Optional exercises follow)

Section 5: Optional: Create PS from in-stream

19. Cı	reate member LAB5#41 in data set <i>userid</i> .ES10.CNTL.
 ne	opy the member JOBCARD into it and create a job step that copies in-stream data to a ew Physical Sequential (PS) data set with name <code>userid.ES10.INPUT</code> and the following paracteristics:
a. b.	Space: 1 track primary, no secondary allocation RECFM: FB
c.	LRECL: 80
d.	BLKSIZE: 0

___ 21. Copy the in-stream data from member **INSTREAM** in data set **D80ww.ES10v15.CNTL**. The in-stream data looks like this:

TEST1
TEST2
TEST3
TEST4
TEST5
TEST6
TEST7
TEST8
TEST9
TEST10
TEST11
TEST12
TEST13
TEST14
TEST15

22. Use the //SYSUT1 DD DATA, DLM=\$\$.... statement to define the input string.

```
EXEC PGM=IEBGENER
//SYSUT1 DD DATA, DLM=$$
TEST1
TEST2
TEST3
TEST4
TEST5
TEST6
TEST7
TEST8
TEST9
TEST10
TEST11
TEST12
TEST13
TEST14
TEST15
TEST16
//SYSUT2 DD DISP=(,CATLG),DSN=TSOZXXX.ES10.INPUT,
// SPACE=(TRK, (1,0)), RECFM=FB, LRECL=80, BLKSIZE=0
//SYSPRINT DD SYSOUT=*
//SYSIN DD DUMMY
```

__ 23. Check the results of your job. Verify with ISPF 3.4 that dataset TSOZXXX.ES10.INPUT has been created and populated with the above instream data records. In case of error, remove the cause and rerun the job.

Section 6: Optional: Conditional processing

- 24. Create member LAB5#42 in data set userid. ES10.CNTL.
- 25. Copy the member **JOBCARD** into it and create job steps that perform the following:
- ___ 26. Using **IEBGENER**, create a member named **TEXT1** in the new data set **userid.ES10.DATA** and copy in-stream data into it. The data should look like:

- ___ 27. The data set *userid*.ES10.DATA must have the same characteristics as *userid*.ES10.CNTL.
- ___ 28. If the first step returns RC=0, copy member **TEXT1** to a new PS data set named userid.ES10.OUT.
 - __ a. One track primary, one track secondary
 - __ b. Fixed blocked
 - __ c. Record length 80
 - __ d. Best block size
- ___ 29. If the second step returns with RC=0, then print data set *userid.*ES10.OUT to SYSOUT=* using IEBGENER.
- __ 30. If the third step ends with RC=0, delete data set userid.ES10.OUT using IEFBR14.
- __ 31. For all conditional JCL, use the IF/THEN/ELSE clause.
- ___ 32. Check the results of your job. In case of error, remove the cause of the error and rerun the job.

Section 7: Optional: Route a job to INTRDR using IEBGENER

__ 33. First, copy member **LAB5#43** from data set **D80ww.ES10V15.CNTL** and tailor it to your needs. It should look like:



- 34. Second, create member **LAB5#44** in data set *userid*.**ES10.CNTL**.
- __ 35. Copy member **JOBCARD** into it and create a job step that performs the following:

36. With the in-stream procedure PROC32 , execute IEBGENER to route a job from any input data set to SYSOUT=.
37. To define the input data set, use the symbol &DS, and for the SYSOUT= value, use &OUT.
38. Run the in-stream procedure with the values:
DS= userid.ES10.CNTL(LAB5#43),OUT=(,INTRDR)
39. Submit your LAB5#44 job, this will in turn submit another job LAB5#43.
40. So you should see two jobs being submittted:
a. the one you just submited with your submit command in LAB5#44, and
b. the job submited to the internal reader LAB5#43.
14.54.04 JOB01386 \$HASP165 TSOZA054 ENDED AT MVSCZ01 MAXCC=0000 CN(INTERNAL) 14.54.04 JOB01387 \$HASP165 TSOZA053 ENDED AT MVSCZ01 MAXCC=0000 CN(INTERNAL) ***
41. Check the results of your jobs. In case of errors, remove the cause of error and rerun the

End of optional exercises

Exercise hints

Section 2: Override DD-statements of an in-stream procedure

Step 2:

```
//FINAL EXEC COMP

//S1.SYSUT1 DD DISP=SHR, DSN=TSOZA60.COPY.CNTL

//S1.SYSUT2 DD DISP=(,CATLG), DSN=TSOZA60.ES10.BACK,

// LIKE=TSOZA60.COPY.CNTL

//S2.SYSUT1 DD DISP=SHR, DSN=TSOZA60.COPY.CNTL

//S2.SYSUT2 DD DISP=OLD, DSN=TSOZA60.COPY.CNTL
```

Section 4: Use of DFSORT (ICEMAN)

Step 12: FIELDS=(start column, column count, data type, sort order, next field) SKIPREC=(amount of records to be skipped)

Step 17: JCL:

```
000001 //TSOFSXX4 JOB 3ES10G10000012,'TSOFSXX',MSGCLASS=Q,MSGLEVEL=(1,1),
000002 // NOTIFY=TSOFSXX,CLASS=A,REGION=2M
000003 //COPY EXEC PGM=IBBCOPY
000004 //SYSPRINT DD SYSOUT=*
000005 //IN1 DD DISP=SHR,DSN=DB0WW.ES10V12.CNTL
000006 //OUT1 DD DISP=OLD,DSN=TSOFSXX.ES10.CNTL
000007 //SYSIN DD *
000008 COPY OUTDD=OUT1,INDD=IN1
000009 SELECT MEMBER=(SORTTEST)
000010 //SORT EXEC PGM=ICEMAN
000011 //SYSOUT DD SYSOUT=*
000012 //SORTIN DD DISP=SHR,DSN=TSOFSXX.ES10.CNTL(SORTTEST)
000013 //SORTOUT DD DISP=SHR,DSN=TSOFSXX.ES10.CNTL(SORTOUT1)
000014 //SYSIN DD *
000015 SORT FIELDS=(1,3,CH,D,4,12,CH,A)
000016 OPTION SKIPREC=1
```

Exercise 5. z/OS Management Facility

Estimated time

00:30

Overview:

The IBM z/OS Management Facility (z/OSMF) is a z/OS component that simplifies, optimizes, and modernizes the z/OS system programmer experience.

In this exercise, you will see how z/OSMF delivers solutions in a task-oriented, web browser-based user interface with integrated user assistance. Its focus is to improve system programmer productivity, and make the z/OS functions easier to understand and use.

Objectives:

- Logon and access z/OSMF
- Explore the layout of z/OSMF
- Access TSO
- · Access web links
- · Access z/OS consoles
- Enter and decipher z/OS commands
- Enter z/OS commands to decipher the system configuration

References

SA27-8419 IBM z/OS Management Facility Configuration Guide V2R3

SG24-7851 z/OS Management Facility V2R3 Redbook

SA38-0666 z/OS MVS System Commands V2R3

z/OSMF Knowledge Center:

https://www.ibm.com/support/knowledgecenter/SSLTBW 2.3.0/com.ibm.zos.v2r3.izu/izu.htm

Exercise instructions


Prefix

- The answers to all questions are located at the end of this exercise.
- All action items followed by a * sign, include exercise hints, which are located at the end of this
 exercise.
- IMPORTANT: You MUST log-off TSO BEFORE starting this exercise!

Section 1: Accessing the z/OS Management Facility

Accessing z/OSMF is done through a Skytap session and through a browser URL.

- 1. Ensure that you have a Skytap connection.
- 2. Double click the **FIREFOX** icon.



Access the following URL for z/OSMF:


https://mvsczxx.ilsvpn.ibm.com/zosmf where mvsczxx is the system name that has been assigned to you in your course lab kit. (it can be MVSCZ01 MVSCZ02...refer to exercise 1 how to access your course lab kit).




Important

If you receive a message indicating "Your connection is not secure", select **Advanced** and add an exception to allow access.

4. On the IBM z/OS Management Facility window, enter your **TSO user ID** and **password**.




After logging in to IBM z/OS Management Facility, you will see the Welcome screen:



Section 2: z/OSMF interface layout

z/OSMF provides a visual framework surrounding a work area where various pages are displayed. This framework provides the basis for a common look-and-feel and serves as the launch point for the tasks that you can perform.

- __ 5. Select **Getting started with z/OSMF** in the middle of the screen.
- 6. Select and open the twistie for **Getting started with z/OSMF** in the navigation pane.
- ___ 7. Select and open the twistie for **Understanding the z/OSMF interface layout** in the navigation pane.
- __ 8. Select z/OSMF interface layout.
- 9. Familiarize yourself with the layout.



- __ 10. Scroll down to scan through the descriptions of each area.
 - 11. In the navigation pane, click **Welcome** to open its contents.
- 12. Select z/OSMF tasks at a glance.



Questions

Q1: How can you determine if a task on the list is new for the current release?

- ___ 13. Scroll through the tasks which are shipped with z/OSMF.
- 14. Collapse all expanded items in the navigation bar.

Section 3: TSO interface

The ISPF option in the navigation area starts a full-functional ISPF interface to z/OS that is almost identical to that used via a 3270 terminal emulator. The user will have to log on with a user ID that has access to TSO/E.

- ___ 15. Select the twistie to the left of **z/OS Classic Interfaces**.
- 16. Select **ISPF** by clicking it.




Note

To see the ISPF screen to allocate a new data set, you may have to click the 'close all' link to suppress all messages and make space on the screen.

- ___ 17. As you can see, this is the ISPF Primary Option Menu screen.
- 18. You may need to use the slider bar to scroll up and down to view all of the options.



- ___ 19. Allocate a Partitioned Data Set Extended (PDSE) named *userid*.**ES10.ZOSMF** (where *userid* is the user ID you used to log on to TSO with) according to the following specifications: *
 - __ a. Ten blocks primary space (Primary quantity)
 - b. Five block secondary space (Secondary quantity)
 - __ c. Directory size five blocks (Directory blocks)
 - __ d. Fixed length records (Record format = F)
 - e. Record length 80 bytes (Record length)
- 20. Press the **Enter key** to allocate the data set.



As you can see, z/OSMF can also be used to allocate data sets.

___ 21. To verify whether the data set has been allocated properly, use the Data Set information panel.

Section 4: Links

The z/OSMF provides features to customize the screen by adding links to web sites and other tailored external applications.

When you are performing system management tasks with z/OSMF, you might find it helpful to refer to other tools and information on the web. The z/OSMF navigation area comes supplied with several useful links in the Links category.

Installations can customize the z/OSMF navigation area with its own links, as needed. Links can be added to the Links category or to any other category in the z/OSMF navigation area.

When a link is selected, the link launches in either a separate browser window or tab, or as a tab in the z/OSMF work area. This launch behavior is specified when the link is defined to z/OSMF.

22. Select the twistie to the left of **Links** in the navigation pane.



_ 23. Take a few minutes to explore the various links that are configured for this z/OSMF.



Note

Observe that when you select a link, it opens in another browser. *

- 24. When you are finished, close all open browser sessions except the main z/OSMF screen.
- ___ 25. Collapse the twistie to the left of **Links** by selecting it.

Section 5: Setting up a z/OS console

The z/OSMF z/OS Operator Consoles task provides function to work with z/OS consoles. This provides the ability to issue system commands and view system messages.

- ___ 26. Select the twistie to the left of **Consoles** in the navigation pane.
- 27. Select z/OS Operator Consoles.
- ___ 28. Select the **PLEX1** console. It should normally show 'setup complete', so you can skip to Section 6.



29. If you see 'setup required', click 'actions', then click 'complete setup'




- CHECK THE FOLLOWING:
- __ a. In the EMCS Console Name field, enter **IZTSOxxx** (Where **xxx** is the last three characters of your user ID, i.e **IZTSOA05** for userid **TSOZA05**).
- b. Select and click button Complete Setup.



Section 6: Using the z/OS console

- ___ 30. To start the console session, select the **Actions** pull-down. Ensure that your console has a checkmark besides it.
- 31. Select Start console.



__ 32. Select your console to open the session:



Section 7: Entering z/OS commands and interpreting the output

All z/OS commands are entered in the Command area at the bottom of the screen.






Note

z/OS commands are not case sensitive. They are displayed in upper case for ease of reading.

Use the DISPLAY system command to display information about the operating system, the jobs and application programs that are running, the processor, devices that are on-line and off-line, central storage, workload management service policy status, and the time of day.

__ 33. On the command line, enter: **D** A

An example of the **D A** command is displayed below:



When entering z/OS commands, the output is displayed with a message number.

The IBM Z: Look@ Knowledge Center is a site used for Message Lookup Facility.

_ 34. Open a new browser and access the following website:

https://www-304.ibm.com/servers/resourcelink/svc00100.nsf/pages/lookatkc?OpenDocument



5

Questions

Q2: What is the z/OS message ID?

- __ 35. Enter the **message ID** for the D A command in the IBM Z: Look@ Knowledge Center field and select **Go**.
- __ 36. Click the message ID to expand its contents:

+ CNZ4105I

___ 37. Review the information for the **D A** command and answer the following questions:



Questions

Q3: Which field in the command output identifies the number of address spaces running under initiators?

Q4: What is the correct syntax of the z/OS command to display a list of all active TSO/E users?

Q5: Which column field displays the status of the job? _____*

Every z/OS message ID contains message codes. The last letter at the end of the message ID identifies the type of message.

А	Immediate action	System operator action is required immediately. The associated task does not continue until the requested action has been taken.
D	Immediate decision	System operator decision or action is required immediately. The operator is requested to select from specific options, such as retry or cancel . The associated task does not continue until the requested decision has been made or action has been taken.
E	Eventual action	System operator action will be required; however, the associated task continues independently of system operator action.
I	Information only	No operator action is required.



Questions

Q6: What type of z/OS message is: IEE234I?	*
**	

Even though the above z/OS message ID is a system failure, there is no action to be taken.

__ 38. Enter: **D U**,**DASD**,**ONLINE**

The UNIT is the Device Number.

A Device number is any 4 digit hexadecimal numbers assigned to a device for communication purposes.



Questions

Q7: The STATUS field indicates the status of the device.

What does the following status' indicate?

S:	
A:	
O:	_
Q8: Which device contains the IPL Bootstrap?	

Section 8: Identifying the system configuration

~~	^ ' ' ' '					
	Select a device	number from	the authorit	of the	nravialie	command
JJ.	Ocicul a device	HUHIDEI HUHI	uic outbut	OI LIIC	DIEVIOUS	communana.

___ 40. Enter: **D M=DEV(xxxx)**

The following command was entered for device number 0502:

```
D M=DEV(502)
Sep 13 19:47:32 CZ01 IEE174I 19.47.32 DISPLAY M 061
                        DEVICE 00502 STATUS=ONLINE
                        CHP
                                                             B0
                                                      5C
                                           5C 5E
84 B4
Y Y
                        ENTRY LINK ADDRESS
                                                             5E
                        DEST LINK ADDRESS
                        PATH ONLINE
                                                        Y
                        CHP PHYSICALLY ONLINE Y Y
                        PATH OPERATIONAL Y
                                                   Y
                                                        Y
                                                             Y
                                              N
                        MANAGED
                                                  N
                                                        N
                                      6100 6100 6100 6100
0300 0330 0100 0130
                        CU NUMBER
                        INTERFACE ID
                        MAXIMUM MANAGED CHPID(S) ALLOWED: 0
                        DESTINATION CU LOGICAL ADDRESS = 01
                                      = 002107.900.IBM.75.0000000WY211.0300
                        SCP CU ND
                        SCP TOKEN NED
                                         = 002107.900.IBM.75.0000000WY211.0100
                        SCP DEVICE NED = 002107.900.IBM.75.0000000WY211.015B
                                         = 500507630BFFC34E
                        FUNCTIONS ENABLED = MIDAW
```

There is a possibility that the system configuration could change. If this occurs, then the output data from your command could differ from the one displayed above.


41. If your output does not reflect the correct data as the one above, use the above example to answer the following questions:



Questions

Q9: What CHPID numbers are defined to access device 0502?
Q10: What are the entry ports into a FICON switch for each CHPID?
Q11: What are exit ports from the FICON switch for each CHPID?

42. Using the above information, complete the following diagram, filling in the CHPID number, entry and exit ports. *



This is a good example on how informative z/OS commands can be.

Notice that the range of DASD devices are device number 0500 up to device number 050F.

This range of device addresses indicates that there are 16 devices.

Hexadecimal (also base 16, or hex) is a positional numeral system with a base of 16. It uses sixteen distinct symbols, most often the symbols 0–9 to represent values zero to nine, and A–F to represent values ten to fifteen.

Example:


0123456789ABCDEF

So, 0500 through 050F is 16 DASD devices.

But, how did we figure out there were 16 DASD device addresses? Not from the D M=DEV(xxxx) command.

___ 43. Enter: **D M=CHP(cc)**, where cc is any CHPID from the diagram.

___ 44. If your output does not reflect the correct data as the one above, use the above example to answer the following questions:



Section 9: The DEVSERV command

The DEVSERV PATHS command can help you solve hardware or configuration problems. The display includes the status of paths, the channel path ids, the logical mode of devices, the number of data sets allocated on volumes, and volume serial labels. Because the DEVSERV command causes the system to issue an I/O request on paths to a device or devices, the resulting display reflects the current physical state of the path.

The DEVSERV PATHS command only supports DASD or Tape devices.

_ 45.	From the	previous	command,	select a	DASD	device	number	other th	an the	SYS	RES
	device.										

46. Enter: DS P,xxxx,1	(Where xxxx is the device number	you selected).
-------------------------------	----------------------------------	----------------

The number 1 indicates that you only want to issue the DEVSERV command to one device.



Questions

Q15: What is the syntax of the DEVSERV command for eight devices?

- 47. Issue the DEVSERV command to eight devices.
- 48. Take some time to decipher the output.
- 49. If you would like to experiment with other z/OS commands, please feel free to do so at this time.
- __ 50. After experimenting with other commands, display the allocation attributes for data set **userid.ES10.ZOSMF** using the ISPF Classic interface tab of z/OSMF.



Important

Now first perform a logoff from the ISPF classic application, otherwise you will retain an ENQ on ISPPROF, and you will no longer be able to logon to TSO in the next exercise!

__ 51. You can enter '=xall' on all ISPF active screens, until all screens close, and the ISPF tab disappears.

```
Insert on TSO Messages S

1-PRIMARY ×

Menu Utilities Compilers Options Status Help

ISPF Primary Option Menu
```

```
5 Batch
               Submit job for language processing
                                                     Appl ID . : ISR
 Command
               Enter TSO or Workstation commands
                                                     TSO logon : STUDENT
 Dialog Test Perform dialog testing
                                                    TSO prefix: TSOZA05
                                                     System ID : CZ01
 LM Facility Library administrator functions
                                                   MVS acct. : 0000
 ITS MENU
               ITS extended menu
                                                    Release . : ISPF 7.3
S SDSF
               System Display and Search Facility
                SW Configuration Library Manager
10 SCLM
```

Enter X to Terminate using log/list defaults

ENTER F1=Help F2=Split F3=Exit F7=Backward F8=Forward F9=Swap Nxt F10=Actions F12=Cancel

52. Now log-off of z/OSMF.

Option ===> =xall

53. Select the down arrow to the right of your logon user ID (on the top right corner).

_ 54. Select Log Out.



Important

You must do a z/OSMF logoff, not just close the browser.



End of exercise

Exercise answers

Section 2: z/OSMF interface layout

Q1: How can you determine if a task on the list is new for the current release?

A1: Its name is followed by the new icon:



Section 7: Entering z/OS commands and interpreting the output

Q2: What is the z/OS message ID?

A2: CNZ4105I. The last letter is an I, for information.

Q3: Which field in the command output identifies the number of address spaces running under initiators?

A3: JOBS.

Q4: What is the correct syntax of the z/OS command to display a list of all active TSO/E users?

A4: D TS,LIST or D TS,L

Q5: Which column field displays the status of the job?

A5: SYSAS.

Q6: What type of z/OS message is: IEE234I?

A6: Information only.

Q7: The STATUS field indicates the status of the device.

What does the following status' indicate?

A7: S: SYSRES. A: Allocated. O: Online.

Q8: Which device contains the IPL Bootstrap?

A8: The SYSRES device. SYSRES (System Resident).

Section 8: Identifying the system configuration

Q9: What CHPID numbers are defined to access device 0502?

A9: CHPIDs 96, B2, 84, and B0.

Q10: What are the entry ports into a FICON switch for each CHPID?

A10: Ports 5C, 5E, 5C, and 5E.

Q11: What are exit ports from the FICON switch for each CHPID?

A11: Ports 84, B4, 84, and B4.

Q12: What devices numbers are defined to CHPID 96?

A12: Device numbers: 0500 through 050F, 0BC0 through 0BCF, and 0BF0 through 0BFF.

Q13: Which devices are on-line?

A13: Device numbers: 0502 through 0503, 0BCD through 0BCF, and 0BFF.

Q14: What type of CHPID if CHPID 96?

A14: FICON switched.

Section 9: The DEVSERV command

Q15: What is the syntax of the DEVSERV command for eight devices?

A15: DS P,xxxx,8

Exercise hints

Section 3: TSO interface

Step 20. From the ISPF Primary Option Menu, Enter 3.2.

Do not forget to specify the word LIBRARY in the Data set name type to allocate a PDSE instead of a PDS:



Section 4: Links

Note after step 24:




Section 7: Entering z/OS commands and interpreting the output

Q6: Hint. IEE234I: SYSTEM FAILURE DURING INITIALIZATION OF CONSOLE consname.

Section 8: Identifying the system configuration

Step 44. There is not a way to determine the addresses of the FICON switches from the output of the D M=DEV(xxxx) command.



Exercise 6. ISHELL and hierarchical file system

Estimated time

01:00

Optional sections: 00:45

Overview

In this exercise, you access ISHELL. ISHELL is a good starting point for users familiar with TSO and ISPF who want to use z/OS UNIX. ISHELL will also be used to list the contents of, and create, a file system and directories.

Objectives

- Access and customize ISHELL
- · List the contents of the file system
- · Create a hierarchical file system
- · Create files and directories using ISHELL

References

GA32-0884	UNIX System Services Planning
SA22-7801	UNIX System Services User's Guide
SC26-7410	z/OS DFSMS Using Data Sets
REDP-4193	z/OS UNIX Security Fundamentals

Exercise instructions

Preface

- The answers to all questions are located at the end of this exercise.
- All action items followed by a * sign, include exercise hints, which are located at the end of this
 exercise.

Section 1: ISHELL introduction

1.	Log	on	to	TSC).
----	-----	----	----	-----	----

__ 2. From the ISPF menu, choose the TSO option 6 to invoke the ISHELL command use the TSO ISHELL command directly to invoke the ISHELL.

There is also a panel option for the ISHELL on the **ISPF** menu, through option **E.7** (panel @ITMENU).

__ 3. Use the pull-down menus from the action bar to see what actions can be performed.

The ISHELL screen is Common User Access (CUA) based. It has an action bar at the top of the screen.

Placing the cursor under any of the actions listed on the action bar and pressing the Enter key will result in a pop-up window (also called pop-up menu or pull-down menu) for that action being displayed. The window shows a list of actions that can be chosen.

Use the help key (PF1) on any field if you do not know what to do.

There are three actions, which can be done for a file system:

- Work with file systems in the mount table
- Create a new file system
- Mount a file system



Questions

Q1: What character on the File System and Setup actions indicates certain options require superuser or the special attribute for full function?

Section 2: Introduction to the file system




Important

Do not do the next step before saving the path name displayed on the UNIX System Services ISPF Shell. This path name is both your home directory and your current working directory. Write it down or copy it to the clipboard for pasting later.

List the contents of the root file system.

- 4. The name of the root directory is / *
- _ 5. If a / is not already specified on the UNIX System Services ISPF Shell, enter it like it is shown on the following panel:



There are different methods for displaying the contents of a directory. See whether you can find one way of doing it.

- 6. List the contents of the directory /bin in the root file system.
 - __ a. Find the directory /**bin** on the root directory list and choose the option to list its contents. (you can also use action code L in front of the /bin entry)
- ___ 7. Choose a file in this directory to browse.

The procedure is similar to the previous one, but the action is different.

Take notice that the short form of **Browse** is **B**. If you remember this you can use B directly when you want to browse a file instead of prompting the pop-up menu to choose actions from.

8. List the contents of the directory /dev in the root file system.

You can use the same way as you did to list the /bin directory.

Suggestion: Try the action code for list instead of using the pop-up menu.

- 9. Find out from the panels, which type of files are in the /dev directory.
 - a. Try listing the attributes of a file.
- ___ 10. List the actions that can be done for the files in this directory.

The pop-up menu contains a list of actions.

The only actions available for a character special file are:

- Attributes (A)
- Delete (D)
- Rename (R) done for the files in this directory.

	11.	Create a new file called NEWFILE in your home directory.
		To create a new file, you have to go back to the main ISHELL panel. As an alternative you can also enter 'n' in front ofDIR when you are in your home directory (n stands for new)
		a. Use the default permission bits for this file.
	12.	Display the contents of your home directory now to see the new file there.
		Do this the same way as you listed the ROOT directory.
	13.	Edit that new file and add a few lines of text in the file.
		a. The editor is the ISPF editor.
		F3 saves the file and return from editing the file.
Sec	ction .	3: Customize ISHELL
	14.	Modify the display of the directory contents to include information about permission bits, modification time, owner, and file size.
	15.	Display a directory with the additional information.
	16.	Check the default actions for files. *
		hat is the default action for character special files?
	17	
	17.	Specify that you want the command line to be on top of the ISHELL screen.
		Specify that you want the command line to be on top of the ISHELL screen. Change it back to be at the bottom.
Sec	18.	
Sed	18. ction 4	Change it back to be at the bottom.
Sec	18. ction 4 19.	Change it back to be at the bottom. 4: UNIX directory list Enter start on the Option command field to start a new ISPF screen; you can now switch from one session screen to the other using PF9, or using command SWAP LIST and select
Sec	18. ction 4 19.	Change it back to be at the bottom. 4: UNIX directory list Enter start on the Option command field to start a new ISPF screen; you can now switch from one session screen to the other using PF9, or using command SWAP LIST and select the option screen you want to switch to. Now on this new screen, use the ISPF/PDF option UNIX Directory List (option 3.17) to

Display a list of all entries in the path name /u/es10/students

Check column labeled TYPE using F8 to scroll the list.

Notice that the Size of the file is not displayed.

21. Select the Options pull down and select option: 2 - Directory List Column Arrangement.



On the next screen, you can change the width of the fields. Make the fields smaller or remove them completely from the display.



- 22. Change the width of the fields so the **Size** column appears.
- 23. Display the entries in your directory tsoz###.
- 24. Create a new regular UNIX file in your directory: Name it date1 with permission bits 755.
- __ 25. Once created, edit the file, add one line containing the word date, and save it.Now try to execute this UNIX file, by entering x in front of it, and specify a run method of Option 2: Login Shell.
- 26. Execute the UNIX date command under the shell:
 - __ a. Return to the TSO option 6 Command prompt. (you can use 'start' to initialize a new ISPF screen session).
 - b. Enter **owvs** to invoke the shell.
 - c. Enter unix command 'date', then enter command 'date1' or '. date1' (with a dot)
 - d. Enter unix command 'la -al'
 - e. What are the permission bits of date1?
 - __f. Change the permission bits to 444: 'chmod 444 date1'
 - __ g. and try to execute **date1** again.

? Questions			
Q3: Was it successful?			
It should fail with 'file1: cannot execute', because the file no longer has the execute bit on:			
TSOZA05@CZ01:/u/es10/students/tsoza05-(TSOZA05): \$date1 date1: cannot execute			
h. to exit from OMVS, enter 'exit'			

End of exercise (Optional exercises follow)

Soction	E: Ontional: Croate a hierarchical file avetem
	5: Optional: Create a hierarchical file system . Go into the ISHELL.
	List file systems that are already mounted.
	Look under the action File systems on the action bar. Select mount table
20	List the mount point of a mounted file system.
23	
_	a. Choose a file system to display from the list of mounted file systems.
	_ b. Look for an action that will display information about the file system.
	nount point of the root file system / is determined by displaying the Attributes (A) of the system o
	Note
	t point: / . Use the ISHELL to allocate a new file system called userid.OMVS.HFS. Allocate one cylinder for primary and one cylinder for secondary space.
	_a. Use the action File_systems on the action bar. Select 2. New HFS.
	-
	. List the contents of your home directory.
32	Create a directory called dir1 with perm bits 666
Section	6: Optional: Managing files
33	. Copy members FILE1, FILE2, FILE3 from the z/OS PDS called D80ww.ES10v15.OMvs.LABS, to your home directory. The name of the PDS has to be between quotes. Specify these file permissions when copying the files: enter '?' in front of entry 'DIR .' then use option 7. Copy from PDS'
	_a. Owner: All permissions
_	_ b. Group: Read
_	_ c. Other: None
	_d. Specify the copy options to select members from a member list, and to make names

__ a. On the panel where you must specify the new path name of the file, change only the last part of the path name (which is the file name).

© Copyright IBM Corp. 2019 6-7

e. Edit the field **Permissions** to specify the file permission bits.

lowercase.

__ 34. Rename file file1 to file9.

6-8

35. Delete file file3.	
a. When the panel to confirm the deletion is displayed, press the Enter key to confirm you want to delete the file and the file will be deleted.	า that
36. Find the string Test in the file file9 , and call the output file FINDSTR1 in your home directory.	
A panel is displayed where you can specify a path name for the output file.	
Another panel will be displayed where you can enter the text strings to be searched for	or.
37. Enter ? in front of current (dot) dir ',', then use option 10. Find (F)	
38. Find the string test in your home directory and call the output file FINDSTR2 in the sa directory.	me
The action for this is similar to the previous task, except that this is for a directory.	
Note	
When searching a file, only the selected file is searched, and the output contains the lines of the that match the search criteria. When searching a directory, all files in this and lower directories searched, and the output contains the directories and files searched as well as the lines of each that matched the criteria.	s are
39. Set your working directory to your home directory.	
a. Look under the action Directory on the action bar.	
40. Browse the contents of file file2 in your home directory using a relative path name on ISHELL main panel.	the
The working directory can be referred to by a dot (.).	
The relative path name is specified as: ./file2	
Note	
A good tip: Since file names can be up to 255 characters, referencing files relative to a working directory can potentially save a lot of typing.	ıg
41. Create a new directory in your home directory called LABS. Use these permissions:	
a. Owner: Read and write	
b. Group: Read and search	
b. Group. Nead and Search	

__ e. Check the permission bits and set them according to the exercise instructions. Use the

__ d. Creating a new directory is similar to creating a new file.

Help key to find out what the numbers mean.

© Copyright IBM Corp. 2019

42. Try to create a new file called LAB2A (Upper case) in the LABS directory.
Creating a new file was done in a previous step.
43. Change the permission bits for the LABS directory to allow the owner to list the directory at add new files in it.
a. Edit the mode fields to change the permission bits.
Questions
Q4: What is the permission expressed in octal value that allows this?
44. Try again to create a new file called lab2a (Lower Case) in the LABS directory. It is a different file, as unix is case sensitive (not like MVS dataset names which must always be treated as upper case).
See previous instructions if you don't remember how to create a new file, or use F1 to ge help.
45. Write a few lines of text in the new file.
a. Choose the Edit action to edit a file.
46. Copy members PROG1, PROG2, PROG3 from the z/OS PDS called D80ww.ES10v15.OMvs.LABS into your home directory and add the suffix c to the files.
On the panel where you specify the name of the PDS (between single quotes!) and som copy options, you can also specify a suffix for the files that will be copied.
47. Create a new directory called NEWDIR in your home directory.
a. Set the permissions value to 755.
48. Compare the contents of directories LABS and NEWDIR.
If you have time, try any other action that you would like to try, or some actions you would like to practice more.
Below are some additional optional exercises to get you more familiar with the ISPF UNIX shell environment.

Section 7: Optional: Additional UNIX activities

____49. Use the pull-down menus from the action bar to see what actions can be performed.

The ISHELL screen is CUA (Common User Interface) based. It has an action bar at the top of the screen. Note the use of PF10 and tab. (Make sure you have enabled PFKEYS display with command PFSHOW ON.)

Placing the cursor under any of the actions listed on the action bar and pressing the Enter key, results in a pop-up window (also called pop-up menu or pull-down menu) for that action being displayed. The window shows a list of actions that can be chosen.

Use the help key (PF1) on any field if you do not know what to do.


- ___ 50. Locate the actions, which can be done for the File pull down.
- ___ 51. The attributes for a file or directory can be displayed:
 - __ a. In Menu File, select **2** to display attributes of current file or directory. Note the use of F8 and F7 to scroll display.
 - __ b. In Command Line, use command **A** to display attributes of current file or directory. Note the use of F11 to go to command line.

Section 8: Optional: Introduction to the file system

__ 52. List the contents of the root file system.

The name of the root file system is / (forward slash).

If / (forward slash) is not already specified on the ISH main panel, enter it as shown on the following panel.



There are different methods for displaying the contents of a directory.



Questions

Q5: What are the ways to display the contents of a directory?

- ___ 53. Display (list) the contents of the directory **bin** in the root file system.
- 54. Find the directory **bin** on the root directory list and choose the option to list its contents.
- __ 55. Sort the directory list just displayed. Sort items by size, then sort by last change date. For better viewing, make sure you enabled fields display in the directory list, by going back to primary menu, then options, then dir list, and enable the fields to display permission bits (octal display only), change time, owner, and size.


56. Go back to root directory list (/); enter the command sort in the command line, and select Sort by size (or tab to Commands) then option 2. Sort... 57. Sort can be done in two levels on: Default, File name mixed case, File name, File type, Permissions, Size, Owner, and Change time. You can also put the cursor on any of the column titles to sort on the wanted criteria, and press Enter; try it for the Changed-GMT, Size, and file name. Default sort sequence is file name mixed case. The default can be changed by selecting F10, then select **Options**, then select **1** for Directory List, then select **View/Change** sort options. Type Perm Changed-GMT 755 2006-06-28 20:20 OMVSKERN 755 2006-07-08 17:25 OMVSKERN 32768 Dir 8192 777 2006-02-14 20:59 OMVSKERN 755 2005-05-17 17:51 OMVSKERN 755 2005-05-17 17:51 OMVSKERN Syml 27 acl_edit 61440 alias 184320 69632 asa File 755 2005-05-17 17:51 OMVSKERN 58. Choose a file in /bin/ directory to browse. Take note that the short form of **Browse** is **B**. If you remember this, you can use B directly when you want to browse a file instead of prompting the pop-up menu to choose actions from. 59. Look at dev in the root file system. (/dev) Questions Q6: Is it a file or directory? Or something else? 60. If you want to display the content of /dev as a directory and not the content of the symlink (it points to \$SYSNAME/dev), you must append / (forward slash) after /dev, and specify /dev/; try it now; it should display some special files like null, random, console. 61. Create some new files called NEWFILE1, NEWFILE2.... in the /u/es10/students/tsozxxx directory, where tsozxxx is your TSO user ID. 62. To create a new file, go back to the main ISHELL panel, input the file name on the path name (example: /u/es10/students/tsozxxx/newfile2), then press Enter (or select option File, then 1 (New)).

© Copyright IBM Corp. 2019 6-11

__ a. Use file type regular file, and set the permission bits to 755.

Select file source for regular file as edit.

 $\underline{}$ 63. There is also another easier way to create a new file or directory using the ISHELL, by entering \mathbf{n} in front of the . special directory (see example below).



You are then prompted to create either a file (2) or directory (1) or else.

___ 64. Display the contents of your /u/es10/students/<u>tsozxxx</u> directory now to see the new files there. Do this the same way as you listed the root directory.



Questions

Q7: Can you browse an empty file this way?

__ 65. Edit one of the new files and add a few lines of text in the file. The editor is the ISPF editor PF3 saves the file and returns from editing the file.



Note

The following items create three new files. Each create uses a different set of panels. This demonstrates that there are frequently several ways to accomplish a task in the ISHELL.

- __ 66. Create a new file called: /u/es10/students/tsozxxx/test1 using any method you want, for instance:
 - Enter the absolute path name on the path name line: /u/es10/students/tsozxxx/test1
 - On the Action bar, select File.
 - On the pull-down menu, select **New**.
 - Set permission bits to: **755**.
- __ 67. Create a new file called: /u/es10/students/tsozxxx/test2
- ___ 68. Enter the absolute path name on the path name line: /u/es10/students/tsozxxx/test2
- 69. Press the Enter key.
- ___ 70. Set permission bits to **755** and select option to create a regular file.

71. Create a new file called: /u/es10/students/tsozxxx/test3
72. Enter the absolute path name on the path name line: /u/es10/students/tsozxxx/test
73. On the command line, enter: n (the action code for creating a new file).
74. Set permission bits to 755 and select option to create a regular file.
75. Try to find in which file system all your UNIX files have been created:
a. In your /u/es10/students/tsozxxx, select any file, and enter u file system, or tab to File, then select opt15 (U).
76. Enable directory list reference.
77. Go back to Options on primary menu, then option 5 Advanced, then select / Enable directory reference list.
78. Now go to Tools , then select option 4 . Reference list (REF).
You have a direct shortcut to any of the previously used directories, which you can select


You have a direct shortcut to any of the previously used directories, which you can select using **s** or / (forward slash).

You can now use the ref command on any panel to display the reference list.


Note: the list is initially empty since it was just enabled.

ISPF provides a direct interface to edit/view/browse UNIX files and directories. This interface is called UDLIST. In the VIEW (opt1) and EDIT (opt2) panels of ISPF, you can now enter UNIX files and directory paths directly in the Other Partitioned, Sequential or VSAM Data Set, or z/OS UNIX file, instead of specifying an MVS classical non-UNIX data set.

 $_{-}$ 79. Go to ISPF primary option **2** (EDIT), and enter /u/es10/students as the path name.




__ 80. Now select your own directory, by entering **L** in front of **tsozxxx** as the path name.




The same UDLIST interface is available in ISPF option 3.17; go to ISPF **3.17**; you can use the REFLIST panel option to retrieve and work with one of the last used UNIX directories, or

specify a starting directory name in the path name; try it with your home directory /u/es10/students/tsozxxx.



Note that in the Options you can change the column arrangement, as well as the width of columns.



- __ 81. You can also run USS commands from TSO option 6 with the OSHELL and execute TSO command OSHELL to run various shell commands with the OSHELL. Try the following under TSO command option 6:
 - a. OSHELL ps -ef
 - b. OSHELL is -al
 - c. OSHELL id
 - __ d. OSHELL df

End of optional exercises

Exercise answers

Section 1: ISHELL introduction

Q1: What character on the File System and Setup actions indicates certain options require superuser or the special attribute for full function?

A1: An asterisk.

Section 3: Customize ISHELL

Q2: What is the default action for character special files?

A2: Attributes or A.

Section 4: UNIX directory list

Q3: Was it successful?

A3: No, because it is no longer executable (does not have the execute bit on).

Optional sections:

Section 5: Optional: Managing files

You also need search permission to add a new file to a directory.

Q4: What is the permission expressed in octal value that allows this?

A4: Octal 7 allows Read + Write + Search or Execute. The new permissions should be 754.

Section 7: Optional: Introduction to the file system

You also need search permission to add a new file to a directory.

Q5: What are the ways to display the contents of a directory?

A5: Here are some of the ways:

- Press b. Listing the directory is the default action, if a directory is displayed.
- Use PF10 tab twice, and then 1.
- Use PF11, and I (for list).

Q6: Is it a file or directory? Or something else?

A6: No, it is something else. It is a symbolic link.

Q7: Can you browse an empty file this way?

A7: No.

Exercise hints

Section 2: Introduction to the file system

Step 4: Forgot your home directory path name? Issue the following ISHELL command: **Sh echo \$HOME**

Section 3: Customize ISHELL

Step 16: On the Action Bar, select Options, then select Command line on...

Glossary

This glossary includes terms and definitions from:

- The American National Standard Dictionary for Information Systems, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies can be purchased from the American National Standards Institute, 11 West 42nd Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.
- The ANSI/EIA Standard— 440-A, Fiber Optic Terminology. Copies can be purchased from the Electronic Industries Association, 2001 Pennsylvania Avenue, N.W., Washington, DC 20006. Definitions are identified by the symbol (E) after the definition.
- The Information Technology Vocabulary, developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Commission (ISO/IEC JTC1/SC1). Definitions of published parts of this vocabulary are identified by the symbol (I) after the definition; definitions taken from draft international standards, committee drafts, and working papers being developed by ISO/IEC JTC1/SC1 are identified by the symbol (T) after the definition, indicating that final agreement has not yet been reached among the participating National Bodies of SC1.
- The Network Working Group Request for Comments: 1208.

The following cross-references are used in this glossary:

Contrast with: This refers to a term that has an opposed or substantively different meaning.

Synonym for: This indicates that the term has the same meaning as a preferred term, which is defined in its proper place in the glossary.

Synonymous with: This is a backward reference from a defined term to all other terms that have the same meaning.

See: This refers the reader to multiple-word terms that have the same last word.

See also: This refers the reader to terms that have a related, but not synonymous, meaning.

Deprecated term for: This indicates that the term should not be used. It refers to a preferred term, which is defined in its proper place in the glossary.

Numerics

Α

AC:

See Alternating Current.

Access:

- 1) To obtain computing services or data.
- 2) In computer security, a specific type of interaction between a subject and an object that results in flow of information from one to the other

Access-any mode:

One of the two access modes that can be set for the storage system during initial configuration. It enables all Fibre Channel-attached host systems with no defined access profile to access all logical volumes on the storage system. With a profile defined in DS8000 Storage Management GUI for a particular host, that host has access only to volumes that are assigned to the WWPN for that host. See also *pseudo host* and *worldwide port name*.

Access Control Lists (ACLs):

Are used to control access to files and directories by individual user (UID) and group (GID). ACLs are used in conjunction with permission bits.

ACK:

See request for acknowledgment and acknowledgment.

Adaptive Multi-stream Prefetching (AMP):

An autonomic, workload-responsive, self-optimizing prefetching technology that adapts the amount of prefetch and the timing of prefetch on a per-application basis to maximize the performance of the system.

Adaptive Replacement Cache (ARC):

A page replacement algorithm with better performance than LRU (Least Recently Used). This is accomplished by keeping track of both frequently used and recently used pages plus a recent eviction history for both.

Address space:

Is the amount of memory allocated for all possible addresses for a computational entity, such as a device, a file, a server, or a networked computer.

Advanced Encryption Standard (AES):

Is a symmetric block cipher used by the US government to protect classified information and is implemented in software and hardware throughout the world to encrypt sensitive data. A block cipher is a method of encrypting text (to produce ciphertext) in which a cryptographic key and algorithm are applied to a block of data (for example, 63 contiguous bits) at once as a group rather than to 1 bit at a time.

Agent:

A program that automatically initiates some service without user intervention or on a regular schedule. See also *subagent*.

Alert:

A message or log that a storage system generates as the result of error event collection and analysis. An alert indicates that a service action is required.

Aliases:

The number of parallel access volumes (PAVs) defined to be used by a particular volume, or, when HyperPAV is enabled, any volume within the LSS.

All-Flash configuration:

A high-performance storage configuration that supports only high-performance flash enclosures.

Allegiance:

For IBM Z products, a relationship that is created between a device and one or more channel paths during the processing of certain conditions. See also *implicit allegiance*, and *reserved allegiance*.

ALLOCATE command (In UNIX):

Use the **ALLOCATE** command to dynamically allocate VSAM, non-VSAM, and Hierarchical File System (HFS) data sets.

Allocated storage:

The space that is allocated to volumes but not yet assigned. Contrast with assigned storage.

Allocation method:

The means by which capacity is allocated for volumes from within a pool. Possible values include rotate capacity, rotate volumes, and managed.

Alternating Current (AC):

A type of electrical current, in which the direction of the flow of electrons switches back and forth at regular intervals or cycles. Current flowing in power lines and normal household electricity that comes from a wall outlet is alternating current. The standard current used in the US is 60 cycles per second (that is, a frequency of 60 Hz); in Europe and most other parts of the world it is 50 cycles per second (that is, a frequency of 50 Hz.).

American National Standards Institute (ANSI):

A private, nonprofit organization whose membership includes private companies, US government agencies, and professional, technical, trade, labor, and consumer

organizations. ANSI coordinates the development of voluntary consensus standards in the US

American Standard Code for Information Interchange (ASCII):

Is the most common format for text files in computers and on the Internet. In an ASCII file, each alphabetic, numeric, or special character is represented with a 7-bit binary number (a string of seven 0s or 1s). 128 possible characters are defined.

AMP:

See Adaptive Multi-stream Prefetching.

Another Network Block Device (ANBD):

Is a compatible NBD (Network Block Device) extension from 2003. It supports multithreading and promises better error messages than its predecessor.

Anonymous:

In the DS8000 Storage Management GUI, the label on an icon that represents all connections that are using Fibre Channel adapters between the storage system and hosts but are not completely defined to the storage system. See also anonymous host, pseudo host, and access-any mode.

Anonymous host:

Synonym for *pseudo host*. Contrast with *anonymous* and *pseudo host*.

ANSI:

See American National Standards Institute.

AOS:

See Assist On Site.

APAR (Authorized Program Analysis Report):

A request for correction of a problem caused by a defect in a current release of a program unaltered by the user.

Application programming interface (API):

Is a set of routines, protocols, and tools for building software applications. An API specifies how software components should interact and APIs are used when programming graphical user interface (GUI) components.

Application Specific Integrated Circuit (ASIC):

Is a microchip designed for a special application, such as a particular kind of transmission protocol or a hand-held computer.

Arbitrated loop:

For Fibre Channel connections, a topology that enables the interconnection of a set of nodes. See also *point-to-point connection* and *switched fabric*.

ARC:

See Adaptive Replacement Cache.

Array:

A structure that contains an ordered collection of elements of the same data type in which each element can be referenced by its index value or ordinal position in the collection. In the storage system, an array is a group of disks that the user designates to be managed by the RAID technique. See also *Redundant Array of Independent Disk* (RAID).

Array site:

A group of identical drives (same capacity, speed, and drive class). Which drives from an array site is predetermined automatically by the DS8000. There is no predetermined processor node affinity for array sites. Array sites are the building blocks that are used to define arrays.

ASCII:

See American Standard Code for Information Interchange.

ASIC:

See Application Specific Integrated Circuit.

Assigned storage:

The space that is allocated to a volume and that is assigned to a port.

Assist On Site (AOS):

The components of Assist On-site (AOS) interact together to start and maintain a support session between the support engineer and the customer.

Asymmetric encryption:

Also known as public-key encryption, symmetric versus asymmetric encryption utilizes a pair of keys; a public key and a private key. If you encrypt data with the public key, only the holder of the corresponding private key can decrypt the data, hence ensuring confidentiality. Many 'secure' online transaction systems rely on asymmetric encryption to establish a secure channel. SSL, for example, is a protocol that utilizes asymmetric encryption to provide communication security on the Internet. An asymmetric encryption algorithm typically involve exponential operations. They are not lightweight in terms of performance. For that reason, asymmetric algorithms are often used to secure key exchanges rather than used for bulk data encryption.

Availability:

The degree to which a system or resource is capable of performing its normal function. See *data availability*.

В

Bandwidth:

Defined as the amount of data that can be transmitted in a fixed amount of time. For digital devices, the bandwidth is usually expressed in bits per second (bps) or bytes per second.

Bare-metal hypervisor:

Type-1, native or bare-metal hypervisors: These hypervisors run directly on the host's hardware to control the hardware and to manage guest operating systems. For this reason, they are sometimes called bare metal hypervisors.

Type-2 or hosted hypervisors:

These hypervisors run on a conventional operating system just as other computer programs do. A guest operating system runs as a process on the host. Type-2 hypervisors abstract guest operating systems from the host operating system.

Base addressing space:

On an extended address volume, this term refers to cylinders with addresses below 65,536. These cylinder addresses are represented by 16-bit cylinder numbers or by 28-bit cylinder numbers with high order 12 bits of zero (0).

Batch processing:

Batch Processing is used for programs that can be executed with minimal human interaction and at a scheduled time or on an as-needed basis.

Battery Service Module (BSM) set:

The DC-UPS contains integrated battery sets known as Battery Service Modules (BSM) sets. The BSM set is composed of four BSM modules. The BSM sets help protect data if there is a loss of external power to the frame. If there is a complete loss of AC input power to the frame, the batteries are used to maintain power to the processor complexes and I/O enclosures for sufficient time to allow the contents of NVS memory (modified data that is not yet destaged from cache) to be written to the hard disk drives internal to the processor complexes (not the storage enclosure drives).

Bay:

A physical space into which a device can be physically mounted and connected to power and data. For example, a power supply or a disk drive might be inserted into a bay. See also service boundary.

Block:

A string of data elements recorded, processed, or transmitted as a unit. The elements can be characters, words, or physical records. A group of contiguous sectors on a disk that contains a block header and some integral number of records. All blocks on the storage device are the same size (fixed size). See also fixed-block architecture and data record.

Break Point Value (BPV):

When a disk space request is this size or more, the system prefers to use the cylinder-managed space for that extent. This applies to each request for primary or secondary space for data sets that are eligible for the cylinder-managed space. If not enough cylinder-managed space is available, then the system uses the track-managed space or will use both areas. The breakpoint value is expressed in cylinders. When the size of a disk space request is less than the breakpoint value, the system prefers to use the track-managed area. If not enough space is available there, then the system will use the cylinder-managed space, or will use both areas.

BSM:

See Battery Service Module (BSM) set.

Business Class configuration:

A high-density, high-performance storage configuration that includes standard disk enclosures and high-performance flash enclosures and is optimized and configured for cost, by minimizing the number of device adapters and maximizing the number of storage enclosures that are attached to each storage system.

C

Cache:

Memory used to improve access times to instructions, data, or both. Data that resides in cache memory is normally a copy of data that resides elsewhere in slower, less expensive storage, such as on a disk or on another network node.

Cache fast write:

A form of the fast-write operation in which the storage server writes the data directly to cache, where it is available for later destaging.

Cache hit:

An event that occurs when a read operation is sent to the cluster, and the requested data is found in cache. Contrast with cache miss.

Cache memory:

Memory, typically volatile memory, that a storage server uses to improve access times to instructions or data. The cache memory is typically smaller and faster than the primary memory or storage medium. In addition to residing in cache memory, the same data also resides on the storage devices in the storage system.

Cache miss:

An event that occurs when a read operation is sent to the cluster, but the data is not found in cache. Contrast with cache hit.

Call home:

A communication link established between the storage product and a service provider. The storage product can use this link to place a call to IBM or to another service provider when it requires service. With access to the machine, service personnel can process service tasks, such as viewing error logs and problem logs or initiating trace and dump retrievals. See also heartbeat and *Remote Technical Assistance Information Network* (RETAIN).

Capacity Backup (CBU):

Provides the ability to replace model capacity or specialty engines to a backup server in the event of an unforeseen loss of server capacity because of an emergency.

Capacity Upgrade on Demand (CUoD):

Activates additional processors and memory units on selected servers by purchasing a permanent processor or memory unit activation feature. CUoD adds capacity for new workloads, which enables the server to adapt to unexpected performance demands.

Cascading:

- 1) Connecting network controllers to each other in a succession of levels to concentrate many more lines than a single level permits.
- 2) In high-availability cluster system MultiProcessing (HACMP), pertaining to a system configuration in which the system node with the highest priority for a particular resource acquires the resource if the primary node fails. The cluster system node relinquishes the resource to the primary node upon reintegration of the primary node into the system.

Cataloged procedure:

A procedure that is stored as a member of a PDS or PDSE is a cataloged procedure. The data set containing the procedure can either be a private or system data set.

CBU:

See Capacity Backup.

CDS:

See Couple Data Set.

Central Electronic Complex (CEC):

The set of hardware that defines a mainframe, which includes the CPU(s), memory, channels, controllers, and power supplies included in the system. A physical collection of hardware that consists of main storage, one or more Central Processors (CPs), timers, and channels.

CF:

See Coupling facility.

CFCC:

See Coupling Facility Control Code.

Central Processing Unit (CPU):

Is the primary component of a computer that processes instructions. It runs the operating system and applications, constantly receiving input from the user or active software programs. It processes the data and produces output, which may stored by an application or displayed on the screen.

Central Processor (CP):

The part of the computer that contains the sequencing and processing facilities for instruction execution, initial program load, and other machine operations. CPs execute instructions.

Central Processor Complex (CPC):

Refers to the physical collection of hardware that includes main storage, one or more central processors, timers, and channels.

CGI:

See Common Interface Gateway.

Change Mode (CMOD):

In UNIX-like operating systems, chmod is the system and system call, which may change the access permissions to file system objects (files and directories).

Channel:

The part of a channel subsystem that manages a single I/O interface between a channel subsystem and a set of control units.

Channel Path Identifier (CHPID):

The channel, represented by a channel path ID or CHPID, represents the actual communication path. A CHPID is the handle by which communication between the CPC and an external device is facilitated. A CHPID must be unique, since it denotes a unique path of communication for the CPC. The maximum number of allowable CHPIDs within a channel subsystem is 256. Channels can be shared between LPARs. A CHPID is associated with either a physical port or with an internal connection defined inside the mainframe. Valid CHPIDs are in the hexadecimal range from X'00' through X'FF'.

Channel Command Word (CCW):

An instruction to a specialized I/O channel processor, which is, in fact, a finite state machine. It is used to initiate an I/O operation, such as 'read', 'write' or 'sense', on a channel-attached device. On system architectures, which implement channel I/O, typically all devices are connected by channels, and so all I/O requires the use of CCWs.

CICS:

See Customer Information Control System.

CIM:

See Common Information Model.

Ciphertext:

Data that has been encrypted. Ciphertext is unreadable until it has been converted into plaintext (decrypted) with a key.

Citrix XenServer:

Is a server virtualization platform based on the Xen hypervisor that allows IT administrators to host, deploy, and manage virtual machines.

CIU:

See Customer Initiated Upgrade.

CKD:

See Count Key Data.

Cloud:

A cloud is a vast array of computers that are hooked together and meant to operate as a single ecosystem. Clouds are configured to offer one or more services (for example, data storage, content delivery, or applications) and users can access these services remotely.

Cloud Management Platform (CMP):

A Cloud Management Platform is software, which combines a set of features or modules, which enable the management of different cloud environments. Public, private, and hybrid cloud cannot be all handled with a simple virtualization management console.

Cluster:

A partition capable of processing all DS8000 series functions. With two clusters in the storage system, any operational cluster can take over the processing of a failing cluster.

Cluster Structure Storage System (CSS):

CSS is a novel, high-performance disk storage system. CSS divides its disk space into large, fix-sized clusters, which are the basic units for disk reads and writes.

CMOS: See Complementary Metal—Oxide—Semiconductor.

CMPSC: See Compression Coprocessor.

Cold demotion:

An operation of IBM Easy Tier automatic mode. The movement of an extent of inactive data to a lower tier to make its tier available for new data.

Common Information Model (CIM):

Is an open standard that defines how managed elements in an IT environment are represented as a common set of objects and relationships between them.

Command List (CLIST):

CLIST is a procedural programming language for TSO in z/OS systems.

Command Line Interface (CLI):

An interface that defines a set of commands and enables a user to issue these commands by entering text in response to the command prompt (for example, DOS commands or UNIX shell commands). See also *IBM DS CLI*.

Command parameter:

Defines a parameter of a command being created.

Common Gateway Interface (CGI):

Was introduced to enable and standardize the interface between Web servers and external programs. The CGI is a relatively simple, platform and language independent, industry-standard interface for Web application development. Programs that implement the CGI standard are commonly called CGI programs.

Complementary Metal-Oxide-Semiconductor (CMOS):

CMOS is a technology for constructing integrated circuits. CMOS technology is used in microprocessors, micro controllers, static RAM, and other digital logic circuits.

Compression Coprocessor (CMPSC):

Is a high-performance coprocessor that uses compression algorithms to help reduce disk space and memory usage. Each processor unit has a dedicated CMPSC that connects to the main cache-structure for better throughput of the compression dictionaries.

Computer program:

A computer program is a list of instructions that tell a computer what to do.

Concurrent copy:

A facility on a storage server that enables a program to make a backup of a data set while the logical volume remains available for subsequent processing. The data in the backup copy is frozen at the point in time that the server responds to the request.

Concurrent installation of licensed machine code:

Process of installing Licensed Internal Code on a DS8000 series while applications continue to run.

Configure:

In storage, to define the logical and physical devices, optional features, and program products of the input/output subsystem through the user interface that the storage system provides for this function.

Configuration task commands:

Used for creating, modifying, and deleting resources.

Consistency group:

A group of volumes participating in FlashCopy relationships in a logical subsystem, across logical subsystems, or across multiple storage systems that must be kept in a consistent state to ensure data integrity.

Consistency group interval time:

The value in seconds that indicates the length of time between the formation of consistency groups.

Consistent copy:

A copy of a data entity (a logical volume, for example) that contains the contents of the entire data entity at a single instant in time.

Console:

A user interface to a server, for example, the interface provided on a personal computer. See also *Hardware Management Console*.

Control path:

The route that is established from the master storage system to the subordinate storage system when more than one storage system participates in a Global Mirror session. If there is only one storage system (the master) in the Global Mirror session, no control path is required.

Control unit:

1) A device that coordinates and controls the operation of one or more input/output devices,

and synchronizes the operation of such devices with the operation of the system as a whole.

2) For IBM Z, a storage server with FICON or OEMI interfaces. The control unit adapts a native device interface to an I/O interface that an IBM Z Systems host system supports.

3) The portion of the storage system that supports the attachment of emulated count key data devices over ESCON, FICON, or OEMI interfaces. See also *cluster*.

Control-unit image:

In mainframe computing, a logical subsystem that is accessed through an ESCON I/O interface. One or more control-unit images exist in each control unit. Each image appears as an independent control unit, but all control-unit images share a common set of hardware facilities. The DS8000 series can emulate 3990-3, TPF, 3990-6, or 2105 control units.

Control-Unit-Initiated Reconfiguration (CUIR):

A software mechanism that the DS8000 series uses to request that an operating system of IBM Z host verify that one or more subsystem resources can be taken offline for service. The DS8000 series can use this process to automatically vary channel paths offline and online to facilitate bay service or concurrent code installation. Depending on the operating system, support for this process might be model-dependent, might depend on the IBM Enterprise Storage Server Subsystem Device Driver, or might not exist.

Copy Services:

A collection of optional software features, with a web-browser interface, that is used for configuring, managing, and monitoring data-copy functions.

Core:

See processor.

Count field:

The first field of a Count Key Data (CKD) record. This 8-byte field contains a 4-byte track address (CCHH). It defines the cylinder and head that are associated with the track, and a

1-byte record number (R) that identifies the record on the track. It defines a 1-byte key length that specifies the length of the record's key field (0 means no key field). It defines a 2-byte data length that specifies the length of the record's data field (0 means no data field). Only the end-of-file record has a data length of zero.

Count Key Data (CKD):

In mainframe computing, a data-record format employing self-defining record formats in which each record is represented by up to three fields: a count field that identifies the record and specifies its format, an optional key field that identifies the data area contents, and an optional data field that typically contains the user data. For CKD records on the storage system, the logical volume size is defined in terms of the device emulation mode (3390 or 3380 track format). The count field is always 8 bytes long and contains the lengths of the key and data fields, the key field has a length of 0 to 255 bytes, and the data field has a length of 0 to 65 535 or the maximum that will fit on the track. See also data record.

Couple Data Set (CDS):

Couple data sets provides a central shared repository of data that needs to be visible to every system in the sysplex. The CDS and all accesses to the data therein are managed by XCF.

Coupling Facility (CF):

Is a piece of computer hardware which allows multiple processors to access the same data. A Parallel Sysplex relies on one or more Coupling Facilities (CFs).

Coupling Facility Control Code (CFCC):

Is an IBM licensed Internal Code that always runs under an LPAR, regardless of whether the CF is in a standalone CPC or in a general purpose CPC.

Coupling Facility Resource Management (CFRM):

Allows you to define how z/OS is to manage coupling facility resources.

CP:

See Central Processor.

CP Assist for Cryptographic Function (**CPACF**):

Is a set of cryptographic instructions providing improved performance.

CPC:

See Central Processing Complex.

CPU:

See Central Processing Unit.

CRC:

See Cyclic Redundancy Check.

Cross-cluster communication:

DS8880 uses PCIe paths between the I/O enclosures to provide the cross-cluster (XC) communication between CPCs. This configuration means that no separate path is between the XC communications and I/O traffic, which simplifies the topology. During normal operations, the XC communication traffic uses a small portion of the overall available PCIe bandwidth (less than 1.7%) so that the XC communication traffic has a negligible effect on I/O performance.

Cross-System Coupling Facility (XCF):

Is a component of z/OS that manages communications between applications in a sysplex. Applications may be on the same system or different systems.

Systems communicate using messages transported by one of two mechanisms: Dedicated channel-to-channel links (CTC links) and Structures in a Coupling Facility, only available in Parallel Sysplex, not in standard sysplex.

Cross-System Extended Services (XES):

A component of z/OS, enables applications and subsystems to take advantage of the coupling facility.

Cryptography:

- (1) The transformation of data to conceal its information content and to prevent its unauthorized use or undetected modification.
- (2) Protecting information by transforming it (encrypting it) into an unreadable format, called ciphertext. Only those who possess a secret key can decipher (or decrypt) the message into plaintext.

CRUD:

Create, Read, Update, and Delete as an acronym CRUD, are the four basic functions of persistent storage.[

CU:

See Control Unit.

CUoD:

See Capacity Upgrade on Demand.

CUIR:

See Control-Unit Initiated Reconfiguration.

Customer Information Control System (CICS):

Is an online transaction processing monitor from IBM that acts as an interface between the operating system and application programs to provide rapid high-volume online transaction processing.

Customer Initiated Upgrade (CIU):

Is an IBM on-line system through which you can order, download, and install temporary and permanent upgrades for IBM Z servers.

Cylinder-managed space:

This term refers to the space on the volume that is managed only in multicylinder units. Cylinder-managed space begins at cylinder address 65520. Each data set occupies an integral multiple of multicylinder units. Space requests targeted for the cylinder-managed space will be rounded up to the next multicylinder unit. The cylinder-managed space exists only on EAVs.

Cylinder:

A unit of storage on a CKD device with a fixed number of tracks.

Coarse Wavelength Division Multiplexing (CWDM):

Is a method of combining multiple signals on laser beams at various wavelengths for transmission along fiber optic cables, such that the number of channels is fewer than in Dense Wavelength Division Multiplexing (DWDM) but more than in standard Wavelength Division Multiplexing (WDM).

D

DA:

See Device Adapter.

Daisy chain:

See serial connection.

DASD:

See Direct Access Storage Device.

DASD fast write (DFW):

A function in which data is written concurrently to cache and nonvolatile storage, and automatically scheduled for destaging to DASD. Both copies are retained in the storage control until the data is completely written to the DASD, providing data integrity equivalent to writing directly to the DASD. Use of DASD fast write for system-managed data sets is controlled by storage class attributes to improve performance.

DAT:

See Dynamic Address Translation.

Data availability:

The degree to which data is available when needed, typically measured as a percentage of time that the system would be capable of responding to any data request (for example, 99.999% available).

Data Base 2 (DB2):

DB2 provides an open database environment that runs on a wide variety of computing platforms.

Data compression:

The process of eliminating gaps, empty fields, redundancies, and unnecessary data to shorten the length of records or blocks.

Data Facility Storage Management Subsystem data set services (DFSMSdss) utilities:

DFSMSdss is a component of DFSMS (Data Facility Storage Management Subsystem). It is used to move and replicate data, manage storage space efficiently, backup and recover data, and convert data sets and volumes.

Data field:

The optional third field of a Count Key Data (CKD) record. The count field specifies the length of the data field. The data field contains data that the program writes.

Data record:

The basic unit of IBM Z storage on a DS8000, also known as a Count Key Data (CKD) record. Data records are stored on a track. The records are sequentially numbered starting with 0. The first record, R0, is typically called the track descriptor record and contains data that the operating system normally uses to manage the track. See also *count-key-data* and *fixed-block architecture*.

Data set FlashCopy:

For IBM Z hosts, a feature of FlashCopy that indicates how many partial volume FlashCopy relationships are active on a volume.

Data space / Hiperspace:

A data space or hiperspace contains only user data or user programs stored as data.

Data Set Command Line Interface (DS CLI):

A software package that allows open systems hosts to invoke and manage Copy Services functions as well as to configure and manage all storage units in a storage complex. The DS CLI is a full-function command set.

Data sharing:

The ability of multiple host systems to concurrently utilize data that they store on one or more storage devices. The storage system enables configured storage to be accessible to

any, or all, attached host systems. To use this capability, the host program must be designed to support data that it is sharing.

DC:

See Direct Current.

DC-UPS (Direct Current-Uninterruptible Power Supply:

Converts incoming AC line voltage to rectified AC, and contains an integrated battery subsystem.

Decrypt:

In Cryptographic Support, to convert ciphertext into plaintext. See also *encrypt*.

Decryption:

In computer security, the process of transforming encoded text or ciphertext into plaintext. The process of decoding data that has been encrypted into a secret format. Decryption requires a secret key or password.

DELETE command (In UNIX):

Use the **DELETE** command to delete one or more data set entries or one or more members of a partitioned data set.

Demote:

To remove a logical data unit from cache memory. A storage server demotes a data unit to create room for other logical data units in the cache or because the logical data unit is not valid. The storage system must destage logical data units with active write units before they can be demoted. See also *destage*.

Dense Wavelength Division Multiplexing (DWDM):

Is a technology that puts data from different sources together on an optical fiber, with each signal carried at the same time on its own separate light wavelength. Using DWDM, up to 80 (and theoretically more) separate wavelengths or channels of data can be multiplexed into a lightstream transmitted on a single optical fiber. Each channel carries a Time Division Multiplexed (TDM) signal. In a system with each channel carrying 2.5 Gbps (billion bits per second), up to 200 billion bits can be delivered a second by the optical fiber. DWDM

is also sometimes called Wave Division Multiplexing (WDM).

Destage:

The storage system stages incoming data into cache and then destages it to disk.

Device:

For IBM Z, a disk drive.

Device Adapter (DA):

A physical component of DS8000 series that provides communication between the clusters and the storage devices. DS8000 series has eight device adapters that it deploys in pairs, one from each cluster. Device adapter pairing enables DS8000 series to access any disk drive from either of two paths, providing fault tolerance and enhanced availability.

Device address:

For IBM Z, the field of an ESCON device-level frame that selects a specific device on a control-unit image.

Device ID:

The unique two-digit hexadecimal number that identifies the logical device.

device interface card:

A physical subunit of a storage cluster that provides the communication with the attached device drive modules.

Device number:

For IBM Z, a four-hexadecimal-character identifier, for example 13A0, that the systems administrator associates with a device to facilitate communication between the program and the host operator. The device number is associated with a subchannel.

Device Support Facility (ICKDSF):

Is the utility used to install, initialize, and maintain IBM DASD. It can be run as a standalone job or under a system such as z/OS. 'ICK' is not an acronym for anything.

DEVSER command:

A z/OS command used to request a display of the status of DASD and tape devices. The

response is a display of basic status information about a device, a group of devices, or storage control units. Because the **DEVSERV** command causes the system to issue an I/O request on paths to a device or devices, the resulting display reflects the current physical state of the path.

DFSMSdss:

See Data Facility Storage Management Subsystem data set services utilities.

DFSORT:

DFSORT is IBM's high-performance sort, merge, copy, analysis, and reporting product for z/OS.

DIMM:

See Dual In-line Memory Module.

Direct Access Device Space Management (DADSM):

Performs the functions required to allocate or free space on a Direct Access Storage Device (DASD). The DADSM routines control allocation of space on DASD volumes, and provide information on volume contents on request. The information is kept by DADSM in its own data set which it maintains for each volume: the Volume Table Of Contents (VTOC).

Direct Access Storage Device (DASD):

- 1) A mass storage medium on which a computer stores data.
- 2) A disk device.

Direct Current (DC):

Is an electrical current, which flows consistently in one direction.

Disk Drive Module (DDM):

A Field Replaceable Unit (FRU) that consists of a single disk drive and its associated packaging.

Disk enclosure:

The DS8000 data disks are installed in enclosures called disk enclosures or storage enclosures. These disk enclosures are installed in pairs.

Disk group:

A collection of 4 disk drives that are connected to the same pair of IBM Serial Storage adapters and can be used to create a RAID array. A disk group can be formatted as count key data or fixed block, and as RAID or non-RAID, or it can be left unformatted. A disk group is a logical assemblage of disk drives.

Disk Operating System (DOS):

Is an operating system that runs from a hard disk drive.

Disk scrubbing:

The DS8000 periodically reads all sectors on a disk. This reading is designed to occur without any interference with application performance. If Error Correction Code (ECC) detects correctable bad bits, the bits are corrected immediately. This ability reduces the possibility of multiple bad bits accumulating in a sector beyond the ability of ECC to correct them. If a sector contains data that is beyond ECC's ability to correct, RAID is used to regenerate the data and write a new copy onto a spare sector of the drive. This scrubbing process applies to drives that are array members and spares.

Disk Storage Feature Activation (DSFA):

The Data Storage Feature Activation (DSFA) application provides feature activation codes and license keys to technically activate functions acquired for IBM storage products.

Distributed Network Block Device (DNBD):

Uses UDP as its transport protocol, and thus supports multicasting, client-side caching, and server redundancy. It only supports RO exports.

Distributed ledger technology (DLT):

Allow their users to store and access information relating to a given set of assets and their holders in a shared database of either transactions or account balances. This information is distributed among users who could then use it to settle their transfers of, for example, securities and cash, without needing to rely on a trusted central validation system.

DNS:

See Domain Name System.

Domain:

- 1) That part of a computer network in which the data processing resources are under common control.
- 2) In TCP/IP, the naming system used in hierarchical networks.

Domain Name System (DNS):

In TCP/IP, the server program that supplies name-to-address translation by mapping domain names to Internet addresses. The address of a DNS server is the Internet address of the server that hosts the DNS software for the network.

DOS:

See Disk Operating system.

Dotted decimal notation:

A convention used to identify IP addresses. The notation consists of four 8-bit numbers written in base 10. For example, 9.113.76.250 is an IP address that contains the octets 9, 113, 76, and 250.

DRAM:

See Dynamic Random Access Memory.

Drawer:

A unit that contains multiple drive modules and provides power, cooling, and related interconnection logic to make the drive modules accessible to attached host systems.

Drive:

A drive can be either a magnetic drive or a Solid State Drive (SSD).

A field replaceable unit that consists of a single drive and its associated packaging.

DS CLI:

See Data Set Command Line Interface.

DS Network Interface (DSNI):

See Enterprise Storage Server Network Interface.

DS8000 series:

See IBM DS8000.

DS8000 Storage Management GUI:

See IBM DS Storage Manager.

Dual In-line Memory Module (DIMM):

Is a double SIMM (Single In-Line Memory Module). It's a module containing one or several Random Access Memory (RAM) chips on a small circuit board with pins that connect it to the computer motherboard. A DIMM has a 168-pin connector and supports 64-bit data transfer.

Duplex:

- 1) Regarding Copy Services, the state of a volume pair after Remote Mirror and Copy has completed the copy operation and the volume pair is synchronized.
- 2) In general, pertaining to a communication mode in which data can be sent and received at the same time.

Dynamic Address Translation (DAT):

When a virtual address is used by a CPU to access main storage, it is first converted by Dynamic Address Translation (DAT) to a real address and then by prefixing, to an absolute address.

Dynamic CHPID Management (DCM):

Provides the ability to have the system dynamically manage ESCON and FICON Bridge (FICON converter, or FCV) connected to DASD subsystems, based on the current work load and its service goals.

Dynamic Partition Manager (DPM):

Is a guided management interface in the HMC that can be used to define the IBM Z hardware and virtual infrastructure, including integrated dynamic I/O management that runs a KVM for IBM Z Systems environment.

Dynamic Random Access Memory (DRAM):

A type of memory that is typically used for data or program code that a computer processor needs to function. DRAM is a common type of Random Access Memory (RAM) used in Personal Computers (PCs), workstations and servers. Random access allows the PC processor to access any part of the memory

directly rather than having to proceed sequentially from a starting place. RAM is located close to a computer's processor and enables faster access to data than storage media such as hard disk drives and solid-state drives.

Dynamic volume expansion:

The capability of the storage system to increase the capacity of host volumes up to a maximum size while online.

F

EAM:

See Extent Allocation Method.

EAV:

See Extended Address Volume.

Easy Tier:

Is a built-in dynamic data relocation feature that allows the host-transparent movement of data among the storage system resources. This feature significantly improves configuration flexibility and performance tuning and planning.

EC:

See Engineering Change.

ECC:

See Error Correction Code.

See Elliptic Curve Cryptography.

ECKD:

See Extended Count Key Data.

eDRAM:

See Embedded DRAM.

ElectroStatic Discharge (ESD):

An undesirable discharge of static electricity that can damage equipment and degrade electrical circuitry.

Elliptic Curve Cryptography (ECC):

Cryptographic capabilities that are designed to provide public key support for constrained digital environments.

Embedded DRAM (eDRAM):

Is Dynamic Random Access Memory (DRAM) integrated on the same die or Multi-Chip

Module (MCM) of an Application-Specific Integrated Circuit (ASIC) or microprocessor. eDRAM's cost-per-bit is higher when compared to equivalent standalone DRAM chips used as external memory, but the performance advantages of placing eDRAM onto the same chip as the processor outweigh the cost disadvantages in many applications.

Emergency Power Off (EPO):

A means of turning off power during an emergency, usually a switch.

EMIF:

See ESCON Multiple Image Facility.

Enclosure:

A unit that houses the components of a storage subsystem, such as a control unit, disk drives, and power source.

Encrypt:

In Cryptographic Support, to systematically scramble information so that it cannot be read without knowing the coding key. See also *decrypt*.

Encryption:

In computer security, the process of transforming data into an unintelligible form in such a way that the original data either cannot be obtained or can be obtained only by using a decryption process.

Encryption algorithm:

An algorithm that scrambles the data so that it becomes unreadable to someone who intercepts it.

Encryption group:

Indicates whether encryption is enabled (select 1) or disabled (select None) for ranks.

Enhanced Network Block Device (ENBD):

Is being pushed along by one active developer; there is a mailing list that sees a couple of messages a month. ENBD extends NBD adding an automatic restart if the connection is lost, authentication, and support for removable media.

Extended Address Volume (EAV):

This term refers to a volume with more than 65520 cylinders. Only 3390 Model A devices can be an EAV.

Engineering change:

An update to a machine, part, or program.

Enterprise Service Bus (ESB):

It implements a communication system between mutually interacting software applications in a service-oriented architecture (SOA)

Enterprise Systems Architecture/390 (ESA/390):

An IBM architecture for mainframe computers and peripherals. Processor systems that follow the ESA/390 architecture include the ES/9000 family. See also *z/Architecture*.

Enterprise Class configuration:

A high-density, high-performance storage configuration that includes standard disk enclosures and high-performance flash enclosures and is optimized and configured for performance and throughput, by maximizing the number of device adapters and paths to the storage enclosures.

Enterprise Storage Server Network Interface (ESSNI):

Is the logical server that communicates with the DS GUI server and interacts with the two processor nodes of the DS8880. Also referred to as DS Network Interface (DSNI).

Enterprise Systems Connection (ESCON):

- 1) An IBM Z computer peripheral interface. The I/O interface uses IBM Z logical protocols over a serial interface that configures attached units to a communication fabric.
- 2) A set of IBM products and services that provide a dynamically connected environment within an enterprise.

Entropy Encoding:

Is a lossless data compression scheme that is independent of the specific characteristics of the medium.

EPS:

See Emergency Power Off.

ERDS:

See Error-Recording Data Set.

Error Correction Code (ECC):

Checks read or transmitted data for errors and corrects them as soon as they are found. ECC is similar to parity checking except that it corrects errors immediately upon detection.

Error-Recording Data Set (ERDS):

On IBM Z hosts, a data set that records data-storage and data-retrieval errors. A Service Information Message (SIM) provides the error information for the ERDS.

Error recovery procedure:

Procedures designed to help isolate and, where possible, to recover from errors in equipment. The procedures are often used in conjunction with programs that record information on machine malfunctions.

SSB:

See Enterprise Service Bus.

ESCD:

See ESCON Director.

ESCON:

See Enterprise System Connection.

ESCON channel:

An IBM Z channel that supports ESCON protocols.

ESCON Director (ESCD):

An I/O interface switch that allows the interconnection of multiple ESCON interfaces in a distributed-star topology.

ESCON host systems:

IBM Z hosts that attach to the DS8000 series with an ESCON adapter. Such host systems run on operating systems that include z/OS, VSE, TPF, or versions of VM.

ESCON Multiple Image Facility (EMIF):

For IBM Z, a function that enables LPARs to share an ESCON channel path by providing

each LPAR with its own channel-subsystem image.

EsconNet:

In the DS8000 Storage Management GUI, the label on a pseudo host icon that represents a host connection that uses the ESCON protocol and that is not completely defined on DS8000 series. See also pseudo host and access-any mode.

ESD:

See ElectroStatic Discharge.

ESE:

See Extent Space-Efficient.

ESSNet:

See IBM Enterprise Storage Server Network.

ESSNI:

See Enterprise Storage Server Network Interface.

Evaluation Assurance Level (EAL):

The Evaluation Assurance Level (EAL1 through EAL7) of an IT product or system is a numerical grade assigned following the completion of a Common Criteria security evaluation, an international standard in effect since 1999. The increasing assurance levels reflect added assurance requirements that must be met to achieve Common Criteria certification. The intent of the higher levels is to provide higher confidence that the system's principal security features are reliably implemented. The EAL level does not measure the security of the system itself, it simply states at what level the system was tested.

Extended Count Key Data (ECKD):

An extension of the Count Key Data (CKD) architecture.

Extended Addressing Space (EAS):

On an extended address volume, this term refers to cylinders with addresses that are equal to or greater than 65,536. These cylinder addresses are represented by 28-bit cylinder numbers.

Extended Address Volume (EAV):

A volume with more than 65,520 cylinders. An extended address volume increases the amount of addressable DASD storage per volume beyond 65,520 cylinders by changing how tracks on ECKD (Extended Count Key Data) volumes are addressed.

Extent:

A continuous space on a disk that is occupied by or reserved for a particular data set, data space, or file. The unit of increment is a track. See also *multiple allegiance* and *parallel* access volumes.

Extent Allocation Method (EAM):

Defines how volumes extents are allocated on the ranks in the Extent Pool.

Extent pool:

A group of extents. See also extent.

Extent Space-Efficient:

A thin-provisioning method in which capacity is allocated in a performance efficient manner on a per extent basis in pool or ESE repository if one is created on an as-needed basis.

Extent Space Efficient (ESE) volumes:

Are the actual thin provisioned volumes that can be used by host applications. The dynamic allocation increments for ESE logical volumes is based on the same existing 1 GB extents used for standard volumes.

F

Fabric:

In Fibre Channel technology, a routing structure, such as a switch, receives addressed information and routes to the appropriate destination. A fabric can consist of more than one switch. When multiple Fibre Channel switches are interconnected, they are said to be cascaded.

Failback:

Pertaining to a cluster recovery from failover following repair. See also *failover*.

Failover:

Pertaining to the process of transferring all control to a single cluster when the other cluster

in the storage system fails. See also *cluster* and *failback*.

Fast File System (FFS):

FFS invented cylinder groups, which break the disk up into smaller chunks, with each group having its own inodes and data blocks.

Fast write:

A write operation at cache speed that does not require immediate transfer of data to a disk drive. The subsystem writes the data directly to cache, to nonvolatile storage, or to both. The data is then available for destaging. A fast-write operation reduces the time an application must wait for the I/O operation to complete.

FBA:

See Fixed-Block Architecture.

FC:

See feature code.

Note: *FC* is a common abbreviation for Fibre Channel in the industry, but the DS8000 customer documentation library reserves *FC* for feature code.

FC:

See Fibre Channel.

FC-AL:

See Fibre Channel Arbitrated Loop.

FCP:

See Fibre Channel Protocol.

FCS:

See Fibre Channel standard.

Feature Code (FC):

A code that identifies a particular orderable option and that is used by service personnel to process hardware and software orders. Individual optional features are each identified by a unique feature code.

Fibre Channel (FC):

A data-transmission architecture based on the ANSI Fibre Channel standard, which supports full-duplex communication. DS8000 series supports data transmission over fiber-optic cable through its Fibre Channel adapters. See

also Fibre Channel Protocol and Fibre Channel standard.

Fibre Channel Arbitrated Loop (FC-AL):

An implementation of the Fibre Channel Standard that uses a ring topology for the communication fabric. Refer to American National Standards Institute (ANSI) X3T11/93-275. In this topology, two or more Fibre Channel end points are interconnected through a looped interface. This topology directly connects the storage system to an open systems host without going through a fabric switch.

Fibre Channel Connection (FICON):

A Fibre Channel communications protocol that is designed for IBM mainframe computers and peripherals. It connects the storage system to one or more IBM Z hosts using a FICON z/OS channel either directly or through a FICON switch.

Fibre Channel Protocol (FCP):

A protocol used in Fibre Channel communications with five layers that define how Fibre Channel ports interact through their physical links to communicate with other ports. FCP (Fibre Channel Protocol) supports access to Small Computer System Interface (SCSI) peripheral devices.

Fibre Channel Standard (FCS):

An ANSI standard for a computer peripheral interface. The I/O interface defines a protocol for communication over a serial interface that configures attached units to a communication fabric. The protocol has two layers. The IP layer defines basic interconnection protocols. The upper layer supports one or more logical protocols (for example, FCP for SCSI command protocols and SBCON for IBM Z command protocols). Refer to American National Standards Institute (ANSI) X3.230-199x.

Fibre Channel Switched Fabric (FC-SF):

An implementation of the Fibre Channel Standard that connects the storage system to one or more open systems hosts through a fabric switch or connects one or more z/OS hosts that run LINUX on a Fibre Channel Protocol z/OS channel.

FICON:

See Fibre Channel CONnection.

FiconNet:

In the DS8000 Storage Management GUI, the label on a pseudo host icon that represents a host connection that uses the FICON protocol and that is not completely defined on DS8000 series. See also *pseudo host* and *access-any mode*.

Field Replaceable Unit (FRU):

An assembly that is replaced in its entirety when any one of its components fails. In some cases, a field replaceable unit might contain other field replaceable units.

File Transfer Protocol (FTP):

In TCP/IP, an application protocol used to transfer files to and from host computers. See also *Transmission Control Protocol/Internet Protocol*.

Firewall:

A protection against unauthorized connection to a computer or a data storage system. The protection is usually in the form of software on a gateway server that grants access to users who meet authorization criteria.

Fixed Block Architecture:

An architecture for logical devices that specifies the format of and access mechanisms for the logical data units on the device. The logical data unit is a block. All blocks on the device are the same size (fixed size). The subsystem can access them independently.

Flag parameter:

An integer flag that indicates whether the match needs to be performed on the supplied project name or number.

Flash cards:

Are high2-IOPS (Input/Output Operations Per Second) class enterprise storage devices that are targeted at Tier 0, I/O-intensive workload

applications that can use a high level of fast-access storage.

FlashCopy:

FlashCopy is an IBM feature supported on various IBM storage devices that made it possible to create, nearly instantaneously, point-in-time snapshot copies of entire logical volumes or data sets. The copies are immediately available for both read and write access.

FlashCopy relationship:

A mapping of a FlashCopy source volume and a FlashCopy target volume that allows a point-in-time copy of the source volume to be copied to the target volume. FlashCopy relationships exist from the time that you initiate a FlashCopy operation until the storage system copies all data from the source volume to the target volume or until you delete the FlashCopy relationship, if it is persistent.

FlashCopy SE:

An optional feature of DS8880 series that allocates storage space on an 'as-needed' basis and uses only the required number of tracks to write changed data during the lifetime of the FlashCopy relationship.

Flash Raid Adapter:

An adapter that manages external I/O interfaces that use Fibre Channel protocols for host-system attachment. It is also used for replicating data between storage systems.

Flexible Service Processor (FSP):

Firmware that provides diagnostics, initialization, configuration, run-time error detection, and correction. FSP is what connects the managed system to the Hardware Management Console (HMC).

Floating spare:

When a DDM fails and the data it contained is rebuilt onto a spare, then when the disk is replaced, the replacement disk becomes the spare. The data is not migrated to another DDM, such as the DDM in the original position the failed DDM occupied. The DS8000

microcode takes this idea one step further. It might choose to allow the hot spare to remain where it has been moved, but it can instead choose to migrate the spare to a more optimum position. This will be done to better balance the spares across the DA pairs, the loops, and the disk enclosures.

FMID:

See Function Modification Identifier.

Frame:

The hardware support structure, covers, and all electrical parts mounted therein that are packaged as one entity for shipping.

FREE command (In UNIX):

Use the FREE command to release (deallocate) previously allocated data sets or Hierarchical File System (HFS) files that you no longer need. You can also use this command to change the output class of SYSOUT data sets to delete attribute lists, and to change the data set disposition specified with the ALLOCATE command. There is a maximum number of data sets that can be allocated to you at any one time.

FRU:

See Field Replaceable Unit.

FSP:

See Flexible Service Processor.

FTP:

See File Transfer Protocol.

Full duplex:

See duplex.

Full Disk Encryption (FDE):

Is the encryption of all data on a disk drive, including the program that encrypts the bootable operating system partition. It is performed by disk encryption software or hardware that is installed on the drive during manufacturing or from an additional software driver. FDE converts all device data into a form that can be only understood by the one who has the key to decrypt the encrypted data. An authentication key is used to reverse

conversion and render the data readable. FDE prevents unauthorized drive and data access.

Fully provisioned:

The volume capacity is entirely allocated at the time the volume is created. In this case, the host to which the fully provisioned volume is attached owns the full capacity, therefore consuming unused storage in the back-end system.

Function Modification Identifier (FMID):

An identifier that is used to identify a separate product or function of a product.

Fuzzy copy:

A function of the Global Copy feature wherein modifications to the primary logical volume are performed on the secondary logical volume at a later time. The original order of update is not strictly maintained. See also *Global Copy*.



GB:

See gigabyte.

GiB:

See gibibyte.

GDPS:

See Geographically Dispersed Parallel Sysplex.

Geographically Dispersed Parallel Sysplex (GDPS):

Is a multi-site or single-site end to end application availability solution that provides the capability to manage remote copy configuration and storage subsystems (including IBM TotalStorage Enterprise Storage Server) to automate Parallel Sysplex operation tasks and perform failure recovery from a single point of control. GDPS helps automate recovery procedures for planned and unplanned outages to provide near-continuous availability and disaster recovery capability.

Gigabyte (GB):

A base-10 unit of measurement equal to 1,000,000,000 bytes (10^9). A *decimal* gigabyte (GB) is used as a measure of capacity. A *binary* gigabyte (or gibibyte [GiB]) is used as a measure of memory.

Gibibyte (GiB):

A base-2 unit of measurement equal to 1,073,741,824 bytes (2^30).

Note: A GiB is used as a measure of memory and is also known as a *binary* gigabyte.

Gigapack:

Connects to the drive adapter (in DS8000) through Fibre Channel protocol and converts to SAS protocol through the control card switch in the RAID adapter.

Global Copy:

An optional capability of the DS8000 remote mirror and copy feature that maintains a fuzzy copy of a logical volume on the same DS8000 storage system or on another DS8000 storage system. In other words, all modifications that any attached host performs on the primary logical volume are also performed on the secondary logical volume at a later point in time. The original order of update is not strictly maintained. See also *Remote Mirror and Copy* and *Metro Mirror*.

Global Mirror:

An optional capability of the remote mirror and copy feature that provides a 2-site extended distance remote copy. Data that is written by the host to the storage system at the local site is automatically maintained at the remote site. See also *Metro Mirror* and *Remote Mirror* and *Copy*.

Global Network Block Device (GNBD):

Is the basis for GFS (the Global file system).

Global Resource Serialization (GRS):

Is the component within the IBM z/OS operating system responsible for enabling fair access to serially reusable computing resources, such as datasets and tape drives or virtual resources, such as lists, queues, and control blocks.

Group:

In DS8000 documentation, a nickname for two different kinds of groups, depending on the context. See also *disk pack* or *Copy Services* server group.

GRUB:

GNU GRUB (short for GNU GRand Unified Bootloader) is a boot loader package from the GNU Project. GRUB is the reference implementation of the Free Software Foundation's Multiboot Specification, which provides a user the choice to boot one of multiple operating systems installed on a computer or select a specific kernel configuration available on a particular operating system's partitions.

Guests (VM):

A guest virtual machine (guest VM) is the software component of a virtual machine (VM), an independent instance of an operating system (called a guest operating system) and its associated software and information. A VM guest can be a Linux, z/OS, z/VSE, or another z/VM operating system.

GUI (graphical user interface):

A way of communicating with a computer by manipulating icons (pictures) and windows with a mouse. A device that makes a program more user friendly.

Н

HACMP:

See High Availability Cluster Multi-Processing.

Hard disk drive:

- 1) A storage medium within a storage server used to maintain information that the storage server requires.
- 2) A mass storage medium for computers that is typically available as a fixed disk (such as the disks used in system units of personal computers or in drives that are external to a personal computer) or a removable cartridge.

Hardware:

Is the collection of physical parts of a computer system.

Hardware Configuration Definition (HCD):

Defines the I/O configurations to both the software and hardware from a single, interactive interface. HCD is used to create an Input/Output Definition File (IODF).

Hardware Management Console (HMC):

A system that controls managed systems, including the management of logical partitions and use of capacity Upgrade on Demand. Using service applications, the HMC communicates with managed systems to detect and consolidate information, which is then sent to IBM for analysis.

Hardware service manager:

An option on a IBM i host that enables the user to display and work with system hardware resources and to debug input-output processors (IOP), input-output adapters (IOA), and devices.

HCD:

See Hardware Configuration Definition.

hdisk:

An AIX term for storage space.

Heartbeat:

A status report sent at regular intervals from the DS8000 storage system. The service provider uses this report to monitor the health of the call home process. See also *call home*, and *remote technical assistance information network*.

HELP command (In UNIX):

Use the **HELP** command to obtain information about the function, syntax, and operands of commands and subcommands, as well as information about certain messages.

Hierarchical storage management:

A function in storage management software, such as IBM Spectrum Control or Data Facility Storage Management Subsystem/MVS (DFSMS/MVS), that automatically manages free space based on the policy that the storage administrator sets.

Hierarchical File System (HFS):

HFS is a proprietary file system developed by Apple Inc. for use in computer systems running Mac OS.

High Availability Cluster Multi-Processing (HACMP):

Is an older term for PowerHA (High Availability). PowerHA is a special piece of software, which can provide redundancy and high availability to meet the needs in case of a system failure by having another system immediately take over.

High Performance FICON for IBM Z (zHPF):

Is an enhancement of the FICON channel architecture. You can reduce the FICON channel I/O traffic impact by using zHPF with the FICON channel, the z/OS operating system, and the control unit. zHPF allows the control unit to stream the data for multiple commands back in a single data transfer section for I/Os that are initiated by various access methods, which improves the channel throughput on small block transfers.

High-Performance Flash Enclosure (HPFE):

Contains flash cards, which are PCIe-connected to the I/O enclosures.

Hipersocket:

Mainframe HiperSockets is a technology that provides high-speed TCP/IP connectivity within a central processor complex. It eliminates the need for any physical cabling or external networking connection between servers running in different LPARs.

Hop:

Interswitch connection. A hop count is the number of connections that a particular block of data traverses between source and destination. For example, data traveling from one hub over a wire to another hub traverses one hop.

Host:

See host system.

Host Adapter (HA):

A physical subunit of a storage server that provides the ability to attach to one or more host I/O interfaces.

Host name:

The Internet address of a machine in the network. The host name can be entered in the host definition as the fully qualified domain name of the attached host system, such as mycomputer.city.company.com, or as the subname of the fully qualified domain name, for example, mycomputer. See also *host system*.

Host processor:

A processor that controls all or part of a user application network. In a network, the processing unit in which the data communication access method resides. See also *host system*.

Host system:

A computer, either of the mainframe (for example, IBM Z) or of the open-systems type, that is connected to DS8000 series. Hosts are connected through ESCON, FICON, or Fibre Channel interfaces.

HMC:

See Hardware Management Console.

HTTP:

See Hypertext Transfer Protocol.

Huffman Coding:

is a lossless data compression algorithm. The idea is to assign variable-length codes to input characters, lengths of the assigned codes are based on the frequencies of corresponding characters.

HyperPAV:

An optional licensed function that you can use in conjunction with the Parallel Access Volumes (PAV) function. IBM HyperPAV associates the volumes with either an alias address or a specified base logical volume number. When a host system requests IBM HyperPAV processing and the processing is enabled, aliases on the logical subsystem are placed in an IBM HyperPAV alias access state on all logical paths with a given path group ID. IBM HyperPAV is only supported on FICON channel paths.

HyperSwap:

The HyperSwap technology enables the host to transparently switch an application's I/O operations to the secondary Metro Mirror volumes, provided physical connectivity exists between the host and the secondary storage subsystem. This affords the ability to provide continuous operations from a single site or from multiple locations within metro distances. By implementing HyperSwap, disk failures and maintenance functions can be endured without incurring any interruption to the application service.

Hypertext Transfer Protocol (HTTP):

Is an application protocol for distributed, collaborative, and hypermedia information systems. HTTP is the foundation of data communication for the World Wide Web.

Hypervisor:

Is a piece of computer software, firmware, or hardware that creates and runs virtual machines. A computer on which a hypervisor runs one or more virtual machines is called a host machine, and each virtual machine is called a guest machine. The hypervisor presents the guest operating systems with a virtual operating platform and manages the execution of the guest operating systems.

I

laaS:

See Infrastructure as a Service.

IBF:

See Internal Battery Feature.

IBM i:

The IBM licensed program that is the integrated operating system for Power Systems servers. It integrates such functions as relational database, security, web services, networking, and storage management capabilities. The predecessor to IBM i was i5/OS, which was preceded by Operating System/400 (OS/400).

IBM (International Businesses Machine):

The brand name used to identify storage products from IBM, including DS8000 series. See also *DS8000* and *DS Storage Manager*.

IBM DS8000:

A member of the IBM Resiliency Family of storage servers and attached storage devices (drive modules). The DS8000 series storage product delivers high-performance, fault-tolerant storage and management of enterprise data, affording access through multiple concurrent operating systems and communication protocols. High performance is provided by multiple symmetrical multiprocessors, integrated caching, RAID support for the drive modules, and disk access through a high-speed serial storage architecture interface.

IBM DS8880 Series (DS8884, DS8886, DS8888):

New IBM DS8880 family of data systems architected and built for the cognitive business. IBM DS8884: Business class system. Enables organizations to overcome storage challenges with advanced, easy-to-use operations and 24x7 availability for running critical workloads, either as a dedicated platform for consolidated systems or for multiple platforms. Delivered within an affordable, flexible, and space-saving package. Up to 256 GB cache, 64 x 16 GB Fibre Channel/FICON ports and up to 768 HDD/SSD drives, plus 120 flash cards. IBM DS8886: Enterprise class system. Helps accelerate mission-critical applications, backed by 24x7 availability, and superior functionality, all provided in an easily scalable package. Up to 2 TB total system memory, 128 x 16 GB Fibre Channel/FICON ports and up to 1,536 HDD/SSD drives, plus 240 flash cards. IBM DS8888: Enterprise class system. Delivers mission-critical performance and lower latency for applications with up to 4.5 times better performance through an all-flash configuration. Up to 2 TB total system memory, 128 x 16 GB Fibre Channel/FICON ports and up to 480 flash cards.

IBM DS CLI:

The Command-Line Interface (CLI) that works with DS8000 storage subsystems.

IBM DS Storage Manager (DS8000 Storage Management GUI):

Software with a web-browser interface for configuring DS8000 series.

IBM MQ:

IBM MQ is a family of network software products that IBM launched for the first time as an IBM product in December 1993. It was originally called MQSeries, and was renamed WebSphere MQ in 2002 to join the suite of WebSphere products. In April 2014, it was renamed IBM MQ. The products that are included in the MQ family are IBM MQ, IBM MQ Advanced, IBM MQ Appliance, and IBM MQ for z/OS.

IBM Multipath Subsystem Device Driver (SDD):

IBM software that provides multipath configuration support for a host system that is attached to storage devices. SDD provides enhanced data availability, dynamic input/output load balancing across multiple paths, and automatic path failover protection.

IBM POWER8 Processor:

POWER8 is a family of superscalar symmetric multiprocessors based on the Power Architecture.

Systems based on POWER8 became available from IBM in June 2014.

IBM Resiliency Family:

A set of hardware and software features and products, as well as integrated software and services that are available on the DS8000 series and the IBM TotalStorage Enterprise Storage Server, Models 750 and 800.

IBM Spectrum Control:

An interface that allows administrators to configure, manage, and monitor the performance of SAN storage devices from a single console.

IBM Enterprise Storage Server Network (ESSNet)

A private network providing web browser access to the Enterprise Storage Server. IBM installs the ESSNet software on an IBM

workstation called the IBM TotalStorage ESS Master Console, supplied with the first ESS delivery.

IBM Z:

The IBM family of products, which emphasizes near-zero downtime and includes System z10 and System z10s.

ICKDSF (Device Support Facility):

The z/OS ICKDSF utility performs functions needed for the installation, use, and maintenance of IBM direct-access storage devices (DASD). Also used to perform service functions, error detection, and media maintenance. The ICKDSF utility is used primarily to initialize disk volumes. At a minimum, this process involves creating the disk label record and the volume table of contents (VTOC). ICKDSF also can scan a volume to ensure that it is usable, can reformat all the tracks, can write home addresses, as well as other functions.

ICF:

See Internal Coupling Facility.

ICON:

A picture representing something that exists on the computer.

IEBCOMPR:

IEBCOMPR is a z/OS data set utility that is used to compare two sequential data sets, two partitioned data sets, or two Partitioned Data Sets Extended (PDSE) at the logical record level to verify a backup copy.

IEBCOPY:

IEBCOPY is a z/OS data set utility that is used to copy or merge members between one or more partitioned data sets, or Partitioned Data Sets Extended (PDSE), in full or in part.

IEBDG:

IEBDG is a z/OS data set utility that is used to provide a pattern of test data to be used as a programming debugging aid.

IEBGENER:

The IEBGENER utility is a z/OS copy program that is part of the operating system. It is used to copy a sequential data set, a member of a Partitioned Data Set (PDS), or PDSE.

IEBIMAGE:

IEBIMAGE is a z/OS data set utility that creates and maintains specific printer type modules and stores them in a library.

IEBPTPCH:

IEBPTPCH is used to print or punch all, or selected portions of a sequential data set or PDSE.

IEBUPTE:

IEBUPTE is used to create or modify sequential or partitioned data sets, or PDSE.

IEFBR14:

IEFBR14 is a dummy program, normally inserted in JCL when the only desired action is allocation or deletion of data sets.

IEHINITT:

EHINITT is a z/OS system utility used to place standard volume label sets onto any number of magnetic tapes mounted on one or more tape units.

IEHLIST:

IEHLIST is a z/OS system utility used to list entries in the directory of one or more partitioned data sets or PDSEs, or entries in an indexed or non-indexed volume table of contents. Any number of listings can be requested in a single execution of the program.

IEHMOVE:

IEHMOVE is a z/OS system utility used to move or copy logical collections of operating system data.

IEHPROGM:

IEHPROGM is a z/OS system utility that is used to modify system control data and to maintain data sets at an organizational level.

IFL:

See Integrated Facility for Linux.

IFHSTATR:

IFHSTATR is a system utility that formats and prints information from Type 21 SMF (system management facilities) records. These records provide error statistics by volume (ESV) data.

image:

See storage image.

IML:

See Initial Microcode Load.

Information Management System (IMS):

Is a database and transaction management system.

Information Management System transaction manager (IMS TM):

Is a message-based transaction processor.

Information Technology (IT):

Is the use of computers to store, retrieve, transmit, and manipulate data, or information, often in the context of a business or other enterprise.

Integrated Coupling Facility (ICF):

These processors run only Licensed Internal Code. They are not visible to normal operating systems or applications. A coupling facility is, in effect, a large memory scratch pad used by multiple systems to coordinate work. ICFs must be assigned to LPARs that then become coupling facilities.

Infrastructure as a Service (laaS):

Is a form of cloud computing that provides virtualized computing resources over the Internet. IaaS is one of three main categories of cloud computing services, alongside Software as a Service (SaaS) and Platform as a Service (PaaS).

Initial Microcode Load (IML):

The action of loading microcode for a computer into that computer's storage.

Initial Program Load (IPL):

The action of loading software into a computer, typically an operating system that controls the computer.

Initiator:

A SCSI device that communicates with and controls one or more targets. Contrast with *target*.

Inode:

An inode is a data structure on a filesystem on Linux and other UNIX-like operating systems that stores all the information about a file except its name and its actual data. A data structure is a way of storing data so that it can be used efficiently.

Input/Output (I/O):

Pertaining to (a) input, output, or both or (b) a device, process, or channel involved in data input, data output, or both.

I/O Adapter:

A generic term for an electronic circuit, expansion card, or plug-in module that accepts input and generates output in a particular format. The 'adapter' part of the term means that a conversion of the data format and electronic timing takes place between the input/output streams and the internal computer circuits.

Input/Output Configuration Data Set (IOCDS):

A configuration definition built by the I/O Configuration Program (IOCP) and stored on disk files associated with the processor controller.

Input/Output Definition File (IODF):

Created by HCD (Hardware Configuration Definition) and contains information about the I/O configuration, such as: Operating system data, Switch data, Device data, including EDT definition, Processor data, Partition data, Channel path data, Control unit data, and Channel subsystem data.

I/O enclosure:

The I/O enclosures hold the adapters and provide connectivity between the adapters and the processors. Both device adapters and host adapters are installed in the I/O enclosure.

In-stream procedure:

Are procedures whose JCL statements are placed within the job executing them. The beginning of an in-stream procedure must be marked by a PROC statement, its ending by a PEND statement. In-stream procedures must be defined before they can be used, meaning the procedure definition must precede its invocation.

Integrated Facility for Linux (IFL):

This is a normal processor with one or two instructions disabled that are used only by z/OS. Linux does not use these instructions and can be executed by an IFL. Linux can be executed by a CP as well. The difference is that an IFL is not counted when specifying the model number of the system. This can make a substantial difference in software costs.

Intelligent Resource Director:

Intelligent Resource Director (IRD) is software that automates the management of CPU resources and certain I/O resources.

Intelligent Write Caching (IWC):

Improves performance through better write cache management and a better destaging of order of writes.

Interactive mode:

The interactive command mode provides a history function that makes repeating or checking prior command usage easy to do. Log on to the DS CLI application at the directory where it is installed, and begin using the DS CLI commands and parameters.

Interactive System Productivity Facility (ISPF):

Is a software product for the z/OS operating system that runs on IBM mainframes. ISPF primarily provides an IBM 3270 terminal interface with a set of panels. Each panel may include menus and dialogs to run tools on the underlying Time Sharing Option (TSO). ISPF is frequently used to manipulate z/OS data sets from its Program Development Facility named ISPF/PDF, where PDF refers to Program Development Facility.

Interface cards:

Provide the connection between storage devices and the internal processors and memory.

Interleave:

To automatically create two striped partitions across the drives in a RAID-5 array, both of which use the Count-Key-Data (CKD) record format.

Internal Battery Feature (IBF):

The Internal Battery Feature (IBF) is an optional feature on many of the IBM Z family processors. The IBF provides a local uninterrupted power source and further enhances the robustness of the power design present in the mainframe and increases a mainframe's immunity to power line disturbance. It provides battery backup power to preserve processor data during a loss of power on all power feeds from the computer room. The IBF can hold power briefly during a brownout, or for orderly shutdown if there is a longer outage. The IBF will not be available on the IBM z14 Model ZR1 which introduces customers to another consideration when planning a new build or upgrade to this machine.

Internal Coupling Facility:

Provides a cost effective means for getting started in DB2 data sharing. Additionally, if the ICFs are configured with internal links, there can be a performance benefit over external coupling facilities.

Internet Protocol (IP):

In the Internet suite of protocols, a protocol without connections that routes data through a network or interconnecting networks and acts as an intermediary between the higher protocol layers and the physical network. The upper layer supports one or more logical protocols (for example, a SCSI-command protocol and IBM Z command protocol). Refer to ANSI X3.230-199x. The IP acronym is the IP in TCP/IP. See also *Transmission Control Protocol/Internet Protocol*.

Invalidate:

To remove a logical data unit from cache memory because it cannot support continued access to the logical data unit on the device. This removal might be the result of a failure within the storage server or a storage device that is associated with the device.

I/O:

See Input/Output.

I/O Adapter (IOA):

An input-output adapter on the PCI bus.

IOCDS:

See Input/Output Configuration Data Set.

IOCP (I/O Configuration Program):

A program that defines to a system all the available I/O devices and channel paths.

I/O interface:

An interface that enables a host to perform read and write operations with its associated peripheral devices.

Input/Output Operations Per Second (IOPS):

Is the standard unit of measurement for the maximum number of reads and writes to non-contiguous storage locations.

I/O ports:

It allows the software drivers to communicate with hardware devices on a computer.

I/O Priority Manager (IOPM):

Constantly monitors and balances system resources to help applications meet their performance targets automatically, without operator intervention. Allows increased priority for Critical I/O. The IO Priority manager extends the IBM Z System WorkLoad Manager functionality to include storage. With this feature, the system administrator can use zWLM to manage all computing resources.

I/O priority queuing:

Allows the DS8000 series to use I/O priority information provided by the z/OS Workload Manager to manage the processing sequence of I/O operations.

IOPS:

See Input/Output Operations Per Second.

IP:

See Internet Protocol.

IPL:

See Initial Program Load.

IRD:

See Intelligent Resource Director.

ISPF Shell (ISHELL):

The ISHELL command invokes the ISPF panel interface to z/OS UNIX System Services. ISHELL is a good starting point for users familiar with TSO and ISPF who want to use z/OS UNIX.

IT:

See Information Technology.

IWC:

See Intelligent Write Caching.

J

Java:

Is a general-purpose computer programming language that is concurrent, class-based, object-oriented, and specifically designed to have as few implementation dependencies as possible.

Java Virtual Machine (JVM):

A software implementation of a processor that runs compiled Java code (applets and applications).

Job Control Language (JCL):

JCL is the language used by a batch job to request resources and services from the operating system.

Job Entry System (JES):

In the z/OS operating system, JES manages the input and output job queues and data. Each JES2 processor controls its own job input, job scheduling, and job output processing.

Centralized control over processing through a single global JES3 processor, which does job selection, scheduling, and device allocation on the other JES3 systems.

JVM:

See Java Virtual Machine.

K

KB:

See kilobyte.

Kernel:

The kernel is the central module of an operating system. It is the part of the operating system that loads first, and it remains in main memory.

Kernel-based Virtual Machine (KVM):

Is a virtualization infrastructure for the Linux kernel that turns it into a hypervisor. It was merged into the Linux kernel mainline in kernel version 2.6.20, which was released on February 5, 2007. KVM requires a processor with hardware virtualization extensions.

See kilobyte.

Key field:

The second (optional) field of a count key data record. The key length is specified in the count field. The key length determines the field length. The program writes the data in the key field and uses the key field to identify or locate a given record. The subsystem does not use the key field.

Keyword operand (In UNIX):

Keyword operands are specific names or symbols that are recognized by the system. Therefore, keyword operands can be entered in any order following the positional operands. In the upcoming command descriptions, keyword operands are shown in uppercase characters. You can specify values with some keyword operands. Enclose the values in parentheses following the operand.

Kilobyte (KB):

- 1) For processor storage, real, and virtual storage, and channel volume, 2¹⁰ or 1024 bytes.
- 2) For disk storage capacity and communications volume, 1000 bytes.

Korn shell:

Interactive command interpreter and a command programming language.

L

Large Form Factor (LFF):

3.5-inch hard disk drives (HDDs). The measurement represent the approximate diameter of the platter within the drive enclosures.

Large Volume Support (LVS):

Expands the CKD (Count Key Data) volumes to 65,520 cylinders using the existing 16-bit cylinder addressing.

LAN:

See Local Area Network.

LBA:

See Logical Block Address.

LCU:

See Logical Control Unit.

LDAP:

See Lightweight Directory Access Protocol.

Least Recently Used (LRU):

The LRU caching scheme is to remove the least recently used frame when the cache is full and a new page is referenced which is not there in cache.

LED:

See Light-Emitting Diode.

Legacy view:

A hardware or software view that has been superseded.

LFF:

See Large Form Factor.

Libvirt:

Is an open source API, daemon, and management tool for managing platform virtualization. It can be used to manage KVM, Xen, VMware ESX, QEMU, and other virtualization technologies. These APIs are widely used in the orchestration layer of hypervisors in the development of a cloud-based solution.

LIC:

See License Internal Code.

LICCC:

See Licensed Internal Code Configuration Control

License key:

Is a data string that verifies authorized software product access. This type of software security helps prevent software piracy and gives organizations the ability to protect their software from unauthorized copying or sharing by unlicensed users.

License Internal Code (LIC):

Software that enables the hardware on a server. It is controlled by the System Flexible Service Processor (FSP). It initializes the hardware so that a system boots up and operates correctly and provides the interface for the operating system to interact with the hardware.

Licensed Internal Code Configuration Control (LICCC):

Provides for server upgrades without hardware changes by activation of additional (previously installed) unused capacity.

Licensed Machine Code (LMC):

Microcode that IBM does not sell as part of a machine, but licenses to the customer. LMC is implemented in a part of storage that is not addressable by user programs. Some IBM products use it to implement functions as an alternate to hard-wired circuitry.

Lightweight Directory Access Protocol (LDAP):

Defines a standard method to access and update information in a directory.

Light-Emitting Diode (LED):

A semiconductor chip that displays visible or infrared light when activated.

Link address:

On an ESCON interface, the portion of a source or destination address in a frame that ESCON uses to route a frame through an ESCON director. ESCON associates the link address with a specific switch port that is on the ESCON director. Equivalently, it associates the link address with the channel subsystem or control unit link-level functions that are attached to the switch port.

Link-level facility:

The ESCON hardware and logical functions of a control unit or channel subsystem that allow communication over an ESCON write interface and an ESCON read interface.

Linux:

Is system software that manages computer hardware and software resources and provides common services for computer programs.

LinuxONE:

Built on IBM Z technology and designed for Linux-only environments. The LinuxONE Emperor, which is built on the IBM z13 mainframe and its z13 CPU, and its little brother, Rockhopper, which uses the older z12 processor.

LISTALC command (In UNIX):

Use the **LISTALC** command to obtain a list of the currently allocated data sets. **LISTALC** without operands displays a list of all currently allocated data set names.

LISTCAT command (In UNIX):

Use the **LISTCAT** command to list entries from a catalog. The entries listed can be selected by name or entry type, and the fields to be listed for each entry can additionally be selected.

LISTDS command (In UNIX):

Use the LISTDS command to have the attributes of specific data sets displayed at your terminal. The LISTDS command works differently for VSAM than for non-VSAM data sets. A VSAM data set causes the LISTDS command to display only the data set organization, which is VSAM. Use the LISTCAT command to obtain more information about a VSAM data set.

Local Area Network (LAN):

A computer network located on a user's premises within a limited geographic area.

Log Structured File System (LFS):

LFS is a file system in which data and metadata are written sequentially to a circular buffer, called a log.

Logical Block Address (LBA):

The address assigned by DS8000 series to a sector of a disk.

Logical Control Unit (LCU):

An LCU is equivalent to a Logical SubSystem (LSS). Like an LSS, an LCU can have a maximum of 256 logical devices or volumes.

Logical device:

The facilities of a storage server (such as DS8000 series) associated with the processing of I/O operations directed to a single host-accessible emulated I/O device. The associated storage is referred to as a logical volume. The logical device is mapped to one or more host-addressable units, such as a device on IBM Z I/O interface or a logical unit on a SCSI I/O interface, such that the host initiating I/O operations to the I/O-addressable unit interacts with the storage on the associated logical device.

Lightweight Directory Access Protocol (LPAP):

Is a protocol, which makes directory information available.

Logical Partition (LPAR):

For IBM Z, a set of functions that create the programming environment in which more than one Logical PARtition (LPAR) is established on

a processor. An LPAR is conceptually like a virtual machine environment except that the LPAR is a function of the processor. Also, the LPAR does not depend on an operating system to create the virtual machine environment. (DS8000 series only).

Logical path:

- 1) The relationship between a channel image and a control-unit image that designates the physical path to be used for device-level communications between these images. The logical path is established as part of the channel and control-unit initialization procedures by the exchange of link-level frames.
- 2) With the Remote Mirror and Copy feature, the relationship between a source logical subsystem (LSS) and a target LSS that is created over a physical path through the interconnection fabric that is used for Remote Mirror and Copy functions. An LSS is a primary control unit, which performs the functions of a channel image.

Logical Subsystem (LSS):

A topological construct that consists of a group of up to 256 logical devices. A DS8000 storage system can have (if CDK only) up to 32 CKD-formatted logical subsystems (8192 CKD logical devices) or (if FBA only) up to 32 fixed-block logical subsystems (8192 fixed-block logical devices). If mixed CKD and FBA, DS8000 series can have up to 16 CKD-formatted logical subsystems (4096 CKD logical devices) and up to 16 fixed-block logical subsystems (4096 fixed-block logical devices). The logical subsystem facilitates configuration of DS8000 series and might have other implications relative to the operation of certain functions. There is a one-to-one mapping between a CKD logical subsystem and IBM Z control-unit image.

For IBM Z hosts, a logical subsystem represents a Logical Control Unit (LCU). Each control-unit image is associated with only one logical subsystem. See also *control-unit image*.

Logical unit:

In open systems, a logical disk drive.

Logical Unit Number (LUN):

In the SCSI protocol, a unique number that is used on a SCSI bus to enable it to differentiate between separate devices, each of which is a logical unit. The logical unit number reported to the host by the storage system. The host uses the LUN to identify the volume for SCSI commands.

Logical volume:

The storage medium that is associated with a logical disk drive. A logical volume typically resides on one or more storage devices. The DS8000 administrator defines this unit of storage. The logical volume, when residing on a RAID-formatted array, is spread over the drives in the array.

Logical Volume Manager (LVM):

A set of system commands, library routines, and other tools that allow the user to establish and control logical volume storage. The LVM maps data between the logical view of storage space and the physical drive module.

Longitudinal Redundancy Check (LRC):

1) A method of error checking during data transfer that involves checking parity on a row of binary digits that are members of a set that forms a matrix. Longitudinal redundancy check is also called a longitudinal parity check.
2) A mechanism that DS8000 series uses for locating errors. The LRC checks the data as it progresses from the host, through theDS8000 controller, into the device adapter, and to the

Longwave cable:

Longwave laser has a wavelength of about 1300nm. Used for distances up to 10K between Fibre Channel switches and bridges.

Loop:

array.

The physical connection between a pair of device adapters in the DS8000 storage system. See also *device adapter*.

LPAR:

See Logical PARtition.

LSS:

See Logical SubSystem.

LUN:

See Logical Unit Number.

LVM:

See Logical Volume Manager.

LXC (Linux Containers):

Is an operating-system-level virtualization method for running multiple isolated Linux systems (containers) on a control host using a single Linux kernel.

LXD:

Is a daemon, which provides a REST API to drive LXC containers. Its main goal is to provide a user experience that's similar to that of virtual machines but using Linux containers rather than hardware virtualization.

M

Machine Reported Product Data (MRPD):

Product data gathered by a machine and sent to a destination such as an IBM support server or RETAIN. These records might include such information as feature code information and product logical configuration information.

Machine code:

A set of instructions executed directly by a computer's Central Processing Unit (CPU).

MacVTap:

MacVTap is a new device driver meant to simplify virtualized bridged networking.

Mainframe:

A computer, usually in a computer center, with extensive capabilities and resources to which other computers may be connected so that they can share facilities. (T)

Management console:

See Hardware Management Console.

Management Information Base (MIB):

- 1) A collection of objects that can be accessed by means of a network management protocol.
- 2) The MIB record conforms to the Open Systems Interconnection (OSI) standard defined by the International Organization for

Standardization (ISO) for the exchange of information. See also *simple network management protocol*.

Master storage system:

The physical unit that controls the creation of consistency groups in a Global Mirror session. The master storage system sends commands to subordinate storage systems. A storage system can be a master for only one Global Mirror session. Contrast with *subordinate storage system*.

Maximum consistency group drain time:

The value in seconds that indicates the maximum time that writes from the local site are delayed to the remote site while the current consistency group is being formed at the remote site. When this time is exceeded, the current attempt to form a consistency group is ended and another attempt is started. If this time is exceeded five times, this maximum time is ignored on the next attempt to form a consistency group. The default value is the larger of four minutes or two times the consistency group interval time if this value is set to zero.

Maximum coordination time:

The value in milliseconds that indicates the maximum time that is allowed for host I/O to be delayed during the coordination of the primary volumes of an Global Mirror session. The default is 50 milliseconds if this value is set to zero.

MB:

See megabyte.

MC:

See Hardware Management Console.

MCM:

See Multi-Chip Module:

MCU:

See Multicylinder Unit.

Medium:

For a storage system, the disk surface on which data is stored.

Megabyte (MB):

- 1) For processor storage, real and virtual storage, and channel volume, 2^{20} or 1 048 576 bytes.
- 2) For disk storage capacity and communications volume, 1 000 000 bytes.

Memory:

Also called storage, is a technology consisting of computer components and recording media used to retain digital data. It is a core function and fundamental component of computers.

MFT:

See Multiprogramming with a fixed number of tasks.

Miscellaneous Equipment Specification (MES):

Any server hardware change (addition, improvement, removal, or any combination of these). The server's serial number does not change. Specific types include the following: Customer-Installable Feature (CIF) MES or Install-By-IBM (IBI) MES.

Metro Global Mirror:

A three-site, high availability, disaster recovery solution. Metro Global Mirror uses synchronous replication to mirror data between a local site and an intermediate site, and asynchronous replication to mirror data from an intermediate site to a remote site. A cascaded solution where Metro Mirror synchronously copies data to the target site. This Metro Mirror target is the source volume for Global Mirror that asynchronously copies data to a third site. This solution has the potential to provide a disaster recovery with no data loss at Global Mirror distances when the intermediate site does not participate in the disaster that occurs at the production site.

Metro Mirror:

A function of a storage server that maintains a consistent copy of a logical volume on the same storage server or on another storage server. All modifications that any attached host initiates on the primary logical volume are also processed

on the secondary logical volume. See also Remote Mirror and Copy and Global Copy.

MIB:

See Management Information Base.

Microcode:

A technique that imposes an interpreter between the hardware and the architectural level of a computer. As such, the microcode is a layer of hardware-level instructions that implement higher-level machine code instructions or internal state machine sequencing in many digital processing elements. Microcode is used in general-purpose Central Processing Units (CPUs), as well as in more specialized processors. and in other hardware. Microcode typically resides in special high-speed memory and translates machine instructions, state machine data, or other input into sequences of detailed circuit-level operations. It separates the machine instructions from the underlying electronics so that instructions can be designed and altered more freely. It also facilitates the building of complex multi-step instructions, while reducing the complexity of computer circuits.

Microsoft Hyper-V:

Code named Viridian and formerly known as Windows Server Virtualization, is a native hypervisor; it can create virtual machines on x86-64 systems running Windows.

Migration:

The replacement of a system or subsystem with a different type of system or subsystem, such as replacing a SCSI host adapter with a Fibre Channel host adapter. In the context of data migration regarding DS8000 series, the transfer of data from one storage system to another, such as from a 3390 to DS8000 series.

MIH:

See Missing-Interrupt Handler.

Million Service Units (MSUs):

Is a measurement of the amount of processing work a computer can perform in one hour. It

reflects how IBM rates the machine in terms of charging capacity.

Mirrored pair:

Two units that contain the same data. The system refers to them as one entity.

Mirroring:

In host systems, the process of writing the same data to two disk units within the same auxiliary storage pool at the same time.

MLAG:

See Multi-link Aggregation.

MRPD:

See Machine Reported Product Data.

MSUs:

See Million Service Units.

MySQL:

Is a freely available open source Relational Database Management System (RDBMS) that uses Structured Query Language (SQL).

Multi-Chip Module (MCM:

Is an electronic assembly (such as a package with a number of conductor terminals or "pins") where multiple integrated circuits, semiconductor dies and/or other discrete components are integrated, usually onto a unifying substrate, so that in use it is treated as if it were a single component.

Multicylinder Unit (MCU):

This term refers to a fixed unit of disk space that is larger than a cylinder. Currently, on an EAV, a multicylinder unit is 21 cylinders and the number of the first cylinder in each multicylinder unit is a multiple of 21.

Multipath Subsystem Device Driver:

See IBM DS8000 Multipath Subsystem Device Driver.

Multi-link Aggregation (MLAG):

Enables arrangement of aggregated groups on two separate switchboards of the MLAG-domain.

Multiple allegiance:

A DS8000 hardware function that is independent of software support. This function enables multiple system images to concurrently access the same logical volume on DS8000 series as long as the system images are accessing different extents. See also extent and parallel access volumes.

Multiple relationship FlashCopy:

An option of DS8000 series that creates backup copies from one source to multiple targets by simultaneously establishing multiple FlashCopy relationships.

Multiplex:

The action of transmitting simultaneously.

Multiprocessor:

A computer that includes two or more processors that have common access to a main storage. For DS8000 series, the multiprocessors operate in parallel.

Multiprogramming with a fixed number of tasks (MFT):

Each job gets just the amount of memory it needs. That is, the partitioning of memory changes as jobs enter and leave. MVT is a more efficient user of resources.

Multiprogramming variable number of tasks (MVT):

Is a feature of large computers that allows more efficient operation by having multiple programs (tasks) present and operating in the mainframe computer simultaneously.

Multiple Virtual Systems (MVS):

Was the most commonly used operating system on the System/370 and System/390 IBM mainframe computers.

N

Name server:

A server that stores names of the participating DS8000 clusters.

NAS:

See Network Attached Storage.

NBD:

See Network Block Device.

Near-line:

A type of intermediate storage between online storage (which provides constant, rapid access to data) and off-line storage (which provides infrequent data access for backup purposes or long-term storage).

Network Attached Storage (NAS):

Is a file-level computer data storage server connected to a computer network providing data access to a heterogeneous group of clients. NAS is specialized for serving files either by its hardware, software, or configuration.

Network Block Device (NBD):

Is a device node whose content is provided by a remote machine. Typically, network block devices are used to access a storage device that does not physically reside in the local machine but on a remote one.

Network File System (NFS):

Is a client/server application that lets a computer user view and optionally store and update files on a remote computer as though they were on the user's own computer.

Network Interface Card (NIC):

A network interface controller (NIC, also known as a network interface card, network adapter, LAN adapter or physical network interface, and by similar terms) is a computer hardware component that connects a computer to a computer network.

Network manager:

A program or group of programs that is used to monitor, manage, and diagnose the problems of a network.

Network Time Protocol (NTP):

Is a networking protocol for clock synchronization between computer systems over packet-switched, variable-latency data networks. In operation since before 1985, NTP is one of the oldest Internet protocols in current use.

Node:

The unit that is connected in a Fibre Channel network. DS8000 series is a node in a Fibre Channel network.

Non-removable medium:

A recording medium that cannot be added to or removed from a storage device.

NonVolatile Storage (NVS):

Memory that stores active write data to avoid data loss in the event of a power loss.

NVS:

See NonVolatile Storage.

N+1 redundancy:

Is a form of resilience that ensures system availability in the event of component failure. Components (N) have at least one independent backup component (+1).



Octal:

Octal, from Latin octo or "eight") is a term that describes a base-8 number system. An octal number system consists of eight single-digit numbers: 0, 1, 2, 3, 4, 5, 6, and 7.

OMVS:

The first implementation was known as MVS OpenEdition (or OE, or OMVS), then it became OS/390 UNIX System Services, and finally z/OS UNIX System Services, as we know it today.

OMVS command:

Is used to invoke the z/OS UNIX shell. Users whose primary interactive computing environment is a UNIX system should find the z/OS UNIX shell environment familiar. The OMVS command is used to invoke the z/OS UNIX shell. The shell is a command processor that invokes shell commands or utilities that request services from the system, writes shell scripts using the shell programming language and runs shell scripts and C-language

programs interactively (in the foreground), in the background, or in batch.

OnLine Transaction Processing (OLTP):

A class of information systems that facilitate and manage transaction-oriented applications, typically for data entry and retrieval transaction processing. OLTP has also been used to refer to processing in which the system responds immediately to user requests.

OpenFlow:

Is a protocol that allows a server to tell network switches where to send packets. In a conventional network, each switch has proprietary software that tells it what to do. With OpenFlow, the packet-moving decisions are centralized, so that the network can be programmed independently of the individual switches and data center gear.

OpenStack:

Is a set of software tools for building and managing cloud computing platforms for public and private clouds. Backed by some of the biggest companies in software development and hosting, as well as thousands of individual community members, many think that OpenStack is the future of cloud computing.

Open source software:

Open source refers to a program or software in which the source code (the form of the program when a programmer writes a program in a particular programming language) is available to the general public for use and/or modification from its original design free of charge. Open source code is typically created as a collaborative effort in which programmers improve upon the code and share the changes within the community.

Open system:

A system whose characteristics comply with standards made available throughout the industry and that therefore can be connected to other systems complying with the same standards. Applied to DS8000 series, such systems are those hosts that connect to

DS8000 series through SCSI or FCP protocols. See also *small computer system interface* and *Fibre Channel Protocol*.

Open System Adapter (OSA):

Is the only LAN (Local Area Network) attachment to the IBM Systems.

Open vSwitch (OVS):

Open vSwitch is a production quality, multilayer virtual switch licensed under the open source Apache 2.0 license. It is designed to enable massive network automation through programmatic extension, while still supporting standard management interfaces and protocols.

Operating System (OS):

Is system software that manages computer hardware and software resources and provides common services for computer programs.

Open Systems / 390: (OS/390):

Is an IBM operating system for the System/390 IBM mainframe computers.

P

PaaS:

See Platform As A Service.

PAM:

See Pluggable Authentication Module.

Panel:

The formatted display of information that appears on a display screen.

Parallel Access Volume (PAV):

A licensed function of DS8000 series that enables z/OS systems to issue concurrent I/O requests against a count key data logical volume by associating multiple devices of a single control-unit image with a single logical device. Up to eight device addresses can be assigned to a PAV. The PAV function enables two or more concurrent write operations to the same logical volume, as long as the write operations are not to the same extents.

Parallel Sysplex License Charge (PSLC):

Charges for Parallel Sysplex licenses.

Parity:

A data checking scheme used in a computer system to ensure the integrity of the data. The RAID implementation uses parity to re-create data if a disk drive fails.

Partitioned Data Set (PDS):

Is a data set containing multiple members, each of which holds a separate sub-data set, similar to a directory in other types of file systems.

Partitioned Data Set Extended (PDSE):

Is a data set type that is managed by DFSMS. Externally, a PDSE is very similar to a PDS. Internally, the PDSE has a different directory structure, member format, and record format. A PDSE is indistinguishable from a PDS through most interfaces used to access a PDS directory or member. All ISPF functions support the PDSE.

Path group:

In IBM Z architecture, a set of channel paths that are defined to a control unit as being associated with a single Logical PARtition (LPAR). The channel paths are in a group state and are online to the host. See also *logical partition*.

PAV:

See Parallel Access Volumes.

PCHID:

See Physical Channel Path Identifier.

PCI:

See Peripheral Component Interconnect.

PCIe:

See Peripheral Component Interconnect Express.

PDF:

See Program Development Facility.

PDS:

See Partitioned Data Set.

PDSE:

See Partitioned Data Set Extended.

PDU:

See Protocol Data Unit.

PDU:

See Power Distribution Unit.

Peripheral Component Interconnect (PCI):

An architecture for a system bus and associated protocols that supports attachments of adapter cards to a system backplane.

Peripheral Component Interconnect Express (PCIe or PCIe):

Is a serial expansion bus standard for connecting a computer to one or more peripheral devices. PCle provides lower latency and higher data transfer rates than parallel busses such as PCl and PCl-X. Every device that's connected to a motherboard with a PCle link has its own dedicated point-to-point connection. This means that devices are not competing for bandwidth because they are not sharing the same bus.

Peer-to-Peer Remote Copy (PPRC):

Is a protocol to replicate a storage volume to another control unit in a remote site. Synchronous PPRC causes each write to the primary volume to be performed to the secondary as well, and the I/O is only considered complete when update to both primary and secondary have completed. Asynchronous PPRC will flag tracks on the primary to be duplicated to the secondary when time permits.

Performance Groups:

Are used to assign a numerical value to a performance policy.

Peripheral:

Is defined as any auxiliary device such as a tape drive, disk drive, mouse, or keyboard that connects to and works with the computer in some way.

Persistent FlashCopy:

A state where a FlashCopy relationship remains indefinitely until the user deletes it. The

relationship between the source and target volumes is maintained after a background copy completes.

PFI:

See Predictive Failure Analysis.

Physical Channel Path Identifier (PCHID):

Specifies a physical channel identifier related to their physical location.

Physical path:

A single path through the I/O interconnection fabric that attaches two units. For Copy Services, this is the path from a host adapter on one DS8000 storage system (through cabling and switches) to a host adapter on another DS8000 storage system.

Pinned data:

Data that is held in cache until either an error condition is corrected and it can be moved to disk storage or until the data is discarded by a host command. Pinned data conditions can only occur on an ESS Model 800 during fast-write or dual-copy functions.

PKI:

See Public Key Infrastructure.

Platform As A Service (PaaS):

Platform as a service (PaaS) or application platform as a service (aPaaS) is a category of cloud computing services that provides a platform allowing customers to develop, run, and manage applications without the complexity of building and maintaining the infrastructure typically associated with developing and launching an app. PaaS can be delivered in two ways: As a public cloud service from a provider, where the consumer controls software deployment with minimal configuration options, and the provider provides the networks, servers, storage, operating system, middleware, database, and other services to host the consumer's application; or as a private service (software or appliance) inside the firewall, or as software deployed on a public infrastructure as a service.

Pluggable Authentication Module (PAM):

A mechanism to integrate multiple low-level authentication schemes into a high-level API. It allows programs that rely on authentication to be written independently of the underlying authentication scheme.

Point-to-point connection:

A Fibre Channel topology that enables the direct interconnection of ports. See also arbitrated loop and switched fabric.

Port:

A physical connection on a host adapter to the cable that connects the DS8000 storage system to hosts, switches, or another DS8000 storage system. DS8000 series uses SCSI and ESCON host adapters that have two ports per adapter, and Fibre Channel host adapters that have one port. See also ESCON, Fibre Channel, host adapter, and small computer system interface.

Portable Operating System Interface (POSIX):

POSIX is a set of standard operating system interfaces based on the UNIX operating system.

Positional operands (In UNIX):

Positional operands follow the command name in a certain order. In the command descriptions within this topic, the positional operands are shown in lowercase characters. When you enter a positional operand that is a list of several names or values, you must enclose the list within parentheses.

PostgreSQL:

Often simply Postgres, is an object-relational database management system (ORDBMS) with an emphasis on extensibility and standards compliance. As a database server, its primary functions are to store data securely and return that data in response to requests from other software applications. It can handle workloads ranging from small single-machine applications to large Internet-facing applications (or for data warehousing) with many concurrent users; on macOS Server, PostgreSQL is the default

database; and it is also available for Microsoft Windows and Linux.

Power Distribution Unit (PDU):

A type of electrical component that distributes and manages electricity supply to computers, servers, and networking devices within a data center environment. It provides a central unit to control and distribute electricity across the data center components. Power distribution units are also known as Main Distribution Units (MDUs).

Power Supply Unit (PSU):

Converts mains AC to low-voltage regulated DC power for the internal components of a computer.

PPS:

See Primary Power Supply.

Predictive Failure Analysis (PFA):

Can anticipate certain forms of failures by keeping internal statistics of read and write errors. If the error rates exceed predetermined threshold values, the drive is nominated for replacement. Because the drive has not yet failed, data can be copied directly to a spare drive. This copy ability avoids the use of RAID recovery to reconstruct all of the data onto the spare drive.

Preventive Service Planning (PSP):

Is formation, which contains the latest information that is applicable to machine's hardware and software. PSP information should be reviewed before all system installs, hardware, and software updates. PSP information is provided by the IBM software support center to use when installing a licensed program, cumulative PTF packages, or hardware. It can also be used to order preventive service planning information and review the recommended High Impact PERvasive (HIPER) fixes periodically or to order the HIPER PTF group. The HIPER PTF group is updated every other week.

Primary control program (PCP):

The program which provides the sequential scheduling of jobs and basic operating systems functions.

Primary control unit:

The DS8000 storage system to which a Remote Mirror and Copy primary device is physically attached.

Primary Power Supply (PPS):

A wide range power supply that converts AC input voltage into DC voltage.

PRINTDS command (In UNIX):

Use the **PRINTDS** command to format and print data sets on any printer defined to the Job Entry Subsystem (JES).

Processor:

The key component of a computing device that contains the circuitry necessary to interpret and execute electrical signals fed into the device. Its basic job is to receive input and provide the appropriate output. Also referred to as CPU or core.

Processor complex:

The set of hardware that defines a mainframe, which includes the central processing units, memory, channels, controllers, and power supplies included in the box. Also known as 'Central Electronics Complex (CEC)'.

Processor node:

A partition of a storage server that is capable of performing all defined functions of the storage server. Multiple processor complexes provide redundancy.

Processor Resource System Manager (PR/SM):

Is a type-1 Hypervisor (a virtual machine monitor) that allows multiple logical partitions to share physical resources such as CPUs, I/O channels and direct access storage devices (DASD). It is integrated with all IBM Z mainframes.

Processor Unit (PU):

All of the processors in the CPC begin as equivalent processor units (PUs) or engines

that have not been characterized for use. Each processor is characterized by IBM during installation or at a later time.

The potential characterizations are:

- Central Processor (CP)
- System Assistance Processor (SAP)
- Integrated Facility for Linux (IFL)
- z Application Assist Processor (zAAP)
- The System z9 Integrated Information Processor (zIIP)
- Integrated Coupling Facility (ICF)
- Spare: An uncharacterized PU functions as a spare. If the system controllers detect a failing CP or SAP, it can be replaced with a spare PU. In most cases this can be done without any system interruption, even for the application running on the failing processor.

PROFILE command (In UNIX):

The **PROFILE** command establishes, changes, or lists your user profile. The information in your profile tells the system how you want to use your terminal.

Program:

On a computer, a generic term for software that controls the operation of the computer.

Typically, the program is a logical assemblage of software modules that perform multiple related tasks.

Program Development Facility (PDF):

Provides a panel-driven menu interface and a number of services through which users can work with source code and data stored on a host.

Program Temporary Fix (PTF):

A temporary solution to, or bypass of, a problem diagnosed by IBM as the result of a defect in a current unaltered release of a licensed program.

Promote:

To add a logical data unit to cache memory.

Protocol Data Unit (PDU):

A unit of data specified in the protocol of a given layer and consisting of protocol control information for the layer and, possibly, user data for the layer.

PR/SM:

See Processor Resource System Manager.

Pseudo host:

A host connection that is not explicitly defined to the DS8000 storage system and that has access to at least one volume that is configured on the DS8000 storage system. The FiconNet pseudo host icon represents the FICON protocol. The EsconNet pseudo host icon represents the ESCON protocol. The pseudo host icon labeled Anonymous represents hosts connected through the FCP protocol. Anonymous host is a commonly used synonym for pseudo host. DS8000 series adds a pseudo host icon only when it is set to access-any mode. See also access-any mode.

PSP:

See Preventive Service Planning.

PSU:

See Power Supply Unit.

PTF:

See Program Temporary Fix.

Public Key Infrastructure (PKI):

Supports the distribution and identification of public encryption keys, enabling users and computers to both securely exchange data over networks such as the Internet and verify the identity of the other party.

PV Links:

Short for Physical Volume Links, an alternate pathing solution from Hewlett-Packard that provides for multiple paths to a volume, as well as static load balancing.

Q

qcow2 (QEMU Copy On Write):

Is a file format for disk image files used by QEMU, a hosted virtual machine monitor. It uses a disk storage optimization strategy that

delays allocation of storage until it is actually needed. Files in qcow format can contain a variety of disk images, which are generally associated with specific guest operating systems.

QEMU:

QEMU (short for Quick Emulator) is a free and open-source hosted hypervisor that performs hardware virtualization (not to be confused with hardware-assisted virtualization). QEMU is a hosted virtual machine monitor: it emulates CPUs through dynamic binary translation and provides a set of device models, enabling it to run a variety of unmodified guest operating systems. It also can be used together with KVM in order to run virtual machines at near-native speed (requiring hardware virtualization extensions on x86 machines). QEMU can also do CPU emulation for user-level processes, allowing applications compiled for one architecture to run on another.

Quality of Service (QoS):

An assessment of how well a delivered service conforms to the client's expectations. Service business operators often assess the service quality provided to their customers in order to improve their service, to quickly identify problems, and to better assess client satisfaction.

R

RACF:

See Resource Access Control Facility.

Rack Power Control (RPC) cards:

Manages the DS8000 power subsystem and provide control, monitoring, and reporting functions. RPC cards are responsible for receiving DC-UPS status and controlling DC-UPS functions.

Rack Unit:

Abbreviated as U or RU, is a unit of measure defined as 1.75 inches (44.45mm). It is most frequently used as a measurement of the overall height of 19-inch and 23-inch rack frames, as well as the height of equipment that mounts in these frames, whereby the height of

the frame or equipment is expressed as multiples of rack units.

RAID:

See *redundant array of independent disks*. RAID is also commonly expanded to redundant array of *inexpensive* disks. See also *array*.

RAID 5:

A type of RAID that optimizes cost-effective performance while emphasizing use of available capacity through data striping. RAID 5 provides fault tolerance for up to two failed disk drives by distributing parity across all the drives in the array plus one parity disk drive. DS8000 series automatically reserves spare disk drives when it assigns arrays to a Device Adapter pair (DA pair). See also device adapter, RAID 10, and redundant array of independent disks.

RAID 6:

Any form of RAID that can continue to process read and write requests to all virtual disks of an array in the presence of two concurrent failures. See also device adapter, RAID 5, RAID 10, and redundant array of independent disks.

RAID 10:

A type of RAID that optimizes high performance while maintaining fault tolerance for up to two failed disk drives by striping volume data across several disk drives and mirroring the first set of disk drives on an identical set. DS8000 series automatically reserves spare disk drives when it assigns arrays to a device adapter pair (DA pair). See also device adapter, RAID 5, and redundant array of independent disks.

Random access:

A mode of accessing data on a medium in a manner that requires the storage device to access nonconsecutive storage locations on the medium.

Random Access Memory (RAM):

A type of computer memory that can be accessed randomly; that is, any byte of memory can be accessed without touching the preceding bytes. RAM is the most common

type of memory found in computers and other devices, such as printers.

Rank:

One or more arrays that are combined to create a logically contiguous storage space.

RAS:

See Reliability, Availability, and Serviceability.

Reboot:

Booting is starting a computer's operating system, so rebooting is to start it for a second or third time. Rebooting is usually necessary after a computer crashes, meaning it stops working because of a malfunction. Rebooting allows the computer to restart and get back to working normally. After a crash, the computer is useless until it is rebooted.

Recovery Point Objective (RPO):

The maximum targeted period in which data might be lost from an IT service due to a major incident.

Recovery Time Objective (RTO):

The targeted duration of time and a service level within which a business process must be restored after a disaster (or disruption) in order to avoid unacceptable consequences associated with a break in business continuity.

RECEIVE command (In UNIX):

The **RECEIVE** command is used by the addressee of a file transmission to retrieve transmitted files and to restore them to their original format.

Reduced Instruction Set Computer (RISC):

Is one whose instruction set architecture (ISA) allows it to have fewer cycles per instruction (CPI) than a complex instruction set computer.

Redundant Array of Independent Disks (RAID):

A methodology of grouping disk drives for managing disk storage to insulate data from a failing disk drive.

Redundant Array of Independent Memory (RAIM):

Is a design feature found in certain computers' main random access memory. RAIM utilizes additional memory modules and striping algorithms to protect against the failure of any particular module and keep the memory system operating continuously.

Relative Record Data Set (RRDS):

Has fixed-length slots, predefined to VSAM, in which records can be stored. An RRDS record is always fixed length, equal to the slot size. A record that is in an RRDS is identified by the Relative Record Number (RRN) of the slot that holds it. When a new record is added to an RRDS, VSAM uses the number that you supply with the file control request.

Reliability, Availability, and Serviceability (RAS):

Is a computer hardware engineering term involving reliability engineering, high availability, and serviceability design. Computers designed with higher levels of RAS have many features that protect data integrity and help them stay available for long periods of time without failure, this data integrity and uptime is a particular selling point for mainframes and fault-tolerant systems.

Remote I/O loop (RIO loop):

I/O subsystems are connected to the processor subsystem through Remote I/O cable loops. The cable loops are connected to ports that are available from the rear of the processor subsystem. The RIO cables are connected in loops so that the system has two paths to each I/O subsystem. There are two typical RIO loops: 1) one port of a hub connected to the input port of an I/O drawer, and the output port of this I/O drawer connected to the companion port of the same hub; 2) one port of a hub connected to the input port of an I/O drawer, the output port of this I/O drawer connected to the input port of another I/O drawer, and the output port of the other I/O drawer connected to the companion port of the same hub.

Remote Mirror and Copy:

A feature of a storage server that constantly updates a secondary copy of a logical volume to match changes made to a primary logical volume. The primary and secondary volumes can be on the same storage server or on separate storage servers. See also *Global Mirror*, *Metro Mirror*, and *Global Copy*.

Remote Procedure Call (RPC):

In distributed computing, a remote procedure call (RPC) is when a computer program causes a procedure (subroutine) to execute in a different address space (commonly on another computer on a shared network), which is coded as if it were a normal (local) procedure call, without the programmer explicitly coding the details for the remote interaction.

Reporting task commands:

Used for creating reports.

Resource Access Control Facility (RACF):

A security system that provides access control and auditing functionality for the z/OS and z/VM operating systems.

Resource Management Facility (RMF):

IBM's strategic product for z/OS performance measurement and management. It is the base product to collect performance data for z/OS and sysplex environments to monitor systems' performance behavior and provides the ability to optimally tune and configure the system according to business needs.

REST API:

A REST API defines a set of functions which developers can perform requests and receive responses using HTTP protocol such as GET and POST. Because REST API's use HTTP, they can be used by practically any programming language and easy to test (it's a requirement of a REST API that the client and server are independent of each other allowing either to be coded in any language and improved upon supporting longevity and evolution).

Resource Group:

Define a collection of resources and associate a set of policies relative to how the resources are configured and managed.

RESTful API:

Is an application programming interface (API) that uses HTTP requests to GET, PUT, POST, and DELETE data.

Restructured Extended Executor (REXX):

REXX is an interpreted programming language developed at IBM. It is a structured, high-level programming language designed for ease of learning and reading. Proprietary and open source REXX interpreters exist for a wide range of computing platforms; compilers exist for IBM mainframe computers.

Revolutions Per Minute (RPM):

Used to help determine the access time on computer hard drives. RPM is a measurement of how many revolutions a computer's hard drive makes in a single minute. The higher the RPM, the faster the data will be accessed.

RIO loop:

See Remote I/O loop.

RISC:

See Reduced Instruction Set Computer.

R0:

See track-descriptor record.

Rotate extents:

Distributes the extents of each volume successfully across all ranks in a pool to achieve a well balanced capacity based distribution of the workload. See *Storage Pool Striping*.

Rotate volume:

Reduces the configuration effort compared to single rank extent pools by easily distributing a set of volumes to different ranks in a specific extent pool for workloads where the use of host based stripping methods is still present.

RPC:

See Rack Power Control cards or Remote Procedure Call.

RPM:

See Revolutions Per Minute.

RRDS:

See Relative Record Data Set.

RSA:

Is algorithm used by modern computers to encrypt and decrypt messages. It is an asymmetric cryptographic algorithm.

Asymmetric means that there are two different keys. This is also called public key cryptography, because one of them can be given to everyone. The other key must be kept private. It is based on the fact that finding the factors of an integer is hard (the factoring problem). RSA stands for Ron Rivest, Adi Shamir, and Leonard Adleman, who first publicly described it in 1978.

S

SAF:

See System Access Facility.

SAID:

See System Adapter Identification Number.

SAM:

See Sequential Access Method.

SAN:

See Storage Area Network.

SAP:

See System Assistance Processor.

SARC:

See Sequential Adaptive Replacement Cache.

SAS:

See Statistical Analysis System.

SE:

See Support Element.

Screen:

The physical surface of a display device upon which information is shown to users.

Script command mode:

The main thing to remember here is that the script that DS CLI executes can only contain DS CLI commands.

SCSI:

See Small Computer System Interface.

SCSI device:

A disk drive connected to a host through an I/O interface using the SCSI protocol. A SCSI device is either an initiator or a target. See also *initiator* and *small computer system interface*.

SCSI-FCP:

Synonym for Fibre Channel Protocol, a protocol used to transport data between an open-systems host and a Fibre Channel adapter on a DS8000. See also Fibre Channel Protocol and small computer system interface.

SDD:

See IBM Subsystem Multipathing Device Driver.

SE:

See Support Element.

Secondary control unit:

The DS8000 to which a Remote Mirror and Copy secondary device is physically attached.

Secure Data Overwrite (SDO):

A method of securely overwriting sensitive data in a way that makes the data unreadable.

Secure Hash Algorithm 3 (SHA-3):

A cryptographic hash algorithm (alternatively, hash "function") is designed to provide a random mapping from a string of binary data to a fixed-size "message digest" and achieve certain security properties. Hash algorithms can be used for digital signatures, message authentication codes, key derivation functions, pseudo random functions, and many other security applications

Sector:

An area of a disk that contains the smallest addressable unit of information. When a disk is formatted, the operating system divides it into sectors and tracks. A sector is the theoretically minimal region of the disk upon which data can be read or written at one time.

SEND command (In UNIX):

Use the **SEND** command to send messages to other users. To receive the messages, the recipient's profile setting must include INTERCOM.

Sequential access:

A mode of accessing data on a medium in a manner that requires the storage device to access consecutive storage locations on the medium.

Sequential Adaptive Replacement Cache (SARC):

Is a caching algorithm that allows you to run different workloads, such as sequential and random workloads, without negatively affecting each other.

Sequential Data Set:

In a sequential data set, records are data items that are stored consecutively.

Serial Attached SCSI (SAS):

Full-duplex. Uses the native SCSI command set, which has more functionality. A SAS drive uses SCSI error checking and reporting. This allows your storage system to collect richer information from the drive if errors are occurring (such as a failing or marginal disk). SAS drives are dual ported, which is vital in dual controller enclosures.

Serial connection:

A method of device interconnection for determining interrupt priority by connecting the interrupt sources serially.

Server:

A host that provides certain services to other hosts that are referred to as clients.

A functional unit that provides services to one or more clients over a network.

Server Time Protocol (STP):

Is a server-wide facility that is implemented in the Licensed Internal Code (LIC) and presents a single view of time to Processor Resource/Systems Manager (PR/SM).

Service clearance:

The area that is required to open the service covers and to pull out components for servicing.

Service Information Message (SIM):

A message sent by a storage server to service personnel through an IBM Z operating system.

Service personnel:

A generalization referring to individuals or companies authorized to service the DS8880. The terms *service provider*, *service representative*, and *IBM service representative* refer to types of service personnel. See also *System Services Representative*.

Service provider interface (SPI):

The set of public interfaces and abstract classes that a service defines. The SPI defines the classes and methods available to your application.

SES:

SCSI Enclosure Services.

Session:

A collection of volumes within a logical subsystem that are managed together during the creation of consistent copies of data. All volumes in a session must transfer their data successfully to the remote site before the increment can be called complete.

SFF:

See Small Form Factor.

SFI:

See Storage Facility Image.

SHA-3:

See Secure Hash Algorithm 3.

Shared storage:

Storage that is configured so that multiple hosts can concurrently access the storage. The storage has a uniform appearance to all hosts. The host programs that access the storage must have a common model for the information on a storage device. The programs must be

designed to handle the effects of concurrent access.

Shortwave cable:

Shortwave laser uses a wavelength of approximately 850 nm. Typically used for medium and longer distance connections (up to 500m).

SIM:

See Service Information Message.

Simple Network Management Protocol (SNMP):

In the Internet suite of protocols, a network management protocol that is used to monitor routers and attached networks. SNMP is an application layer protocol. Information on devices managed is defined and stored in the application's Management Information Base (MIB). See also management information base.

Simultaneous Multithreading (SMT):

Is a technique for improving the overall efficiency of superscalar CPUs with hardware multithreading. SMT permits multiple independent threads of execution to better utilize the resources provided by modern processor architectures.

Single-Byte Command Code Sets Connection (SBCON):

The ANSI standard for the ESCON I/O interface.

Single Point Of Failure (SPOF):

A potential risk posed by a flaw in the design, implementation, or configuration of a circuit or system in which one fault or malfunction causes an entire system to stop operating.

Single-shot mode:

Use the DS CLI single-shot command mode if your want to issue an occasional command but do not want to keep a history of the commands that you have issued. When typing the command, you can use the host name or the IP address of the DS HMC. Wait for the command to process and display the end results.

Single Virtual Storage (SVS):

An operating system from IBM. OS/VS2 R1 was known as SVS (Single Virtual Storage) as it had a single 16 MB virtual address space. Takes advantage of virtual memory.

Small Computer System Interface (SCSI):

A standard hardware interface that enables a variety of peripheral devices to communicate with one another.

Smart relay host:

A mail relay or mail gateway that has the capability to correct email addressing problems.

Small Form Factor (SFF):

2.5-inch hard disk drives (HDDs). The measurement represent the approximate diameter of the platter within the drive enclosures.

SMF:

See System Management Facility.

SMP:

See Symmetrical MultiProcessor.

SMT:

See Simultaneous Multithreading.

SNMP:

See Simple Network Management Protocol.

SNMP agent:

A server process that resides on a network node and is responsible for communicating with managers regarding that node. The node is represented as a managed object, which has various fields or variables that are defined in the appropriate MIB.

SNMP manager:

A managing system that runs a managing application or suite of applications. These applications depend on Management Information Base (MIB) objects for information that resides on the managed system. Managers generate requests for this MIB information, and an SNMP agent on the managed system responds to these requests. A request can either be the retrieval or modification of MIB information.

Software:

Is the part of a computer system that consists of encoded information or computer instructions.

Solid State Drive (SSD):

Are high-IOPS (Input/Output Operations Per Second) class enterprise storage devices targeted at business critical production applications that can benefit from high level of fast-access storage.

Source device:

One of the devices in a dual-copy or remote-copy volume pair. All channel commands to the logical volume are directed to the source device. The data on the source device is duplicated on the target device. See also *target device*.

Space efficient volumes:

A space efficient volume does not occupy physical capacity when it is created. Space gets allocated when data is actually written to the volume. The amount of space that gets physically allocated is a function of the amount of data changes that are performed on a volume. The sum of all defined space efficient volumes can be larger than the physical capacity available.

Spare:

A disk drive on the DS8000 that can replace a failed disk drive. A spare can be predesignated to allow automatic dynamic sparing. Any data preexisting on a disk drive that is invoked as a spare is destroyed by the dynamic sparing copy process.

SPI:

See Service provider interface.

SPOF:

See Single Point Of Failure.

SRM:

See Storage Resource Management.

SSD:

See Solid State Drive.

SSID:

See SubSystem IDentifier.

SSPC:

See System Storage Productivity Center.

SSR:

See System Services Representative.

Staging:

To move data from an offline or low-priority device back to an online or higher priority device, usually on demand of the system or on request of the user.

Standard volume:

A volume that emulates one of several IBM Z volume types, including 3390-2, 3390-3, 3390-9, 3390-2 (3380-track mode), or 3390-3 (3380-track mode), by presenting the same number of cylinders and capacity to the host as provided by the native IBM Z volume type of the same name.

Statistical Analysis System (SAS):

Is a software suite developed by SAS Institute for advanced analytics, multivariate analyses, business intelligence, data management, and predictive analytics.

Storage:

Also called memory, is a technology consisting of computer components and recording media used to retain digital data. It is a core function and fundamental component of computers.

Storage Area Network (SAN):

A network that connects a company's heterogeneous storage resources.

Storage capacity:

The amount of data that a storage medium can hold; usually expressed in kilobytes, megabytes, or gigabytes.

Storage complex:

A configuration of one or more storage systems that is managed by a management console.

Storage device:

A physical unit that provides a mechanism to store data on a given medium such that it can be subsequently retrieved.

Storage Facility Image (SFI):

A storage facility image consists of two LPARs, one on each processor complex in a storage facility. A storage facility image is capable of performing all functions of a storage server from the host's perspective. More than one SFI can be configured on a storage facility. A storage facility image might also be referred to as a storage image.

Storage image:

A partitioning of a storage system that provides emulation of a storage server with one or more storage devices that provides storage capability to a host computer. You can configure more than one storage image on a storage system. (DS8000 series only)

Storage pool striping:

Improves overall performance and reduces the effort of performance management by evenly distributing data and workloads across a larger set of ranks, which reduces skew and hot spots. See *Rotate Extents*.

Storage Resource Management (SRM):

Is a proactive approach to optimizing the efficiency and speed with which available drive space is utilized in a Storage Area Network (SAN).

Storage server:

A physical unit that manages attached storage devices and provides an interface between them and a host computer by providing the function of one or more logical subsystems. The storage server can provide functions that the storage device does not provide. The storage server has one or more clusters. A storage server may also be called a file server.

Storage system:

A storage system can include facilities for host attachment, user role authentication, a Command-Line Interface (CLI), a graphical user interface (GUI), and storage devices that most often include Redundant Array of Independent Disks (RAID) controllers. It might also include agents for enabling third-party

management software to monitor or manage the storage devices.

Storage unit:

DS8880 base frame plus installed expansion frames.

STP:

See Server Time Protocol.

Striping:

A data mapping technique for disk arrays in which fixed-length sequences of virtual-disk data addresses are mapped to sequences of member disk addresses in a regular rotating pattern.

SUBMIT command (In UNIX):

Use the **SUBMIT** command to submit one or more batch jobs for background processing.

Subordinate storage system:

The physical unit that receives commands from the master storage system and is specified when a Global Mirror session is started. The subordinate storage system forms consistency groups and performs other Global Mirror processing. A subordinate storage system can be controlled by only one master storage system. Contrast with *master storage system*.

SubSystem IDentifier (SSID):

A number that uniquely identifies a logical subsystem within a computer installation.

SuperPAV (Parallel Access Volume):

SuperPAV extends upon the previous HyperPAV capabilities by enabling alias devices to be used across multiple Logical SubSystems (LSS). An alias device can be used for any base device on the same DS8000 server and in the same path group on the server. SuperPAV will enable performance to be sustained with fewer overall alias devices and offer greater parallelism for individual larger volumes, improving scalability and performance.

Super Zap (SZAP):

SPZAP can list, map, and modify load modules (executable programs) or patch or fix the Volume Table Of Contents (VTOC).

Support Element (SE):

A Support Element is a dedicated workstation used for monitoring and operating a system. It is attached to the central processor complex (CPC) of a system. The Support Element is located inside the same frame that the central processor complex (CPC) is located. An alternate support element is also provided to switch from your primary support element to the alternate Support Element if hardware problems occur.

Switched fabric:

A Fibre Channel topology in which ports are interconnected through a switch. Fabric switches can also be interconnected to support numerous ports on a single network. See also arbitrated loop and point-to-point connection.

System Access Facility (SAF):

Is an interface defined by z/OS that enables programs to use system authorization services to control access to resources, such as data sets and z/OS commands.

System Assistance Processor (SAP):

Every modern mainframe has at least one SAP; larger systems may have several. The SAPs execute internal code to provide the I/O subsystem. An SAP, for example, translates device numbers and real addresses of channel path identifiers (CHPIDs), control unit addresses, and device numbers. It manages multiple paths to control units and performs error recovery for temporary errors. Operating systems and applications cannot detect SAPs, and SAPs do not use any normal memory. SAPs execute commands.

System Management Facility (SMF):

Is a component of IBM's z/OS for mainframe computers, providing a standardized method for writing out records of activity to a file.

Symmetric encryption:

Means that the encryption and decryption operations utilize the same key. For two communicating parties using symmetric encryption for secure communication, the key

represents a shared secret between the two. Symmetric encryption is typically more efficient than asymmetric encryption, and is often used for bulk data encryption.

Symmetric MultiProcessing (SMP):

Is the processing of programs by multiple processors that share a common operating system and memory. In symmetric (or 'tightly coupled') multiprocessing, the processors share memory, and the I/O bus or data path. A single copy of the operating system is in charge of all the processors.

Synchronous write:

A write operation whose completion is indicated after the data has been stored on a storage device.

System Adapter Identification Number (SAID):

The unique identification number that is automatically assigned to each DS8000 host adapter for use by Copy Services.

System Data Mover (SDM):

A DFSMS component that interacts with data storage subsystems and with various advanced copy services functions to efficiently move large amounts of data. As updates occur to primary volumes, the SDM manages the process of copying those updates to secondary volumes. The SDM ensures that updates to secondary volumes are made in the same order in which they were made to the primary volumes, maintaining sequence consistency.

System Management Facilities (SMF):

A component of IBM's z/OS for mainframe computers, providing a standardized method for writing out records of activity to a file or data set.

System Modification Program:

A program used to install software and software changes on z/OS systems.

System p:

The IBM family of products, which emphasizes performance and includes System p5, eServer

p5, eServer pSeries, eServer OpenPower, and RS/6000.

System Services Representative (SSR):

Responsible for performing basic technical services for IBM customers including some or all of the following: element exchange, minor repair, depot or bench maintenance, equipment refurbish, installation, relocation, discontinuance, upgrade and modification, and so on. Services are typically performed in a high volume environment with access to exchangeable units and parts requiring minimum, if any, problem determination activity. Services may be directed by a service call management process or be performed as part of a team.

System Storage Productivity Center (SSPC):

IBM System Storage Productivity Center is an integrated offering that provides a consolidated focal point for managing IBM storage products as well as managing mixed-vendor storage environments. SSPC provides enhancements to daily storage administration by making available a broad set of configuration functions. System Storage Productivity Center's user-friendly interface provides utilities to configure storage devices, and enhancements that offer a wide range of management capabilities.

System x:

The IBM family of products, which emphasizes industry-standard server scalability and self-managing server technologies. It includes System x3nnn, eServer xSeries, and AMD processor-based eServer servers.

Systems Network Architecture (SNA):

SNA is IBM's proprietary networking architecture. It is a complete protocol stack for interconnecting computers and their resources.

Т

Target:

A SCSI device that acts as a subordinate to an initiator and consists of a set of one or more logical units, each with an assigned Logical Unit Number (LUN). The logical units on the target

are typically I/O devices. A SCSI target is analogous to an IBM Z control unit. See also small computer system interface.

Target device:

One of the devices in a dual-copy or remote-copy volume pair that contains a duplicate of the data that is on the source device. Unlike the source device, the target device might only accept a limited subset of data. See also *source device*.

TB:

See terabyte.

TCO:

See Total Cost of Ownership.

TCP/IP:

See Transmission Control Protocol/Internet Protocol.

Telemetry:

OpenStack Telemetry provides user-level usage data for OpenStack-based clouds. The data can be used for customer billing, system monitoring, or alerts. Telemetry can collect data from notifications sent by existing OpenStack components such as Compute usage events, or by polling OpenStack infrastructure resources such as libvirt. Telemetry includes a storage daemon that communicates with authenticated agents through a trusted messaging system to collect and aggregate data. Additionally, the service uses a plug-in system that you can use to add new monitors. You can deploy the API Server, central agent, data store service, and collector agent on different hosts.

Terabyte (TB):

- 1) Nominally, 1 000 000 000 000 bytes, which is accurate when speaking of bandwidth and disk storage capacity.
- 2) For DS8000 cache memory, processor storage, real and virtual storage, a terabyte refers to 2⁴⁰ or 1 099 511 627 776 bytes.

Total Cost of Ownership (TCO):

Is a financial estimate intended to help buyers and owners determine the direct and indirect costs of a product or system.

Tracks:

Are concentric circles around the disk. The operating system and disk drive keep track of where information is stored on the disk by noting the range of track and sector numbers.

Transport Control Word (TCW):

A TCW combines the functions of the Prefix CCW and the Read or Write CCW into a single entity that further reduces channel overhead. Used by z High Performance FICON (zHPF) channel programs.

Time Sharing Option (TSO):

An operating system option that provides interactive time sharing from remote terminals.

Thin provisioning:

A mechanism that provides the ability to define logical volume sizes that are larger than the physical capacity installed on the system. The volume allocates capacity on an as-needed basis as a result of host-write actions.

Tivoli Key Lifecycle Manager (TKLM):

JAVA software program that manages keys enterprise wide and provides encryption enable tape drives with keys for encryption and decryption.

Tivoli Productivity Center for Replication (TPC-R):

Provides support for Metro Mirror and Global Mirror configurations as well as three-site recovery management, supporting IBM System Storage DS8000 Metro Global Mirror and Metro Global Mirror with HyperSwap. It is designed to support fast failover and failback, fast reestablishment of three-site mirroring, data currency at the remote site with minimal lag behind the local site, and quick re-synchronization of mirrored sites using incremental changes only.

TKLM:

See Tivoli Key Lifecycle Manager.

Tivoli Storage Productivity Center (TPC):

The name of the suite of products comprising the Tivoli Storage Productivity Center.

TPF:

See Transaction Processing Facility.

Track:

A unit of storage on a CKD device that can be formatted to contain a number of data records. See also *home address*, *track-descriptor record*, and *data record*.

Track address:

This term refers to a 32-bit number that identifies each track within a volume. It is in the format hexadecimal CCCCcccH, where CCCC is the low order 16 bits of the cylinder number, ccc is the high order 12 bits of the cylinder number, and H is the four-bit track number. For compatibility with older programs, the ccc portion is hexadecimal 000 for tracks in the base addressing space.

Track managed space:

This term refers to the space on a volume that is managed in tracks and cylinders.

Track-managed space ends at cylinder address 65519. Each data set occupies an integral multiple of tracks. Track-managed space also exists on all non-EAVs.

Track Space Efficient (TSE) volumes:

Are used as target volumes of a FlashCopy Space Efficient operation and require the definition of a repository from which tracks are gradually allocated.

Transaction Processing Facility (TPF):

A high-availability, high-performance IBM operating system, designed to support real-time, transaction-driven applications. The specialized architecture of TPF is intended to optimize system efficiency, reliability, and responsiveness for data communication and database processing. TPF provides real-time inquiry and updates to a large, centralized database, where message length is relatively short in both directions, and response time is typically less than three seconds. Formerly known as the Airline Control

Program/Transaction Processing Facility (ACP/TPF).

Transmission Control Protocol (TCP):

A communications protocol used in the Internet and in any network that follows the Internet Engineering Task Force (IETF) standards for internetwork protocol. TCP provides a reliable host-to-host protocol between hosts in packet-switched communications networks and in interconnected systems of such networks. It uses the Internet Protocol (IP) as the underlying protocol.

Transmission Control Protocol/Internet Protocol (TCP/IP):

- 1) A combination of data-transmission protocols that provide end-to-end connections between applications over interconnected networks of different types.
- 2) A suite of transport and application protocols that run over the Internet Protocol. See also *Internet Protocol* and *Transmission Control Protocol*.

TRANSMIT command (In UNIX):

Use the **TRANSMIT** command to send messages, data sets, or both, to another user. The **TRANSMIT** command converts this data into a special format so that it can be transmitted to other users in the network.

Transparency:

See software transparency.

Trusted Key Entry (TKE):

A feature that is a means for ensuring secure creation and management of key material and for managing the crypto adapters on the host.

TSE:

See Track Space Efficient.

TSO:

See Time Sharing Option.

U

UFS:

UNIX Filing System.

Universal Access Authority (UAA):

Each data set profile defined using RACF requires a universal access authority (UACC). The UACC is the default access authority that RACF gives to users and groups that are not defined in the profile's access list. If one of these users or groups requests access to a data set that is protected by the profile, RACF grants or denies the request based on the UACC.

Unit address:

For IBM Z, the address associated with a device on a given control unit. On ESCON interfaces, the unit address is the same as the device address. On OEMI interfaces, the unit address specifies a control unit and device pair on the interface.

Unit Control Block (UCB):

z/OS control block used to define channel attached devices.

UNIX System Services (USS):

UNIX System Services (USS) is a required, included component of z/OS. USS is a certified UNIX operating system implementation optimized for mainframe architecture.

Upper-layer protocol:

The layer of the Internet Protocol (IP) that supports one or more logical protocols (for example, a SCSI-command protocol and an ESA/390 command protocol). Refer to ANSI X3.230-199x.



virsh:

Is a command line interface tool for managing guests and the hypervisor.

Virtual Ethernet Port Aggregator (VEPA):

Data from one endpoint to another endpoint on the same lower device gets sent down the lower device to external switch. If that switch supports the hairpin mode, the frames get sent back to the lower device and from there to the destination endpoint.

Virtualization:

The act of creating a virtual (rather than actual) version of something, including virtual computer hardware platforms, operating systems, storage devices, and computer network resources.

Virtual machine facility:

A virtual data processing machine that appears to the user to be for the exclusive use of that user, but whose functions are accomplished by sharing the resources of a shared data processing system. An alternate name for the VM/370 IBM operating system.

Virtual Local Access Network (VLAN):

Is any broadcast domain that is partitioned and isolated in a computer network at the data link layer. VLANs work by applying tags to network packets and handling these tags in networking systems - creating the appearance and functionality of network traffic that is physically on a single network but acts as if it is split between separate networks. In this way, VLANs can keep network applications separate despite being connected to the same physical network, and without requiring multiple sets of cabling and networking devices to be deployed.

Virtual Machine (VM):

Is an emulation of a computer system. Virtual machines are based on computer architectures and provide functionality of a physical computer.

Virtual Machine Monitor (VMM):

A Virtual Machine Monitor is a software program that enables the creation, management, and governance of virtual machines (VMs) and manages the operation of a virtualized environment on top of a physical host machine.

Virtual Memory:

Virtual memory, or virtual storage, is a feature of an operating system that allows a computer to compensate for shortages of physical memory by temporarily transferring pages of data from Random Access Memory (RAM) to disk storage.

Virtual Private Network (VPN):

is a network that is constructed using public wires, usually the Internet, to connect to a private network, such as a company's internal network.

Vital Product Data (VPD):

Information that uniquely defines the system, hardware, software, and microcode elements of a processing system.

Virtual Storage Access Method (VSAM):

VSAM is a file storage access method used in z/OS operating systems. It is a high performance access method used to organize data in form of files in Mainframes.

Virtual Telecommunications Access Method (VTAM):

VTAM is the IBM subsystem that implements Systems Network Architecture (SNA) for mainframe environments. VTAM provides an application programming interface (API) for communication applications, and controls communication equipment such as adapters and controllers.

VM:

The root name of several IBM operating systems, such as VM/XA, VM/ESA, VM/CMS, and z/VM. See also *virtual machine facility*.

VMware:

VMware provides different software and applications for virtualization. It has become one of the key providers of virtualization software in the industry. VMware's products can be categorized in two levels: desktop applications and server applications.

VMware ESXi:

Formerly ESX, is an enterprise-class, type-1 hypervisor developed by VMware for deploying and serving virtual computers. As a type-1 hypervisor, ESXi is not a software application that one installs in an operating system; instead, it includes and integrates vital operating system components, such as a kernel.

Volume:

For IBM Z, the information recorded on a single unit of recording medium. Indirectly, it can refer to the unit of recording medium itself. On a non removable-medium storage device, the term can also indirectly refer to the storage device associated with the volume. When multiple volumes are stored on a single storage medium transparently to the program, the volumes can be referred to as logical volumes.

Volume group:

A collection of either physical or logical volumes.

Volume Table Of Contents (VTOC):

A table on a Direct Access Storage Device (DASD) volume that describes the location, size, and other characteristics of each data set on the volume.

VPD:

See Vital Product Data.

VSE/ESA:

An IBM operating system, the letters of which represent virtual storage extended/enterprise systems architecture.

VSAM:

See Virtual Storage Access Method.

VTAM:

See Virtual Telecommunications Access Method.

W

Warm demotion:

An operation of IBM Easy Tier automatic mode. The movement of an extent of moderately active data to a lower tier when its tier has exceeded its optimal bandwidth capacity.

Wavelength-Division Multiplexing (WDM):

Is a method of combining multiple signals on laser beams at various Infrared (IR) wavelengths for transmission along fiber optic media. Each laser is modulated by an independent set of signals.

Wavelength-sensitive filters, the IR analog of visible-light color filters, are used at the receiving end.

WebSM (Web-based System Manager):

Is a client/server application that gives the user a powerful interface to manage UNIX systems. Web-based System Manager uses its graphical interface to enable the user to access and manage multiple remote machines.

Weight distribution area:

The area that is required to distribute the weight of the storage system.

Workload Manager (WLM):

Is a base component of the z/OS mainframe operating system. It controls the access to system resources for the work executing on z/OS based on administrator-defined goals.

Worldwide Node Name (WWNN):

A unique 64-bit identifier for a host that contains a Fibre Channel port. See also worldwide port name.

Worldwide port name (WWPN):

A unique 64-bit identifier associated with a Fibre Channel adapter port. It is assigned in an implementation- and protocol-independent manner. See also *worldwide node name*.

WWNN:

See Worldwide Node Name.

WWPN:

See Worldwide Port Name.



XCF:

See Cross-System Coupling Facility.

Xen:

Xen Project is a hypervisor using a micro kernel design, providing services that allow multiple computer operating systems to execute on the same computer hardware concurrently.

XES:

See Cross-System Extended Services.

Extensible Markup Language (XML):

Is a markup language that defines a set of rules for encoding documents in a format that is both human-readable and machine-readable.



Z

z Application Assist Processor (zAAP):

This is a processor with a number of functions disabled (interrupt handling, some instructions) such that no full operating system can be executed on the processor. However, z/OS can detect the presence of zAAP processors and will use them to execute Javacode. The same Java code can be executed on a standard CP. Again, zAAP engines are not counted when specifying the model number of the system. Like IFLs, they exist only to control software costs.Note: zAAPs are not supported on IBM z13, z13s, and the z14 mainframes.

zDAC:

See z/OS Discovery and Auto Configuration.

Integrated Information Processor (zIIP):

Is a specialized engine for processing eligible database workloads. The zIIP is designed to help lower software costs for select workloads on the mainframe, such as business intelligence (BI), enterprise resource planning (ERP) and customer relationship management (CRM). The zIIP reinforces the mainframe's role as the data hub of the enterprise by helping to make direct access to DB2® more cost effective and reducing the need for multiple copies of the data.

zHPF:

See High Performance FICON for IBM Z.

zHPF:

See High Performance FICON for IBM Z.

IBM Z Hypervisor Performance Manager (zHPM):

Monitors virtual machines running on KVM to achieve goal-oriented policy based performance goals.

zKVM (KVM for IBM Z):

A virtualization infrastructure for the Linux kernel that turns it into a hypervisor. It simplifies configuration and operation of server virtualization, leverages common Linux administration skills to administer virtualization, supports flexibility and agility leveraging the open source community, and provides an Open Source virtualization choice.

Zoning:

In Fibre Channel environments, the grouping of multiple ports to form a virtual, private, storage network. Ports that are members of a zone can communicate with each other, but are isolated from ports in other zones.

zSeries File System (ZFS):

zFS is a z/OS UNIX file system that can be used like the Hierarchical File System (HFS). zFS file systems contain files and directories, including Access Control Lists (ACLs), that can be accessed with the z/OS HFS application programming interfaces (APIs).

z/OS:

An operating system for the IBM Z family of products.

z/OS Discovery and Auto Configuration (zDAC):

Designed to automatically run several I/O configuration definition tasks for new and changed disk and tape controllers that are connected to a switch or director, when attached to a FICON channel.

z/OS Global Mirror:

Remote mirror and copy feature for IBM Z environments. A function of a storage server that assists a control program to maintain a consistent copy of a logical volume on another storage system. All modifications of the primary logical volume by any attached host are presented in order to a single host. The host then makes these modifications on the secondary logical volume. This function was formerly called *Extended Remote Copy* or *XRC*.

z/OS Management Facility (Z/OSMF):

Is a product for z/OS that simplifies, optimizes, and modernizes the z/OS system programmer experience

z/TPF:

Is an emulation of a computer system. Virtual machines are based on computer architectures and provide functionality of a physical computer.

z/VM:

A guest virtual machine (guest VM) is the software component of a virtual machine (VM), an independent instance of an operating system (called a guest operating system) and its associated software and information. A VM guest can be a Linux, z/OS, z/VSE, or another z/VM operating system.

z/VSE:

A general-purpose computer programming language that is concurrent, class-based, object-oriented, and specifically designed to have as few implementation dependencies as possible.



