IDL HandiGuide

This quick reference guide contains both a functional and alphabetical listing of all IDL routines. The alphabetical listing contains all functions, procedures, statements, and objects, including the syntax of each. The following information is included in this guide:

Restricted Rights Notice

The IDL® software program and the accompanying procedures, functions, and documentation described herein are sold under license agreement. Their use, duplication, and disclosure are subject to the restrictions stated in the license agreement. Research Systems, Inc., reserves the right to make changes to this document at any time and without notice.

Limitation of Warranty

Research Systems, Inc. makes no warranties, either express or implied, as to any matter not expressly set forth in the license agreement, including without limitation the condition of the software, merchantability, or fitness for any particular purpose.

Research Systems, Inc. shall not be liable for any direct, consequential, or other damages suffered by the Licensee or any others resulting from use of the IDL software package or its documentation.

Permission to Reproduce this Manual

If you are a licensed user of this product, Research Systems, Inc. grants you a limited, non-transferable license to reproduce this particular document provided such copies are for your use only and are not sold or distributed to third parties. All such copies must contain the title page and this notice page in their entirety.

Acknowledgments

Functional Listing

The following is a list of all routines included in IDL 5.4, categorized by functionality.

3D Visualization

3D Transformations & Scene Setup

CONVERT_COORD - Transforms coordinates to and from the coordinate systems supported by IDL.

COORD2TO3 - Returns 3D data coordinates given normalized screen coordinates.

CREATE_VIEW - Sets up 3D transformations.

CV_COORD - Converts 2D and 3D coordinates between coordinate systems.

SCALE3 - Sets up axis ranges and viewing angles for 3D plots.

SCALE3D - Scales 3D unit cube into the viewing area.

SET_SHADING - Sets the light source shading parameters.

SURFR - Sets up 3D transformations by duplicating rotation, translation, and scaling of SURFACE.

T3D - Performs various 3D transformations.

VERT_T3D - Transforms a 3D array by a 4x4 transformation matrix.

VOXEL_PROJ - Generates volume visualizations using voxel technique.

Polygonal Mesh Routines

COMPUTE_MESH_NORMALS - Computes normal vectors for a set of polygons described by the input array.

MESH_CLIP - Clips a polygonal mesh to an arbitrary plane in space and returns a polygonal mesh of the remaining portion.

MESH_DECIMATE - Reduces the density of geometry while preserving as much of the original data as possible.

MESH_ISSOLID - Computes various mesh properties and enables IDL to determine if a mesh encloses space (is a solid).

MESH_MERGE - Merges two polygonal meshes.

MESH_NUMTRIANGLES - Computes the number of triangles in a polygonal mesh..

MESH_OBJ - Generates a polygon mesh for various simple objects.

MESH_SMOOTH - Performs spatial smoothing on a polygon mesh.

MESH_SURFACEAREA - Computes various mesh properties to determine the mesh surface area, including integration of other properties interpolated on the surface of the mesh.

MESH_VALIDATE - Checks for NaN values in vertices, removes unused vertices, and combines close vertices.

MESH_VOLUME - Computes the volume that the mesh encloses.

POLYSHADE - Creates a shaded surface representation from a set of polygons.

Surfaces and Contours

CONTOUR - Draws a contour plot.

IMAGE_CONT - Overlays an image with a contour plot. -

MIN_CURVE_SURF - Interpolates points with a minimum curvature surface or a thin-plate-spline surface. Useful with CONTOUR.

POLAR_CONTOUR - Draws a contour plot from data in polar coordinates.

SHADE_SURF - Creates a shaded-surface representation of gridded data.

SHADE_SURF_IRR - Creates a shaded-surface representation of an irregularly gridded dataset.

SHOW3 - Displays array as image, surface plot, and contour plot simultaneously.

SURFACE - Plots an array as a wireframe mesh surface.

XSURFACE - Provides GUI to SURFACE and SHADE_SURF.

Tetrahedral Mesh Routines

TETRA_CLIP - Clips a tetrahedral mesh to an arbitrary plane in space and returns a tetrahedral mesh of the remaining portion.

TETRA_SURFACE - Extracts a polygonal mesh as the exterior surface of a tetrahedral mesh.

TETRA_VOLUME - Computes properties of tetrahedral mesh array.

Vector Field Visualization

FLOW3 - Draws lines representing a 3D flow/velocity field.

INTERPOL - Performs linear interpolation on vectors.

PARTICLE_TRACE - Traces the path of a massless particle through a vector field.

STREAMLINE - Generates the visualization graphics from a path.

VECTOR_FIELD - Places colored, oriented vectors of specified length at each vertex in an input vertex array.

VEL - Draws a velocity (flow) field with streamlines.

VELOVECT - Draws a 2D velocity field plot.

Volume Visualization

EXTRACT_SLICE - Returns 2D planar slice extracted from volume.

IDLgrVolume - Represents a mapping from a 3D array of data to a 3D array of voxel colors, which, when drawn, are projected to two dimensions.

ISOSURFACE - Returns topologically consistent triangles by using oriented tetrahedral decomposition.

PROJECT_VOL - Returns a translucent rendering of a volume projected onto a plane.

RECON3 - Reconstructs a 3D representation of an object from 2D images.

SEARCH3D - Finds "objects" or regions of similar data values within a volume.

SHADE_VOLUME - Contours a volume to create a list of vertices and polygons that can be displayed using POLYSHADE.

SLICER3 - Interactive volume visualization tool.

VOXEL_PROJ - Generates volume visualizations using voxel technique.

XOBJVIEW - Displays object viewer widget.

XVOLUME - Utility for viewing and interactively manipulating volumes and isosurfaces.

Animation

CW_ANIMATE - Creates a compound widget for animation.

CW_ANIMATE_GETP - Gets pixmap window IDs used by CW_ANIMATE.

CW_ANIMATE_LOAD - Loads images into CW_ANIMATE.

CW_ANIMATE_RUN - Displays images loaded into CW_ANIMATE.

FLICK - Causes the display to flicker between two images.

MPEG_CLOSE - Closes an MPEG sequence.

MPEG_OPEN - Opens an MPEG sequence.

MPEG_PUT - Inserts an image array into an MPEG sequence.

MPEG_SAVE - Saves an MPEG sequence to a file.

XINTERANIMATE - Displays animated sequence of images.

Array Creation

BINDGEN - Returns byte array with each element set to its subscript.

BYTARR - Creates a byte vector or array.

CINDGEN - Returns a complex array with each element set to its subscript.

COMPLEXARR - Creates a complex, single-precision, floating-point vector or array.

DBLARR - Creates a double-precision array.

DCINDGEN - Returns a double-precision, complex array with each element set to its subscript.

DCOMPLEXARR - Creates a complex, double-precision vector or array.

DINDGEN - Returns a double-precision array with each element set to its subscript.

FINDGEN - Returns a floating-point array with each element set to its subscript.

FLTARR - Returns a single-precision, floating-point vector or array.

INDGEN - Return an integer array with each element set to its subscript.

INTARR - Creates an integer vector or array.

L64INDGEN - Returns a 64-bit integer array with each element set to its subscript.

LINDGEN - Returns a longword integer array with each element set to its subscript.

LON64ARR - Returns a 64-bit integer vector or array.

LONARR - Returns a longword integer vector or array.

MAKE_ARRAY - Returns an array of the specified type, dimensions, and initialization.

OBJARR - Creates an array of object references.

PTRARR - Creates an array of pointers.

REPLICATE - Creates an array of given dimensions, filled with specified value.

SINDGEN - Returns a string array with each element set to its subscript.

STRARR - Returns string array containing zero-length strings.

TIMEGEN - Returns an array of double-precision floating-point values that represent times in Julian dates.

UINDGEN - Returns unsigned integer array with each element set to its subscript.

UINTARR - Returns an unsigned integer vector or array.

UL64INDGEN - Returns an unsigned 64-bit integer array with each element set to its subscript.

ULINDGEN - Returns an unsigned longword array with each element set to its subscript.

ULON64ARR - Returns an unsigned 64-bit integer vector or array.

ULONARR - Returns an unsigned longword integer vector or array.

Array Manipulation

ARRAY_EQUAL - Provides fast test for data equality in cases where the positions of the differing data elements is not required.

BLAS_AXPY - Updates existing array by adding a multiple of another array.

INVERT - Computes the inverse of a square array.

MAX - Returns the value of the largest element of Array.

MEDIAN - Returns the median value of Array or applies a median filter.

MIN - Returns the value of the smallest element of an array.

REFORM - Changes array dimensions without changing the total number of elements.

REPLICATE_INPLACE - Updates an array by replacing all or selected parts of it with a specified value.

REVERSE - Reverses the order of one dimension of an array.

ROT - Rotates an image by any amount.

ROTATE - Rotates/transposes an array in multiples of 90 degrees.

SHIFT - Shifts elements of vectors or arrays by a specified number of elements.

SIZE - Returns array size and type information.

SORT - Returns indices of an array sorted in ascending order.

TOTAL - Sums of the elements of an array.

TRANSPOSE - Transposes an array.

UNIQ - Returns subscripts of the unique elements in an array.

WHERE - Returns subscripts of nonzero array elements.

XVAREDIT - Provides widget-based editor for IDL variables.

Color Table Manipulation

COLOR_CONVERT - Converts color triples to and from RGB, HLS, and HSV.

COLOR_QUAN - Converts true-color (24-bit) image to pseudo-color (8-bit) image.

COLORMAP_APPLICABLE - Determines whether the current visual class supports the use of a colormap.

CT_LUMINANCE - Calculates the luminance of colors.

CW_PALETTE_EDITOR - Creates compound widget to display and edit color palettes.

CW_PALETTE_EDITOR_GET - Gets CW_PALETTE_EDITOR properties.

CW_PALETTE_EDITOR_SET - Sets CW_PALETTE_EDITOR properties.

GAMMA_CT - Applies gamma correction to a color table.

H_EQ_CT - Histogram-equalizes the color tables for an image or a region of the display.

H_EQ_INT - Interactively histogram-equalizes the color tables of an image or a region of the display.

HLS - Creates color table in Hue, Lightness, Saturation color system.

HSV - Creates color table based on Hue and Saturation Value color system.

LJLCT - Loads standard color tables for LJ-250/252 printer.

LOADCT - Loads one of the predefined IDL color tables.

MODIFYCT - Saves modified color tables in the IDL color table file.

MULTI - Replicates current color table to enhance contrast.

PSEUDO - Creates pseudo-color table based on Lightness, Hue, and Brightness system.

REDUCE_COLORS - Reduces the number of colors used in an image by eliminating unused pixel values.

STRETCH - Stretches color table for contrast enhancement.

TEK_COLOR - Loads color table based on Tektronix printer.

TVLCT - Loads display color tables.

XLOADCT - Provides GUI to interactively select and load color tables.

XPALETTE - Displays widget used to create and modify color tables.

Date and Time

BIN_DATE - Converts ASCII date/time string to binary string.

CALDAT - Converts Julian date to month, day, year.

CALENDAR - Displays a calendar for a given month or year.

JULDAY - Returns Julian Day Number for given month, day, and year.

SYSTIME - Returns the current time as either a date/time string, as the number of seconds elapsed since 1 January 1970, or as a Julian date/time value.

TIMEGEN - Returns an array of double-precision floating-point values that represent date/times in terms of Julian values.

Debugging

.CONTINUE - Continues execution of a stopped program.

.SKIP - Skips over the next *n* statements and then single steps.

.STEP - Executes one or *n* statements from the current position.

.STEPOVER - Executes a single statement if the statement doesn't call a routine.

.TRACE - Similar to .CONTINUE, but displays each line of code before execution.

BREAKPOINT - Sets and clears breakpoints for debugging.

STOP - Stops the execution of a running program or batch file.

Dialog Routines

DIALOG_MESSAGE - Creates modal message dialog.

DIALOG_PICKFILE - Creates native file-selection dialog.

DIALOG_PRINTERSETUP - Opens native dialog used to set properties for a printer.

DIALOG_PRINTJOB - Opens native dialog used to set parameters for a print job.

DIALOG_READ_IMAGE - Presents GUI for reading image files.

DIALOG_WRITE_IMAGE - Presents GUI for writing image files.

Direct Graphics, General

ANNOTATE - Starts IDL widget used to interactively annotate images and plots with text and drawings.

ARROW - Draws line with an arrow head.

BOX_CURSOR - Emulates operation of a variable-sized box cursor.

CONVERT_COORD - Transforms coordinates to and from the coordinate systems supported by IDL.

CURSOR - Reads position of the interactive graphics cursor.

CVTTOBM - Creates a bitmap byte array for a button label.

DEVICE - Sets to plot in device coordinates.

EMPTY - Empties the graphics output buffer.

ERASE - Erases the screen of the current graphics device, or starts a new page if the device is a printer.

FORMAT_AXIS_VALUES - Formats numbers as strings for use as axis values.

PLOTS - Plots vectors and points.

POLYFILL - Fills the interior of a polygon.

PROFILE - Extracts a profile from an image.

PROFILES - Interactively examines image profiles.

SET_PLOT - Sets the output device used by the IDL direct graphics procedures.

THREED - Plots a 2D array as a pseudo 3D plot.

TV - Displays an image.

TVCRS - Manipulates the image display cursor.

TVSCL - Scales and displays an image.

XYOUTS - Draws text on currently-selected graphics device.

ZOOM - Zooms portions of the display.

ZOOM_24 - Zooms portions of true-color (24-bit) display.

Error Handling

CATCH - Intercepts and processes error messages, and continues program execution.

MESSAGE - Issues error and informational messages.

ON_ERROR - Designates the error recovery method.

ON_IOERROR - Declares I/O error exception handler.

STRMESSAGE - Returns the text of a given error number.

Executive Commands

.COMPILE - Compiles programs without running.

.CONTINUE - Continues execution of a stopped program.

.EDIT - Opens files in editor windows of the IDLDE (Windows and Motif only).

.FULL_RESET_SESSION - Does everything .RESET_SESSION does, plus additional reset tasks such as unloading sharable libraries.

.GO - Executes previously-compiled main program.

.OUT - Continues execution until the current routine returns.

.RESET_SESSION - Resets much of the state of an IDL session without requiring the user to exit and restart the IDL session.

.RETURN - Continues execution until RETURN statement.

.RNEW - Erases main program variables and then does .RUN.

.RUN - Compiles and executes IDL commands from files or keyboard.

.SKIP - Skips over the next *n* statements and then single steps.

.STEP - Executes one or *n* statements from the current position.

.STEPOVER - Executes a single statement if the statement doesn't call a routine.

.TRACE - Similar to .CONTINUE, but displays each line of code before execution.

External Linking

CALL_EXTERNAL - Calls a function in an external sharable object and returns a scalar value.

DLM_LOAD - Explicitly causes a DLM to be loaded.

LINKIMAGE - Merges routines written in other languages with IDL at run-time.

MAKE_DLL - Compiles and links sharable libraries (DLLs) for Unix, VMS, and Windows.

Font Manipulation

EFONT - Interactive vector font editor and display tool.

PS_SHOW_FONTS - Displays all the PostScript fonts that IDL knows about.

PSAFM - Converts Adobe Font Metrics file to IDL format.

SHOWFONT - Displays a TrueType or vector font

XFONT - Creates modal widget to select and view an X Windows font.

Help Routines

? - Invokes the IDL Online Help facility when entered at the IDL command line.

DOC_LIBRARY - Extracts documentation headers from IDL programs.

HELP - Provides information about the current IDL session.

MEMORY - Returns information about dynamic memory currently in use by the IDL session.

MK_HTML_HELP - Converts text documentation headers to HTML files.

ONLINE_HELP - Invokes hypertext help viewer from programs.

STRUCT_HIDE - Prevents the IDL HELP procedure from displaying information about structures or objects.

Image Processing

Contrast Enhancement and Filtering

ADAPT_HIST_EQUAL - Performs adaptive histogram equalization

BYTSCL - Scales all values of an array into range of bytes.

CONVOL - Convolves two vectors or arrays.

DIGITAL_FILTER - Calculates coefficients of a non-recursive, digital filter.

FFT - Returns the Fast Fourier Transform of an array.

HILBERT - Constructs a Hilbert transform.

HIST_EQUAL - Histogram-equalizes an image.

LEEFILT - Performs the Lee filter algorithm on an image array.

MEDIAN - Returns the median value of Array or applies a median filter.

ROBERTS - Returns an approximation of Roberts edge enhancement.

SMOOTH - Smooths with a boxcar average.

SOBEL - Returns an approximation of Sobel edge enhancement.

See Also - Wavelet Toolkit

Feature Extraction/Image Segmentation

CONTOUR - Draws a contour plot.

DEFROI - Defines an irregular region of interest of an image.

HISTOGRAM - Computes the density function of an array.

HOUGH - Returns the Hough transform of a two-dimensional image.

IMAGE_STATISTICS - Computes sample statistics for a given array of values.

ISOCONTOUR - Interprets the contouring algorithm found in the IDLgrContour object.

ISOSURFACE - Returns topologically consistent triangles by using oriented tetrahedral decomposition.

LABEL_REGION - Labels regions (blobs) of a bi-level image.

MAX - Returns the value of the largest element of Array.

MEDIAN - Returns the median value of Array or applies a median filter.

MIN - Returns the value of the smallest element of an array.

PROFILES - Interactively examines image profiles.

RADON - Returns the Radon transform of a two-dimensional image.

SEARCH2D - Finds "objects" or regions of similar data within a 2D array.

THIN - Returns the "skeleton" of a bi-level image.

UNIQ - Returns subscripts of the unique elements in an array.

WATERSHED - Applies the morphological watershed operator to a grayscale image.

WHERE - Returns subscripts of nonzero array elements.

Image Display

DISSOLVE - Provides a digital "dissolve" effect for images.

LIVE_IMAGE - Displays visualizations using a GUI.

RDPIX - Interactively displays image pixel values.

SLIDE_IMAGE - Creates a scrolling graphics window for examining large images.

TV - Displays an image.

TVCRS - Manipulates the image display cursor.

TVLCT - Loads display color tables.

TVSCL - Scales and displays an image.

XOBJVIEW - Displays object viewer widget.

ZOOM - Zooms portions of the display.

ZOOM_24 - Zooms portions of true-color (24-bit) display.

Image Geometry Transformations

CONGRID - Resamples an image to any dimensions.

EXPAND - Shrinks/expands image using bilinear interpolation.

EXTRAC - Returns sub-matrix of input array. Array operators (e.g., * and :) should usually be used instead.

INTERPOLATE - Returns an array of interpolates.

INVERT - Computes the inverse of a square array.

POLY_2D - Performs polynomial warping of images.

POLYWARP - Performs polynomial spatial warping.

REBIN - Resizes a vector or array by integer multiples.

REFORM - Changes array dimensions without changing the total number of elements.

REVERSE - Reverses the order of one dimension of an array.

ROT - Rotates an image by any amount.

ROTATE - Rotates/transposes an array in multiples of 90 degrees.

SHIFT - Shifts elements of vectors or arrays by a specified number of elements.

TRANSPOSE - Transposes an array.

WARP_TRI - Warps an image using control points.

Morphological Image Operators

DILATE - Implements morphologic dilation operator on binary and grayscale images.

ERODE - Implements the erosion operator on binary and grayscale images and vectors.

LABEL_REGION - Labels regions (blobs) of a bi-level image.

MORPH_CLOSE - Applies closing operator to binary or grayscale image.

MORPH_DISTANCE - Estimates *N*-dimensional distance maps, which contain for each foreground pixel the distance to the nearest background pixel, using a given norm.

MORPH_GRADIENT - Applies the morphological gradient operator to a grayscale image.

MORPH_HITORMISS - Applies the hit-or-miss operator to a binary image.

MORPH_OPEN - Applies the opening operator to a binary or grayscale image.

MORPH_THIN - Performs a thinning operation on binary images.

MORPH_TOPHAT - Applies top-hat operator to a grayscale image.

WATERSHED - Applies the morphological watershed operator to a grayscale image.

Regions of Interest

CW_DEFROI - Creates compound widget used to define region of interest.

DEFROI - Defines an irregular region of interest of an image.

DRAW_ROI - Draws region or group of regions to current Direct Graphics device.

IDLanROI - Represents a region of interest.

IDLanROIGroup - Analytical representation of a group of regions of interest.

IDLgrROI - Object graphics representation of a region of interest.

IDLgrROIGroup - Object Graphics representation of a group of regions of interest.

LABEL_REGION - Labels regions (blobs) of a bi-level image.

Input/Output

ASCII_TEMPLATE - Presents a GUI that generates a template defining an ASCII file format.

ASSOC - Associates an array structure with a file.

BINARY_TEMPLATE - Presents a GUI for interactively generating a template structure for use with READ_BINARY.

CDF Routines - Common Data Format routines.

CLOSE - Closes the specified files.

DIALOG_READ_IMAGE - Presents GUI for reading image files.

DIALOG_WRITE_IMAGE - Presents GUI for writing image files.

EOF - Tests the specified file for the end-of-file condition.

EOS Routines - HDF-EOS (Hierarchical Data Format-Earth Observing System) routines.

FILEPATH - Returns full path to a file in the IDL distribution.

FINDFILE - Finds all files matching given file specification.

FLUSH - Flushes file unit buffers.

FREE_LUN - Frees previously-reserved file units.

FSTAT - Returns information about a specified file unit.

GET_KBRD - Gets one input IDL character.

GET_LUN - Reserves a logical unit number (file unit).

HDF Routines - Hierarchical Data Format routines.

HDF_BROWSER - Opens GUI to view contents of HDF, HDF-EOS, or NetCDF file.

HDF_READ - Extracts HDF, HDF-EOS, and NetCDF data and metadata into an output structure.

IDLffDICOM - Contains the data for one or more images embedded in a DICOM part 10 file.

IDLffDXF - Object that contains geometry, connectivity, and attributes for graphics primitives.

IDLffShape - Contains geometry, connectivity and attributes for graphics primitives accessed from ESRI Shapefiles.

IOCTL - Performs special functions on UNIX files.

MPEG_CLOSE - Closes an MPEG sequence.

MPEG_OPEN - Opens an MPEG sequence.

MPEG_PUT - Inserts an image array into an MPEG sequence.

MPEG_SAVE - Saves an MPEG sequence to a file.

NCDF Routines - Network Common Data Format routines.

OPEN - Opens files for reading, updating, or writing.

POINT_LUN - Sets or gets current position of the file pointer.

PRINT/PRINTF - Writes formatted output to screen or file.

READ/READF - Reads formatted input from keyboard or file.

READ_ASCII - Reads data from an ASCII file.

READ_BINARY - Reads the contents of a binary file using a passed template or basic command line keywords.

READ_BMP - Reads Microsoft Windows bitmap file (.BMP).

READ_DICOM - Reads an image from a DICOM file.

READ_IMAGE - Reads the image contents of a file and returns the image in an IDL variable.

READ_INTERFILE - Reads Interfile (v3.3) file.

READ_JPEG - Reads JPEG file.

READ_PICT - Reads Macintosh PICT (version 2) bitmap file.

READ_PNG - Reads Portable Network Graphics (PNG) file.

READ_PPM - Reads PGM (gray scale) or PPM (portable pixmap for color) file.

READ_SRF - Reads Sun Raster Format file.

READ_SYLK - Reads Symbolic Link format spreadsheet file.

READ_TIFF - Reads TIFF format file.

READ_WAV - Reads the audio stream from the named .WAV file.

READ_WAVE - Reads Wavefront Advanced Visualizer file.

READ_X11_BITMAP - Reads X11 bitmap file.

READ_XWD - Reads X Windows Dump file.

READS - Reads formatted input from a string variable.

READU - Reads unformatted binary data from a file.

REWIND (VMS only) - Rewinds tape on designated IDL tape unit.

SKIPF - Skips records or files on the designated magnetic tape unit.

SOCKET - Opens a client-side TCP/IP Internet socket as an IDL file unit.

TAPRD - Reads the next record on a tape.

TAPWRT - Writes data to a tape.

TVRD - Reads an image from a window into a variable.

WEOF - Writes an end-of-file mark on the designated tape unit.

WRITE_BMP - Writes Microsoft Windows Version 3 device independent bitmap file (.BMP).

WRITE_IMAGE - Writes an image and its color table vectors, if any, to a file of a specified type.

WRITE_JPEG - Writes JPEG file.

WRITE_NRIF - Writes NCAR Raster Interchange Format rasterfile.

WRITE_PICT - Writes Macintosh PICT (version 2) bitmap file.

WRITE_PNG - Writes Portable Network Graphics (PNG) file.

WRITE_PPM - Writes PPM (true-color) or PGM (gray scale) file.

WRITE_SRF - Writes Sun Raster File (SRF).

WRITE_SYLK - Writes SYLK (Symbolic Link) spreadsheet file.

WRITE_TIFF - Writes TIFF file with 1 to 3 channels.

WRITE_WAV - Writes the audio stream to the named .WAV file.

WRITE_WAVE - Writes Wavefront Advanced Visualizer (.WAV) file.

WRITEU - Writes unformatted binary data to a file.

VAX_FLOAT - Determines the default value for the VAX_FLOAT keyword to the OPEN procedures, or if an open file unit has the VAX_FLOAT attribute set.

Language Catalogs

IDLffLanguageCat - Provides an interface to IDL language catalog files.

LOCALE_GET - Returns the current locale of the operating platform.

MSG_CAT_CLOSE - Closes a catalog file from the stored cache.

MSG_CAT_COMPILE - Creates an IDL language catalog file.

MSG_CAT_OPEN - Returns a catalog object for the given parameters if found.

Live Routines

LIVE_CONTOUR - Displays contour plots using a GUI.

LIVE_CONTROL - Sets the properties of a visualization in a LIVE tool from the IDL command line.

LIVE_DESTROY - Destroys a window visualization or an element in a visualization.

LIVE_EXPORT - Exports visualization or window to a file.

LIVE_IMAGE - Displays visualizations using a GUI.

LIVE_INFO - Gets the properties of a LIVE tool.

LIVE_LINE - Provides an interface for line annotation.

LIVE_LOAD - Loads into memory the complete set of routines necessary to run all LIVE tools.

LIVE_OPLOT - Inserts data into pre-existing plots.

LIVE_PLOT - Displays a plot using a GUI.

LIVE_PRINT - Prints a given window to the printer.

LIVE_RECT - Provides an interface for insertion of rectangles.

LIVE_STYLE - Controls style settings for a LIVE_ tool.

LIVE_SURFACE - Displays a surface using a GUI.

LIVE_TEXT - Provides an interface for text annotation.

Mapping

LL_ARC_DISTANCE - Returns the longitude and latitude of a point given arc distance and azimuth.

MAP_2POINTS - Returns distance, azimuth, and path relating to the great circle or rhumb line connecting two points on a sphere.

MAP_CONTINENTS - Draws continental boundaries, filled continents, political boundaries, coastlines, and/or rivers, over an existing map projection established by MAP_SET.

MAP_GRID - Draws parallels and meridians over a map projection.

MAP_IMAGE - Returns an image warped to fit the current map projection. (Use when map data is larger than the display).

MAP_PATCH - Returns an image warped to fit the current map projection. (Use when map data is smaller than the display).

MAP_PROJ_INFO - Returns information about current map and/or the available projections.

MAP_SET - Establishes map projection type and limits.

Mathematics

Complex Numbers

COMPLEX - Converts argument to complex type.

CONJ - Returns the complex conjugate of X.

DCOMPLEX - Converts argument to double-precision complex type.

IMAGINARY - Returns the imaginary part of a complex value.

Correlation Analysis

A_CORRELATE - Computes autocorrelation.

C_CORRELATE - Computes cross correlation.

CORRELATE - Computes the linear Pearson correlation.

M_CORRELATE - Computes multiple correlation coefficient.

P_CORRELATE - Computes partial correlation coefficient.

R_CORRELATE - Computes rank correlation.

Curve and Surface Fitting

COMFIT - Fits paired data using one of six common filtering functions.

CRVLENGTH - Computes the length of a curve.

CURVEFIT - Fits multivariate data with a user-supplied function.

GAUSS2DFIT - Fits a 2D elliptical Gaussian equation to rectilinearly gridded data.

GAUSSFIT - Fits the sum of a Gaussian and a quadratic.

GRID_TPS - Uses thin plate splines to interpolate a set of values over a regular 2D grid, from irregularly sampled data values.

KRIG2D - Interpolates set of points using kriging.

LADFIT - Fits paired data using least absolute deviation method.

LINFIT - Fits by minimizing the Chi-square error statistic.

LMFIT - Does a non-linear least squares fit.

MIN_CURVE_SURF - Interpolates points with a minimum curvature surface or a thin-plate-spline surface. Useful with CONTOUR.

POLY_FIT - Performs a least-square polynomial fit.

REGRESS - Computes fit using multiple linear regression.

SFIT - Performs polynomial fit to a surface.

SVDFIT - Multivariate least squares fit using SVD method.

TRIGRID - Interpolates irregularly-gridded data to a regular grid from a triangulation.

Differentiation and Integration

CRVLENGTH - Computes the length of a curve.

DERIV - Performs differentiation using 3-point Langrangian interpolation.

DERIVSIG - Computes standard deviation of derivative found by DERIV.

INT_2D - Computes the double integral of a bivariate function.

INT_3D - Computes the triple integral of a trivariate function.

INT_TABULATED - Integrates a tabulated set of data.

LSODE - Advances a solution to a system of ordinary differential equations one time-step H.

QROMB - Evaluates integral over a closed interval.

QROMO - Evaluates integral over an open interval.

QSIMP - Evaluates integral using Simpson's rule.

RK4 - Solves differential equations using fourth-order Runge-Kutta method.

Eigenvalues and Eigenvectors

EIGENQL - Computes eigenvalues and eigenvectors of a real, symmetric array.

EIGENVEC - Computes eigenvectors of a real, non-symmetric array.

ELMHES - Reduces nonsymmetric array to upper Hessenberg form.

HQR - Returns all eigenvalues of an upper Hessenberg array.

TRIQL - Determines eigenvalues and eigenvectors of tridiagonal array.

TRIRED - Reduces a real, symmetric array to tridiagonal form.

Gridding and Interpolation

BILINEAR - Computes array using bilinear interpolation.

GRID_TPS - Uses thin plate splines to interpolate a set of values over a regular 2D grid, from irregularly sampled data values.

GRID3 - Creates a regularly-gridded 3D dataset from a set of scattered 3D nodes.

INTERPOL - Performs linear interpolation on vectors.

INTERPOLATE - Returns an array of interpolates.

KRIG2D - Interpolates set of points using kriging.

MIN_CURVE_SURF - Interpolates points with a minimum curvature surface or a thin-plate-spline surface. Useful with CONTOUR.

POLAR_SURFACE - Interpolates a surface from polar coordinates to rectangular coordinates.

SPH_SCAT - Performs spherical gridding.

SPL_INIT - Establishes the type of interpolating spline.

SPL_INTERP - Performs cubic spline interpolation (Numerical Recipes).

SPLINE - Performs cubic spline interpolation.

SPLINE_P - Performs parametric cubic spline interpolation.

TRI_SURF - Interpolates gridded set of points with a smooth quintic surface.

TRIANGULATE - Constructs Delaunay triangulation of a planar set of points.

TRIGRID - Interpolates irregularly-gridded data to a regular grid from a triangulation.

VALUE_LOCATE - Finds the intervals within a given monotonic vector that brackets a given set of one or more search values.

VORONOI - Computes Voronoi polygon given Delaunay triangulation.

Hypothesis Testing

CTI_TEST - Performs chi-square goodness-of-fit test.

FV_TEST - Performs the F-variance test.

KW_TEST - Performs Kruskal-Wallis H-test.

LNP_TEST - Computes the Lomb Normalized Periodogram.

MD_TEST - Performs the Median Delta test.

R_TEST - Runs test for randomness.

RS_TEST - Performs the Wilcoxon Rank-Sum test.

S_TEST - Performs the Sign test.

TM_TEST - Performs t-means test.

XSQ_TEST - Computes Chi-square goodness-of-fit test.

Linear Systems

CHOLDC - Constructs Cholesky decomposition of a matrix.

CHOLSOL - Solves set of linear equations (use with CHOLDC).

COND - Computes the condition number of a square matrix.

CRAMER - Solves system of linear equations using Cramer's rule.

CROSSP - Computes vector cross product.

DETERM - Computes the determinant of a square matrix.

GS_ITER - Solves linear system using Gauss-Seidel iteration.

IDENTITY - Returns an identity array.

INVERT - Computes the inverse of a square array.

LINBCG - Solves a set of sparse linear equations using the iterative biconjugate gradient method.

LU_COMPLEX - Solves complex linear system using LU decomposition.

LUDC - Replaces array with the LU decomposition.

LUMPROVE - Uses LU decomposition to iteratively improve an approximate solution.

LUSOL - Solves a set of linear equations. Use with LUDC.

NORM - Computes Euclidean norm of vector or Infinity norm of array.

SVDC - Computes Singular Value Decomposition of an array.

SVSOL - Solves set of linear equations using back-substitution.

TRACE - Computes the trace of an array.

TRISOL - Solves tridiagonal systems of linear equations.

Mathematical Error Assessment

CHECK_MATH - Returns and clears accumulated math error status.

FINITE - Returns True if its argument is finite.

MACHAR - Determines and returns machine-specific parameters affecting floating-point arithmetic.

Miscellaneous Math Routines

ABS - Returns the absolute value of X.

CEIL - Returns the closest integer greater than or equal to X.

CIR_3PNT - Returns radius and center of circle, given 3 points.

COMPLEXROUND - Rounds a complex array.

DIST - Creates array with each element proportional to its frequency.

EXP - Returns the natural exponential function of given expression.

FLOOR - Returns closest integer less than or equal to argument.

IMAGINARY - Returns the imaginary part of a complex value.

ISHFT - Performs integer bit shift.

LEEFILT - Performs the Lee filter algorithm on an image array.

MATRIX_MULTIPLY - Calculates the IDL matrix-multiply operator (#) of two (possibly transposed) arrays.

PNT_LINE - Returns the perpendicular distance between a point and a line.

POLY_AREA - Returns the area of a polygon given the coordinates of its vertices.

PRIMES - Computes the first K prime numbers.

ROUND - Returns the integer closest to its argument.

SPH_4PNT - Returns center and radius of a sphere given 4 points.

SQRT - Returns the square root of *X*.

TOTAL - Sums of the elements of an array.

VOIGT - Calculates intensity of atomic absorption line (Voight) profile.

Multivariate Analysis

CLUST_WTS - Computes cluster weights of array for cluster analysis.

CLUSTER - Performs cluster analysis.

CTI_TEST - Performs chi-square goodness-of-fit test.

KW_TEST - Performs Kruskal-Wallis H-test.

M_CORRELATE - Computes multiple correlation coefficient.

P_CORRELATE - Computes partial correlation coefficient.

PCOMP - Computes principal components/derived variables.

STANDARDIZE - Computes standardized variables.

Nonlinear Equations

BROYDEN - Solves nonlinear equations using Broyden's method.

FX_ROOT - Computes real and complex roots of a univariate nonlinear function using an optimal Müller's method.

FZ_ROOTS - Finds the roots of a complex polynomial using Laguerre's method.

NEWTON - Solves nonlinear equations using Newton's method.

Optimization

AMOEBA - Minimizes a function using downhill simplex method.

CONSTRAINED_MIN - Minimizes a function using Generalized Reduced Gradient Method.

DFPMIN - Minimizes a function using Davidon-Fletcher-Powell method.

POWELL - Minimizes a function using the Powell method.

Probability

BINOMIAL - Computes binomial distribution function.

CHISQR_CVF - Computes cutoff value in a Chi-square distribution.

CHISQR_PDF - Computes Chi-square distribution function.

F_CVF - Computes the cutoff value in an F distribution.

F_PDF - Computes the F distribution function.

GAUSS_CVF - Computes cutoff value in Gaussian distribution.

GAUSS_PDF - Computes Gaussian distribution function.

GAUSSINT - Returns integral of Gaussian probability function.

T_CVF - Computes the cutoff value in a Student's t distribution.

T_PDF - Computes Student's t distribution.

Sparse Arrays

FULSTR - Restores a sparse matrix to full storage mode.

LINBCG - Solves a set of sparse linear equations using the iterative biconjugate gradient method.

READ_SPR - Reads a row-indexed sparse matrix from a file.

SPRSAB - Performs matrix multiplication on sparse matrices.

SPRSAX - Multiplies sparse matrix by a vector.

SPRSIN - Converts matrix to row-index sparse matrix.

SPRSTP - Constructs the transpose of a sparse matrix.

WRITE_SPR - Writes row-indexed sparse array structure to a file.

Special Math Functions

BESELI - Returns the I Bessel function of order N for *X*.

BESELJ - Returns the J Bessel function of order N for *X*.

BESELK - Returns the K Bessel function of order N for *X*.

BESELY - Returns the Y Bessel function of order N for *X*.

BETA - Returns the value of the beta function.

ERRORF - Returns the value of an error function.

EXPINT - Returns the value of the exponential integral.

GAMMA - Returns the gamma function of *X*.

IBETA - Computes the incomplete beta function.

IGAMMA - Computes the incomplete gamma function.

LAGUERRE - Returns value of the associated Laguerre polynomial.

LEGENDRE - Returns value of the associated Legendre polynomial.

LNGAMMA - Returns logarithm of the gamma function of *X*.

POLY - Evaluates polynomial function of a variable.

SPHER_HARM - Returns value of the spherical harmonic function.

Statistical Fitting

COMFIT - Fits paired data using one of six common filtering functions.

CURVEFIT - Fits multivariate data with a user-supplied function.

FUNCT - Evaluates the sum of a Gaussian and a 2nd-order polynomial and optionally returns the value of its partial derivatives.

LADFIT - Fits paired data using least absolute deviation method.

LINFIT - Fits by minimizing the Chi-square error statistic.

REGRESS - Multiple linear regression.

SVDFIT - Multivariate least squares fit using SVD method.

Statistical Tools

FACTORIAL - Computes the factorial N!.

HIST_2D - Returns histogram of two variables.

HISTOGRAM - Computes the density function of an array.

KURTOSIS - Computes statistical kurtosis of *n*-element vector.

MAX - Returns the value of the largest element of an array.

MEAN - Computes the mean of a numeric vector.

MEANABSDEV - Computes the mean absolute deviation of a vector.

MEDIAN - Returns the median value of Array or applies a median filter.

MIN - Returns the value of the smallest element of an array.

MOMENT - Computes mean, variance, skewness, and kurtosis.

RANDOMN - Returns normally-distributed pseudo-random numbers.

RANDOMU - Returns uniformly-distributed pseudo-random numbers.

RANKS - Computes magnitude-based ranks.

SKEWNESS - Computes statistical skewness of an *n*-element vector.

SORT - Returns the indices of an array sorted in ascending order.

STDDEV - Computes the standard deviation of an *n*-element vector.

TOTAL - Sums of the elements of an array.

VARIANCE - Computes the statistical variance of an *n*-element vector.

Time-Series Analysis

A_CORRELATE - Computes autocorrelation.

C_CORRELATE - Computes cross correlation.

SMOOTH - Smooths with a boxcar average.

TS_COEF - Computes the coefficients for autoregressive time-series.

TS_DIFF - Computes the forward differences of a time-series.

TS_FCAST - Computes future or past values of stationary time-series.

TS_SMOOTH - Computes moving averages of a time-series.

Transcendental Functions

ACOS - Returns the arc-cosine of *X*.

ALOG - Returns the natural logarithm of *X*.

ALOG10 - Returns the logarithm to the base 10 of *X*.

ASIN - Returns the arc-sine of *X*.

ATAN - Returns the arc-tangent of *X*.

COS - Returns the cosine of *X*.

COSH - Returns the hyperbolic cosine of *X*.

EXP - Returns the natural exponential function of a given expression.

SIN - Returns the trigonometric sine of *X*.

SINH - Returns the hyperbolic sine of *X*.

TAN - Returns the tangent of *X*.

TANH - Returns the hyperbolic tangent of *X*.

Transforms

BLK_CON - Convolves input signal with impulse-response sequence.

CHEBYSHEV - Returns the forward or reverse Chebyshev polynomial expansion.

CONVOL - Convolves two vectors or arrays.

FFT - Returns the Fast Fourier Transform of an array.

HILBERT - Constructs a Hilbert transform.

HOUGH - Returns the Hough transform of a two-dimensional image.

RADON - Returns the Radon transform of a two-dimensional image.

WTN - Returns wavelet transform of the input array.

See Also - Wavelet Toolkit

Operating System Access

CALL_EXTERNAL - Calls a function in an external sharable object and returns a scalar value.

CD - Sets and/or changes the current working directory.

DELETE_SYMBOL (VMS Only) - Deletes a DCL interpreter symbol for the current process.

DELLOG (VMS Only) - Deletes a VMS logical name.

DO_APPLE_SCRIPT - Compiles, executes AppleScript code.

FILE_CHMOD - Changes file access permissions.

FILE_DELETE - Deletes files and empty directories.

FILE_EXPAND_PATH - Fully qualifies file and directory paths.

FILE_MKDIR - Creates directories.

FILE_TEST - Test a file or directory for existence and other specific attributes.

FILE_WHICH - Searches for a specified file in a directory search path.

GET_DRIVE_LIST (Windows/Mac only) - Returns string array of the names of valid drives/volumes for the file system.

GET_SCREEN_SIZE - Returns dimensions of the screen.

GET_SYMBOL (VMS Only) - Returns value of a VMS DCL interpreter symbol.

GETENV - Returns the value of an environment variable.

LINKIMAGE - Merges routines written in other languages with IDL at run-time.

POPD - Removes the top directory on the working directory stack maintained by PUSHD/POPD.

PRINTD - Prints contents of the directory stack maintained by PUSHD/POPD.

PUSHD - Pushes a directory to top of directory stack maintained by PUSHD/POPD.

SET_SYMBOL (VMS Only) - Defines a VMS DCL interpreter symbol.

SETENV (UNIX/Windows Only) - Adds or changes an environment variable.

SETLOG (VMS Only) - Defines a VMS logical name.

SETUP_KEYS - Sets function keys for UNIX versions of IDL.

SPAWN - Spawns child process for access to operating system.

TRNLOG (VMS Only) - Searches the VMS logical name tables for a specified logical name.

Performance Testing

TIME_TEST2 - Performs speed benchmarks for IDL.

PROFILER - Accesses the IDL Code Profiler used to analyze performance of applications.

Plotting

AXIS - Draws an axis of the specified type and scale.

BAR_PLOT - Creates a bar graph.

ERRPLOT - Plots error bars over a previously drawn plot.

LABEL_DATE - Labels axes with dates. Use with [XYZ]TICKFORMAT keyword.

OPLOT - Plots vector data over a previously-drawn plot.

OPLOTERR - Draws error bars over a previously drawn plot.

PLOT - Plots vector arguments as X versus Y graphs.

PLOT_3DBOX - Plots function of two variables inside 3D box.

PLOT_FIELD - Plots a 2D field using arrows.

PLOTERR - Plots individual data points with error bars.

PLOTS - Plots vectors and points.

POLYFILL - Fills the interior of a polygon.

POLYFILLV - Returns subscripts of pixels inside a polygon.

PROFILE - Extracts a profile from an image.

PROFILES - Interactively examines image profiles.

THREED - Plots a 2D array as a pseudo 3D plot.

TRIANGULATE - Constructs Delaunay triangulation of a planar set of points.

TRIGRID - Interpolates irregularly-gridded data to a regular grid from a triangulation.

USERSYM - Defines a new plotting symbol.

VEL - Draws a velocity (flow) field with streamlines.

VELOVECT - Draws a 2D velocity field plot.

WF_DRAW - Draws weather fronts with smoothing.

XPLOT3D - Utility for creating and interactively manipulating 3D plots.

XYOUTS - Draws text on currently-selected graphics device.

Programming and IDL Control

ARG_PRESENT - Returns TRUE if the value of the specified variable can be passed back to the caller.

BREAKPOINT - Sets and clears breakpoints for debugging.

BYTEORDER - Converts between host and network byte ordering.

CALL_FUNCTION - Calls an IDL function.

CALL_METHOD - Calls an IDL object method.

CALL_PROCEDURE - Calls an IDL procedure.

CATCH - Declares and clears exception handlers..

CREATE_STRUCT - Creates and concatenates structures.

DEFINE_KEY - Programs keyboard function keys.

DEFSYSV - Creates a new system variable.

EXECUTE - Compiles, executes IDL statements contained in a string.

EXIT - Quits IDL and exits back to the operating system.

EXPAND_PATH - Expands path-definition string into full path name for use with the !PATH system variable.

HEAP_GC - Performs "garbage collection" on heap variables.

KEYWORD_SET - Returns True if given expression is defined and nonzero or an array.

LMGR - Determines the type of license used by the current IDL session.

MESSAGE - Issues error and informational messages.

N_ELEMENTS - Returns the number of elements contained in an expression or variable.

N_PARAMS - Returns the number of non-keyword parameters used in calling an IDL procedure or function.

N_TAGS - Returns the number of tags in a structure.

OBJ_CLASS - Determines the class name of an object.

OBJ_DESTROY - Destroys an object reference.

OBJ_ISA - Determines inheritance relationship of an object.

OBJ_NEW - Creates an object reference.

OBJ_VALID - Verifies validity of object references.

ON_ERROR - Designates the error recovery method.

ON_IOERROR - Declares I/O error exception handler.

PTR_FREE - Destroys a pointer.

PTR_NEW - Creates a pointer.

PTR_VALID - Verifies the validity of pointers.

PTRARR - Creates an array of pointers.

RECALL_COMMANDS - Returns entries in IDL's command recall buffer.

RESOLVE_ALL - Compiles any uncompiled routines.

RESOLVE_ROUTINE - Compiles a routine.

RETALL - Returns control to the main program level.

RETURN - Returns control to the next-higher program level.

ROUTINE_INFO - Provides information about compiled procedures and functions.

SETUP_KEYS - Sets function keys for UNIX versions of IDL.

STOP - Stops the execution of a running program or batch file.

STRMESSAGE - Returns the text of a given error number.

STRUCT_ASSIGN - Uses "Relaxed Structure Assignment" to copy structures.

STRUCT_HIDE - Prevents the IDL HELP procedure from displaying information about structures or objects.

SWAP_ENDIAN - Reverses the byte ordering of scalars, arrays or structures.

TAG_NAMES - Returns the names of tags in a structure.

TEMPORARY - Returns a temporary copy of a variable, and sets the original variable to "undefined".

WAIT - Suspends execution of an IDL program for a specified period.

Query Routines

QUERY_BMP - Obtains information about a BMP image file.

QUERY_DICOM - Tests file for compatibility with READ_DICOM.

QUERY_IMAGE - Determines if a file is recognized as an image file.

QUERY_JPEG - Obtains information about a JPEG image file.

QUERY_PICT - Obtains information about a PICT image file.

QUERY_PNG - Obtains information about a PNG image file.

QUERY_PPM - Obtains information about a PPM image file.

QUERY_SRF - Obtains information about an SRF image file.

QUERY_TIFF - Obtains information about a TIFF image file.

QUERY_WAV - Checks that the file is actually a .WAV file and that the READ_WAV function can read the data in the file.

Signal Processing

A_CORRELATE - Computes autocorrelation.

BLK_CON - Convolves input signal with impulse-response sequence.

C_CORRELATE - Computes cross correlation.

CONVOL - Convolves two vectors or arrays.

CORRELATE - Computes the linear Pearson correlation.

DIGITAL_FILTER - Calculates coefficients of a non-recursive, digital filter.

FFT - Returns the Fast Fourier Transform of an array.

HANNING - Creates Hanning and Hamming windows.

HILBERT - Constructs a Hilbert transform.

INTERPOL - Performs linear interpolation on vectors.

LEEFILT - Performs the Lee filter algorithm on an image array.

M_CORRELATE - Computes multiple correlation coefficient.

MEDIAN - Returns median value of an array or applies a median filter.

P_CORRELATE - Computes partial correlation coefficient.

R_CORRELATE - Computes rank correlation.

SAVGOL - Returns coefficients of Savitzky-Golay smoothing filter.

SMOOTH - Smooths with a boxcar average.

TS_COEF - Computes the coefficients for autoregressive time-series.

TS_DIFF - Computes the forward differences of a time-series.

TS_FCAST - Computes future or past values of stationary time-series.

TS_SMOOTH - Computes moving averages of a time-series.

WTN - Returns wavelet transform of the input array.

See Also - Wavelet Toolkit

Saving/Restoring a Session

JOURNAL - Logs IDL commands to a file.IDL.

RESTORE - Restores IDL variables and routines in an IDL SAVE file.

SAVE - Saves variables, system variables, and IDL routines in a file for later use.

String Processing

STRCMP - Compares two strings.

STRCOMPRESS - Removes whitespace from a string.

STREGEX - Performs regular expression matching.

STRJOIN - Collapses a string scalar or array into merged strings.

STRLEN - Returns the length of a string.

STRLOWCASE - Converts a string to lower case.

STRMATCH - Compares search string against input string expression.

STRMID - Extracts a substring from a string.

STRPOS - Finds first occurrence of a substring within a string.

STRPUT - Inserts the contents of one string into another.

STRSPLIT - Splits its input string argument into separate substrings, according to the specified pattern.

STRTRIM - Removes leading and/or trailing blanks from string.

STRUPCASE - Converts a string to upper case.

Structures

REPLICATE - Creates an array of given dimensions, filled with specified value.

STRUCT_ASSIGN - Uses "Relaxed Structure Assignment" to copy structures.

STRUCT_HIDE - Prevents the IDL HELP procedure from displaying information about structures or objects.

Type Conversion

BYTE - Converts argument to byte type.

COMPLEX - Converts argument to complex type.

DCOMPLEX - Converts argument to double-precision complex type.

DOUBLE - Converts argument to double-precision type.

FIX - Converts argument to integer type, or type specified by TYPE keyword.

FLOAT - Converts argument to single-precision floating-point.

LONG - Converts argument to longword integer type.

LONG64 - Converts argument to 64-bit integer type.

STRING - Converts arguments to string type.

UINT - Converts argument to unsigned integer type.

ULONG - Converts argument to unsigned longword integer type.

ULONG64 - Converts argument to unsigned 64-bit integer type.

Utilities

EFONT - Interactive vector font editor and display tool.

SLIDE_IMAGE - Creates a scrolling graphics window for examining large images.

XBM_EDIT - Creates, edits bitmap icons for IDL widget button labels.

XDISPLAYFILE - Displays ASCII text file in scrolling text widget.

XDXF - Utility for displaying and interactively manipulating DXF objects.

XFONT - Creates modal widget to select and view an X Windows font.

XINTERANIMATE - Displays animated sequence of images.

XMTOOL - Displays tool for viewing XMANAGER widgets.

XOBJVIEW - Displays object viewer widget.

XPCOLOR - Adjusts the value of the current foreground plotting color, !P.COLOR.

XPLOT3D - Utility for creating and interactively manipulating 3D plots.

XROI - Utility for interactively defining and obtaining information about regions of interest.

XVOLUME - Utility for viewing and interactively manipulating volumes and isosurfaces.

Wavelet Toolkit (optional)

WV_APPLET - Runs the IDL Wavelet Toolkit GUI.

WV_CW_WAVELET - Compound widget used to select and display wavelet functions.

WV_DWT - Returns the multi-dimensional discrete wavelet transform of the input array.

WV_FN_COIFLET - Constructs wavelet coefficients for the coiflet wavelet function.

WV_FN_DAUBECHIES - Constructs wavelet coefficients for the Daubechies wavelet function.

WV_FN_HAAR - Constructs wavelet coefficients for the Haar wavelet function.

WV_FN_SYMLET - Constructs wavelet coefficients for the symlet wavelet function.

WV_IMPORT_DATA - Allows user to add a variable to the currently active WV_APPLET widget from the IDL> command prompt.

WV_IMPORT_WAVELET - Allows user to add wavelet functions to the IDL Wavelet Toolkit.

WV_PLOT3D_WPS - Runs the GUI for 3D visualization of the wavelet power spectrum.

WV_PLOT_MULTIRES - Runs GUI for multiresolution analysis.

WV_PWT - Returns the partial wavelet transform of the input vector.

WV_TOOL_DENOISE - Runs the GUI for wavelet filtering and denoising.

Widget Routines

WIDGET_BASE - Creates base widget (containers for other widgets).

WIDGET_BUTTON - Creates button widgets.

WIDGET_CONTROL - Realizes, manages, and destroys widgets.

WIDGET_DRAW - Creates drawable widgets.

WIDGET_DROPLIST - Creates droplist widgets.

WIDGET_EVENT - Returns events for the widget hierarchy.

WIDGET_INFO - Obtains information about widgets.

WIDGET_LABEL - Creates label widgets.

WIDGET_LIST - Creates list widgets.

WIDGET_SLIDER - Creates slider widgets.

WIDGET_TABLE - Creates table widgets.

WIDGET_TEXT - Creates text widgets.

XMANAGER - Provides event loop manager for IDL widgets.

XMNG_TMPL - Template for creating widgets.

XMTOOL - Displays tool for viewing XMANAGER widgets.

XREGISTERED - Returns registration status of a given widget.

Widget Routines, Compound

CW_ANIMATE - Creates a compound widget for animation.

CW_ANIMATE_GETP - Gets pixmap window IDs used by CW_ANIMATE.

CW_ANIMATE_LOAD - Loads images into CW_ANIMATE.

CW_ANIMATE_RUN - Displays images loaded into CW_ANIMATE.

CW_ARCBALL - Creates compound widget for intuitively specifying 3D orientations.

CW_BGROUP - Creates button group for use as a menu.

CW_CLR_INDEX - Creates compound widget for the selection of a color index.

CW_COLORSEL - Creates compound widget that displays all colors in current colormap.

CW_DEFROI - Creates compound widget used to define region of interest.

CW_FIELD - Creates a widget data entry field.

CW_FILESEL - Creates compound widget for file selection.

CW_FORM - Creates compound widget for creating forms.

CW_FSLIDER - Creates slider that selects floating-point values.

CW_LIGHT_EDITOR - Creates compound widget to edit properties of existing IDLgrLight objects in a view.

CW_LIGHT_EDITOR_GET - Gets the CW_LIGHT_EDITOR properties.

CW_LIGHT_EDITOR_SET - Sets the CW_LIGHT_EDITOR properties.

CW_ORIENT - Creates compound widget used to interactively adjust the 3D drawing transformation.

CW_PALETTE_EDITOR - Creates compound widget to display and edit color palettes.

CW_PALETTE_EDITOR_GET - Gets the CW_PALETTE_EDITOR properties.

CW_PALETTE_EDITOR_SET - Sets the CW_PALETTE_EDITOR properties.

CW_PDMENU - Creates widget pulldown menus.

CW_RGBSLIDER - Creates compound widget with sliders for adjusting RGB color values.

CW_TMPL - Template for compound widgets that use XMANAGER.

CW_ZOOM - Creates widget for displaying zoomed images.

Window Routines

WINDOW - Creates window for the display of graphics or text.

WDELETE - Deletes IDL graphics windows.

WSET - Selects the current window.

WSHOW - Exposes or hides the designated window.

IDL Syntax Conventions

Function: *Result* = FUNCTION(*Argument1* [, *Argument2*] [, KEYWORD1=*value*] [, /KEYWORD2])

Procedure: PROCEDURE, *Argument1* [, *Argument2*] [, KEYWORD1={*value1* | *value2*}] [, /KEYWORD2]

Statement: IF *expression* THEN *statement* [ELSE *statement*]

Elements of Syntax

Element	Description
[ ] (Square brackets)	Indicates that the contents are optional.
[ ] (Italicized square brackets)	Indicates that the square brackets are part of the statement (used to define an array).
Argument	Arguments are shown in italics, and must be specified in the order listed.
KEYWORD	Keywords are all caps, and can be specified in any order. For functions, all arguments and keywords must be contained within parentheses.
/KEYWORD	Indicates a boolean keyword.
Italics	Indicates arguments, expressions, or statements for which you must provide values.
{ } (Braces)	• Indicates that you must choose one of the values they contain • Encloses a list of possible values, separated by vertical lines (	) • Encloses useful information about a keyword • Defines an IDL structure (this is the only case in which the braces are included in the statement).
	(Vertical lines)	Separates multiple values or keywords.
[, *Value$_1$*, ... , *Value$_n$*]	Indicates that any number of values can be specified.
[, *Value$_1$*, ... , *Value$_8$*]	Indicates the maximum number of values that can be specified.

Square Brackets ([ ])

- Content between square brackets is optional. Pay close attention to the grouping of square brackets. Consider the following examples:

  ROUTINE_NAME, *Value1* [, *Value2*] [, *Value3*] : You must include *Value1*. You do not have to include *Value2* or *Value3*. *Value2* and *Value3* can be specified independently.

  ROUTINE_NAME, *Value1* [, *Value2*, *Value3*] : You must include *Value1*. You do not have to include *Value2* or *Value3*, but you must include both *Value2* and *Value3*, or neither.

  ROUTINE_NAME [, *Value1* [, *Value2*]] : You can specify *Value1* without specifying *Value2*, but if you specify *Value2*, you must also specify *Value1*.

- Do not include square brackets in your statement unless the brackets are italicized. Consider the following syntax:

  Result = KRIG2D(*Z* [, *X*, *Y*] [, BOUNDS=*[xmin*, *ymin*, *xmax*, *ymax]*])

  An example of a valid statement is:

  R = KRIG2D(Z, X, Y, BOUNDS=[0,0,1,1])

- Note that when [, *Value₁*, ... , *Valueₙ*] is listed, you can specify any number of arguments. When an explicit number is listed, as in [, *Value₁*, ... , *Value₈*], you can specify only as many arguments as are listed.

Braces ({ })

- For certain keywords, a list of the possible values is provided. This list is enclosed in braces, and the choices are separated by a vertical line (|). Do not include the braces in your statement. For example, consider the following syntax:

  LIVE_EXPORT [, QUALITY={0 | 1 | 2}]

  In this example, you must choose either 0, 1, or 2. An example of a valid statement is:

  LIVE_EXPORT, QUALITY=1

- Braces are used to enclose the allowable range for a keyword value. Unless otherwise noted, ranges provided are inclusive. Consider the following syntax:

  Result = CVTTOBM(*Array* [, THRESHOLD=*value*{0 to 255}])

  An example of a valid statement is:

  Result = CVTTOBM(A, THRESHOLD=150)

- Braces are also used to provide useful information about a keyword. For example:

  [, LABEL=*n*{label every *n*th gridline}]

  Do not include the braces or their content in your statement.

- Certain keywords are prefaced by X, Y, or Z. Braces are used for these keywords to indicate that you must choose one of the values it contains. For example, [{X | Y}RANGE=*array*] indicates that you can specify either XRANGE=*array* or YRANGE=*array.*

- Note that in IDL, braces are used to define structures. When defining a structure, you *do* want to include the braces in your statement.

Italics

- Italicized words are arguments, expressions, or statements for which you must provide values. The value you provide can be a numerical value, such as 10, an expression, such as DIST(100), or a named variable. For keywords that expect a string value, the syntax is listed as KEYWORD=*string*. The value you provide can be a string, such as 'Hello' (enclosed in single quotation marks), or a variable that holds a string value.

- The italicized values that must be provided for keywords are listed in the most helpful terms possible. For example, [, XSIZE=*pixels*] indicates that the XSIZE keyword expects a value in pixels, while [, ORIENTATION=*ccw_degrees_from_horiz*] indicates that you must provide a value in degrees, measured counter-clockwise from horizontal.

Specifying Keywords

- Certain keywords are boolean, meaning they can be set to either 0 or 1. These keywords are switches used to turn an option on and off. Usually, setting such keywords equal to 1 causes the option to be turned on. Explicitly setting the keyword to 0 (or not including the keyword) turns the option off. All keywords in this reference that are preceded by a slash can be set by prefacing them by the slash. For example, SURFACE, DIST(10), /SKIRT is a shortcut for SURFACE, DIST(10), SKIRT=1. To turn the option back off, you must set the keyword equal to 0, as in SURFACE, DIST(10), SKIRT=0.

    In rare cases, a keyword's default value is 1. In these cases, the syntax is listed as KEYWORD=0, as in SLIDE_IMAGE [, *Image*] [, CONGRID=0]. In this example, CONGRID is set to 1 by default. If you specify CONGRID=0, you can turn it back on by specifying either /CONGRID or CONGRID=1.

- Some keywords are used to obtain values that can be used upon return from the function or procedure. These keywords are listed as KEYWORD=*variable*. Any valid variable name can be used for these keywords, and the variable does not need to be defined first. Note, however that when a keyword calls for a named variable, only a named variable can be used—sending an expression causes an error.

    For example, the WIDGET_CONTROL procedure can return the user values of widgets in a named variable using the GET_UVALUE keyword. To return the user value for a widget ID (contained in the variable mywidget) in the variable userval, you would use the command:

    WIDGET_CONTROL, mywidget, GET_UVALUE = userval

    Upon return from the procedure, userval contains the user value. Note that userval did not have to be defined before the call to WIDGET_CONTROL.

- Some routines have keywords that are mutually exclusive, meaning only one of the keywords can be present in a given statement. These keywords are grouped together, and separated by a vertical line. For example, consider the following syntax:

    PLOT, [*X*,] *Y* [, /DATA | , /DEVICE | , /NORMAL]

    In this example, you can choose either DATA, DEVICE, or NORMAL, but not more than one. An example of a valid statement is:

    PLOT, SIN(A), /DEVICE

- Keywords can be abbreviated to their shortest unique length. For example, the XSTYLE keyword can be abbreviated to XST because there are no other keywords in IDL that begin with XST. You cannot shorten XSTYLE to XS, however, because there are other keywords that begin with XS, such as XSIZE.

Alphabetical Listing

The following alphabetical listing contains all IDL functions, procedures, and statements included in IDL version 5.4.

A

A_CORRELATE - Computes autocorrelation.
Result = A_CORRELATE(*X*, *Lag* [, /COVARIANCE] [, /DOUBLE])

ABS - Returns the absolute value of *X*.
Result = ABS(*X*)

ACOS - Returns the arc-cosine of *X*.
Result = ACOS(*X*)

ADAPT_HIST_EQUAL - Performs adaptive histogram equalization
Result = ADAPT_HIST_EQUAL (*Image* [, CLIP=*value*] [, NREGIONS=*nregions*] [, TOP=*value*])

ALOG - Returns the natural logarithm of *X*.
Result = ALOG(*X*)

ALOG10 - Returns the logarithm to the base 10 of *X*.
Result = ALOG10(*X*)

AMOEBA - Minimizes a function using downhill simplex method.
Result = AMOEBA(*Ftol* [, FUNCTION_NAME=*string*] [, FUNCTION_VALUE=*variable*] [, NCALLS=*value*] [, NMAX=*value*] [, P0=*vector*, SCALE=*vector* | , SIMPLEX=*array*])

ANNOTATE - Starts IDL widget used to interactively annotate images and plots with text and drawings.
ANNOTATE [, COLOR_INDICES=*array*] [, DRAWABLE=*widget_id* | , WINDOW=*index*] [, LOAD_FILE=*filename*] [/TEK_COLORS]

ARG_PRESENT - Returns TRUE if the value of the specified variable can be passed back to the caller.
Result = ARG_PRESENT(*Variable*)

ARRAY_EQUAL - Provides a fast way to compare data for equality in situations where the index of the elements that differ are not of interest.
Result = ARRAY_EQUAL(*Op1* , *Op2* [, /NO_TYPECONV])

ARROW - Draws line with an arrow head.
ARROW, *X0*, *Y0*, *X1*, *Y1* [, /DATA | , /NORMALIZED] [, HSIZE=*length*] [, COLOR=*index*] [, HTHICK=*value*] [, /SOLID] [, THICK=*value*]

ASCII_TEMPLATE - Presents a GUI that generates a template defining an ASCII file format.
Result = ASCII_TEMPLATE([*Filename*] [, BROWSE_LINES=*lines*] [, CANCEL=*variable*] [, GROUP=*widget_id*])

ASIN - Returns the arc-sine of *X*.
Result = ASIN(*X*)

ASSOC - Associates an array structure with a file.
Result = ASSOC(*Unit*, *Array_Structure* [, *Offset*] [, /PACKED])

ATAN - Returns the arc-tangent of *X*.
Result = ATAN(*X*) or *Result* = ATAN(*Y*, *X*)

AXIS - Draws an axis of the specified type and scale.
AXIS [, *X* [, *Y* [, *Z*]]] [, /SAVE] [, XAXIS={0 | 1} | YAXIS={0 | 1} | ZAXIS={0 | 1 | 2 | 3}] [, /XLOG] [, /YNOZERO] [, /YLOG] [, /ZLOG]
Graphics Keywords: [, CHARSIZE=*value*] [, CHARTHICK=*integer*] [, COLOR=*value*] [, /DATA | , /DEVICE | , /NORMAL] [, FONT=*integer*] [, /NODATA] [, /NOERASE] [, SUBTITLE=*string*] [, /T3D] [, TICKLEN=*value*] [, {X | Y | Z}CHARSIZE=*value*] [, {X | Y | Z}GRIDSTYLE=*integer*{0 to 5}] [, {X | Y | Z}MARGIN=*[left*, *right]*] [, {X | Y | Z}MINOR=*integer*] [, {X | Y | Z}RANGE=*[min*, *max]*] [, {X | Y | Z}STYLE=*value*] [, {X | Y | Z}THICK=*value*] [, {X | Y | Z}TICKFORMAT=*string or a vector of strings*] [, {X | Y | Z}TICKINTERVAL=*value*] [, {X | Y | Z}TICKLAYOUT=*scalar*] [, {X | Y | Z}TICKLEN=*value*] [, {X | Y | Z}TICKNAME=*string_array*] [, {X | Y | Z}TICKS=*integer*] [, {X | Y | Z}TICKUNITS=*string or a vector of strings*] [, {X | Y | Z}TICKV=*array*] [, {X | Y | Z}TICK_GET=*variable*] [, {X | Y | Z}TITLE=*string*] [, ZVALUE=*value*{0 to 1}]

B

BAR_PLOT - Creates a bar graph.
BAR_PLOT, *Values* [, BACKGROUND=*color_index*] [, BARNAMES=*string_array*] [, BAROFFSET=*scalar*] [, BARSPACE=*scalar*] [, BARWIDTH=*value*] [, BASELINES=*vector*] [, BASERANGE=*scalar*{0.0 to

1.0}] [, COLORS=*vector*] [, /OUTLINE] [, /OVERPLOT]
[, /ROTATE] [, TITLE=*string*] [, XTITLE=*string*]
[, YTITLE=*string*]

BEGIN...END - Defines a block of statements.
BEGIN
   statements
END | ENDIF | ENDELSE | ENDFOR | ENDREP |
ENDWHILE

BESELI - Returns the I Bessel function of order *N* for *X*.
$Result = $ BESELI(X, N)

BESELJ - Returns the J Bessel function of order *N* for *X*.
$Result = $ BESELJ(X, N)

BESELK - Returns the K Bessel function of order *N* for the *X*.
$Result = $ BESELK(X, N)

BESELY - Returns the Y Bessel function of order *N* for *X*.
$Result = $ BESELY(X, N)

BETA - Returns the value of the beta function.
$Result = $ BETA(Z, W [, /DOUBLE])

BILINEAR - Computes array using bilinear interpolation.
$Result = $ BILINEAR(P, IX, JY)

BIN_DATE - Converts ASCII date/time string to binary string.
$Result = $ BIN_DATE(*Ascii_Time*)

BINARY_TEMPLATE - Presents a GUI for interactively generating a template structure for use with READ_BINARY.
Template = BINARY_TEMPLATE ([*Filename*]
[, CANCEL=*variable*] [, GROUP=*widget_id*]
[, N_ROWS=*rows*] [, TEMPLATE=*variable*])

BINDGEN - Returns byte array with each element set to its subscript.
$Result = $ BINDGEN(D_1, ...,D_8)

BINOMIAL - Computes binomial distribution function.
$Result = $ BINOMIAL(V, N, P [, /DOUBLE]
[, /GAUSSIAN])

BLAS_AXPY - Updates existing array by adding a multiple of another array.
BLAS_AXPY, Y, A, X [, *D1*, *Loc1* [, *D2*, *Range*]]

BLK_CON - Convolves input signal with impulse-response sequence.
$Result = $ BLK_CON(*Filter*, *Signal* [, B_LENGTH=*scalar*]
[, /DOUBLE])

BOX_CURSOR - Emulates the operation of a variable-sized box cursor.
BOX_CURSOR, [*X0*, *Y0*, *NX*, *NY* [, /INIT]
[, /FIXED_SIZE]] [, /MESSAGE]

BREAK - Immediately exits from a loop (FOR, WHILE, REPEAT), CASE, or SWITCH statement.
BREAK

BREAKPOINT - Sets and clears breakpoints for debugging.
BREAKPOINT [, *File*], *Index* [, AFTER=*integer*]
[, /CLEAR] [, CONDITION='*expression*'] [, /DISABLE]
[, /ENABLE] [, /ONCE] [, /SET]

BROYDEN - Solves nonlinear equations using Broyden's method.
$Result = $ BROYDEN(X, *Vecfunc* [, CHECK=*variable*]
[, /DOUBLE] [, EPS=*value*] [, ITMAX=*value*]
[, STEPMAX=*value*] [, TOLF=*value*] [, TOLMIN=*value*]
[, TOLX=*value*])

BYTARR - Creates a byte vector or array.
$Result = $ BYTARR(D_1, ..., D_8 [, /NOZERO])

BYTE - Converts argument to byte type.
$Result = $ BYTE(*Expression*[, *Offset* [, Dim_1, ..., Dim_8]])

BYTEORDER - Converts between host and network byte ordering.
BYTEORDER, $Variable_1$, ..., $Variable_n$ [, /DTOVAX]
[, /DTOXDR] [, /FTOVAX] [, /FTOXDR] [, /HTONL]
[, /HTONS] [, /L64SWAP] [, /LSWAP] [, /NTOHL]
[, /NTOHS] [, /SSWAP] [, /SWAP_IF_BIG_ENDIAN]
[, /SWAP_IF_LITTLE_ENDIAN] [, /VAXTOD]
[, /VAXTOF] [, /XDRTOD] [, /XDRTOF]
VMS keywords: [, /DTOGFLOAT] [, /GFLOATTOD]

BYTSCL - Scales all values of an array into range of bytes.
$Result = $ BYTSCL(*Array* [, MAX=*value*] [, MIN=*value*]
[, /NAN] [, TOP=*value*])

C

C_CORRELATE - Computes cross correlation.
$Result = $ C_CORRELATE(X, Y, *Lag* [, /COVARIANCE]
[, /DOUBLE])

CALDAT - Converts Julian date to month, day, year.
CALDAT, *Julian*, *Month* [, *Day* [, *Year* [, *Hour* [, *Minute*
[, *Second*]]]]]

CALENDAR - Displays a calendar for a given month or year.
CALENDAR [[, *Month*] , *Year*]

CALL_EXTERNAL - Calls a function in an external sharable object and returns a scalar value.
$Result = $ CALL_EXTERNAL(*Image*, *Entry* [, P_0, ..., P_{N-1}]
[, /ALL_VALUE] [, /B_VALUE | , /D_VALUE |
, /F_VALUE | , /I_VALUE | , /L64_VALUE |
, /S_VALUE | , /UI_VALUE | , /UL_VALUE |
, /UL64_VALUE] [, /CDECL] [, RETURN_TYPE=*value*]
[, /UNLOAD] [, VALUE=*byte_array*]
[, WRITE_WRAPPER=*wrapper_file*])
VMS keywords: [, DEFAULT=*string*] [, /PORTABLE]
[, /VAX_FLOAT]
Auto Glue keywords: [, /AUTOGLUE] [, CC=*string*]
[, COMPILE_DIRECTORY=*string*] [,
EXTRA_CFLAGS=*string*] [, EXTRA_LFLAGS=*string*] [,
/IGNORE_EXISTING_GLUE] [, LD=*string*]
[, /NOCLEANUP] [, /SHOW_ALL_OUTPUT] [,
/VERBOSE]

CALL_FUNCTION - Calls an IDL function.
$Result = $ CALL_FUNCTION(*Name* [, P_1, ..., P_n])

CALL_METHOD - Calls an IDL object method.
CALL_METHOD, *Name*, *ObjRef*, [, *P_1*, ..., *P_n*] or
Result = CALL_METHOD(*Name*, *ObjRef*, [, *P_1*, ..., *P_n*])

CALL_PROCEDURE - Calls an IDL procedure.
CALL_PROCEDURE, *Name* [, *P_1*, ..., *P_n*]

CASE - Selects one statement for execution, depending on the value of an expression.
CASE *expression* OF
   expression: *statement*
   ...
   expression: *statement*
[ELSE: *statement*]
ENDCASE

CATCH - Declares and clears exception handlers.
CATCH, *Variable* [, /CANCEL]

CD - Sets and/or changes the current working directory.
CD [, *Directory*] [, CURRENT=*variable*]

CDF_* Routines - See "CDF Routines" on page 53.

CEIL - Returns the closest integer greater than or equal to *X*.
Result = CEIL(*X* [, /L64])

CHEBYSHEV - Returns the forward or reverse Chebyshev polynomial expansion.
Result = CHEBYSHEV(*D*, *N*)

CHECK_MATH - Returns and clears accumulated math error status.
Result = CHECK_MATH([, MASK=*bitmask*] [, /NOCLEAR] [, /PRINT])

CHISQR_CVF - Computes cutoff value in a Chi-square distribution.
Result = CHISQR_CVF(*P*, *Df*)

CHISQR_PDF - Computes Chi-square distribution function.
Result = CHISQR_PDF(*V*, *Df*)

CHOLDC - Constructs Cholesky decomposition of a matrix.
CHOLDC, *A*, *P* [, /DOUBLE]

CHOLSOL - Solves set of linear equations (use with CHOLDC).
Result = CHOLSOL(*A*, *P*, *B* [, /DOUBLE])

CINDGEN - Returns a complex array with each element set to its subscript.
Result = CINDGEN(*D_1*, ..., *D_8*)

CIR_3PNT - Returns radius and center of circle, given 3 points.
CIR_3PNT, *X*, *Y*, *R*, *X0*, *Y0*

CLOSE - Closes the specified files.
CLOSE[, *Unit_1*, ..., *Unit_n*] [, /ALL] [, EXIT_STATUS=*variable*] [, /FILE] [, /FORCE]

CLUST_WTS - Computes the cluster weights of an array for cluster analysis.
Result = CLUST_WTS(*Array* [, /DOUBLE] [, N_CLUSTERS=*value*] [, N_ITERATIONS=*integer*] [, VARIABLE_WTS=*vector*])

CLUSTER - Performs cluster analysis.
Result = CLUSTER(*Array*, *Weights* [, /DOUBLE] [, N_CLUSTERS=*value*])

COLOR_CONVERT - Converts color triples to and from RGB, HLS, and HSV.
COLOR_CONVERT, *I_0*, *I_1*, *I_2*, *O_0*, *O_1*, *O_2* {, /HLS_RGB | , /HSV_RGB | , /RGB_HLS | , /RGB_HSV}

COLOR_QUAN - Converts true-color (24-bit) image to pseudo-color (8-bit) image.
Result = COLOR_QUAN(*Image_R*, *Image_G*, *Image_B*, *R*, *G*, *B*)
or
Result = COLOR_QUAN(*Image*, *Dim*, *R*, *G*, *B*)
Keywords: [, COLORS=*integer*{2 to 256}] [, CUBE={2 | 3 | 4 | 5 | 6} | , GET_TRANSLATION=*variable* [, /MAP_ALL]] [, /DITHER] [, ERROR=*variable*] [, TRANSLATION=*vector*]

COLORMAP_APPLICABLE - Determines whether the current visual class supports the use of a colormap.
Result = COLORMAP_APPLICABLE(*redrawRequired*)

COMFIT - Fits paired data using one of six common filtering functions.
Result = COMFIT(*X*, *Y*, *A* {, /EXPONENTIAL | , /GEOMETRIC | , /GOMPERTZ | , /HYPERBOLIC | , /LOGISTIC | , /LOGSQUARE} [, SIGMA=*variable*] [, WEIGHTS=*vector*] [, YFIT=*variable*])

COMMON - Creates a common block.
COMMON *Block_Name*, *Variable_1*, ..., *Variable_n*

COMPILE_OPT - Gives IDL compiler information that changes the default rules for compiling functions or procedures.
COMPILE_OPT *opt_1* [, *opt_2*, ..., *opt_n*]
Note: *opt_n* can be IDL2, DEFINT32, HIDDEN, OBSOLETE, or STRICTARR

COMPLEX - Converts argument to complex type.

Result = COMPLEX(*Real* [, *Imaginary*])
or
Result = COMPLEX(*Expression*, *Offset*, *Dim_1* [, ..., *Dim_8*])

COMPLEXARR - Creates a complex, single-precision, floating-point vector or array.
Result = COMPLEXARR(*D_1*, ..., *D_8* [, /NOZERO])

COMPLEXROUND - Rounds a complex array.
Result = COMPLEXROUND(*Input*)

COMPUTE_MESH_NORMALS - Computes normal vectors for a set of polygons.
Result=COMPUTE_MESH_NORMALS(*fVerts*[, *iConn*])

COND - Computes the condition number of a square matrix.
Result = COND(*A* [, /DOUBLE])

CONGRID - Resamples an image to any dimensions.
Result = CONGRID(*Array*, *X*, *Y*, *Z* [, CUBIC=*value*{-1 to 0}] [, /INTERP] [, /MINUS_ONE])

CONJ - Returns the complex conjugate of *X*.

Result = CONJ(*X*)

CONSTRAINED_MIN - Minimizes a function using Generalized Reduced Gradient Method.

CONSTRAINED_MIN, *X*, *Xbnd*, *Gbnd*, *Nobj*, *Gcomp*, *Inform* [, ESPTOP=*value*] [, LIMSER=*value*] [, /MAXIMIZE] [, NSTOP=*value*] [, REPORT=*filename*] [, TITLE=*string*]

CONTINUE - Immediately starts the next iteration of the enclosing FOR, WHILE, or REPEAT loop.

CONTINUE

CONTOUR - Draws a contour plot.

CONTOUR, *Z* [, *X*, *Y*] [, C_CHARSIZE=*value*] [, C_CHARTHICK=*integer*] [, C_COLORS=*vector*] [, C_LABELS=*vector*{each element 0 or 1}] [, C_LINESTYLE=*vector*] [{, /FILL | , /CELL_FILL} | , C_ANNOTATION=*vector_of_strings*] [, C_ORIENTATION=*degrees*] [, C_SPACING=*value*]] [, C_THICK=*vector*] [, /CLOSED] [, /DOWNHILL] [, /FOLLOW] [, /IRREGULAR] [, LEVELS=*vector* / NLEVELS=*integer*{1 to 60}] [, MAX_VALUE=*value*] [, MIN_VALUE=*value*] [, /OVERPLOT] [{, /PATH_DATA_COORDS, PATH_FILENAME=*string*, PATH_INFO=*variable*, PATH_XY=*variable*} | , TRIANGULATION=*variable*] [, /PATH_DOUBLE] [, /XLOG] [, /YLOG] [, /ZAXIS] [, /ZLOG]

Graphics Keywords: Accepts all graphics keywords accepted by PLOT except for: LINESTYLE, PSYM, SYMSIZE.

CONVERT_COORD - Transforms coordinates to and from the coordinate systems supported by IDL.

Result = CONVERT_COORD(*X* [, *Y* [, *Z*]] [, /DATA | , /DEVICE | , /NORMAL] [, /DOUBLE] [, /T3D] [, /TO_DATA | , /TO_DEVICE | , /TO_NORMAL])

CONVOL - Convolves two vectors or arrays.

Result = CONVOL(*Array*, *Kernel* [, *Scale_Factor*] [, /CENTER] [, /EDGE_WRAP] [, /EDGE_TRUNCATE])

COORD2TO3 - Returns 3D data coordinates given normalized screen coordinates.

Result = COORD2TO3(*Mx*, *My*, *Dim*, *D0* [, *PTI*])

CORRELATE - Computes the linear Pearson correlation.

Result = CORRELATE(*X* [, *Y*] [, /COVARIANCE] [, /DOUBLE])

COS - Returns the cosine of X.

Result = COS(*X*)

COSH - Returns the hyperbolic cosine of *X*.

Result = COSH(*X*)

CRAMER - Solves system of linear equations using Cramer's rule.

Result = CRAMER(*A*, *B* [, /DOUBLE] [, ZERO=*value*])

CREATE_STRUCT - Creates and concatenates structures.

Result = CREATE_STRUCT([*Tag₁*, *Value₁*, ..., *Tagₙ*, *Valueₙ*])

or

Result = CREATE_STRUCT(NAME=*string*, [*Tag₁*, ..., *Tagₙ*], *Value₁*, ..., *Valueₙ*)

CREATE_VIEW - Sets up 3D transformations.

CREATE_VIEW [, AX=*value*] [, AY=*value*] [, AZ=*value*] [, PERSP=*value*] [, /RADIANS] [, WINX=*pixels*] [, WINY=*pixels*] [, XMAX=*scalar*] [, XMIN=*scalar*] [, YMAX=*scalar*] [, YMIN=*scalar*] [, ZFAC=*value*] [, ZMAX=*scalar*] [, ZMIN=*scalar*] [, ZOOM=*scalar or 3-element vector*]

CROSSP - Computes vector cross product.

Result = CROSSP(*V1*, *V2*)

CRVLENGTH - Computes the length of a curve.

Result = CRVLENGTH(*X*, *Y* [, /DOUBLE])

CT_LUMANCE - Calculates the luminance of colors.

Result = CT_LUMINANCE([*R*, *G*, *B*] [, BRIGHT=*variable*] [, DARK=*variable*] [, /READ_TABLES])

CTI_TEST - Performs chi-square goodness-of-fit test.

Result = CTI_TEST(*Obfreq* [, COEFF=*variable*] [, /CORRECTED] [, CRAMV=*variable*] [, DF=*variable*] [, EXFREQ=*variable*] [, RESIDUAL=*variable*])

CURSOR - Reads position of the interactive graphics cursor.

CURSOR, *X*, *Y* [, *Wait* / [, /CHANGE | , /DOWN | , /NOWAIT | , /UP | , /WAIT]] [, /DATA | , /DEVICE, | , /NORMAL]

CURVEFIT - Fits multivariate data with a user-supplied function.

Result = CURVEFIT(*X*, *Y*, *Weights*, *A* [, *Sigma*] [, CHISQ=*variable*] [, /DOUBLE] [, FUNCTION_NAME=*string*] [, ITER=*variable*] [, ITMAX=*value*] [, /NODERIVATIVE] [, TOL=*value*])

CV_COORD - Converts 2D and 3D coordinates between coordinate systems.

Result = CV_COORD([, /DEGREES] [, /DOUBLE] [, FROM_CYLIN=*cyl_coords* | , FROM_POLAR=*pol_coords* | , FROM_RECT=*rect_coords* | , FROM_SPHERE=*sph_coords*] [, /TO_CYLIN | , /TO_POLAR | , /TO_RECT | , /TO_SPHERE])

CVTTOBM - Creates a bitmap byte array for a button label.

Result = CVTTOBM(*Array* [, THRESHOLD=*value*{0 to 255}])

CW_ANIMATE - Creates a compound widget for animation.

Result = CW_ANIMATE(*Parent*, *Sizex*, *Sizey*, *Nframes* [, /NO_KILL] [, OPEN_FUNC=*string*] [, PIXMAPS=*vector*] [, /TRACK] [, UNAME=*string*] [, UVALUE=*value*])

CW_ANIMATE_GETP - Gets pixmap window IDs used by CW_ANIMATE.

   CW_ANIMATE_GETP, *Widget*, *Pixmaps*
   [, /KILL_ANYWAY]

CW_ANIMATE_LOAD - Loads images into CW_ANIMATE.

   CW_ANIMATE_LOAD, *Widget* [, /CYCLE]
   [, FRAME=*value*{0 to *NFRAMES*}] [, IMAGE=*value*]
   [, /ORDER] [, WINDOW=*[window_num* [, *X0*, *Y0*, *Sx*,
   Sy]*]*] [, XOFFSET=*pixels*] [, YOFFSET=*pixels*]

CW_ANIMATE_RUN - Displays images loaded into CW_ANIMATE.

   CW_ANIMATE_RUN, *Widget* [, *Rate*{0 to 100}]
   [, NFRAMES=*value*] [, /STOP]

CW_ARCBALL - Creates compound widget for intuitively specifying 3D orientations.

   Result = CW_ARCBALL(*Parent* [, COLORS=*array*]
   [, /FRAME] [, LABEL=*string*] [, RETAIN={0 | 1 | 2}]
   [, SIZE=*pixels*] [, /UPDATE] [, UNAME=*string*]
   [, UVALUE=*value*] [, VALUE=*array*])

CW_BGROUP - Creates button group for use as a menu.

   Result = CW_BGROUP(*Parent*, *Names*
   [, BUTTON_UVALUE=*array*] [, COLUMN=*value*]
   [, EVENT_FUNC=*string*] [{, /EXCLUSIVE | ,
   /NONEXCLUSIVE} | [, SPACE=*pixels*] [, XPAD=*pixels*]
   [, YPAD=*pixels*]] [, FONT=*font*] [, FRAME=*width*]
   [, IDS=*variable*] [, /LABEL_LEFT | , /LABEL_TOP]
   [, /MAP] [, /NO_RELEASE] [, /RETURN_ID | ,
   /RETURN_INDEX | , /RETURN_NAME] [, ROW=*value*]
   [, /SCROLL] [, X_SCROLL_SIZE=*width*]
   [, Y_SCROLL_SIZE=*height*] [, SET_VALUE=*value*]
   [, UNAME=*string*] [, UVALUE=*value*]
   [, XOFFSET=*value*] [, XSIZE=*width*]
   [, YOFFSET=*value*] [, YSIZE=*value*])

CW_CLR_INDEX - Creates compound widget for the selection of a color index.

   Result = CW_CLR_INDEX(*Parent*
   [, COLOR_VALUES=*vector* | [, NCOLORS=*value*]
   [, START_COLOR=*value*]]
   [, EVENT_FUNC='*function_name*'] [, /FRAME]
   [, LABEL=*string*] [, UNAME=*string*] [, UVALUE=*value*]
   [, VALUE=*value*] [, XSIZE=*pixels*] [, YSIZE=*pixels*])

CW_COLORSEL - Creates compound widget that displays all colors in current colormap.

   Result = CW_COLORSEL(*Parent* [, /FRAME]
   [, UNAME=*string*] [, UVALUE=*value*]
   [, XOFFSET=*value*] [, YOFFSET=*value*])

CW_DEFROI - Creates compound widget used to define region of interest.

   Result = CW_DEFROI(*Draw* [, IMAGE_SIZE=*vector*]
   [, OFFSET=*vector*] [, /ORDER] [, /RESTORE]
   [, ZOOM=*vector*])

CW_FIELD - Creates a widget data entry field.

   Result = CW_FIELD(*Parent* [, /ALL_EVENTS]
   [, /COLUMN] [, FIELDFONT=*font*] [, /FLOATING | ,
   /INTEGER | , /LONG | , /STRING] [, FONT=*string*]
   [, FRAME=*pixels*] [, /NOEDIT] [, /RETURN_EVENTS]
   [, /ROW] [, /TEXT_FRAME] [, TITLE=*string*]
   [, UNAME=*string*] [, UVALUE=*value*] [, VALUE=*value*]
   [, XSIZE=*characters*] [, YSIZE=*lines*])

CW_FILESEL - Creates compound widget for file selection.

   Result = CW_FILESEL (*Parent* [, /FILENAME]
   [, FILTER=*string array*] [, /FIX_FILTER] [, /FRAME]
   [, /IMAGE_FILTER] [, /MULTIPLE | , /SAVE]
   [, PATH=*string*] [, UNAME=*string*] [, UVALUE=*value*]
   [, /WARN_EXIST])

CW_FORM - Creates compound widget for creating forms.

   Result = CW_FORM([*Parent*,] *Desc* [, /COLUMN]
   [, IDS=*variable*] [, TITLE=*string*] [, UNAME=*string*]
   [, UVALUE=*value*])
   Note: *Desc* is a string array. Each element of string array
   contains 2 or more comma-delimited fields. Each string
   has the following format: *['Depth*, *Item*, *Initial_Value*,
   Keywords']

CW_FSLIDER - Creates slider that selects floating-point values.

   Result = CW_FSLIDER(*Parent* [, /DRAG] [, /EDIT]
   [, FORMAT=*string*] [, /FRAME] [, MAXIMUM=*value*]
   [, MINIMUM=*value*] [, SCROLL=*units*]
   [, /SUPRESS_VALUE] [, TITLE=*string*]
   [, UNAME=*string*] [, UVALUE=*value*]
   [, VALUE=*initial_value*] [, XSIZE=*length* | {,
   /VERTICAL [, YSIZE=*height*]}])

CW_LIGHT_EDITOR - Creates compound widget to edit properties of existing IDLgrLight objects in a view.

   Result = CW_LIGHT_EDITOR (*Parent*
   [, /DIRECTION_DISABLED] [, /DRAG_EVENTS]
   [, FRAME=*width*] [, /HIDE_DISABLED]
   [, LIGHT=*objref(s)*] [, /LOCATION_DISABLED]
   [, /TYPE_DISABLED] [, UVALUE=*value*]
   [, XSIZE=*pixels*] [, YSIZE=*pixels*] [, XRANGE=*vector*]
   [, YRANGE=*vector*] [, ZRANGE=*vector*])

CW_LIGHT_EDITOR_GET - Gets the CW_LIGHT_EDITOR properties.

   CW_ LIGHT_EDITOR_GET, *WidgetID*
   [, DIRECTION_DISABLED=*variable*]
   [, DRAG_EVENTS=*variable*]
   [, HIDE_DISABLED=*variable*] [, LIGHT=*variable*]
   [, LOCATION_DISABLED=*variable*]
   [, TYPE_DISABLED=*variable*] [, XSIZE=*variable*]
   [, YSIZE=*variable*] [, XRANGE=*variable*]
   [, YRANGE=*variable*] [, ZRANGE=*variable*]

CW_LIGHT_EDITOR_SET - Sets the CW_LIGHT_EDITOR properties.

CW_ LIGHT_EDITOR_SET, *WidgetID*
[, /DIRECTION_DISABLED] [, /DRAG_EVENTS]
[, /HIDE_DISABLED] [, LIGHT=*objref(s)*]
[, /LOCATION_DISABLED] [, /TYPE_DISABLED]
[, XSIZE=*pixels*] [, YSIZE=*pixels*] [, XRANGE=*vector*]
[, YRANGE=*vector*] [, ZRANGE=*vector*]

CW_ORIENT - Creates compound widget used to interactively adjust the 3D drawing transformation.

Result = CW_ORIENT(*Parent* [, AX=*degrees*]
[, AZ=*degrees*] [, /FRAME] [, TITLE=*string*]
[, UNAME=*string*] [, UVALUE=*value*] [, XSIZE=*width*]
[, YSIZE=*height*])

CW_PALETTE_EDITOR - Creates compound widget to display and edit color palettes.

Result = CW_PALETTE_EDITOR (*Parent*
[, DATA=*array*] [, FRAME=*width*]
[, HISTOGRAM=*vector*] [, /HORIZONTAL]
[, SELECTION=*[start, end]*] [, UNAME=*string*]
[, UVALUE=*value*] [, XSIZE=*width*] [, YSIZE=*height*])

CW_PALETTE_EDITOR_GET - Gets the CW_PALETTE_EDITOR properties.

CW_PALETTE_EDITOR_GET, *WidgetID*
[, ALPHA=*variable*] [, HISTOGRAM=*variable*]

CW_PALETTE_EDITOR_SET - Sets the CW_PALETTE_EDITOR properties.

CW_PALETTE_EDITOR_SET, *WidgetID*
[, ALPHA=*byte_vector*] [, HISTOGRAM=*byte_vector*]

CW_PDMENU - Creates widget pulldown menus.

Result = CW_PDMENU(*Parent*, *Desc* [, /COLUMN]
[, DELIMITER=*string*] [, FONT=*value*] [, /MBAR
[, /HELP]] [, IDS=*variable*] [, /RETURN_ID |,
/RETURN_INDEX | , /RETURN_NAME | ,
/RETURN_FULL_NAME] [, UNAME=*string*]
[, UVALUE=*value*] [, XOFFSET=*value*]
[, YOFFSET=*value*])

CW_RGBSLIDER - Creates compound widget with sliders for adjusting RGB color values.

Result = CW_RGBSLIDER(*Parent*
[, /CMY | , /HSV | , /HLS | , /RGB]
[, /COLOR_INDEX | , GRAPHICS_LEVEL={1 | 2}]
[, /DRAG] [, /FRAME] [, LENGTH=*value*]
[, UNAME=*string*] [, UVALUE=*value*]
[, VALUE=*[r, g, b]*] [, /VERTICAL])

CW_TMPL - Template for compound widgets that use XMANAGER.

Result = CW_TMPL(*Parent* [, UNAME=*string*]
[, UVALUE=*value*])

CW_ZOOM - Creates widget for displaying zoomed images.

Result = CW_ZOOM(*Parent* [, /FRAME] [, MAX=*scale*]
[, MIN=*scale*] [, RETAIN={0 | 1 | 2}] [, SAMPLE=*value*]
[, SCALE=*value*] [, /TRACK] [, UNAME=*string*]
[, UVALUE=*value*] [, XSIZE=*width*]
[, X_SCROLL_SIZE=*width*] [, X_ZSIZE=*zoom_width*]
[, YSIZE=*height*] [, Y_SCROLL_SIZE=*height*]
[, Y_ZSIZE=*zoom_height*])

D

DBLARR - Creates a double-precision array.

Result = DBLARR(D_1, ..., D_8 [, /NOZERO])

DCINDGEN - Returns a double-precision, complex array with each element set to its subscript.

Result = DCINDGEN(D_1, ..., D_8)

DCOMPLEX - Converts argument to double-precision complex type.

Result = DCOMPLEX(*Real* [, *Imaginary*])
or
Result = DCOMPLEX(*Expression*, *Offset*,
Dim_1 [, ..., Dim_8])

DCOMPLEXARR - Creates a complex, double-precision vector or array.

Result = DCOMPLEXARR(D_1, ..., D_8 [, /NOZERO])

DEFINE_KEY - Programs keyboard function keys.

DEFINE_KEY, *Key* [, *Value*] [, /MATCH_PREVIOUS]
[, /NOECHO] [, /TERMINATE]
UNIX Keywords: [, /BACK_CHARACTER]
[, /BACK_WORD] [, /CONTROL | , /ESCAPE]
[, /DELETE_CHARACTER] [, /DELETE_CURRENT]
[, /DELETE_EOL] [, /DELETE_LINE]
[, /DELETE_WORD] [, /END_OF_LINE]
[, /END_OF_FILE] [, /ENTER_LINE]
[, /FORWARD_CHARACTER] [, /FORWARD_WORD]
[, /INSERT_OVERSTRIKE_TOGGLE] [, /NEXT_LINE]
[, /PREVIOUS_LINE] [, /RECALL] [, /REDRAW]
[, /START_OF_LINE]

DEFROI - Defines an irregular region of interest of an image.

Result = DEFROI(*Sx, Sy* [, *Xverts*, *Yverts*] [, /NOREGION]
[, /NOFILL] [, /RESTORE] [, X0=*device_coord*,
Y0=*device_coord*] [, ZOOM=*factor*])

DEFSYSV - Creates a new system variable.

DEFSYSV,*Name*,*Value* [, *Read_Only*]
[, EXISTS=*variable*]

DELETE_SYMBOL (VMS Only) - Deletes a DCL interpreter symbol for the current process.

DELETE_SYMBOL, *Name* [, TYPE={1 | 2}]

DELLOG (VMS Only) - Deletes a VMS logical name.

DELLOG, *Lognam* [, TABLE=*string*]

DELVAR - Deletes variables from the main IDL program level.

DELVAR, V_1, ..., V_n

DERIV - Performs differentiation using 3-point, Lagrangian interpolation and returns the derivative.

Result = DERIV([*X*,] *Y*)

DERIVSIG - Computes standard deviation of derivative found by DERIV.

Result = DERIVSIG([*X, Y, Sig_x*,] *Sig_y*)

DETERM - Computes the determinant of a square matrix.

Result = DETERM(*A* [, /CHECK] [, /DOUBLE] [, ZERO=*value*])

DEVICE - Sets to plot in device coordinates.

Note: Each keyword to DEVICE is followed by the device(s) to which it applies.

DEVICE [, /AVANTGARDE | , /BKMAN | , /COURIER | , /HELVETICA | , /ISOLATIN1 | , /PALATINO | , /SCHOOLBOOK | , /SYMBOL | , TIMES | , ZAPFCHANCERY | , ZAPFDINGBATS {PS}]

[, /AVERAGE_LINES{REGIS}] [, /BINARY | , /NCAR | , /TEXT {CGM}] [, BITS_PER_PIXEL={1 | 2 | 4 | 8}{PS}] [, /BOLD{PS}] [, /BOOK{PS}]

[, /BYPASS_TRANSLATION{MAC, WIN, X}]

[, /CLOSE{Z}] [, /CLOSE_DOCUMENT{PRINTER}]

[, /CLOSE_FILE{CGM, HP, LJ, METAFILE, PCL, PS, REGIS, TEK}] [, /COLOR{PCL, PS}]

[, COLORS=*value*{CGM, TEK}] [, COPY=*[Xsource, Ysource, cols, rows, Xdest, Ydest [, Window_index]]*{MAC, WIN, X}]

[, /CURSOR_CROSSHAIR{WIN, X}]

[, CURSOR_IMAGE=*value*{16-element short int vector}{MAC, WIN, X}]

[, CURSOR_MASK=*value*{MAC, WIN, X}]

[, /CURSOR_ORIGINAL{MAC, WIN, X}]

[, CURSOR_STANDARD=*value*{MAC: crosshair=1}{WIN: arrow=32512, I-beam=32513, hourglass=32514, black cross=32515, up arrow=32516, size(NT)=32640, icon(NT)=32641, size NW-SE=32642, size NE-SW=32643, size E-W=32644, size N-S=32645}{X: one of the values in file cursorfonts.h}]

[, CURSOR_XY=*[x,y]*{MAC, WIN, X}]

[, /DECOMPOSED{MAC, WIN, X}]

[, DEPTH=*value*{significant bits per pixel}{LJ}]

[, /DIRECT_COLOR{X}] [, EJECT={0 | 1 | 2}{HP}]

[, ENCAPSULATED={0 | 1}{PS}] [, ENCODING={1 (binary) | 2 (text) | 3 (NCAR binary)}{CGM}]

[, FILENAME=*filename*{CGM, HP, LJ, METAFILE, PCL, PS, REGIS, TEK}] [, /FLOYD{LJ, MAC, PCL, X}]

[, FONT_INDEX=*integer*{PS}]

[, FONT_SIZE=*points*{PS}]

[, GET_CURRENT_FONT=*variable*{MAC, METAFILE, PRINTER, WIN, X}]

[, GET_DECOMPOSED=*variable*{MAC, WIN, X}]

[, GET_FONTNAMES=*variable*{MAC, METAFILE, PRINTER, WIN, X}]

[, GET_FONTNUM=*variable*{MAC, METAFILE, PRINTER, WIN, X}]

[, GET_GRAPHICS_FUNCTION=*variable*{MAC, WIN, X, Z}] [, GET_PAGE_SIZE=*variable*{PRINTER}]

[, GET_SCREEN_SIZE=*variable*{MAC, WIN, X}]

[, GET_VISUAL_DEPTH=*variable*{MAC, WIN, X}]

[, GET_VISUAL_NAME=*variable*{MAC, WIN, X}]

[, GET_WINDOW_POSITION=*variable*{MAC, WIN, X}] [, GET_WRITE_MASK=*variable*{X, Z}]

[, GIN_CHARS=*number_of_characters*{TEK}]

[, GLYPH_CACHE=*number_of_glyphs*{MAC, METAFILE, PRINTER, PS, WIN, Z}] [, /INCHES{HP, LJ, METAFILE, PCL, PRINTER, PS}]

[, /INDEX_COLOR{METAFILE, PRINTER}]

[, /ITALIC{PS}] [, /LANDSCAPE | , /PORTRAIT{HP, LJ, PCL, PRINTER, PS}] [, /DEMI | , /LIGHT | , /MEDIUM | , /NARROW | , /OBLIQUE{PS}]

[, OPTIMIZE={0 | 1 | 2}{PCL}] [, /ORDERED{LJ, MAC, PCL, X}] [, OUTPUT=*scalar string*{HP, PS}]

[, /PIXELS{LJ, PCL}] [, PLOT_TO=*logical unit num*{REGIS, TEK}] [, /PLOTTER_ON_OFF{HP}]

[, /POLYFILL{HP}] [, PRE_DEPTH=*value*{PS}]

[, PRE_XSIZE=*width*{PS}] [, PRE_YSIZE=*height*{PS}]

[, /PREVIEW{PS}] [, PRINT_FILE=*filename*{WIN}]

[, /PSEUDO_COLOR{MAC, X}]

[, RESET_STRING=*string*{TEK}]

[, RESOLUTION=*value*{LJ, PCL}] [, RETAIN={0 | 1 | 2}{MAC, WIN, X}]

[, SCALE_FACTOR=*value*{PRINTER, PS}]

[, SET_CHARACTER_SIZE=*[font size, line spacing]*{CGM, HP, LJ, MAC, METAFILE, PCL, PS, REGIS, TEK, WIN, X, Z}]

[, SET_COLORMAP=*value*{14739-element byte vector}{PCL}] [, SET_COLORS=*value*{2 to 256}{Z}]

[, SET_FONT=*scalar string*{MAC, METAFILE, PRINTER, PS, WIN, Z}]

[, SET_GRAPHICS_FUNCTION=*code*{0 to 15}{MAC, WIN, X, Z}] [, SET_RESOLUTION=*[width, height]*{Z}]

[, SET_STRING=*string*{TEK}]

[, SET_TRANSLATION=*variable*{X}]

[, SET_WRITE_MASK=*value*{0 to 2^n-1 for *n*-bit system}{X, Z}] [, STATIC_COLOR=*value*{bits per pixel}{X}] [, STATIC_GRAY=*value*{bits per pixel}{X}]

[, /TEK4014{TEK}] [, TEK4100{TEK}]

[, THRESHOLD=*value*{LJ, MAC, PCL, X}]

[, TRANSLATION=*variable*{MAC, WIN, X}]

[, TRUE_COLOR=*value*{bits per pixel}{MAC, METAFILE, PRINTER, X}] [, /TT_FONT{MAC, METAFILE, PRINTER, WIN, X, Z}] [, /TTY{REGIS, TEK}] [, /VT240 | , /VT241 | , /VT340 | , /VT341 {REGIS}] [, WINDOW_STATE=*variable*{MAC, WIN, X}] [, XOFFSET=*value*{HP, LJ, PCL, PRINTER, PS}]

[, XON_XOFF={0 | 1 (default)}{HP}]

[, XSIZE=*width*{HP, LJ, PCL, METAFILE, PRINTER, PS}] [, YOFFSET=*value*{HP, LJ, PCL, PRINTER, PS}]

[, YSIZE=*height*{HP, LJ, PCL, METAFILE, PRINTER, PS}] [, Z_BUFFERING={0 | 1 (default)}{Z}]

DFPMIN - Minimizes a function using Davidon-Fletcher-Powell method.

DFPMIN, *X*, *Gtol*, *Fmin*, *Func*, *Dfunc* [, /DOUBLE]
[, EPS=*value*] [, ITER=*variable*] [, ITMAX=*value*]
[, STEPMAX=*value*] [, TOLX=*value*]

DIALOG_MESSAGE - Creates modal message dialog.

Result = DIALOG_MESSAGE(*Message_Text*
[, /CANCEL] [, /DEFAULT_CANCEL | ,
/DEFAULT_NO] [, DIALOG_PARENT=*widget_id*]
[, DISPLAY_NAME=*string*] [, /ERROR | ,
/INFORMATION | , /QUESTION]
[, RESOURCE_NAME=*string*] [, TITLE=*string*])

DIALOG_PICKFILE - Creates native file-selection dialog.

Result = DIALOG_PICKFILE([, /DIRECTORY]
[, DIALOG_PARENT=*widget_id*]
[, DISPLAY_NAME=*string*] [, FILE=*string*]
[, FILTER=*string/string array*] [, /FIX_FILTER]
[, GET_PATH=*variable*] [, GROUP=*widget_id*]
[, /MULTIPLE_FILES] [, /MUST_EXIST]
[, PATH=*string*] [, /READ | , /WRITE]
[, /RESOURCE_NAME] [, TITLE=*string*])

DIALOG_PRINTERSETUP - Opens native dialog used to set properties for a printer.

Result = DIALOG_PRINTERSETUP([*PrintDestination*]
[, DIALOG_PARENT=*widget_id*]
[, DISPLAY_NAME=*string*]
[, RESOURCE_NAME=*string*] [, TITLE=*string*])

DIALOG_PRINTJOB - Opens native dialog used to set parameters for a print job.

Result = DIALOG_PRINTJOB([*PrintDestination*]
[, DIALOG_PARENT=*widget_id*]
[, DISPLAY_NAME=*string*]
[, RESOURCE_NAME=*string*] [, TITLE=*string*])

DIALOG_READ_IMAGE - Presents GUI for reading image files.

Result = DIALOG_READ_IMAGE ([*Filename*]
[, DIALOG_PARENT=*widget_id*] [, FILE=*variable*]
[, FILTER_TYPE=*string*] [, /FIX_FILTER]
[, GET_PATH=*variable*] [, IMAGE=*variable*]
[, PATH=*string*] [, QUERY=*variable*] [, RED=*variable*]
[, GREEN=*variable*] [, BLUE=*variable*]
[,TITLE=*string*])

DIALOG_WRITE_IMAGE - Presents GUI for writing image files.

Result = DIALOG_WRITE_IMAGE (*Image* [, *R*, *G*, *B*]
[, DIALOG_PARENT=*widget_id*] [, FILE=*string*]
[, /FIX_TYPE] [, /NOWRITE] [, OPTIONS=*variable*]
[, PATH=*string*] [,TITLE=*string*] [, TYPE=*variable*]
[, /WARN_EXIST])

DIGITAL_FILTER - Calculates coefficients of a non-recursive, digital filter.

Result = DIGITAL_FILTER(*Flow*, *Fhigh*, *A*, *Nterms*)

DILATE - Implements morphologic dilation operator on binary and grayscale images.

Result = DILATE(*Image*, *Structure* [, X_0 [, Y_0 [, Z_0]]]
[, /CONSTRAINED [, BACKGROUND=*value*]]
[, /GRAY [, /PRESERVE_TYPE | , /UINT | , /ULONG]]
[, VALUES=*array*])

DINDGEN - Returns a double-precision array with each element set to its subscript.

Result = DINDGEN(D_1, ..., D_8)

DISSOLVE - Provides a digital "dissolve" effect for images.

DISSOLVE, *Image* [, WAIT=*seconds*] [, /ORDER]
[, SIZ=*pixels*] [, X0=*pixels*, Y0=*pixels*]

DIST - Creates array with each element proportional to its frequency.

Result = DIST(*N* [, *M*])

DLM_LOAD - Explicitly causes a DLM to be loaded.

DLM_LOAD, *DLMNameStr$_1$*
[, *DLMNameStr$_2$*,..., *DLMNameStr$_n$*]

DO_APPLE_SCRIPT - Compiles, executes AppleScript code.

DO_APPLE_SCRIPT, *Script* [, /AG_STRING]
[, RESULT=*variable*]

DOC_LIBRARY - Extracts documentation headers from IDL programs.

DOC_LIBRARY [, *Name*] [, /PRINT]
UNIX keywords: [, DIRECTORY=*string*] [, /MULTI]
VMS keywords: [, /FILE] [, PATH=*string*]
[, /OUTPUTS]

DOUBLE - Converts argument to double-precision type.

Result = DOUBLE(*Expression*[, *Offset* [, *Dim$_1$*, ..., *Dim$_n$*]]))

DRAW_ROI - Draws region or group of regions to current Direct Graphics device.

DRAW_ROI, *oROI* [, /LINE_FILL] [, SPACING=*value*]
Graphics Keywords: [, CLIP=*[X_0, Y_0, X_1, Y_1]*]
[, COLOR=*value*] [, /DATA | , /DEVICE | , /NORMAL]
[, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, /NOCLIP]
[, ORIENTATION=*ccw_degrees_from_horiz*]
[, PSYM=*integer{0 to 10}*] [, SYMSIZE=*value*] [, /T3D]
[, THICK=*value*]

E

EFONT - Interactive vector font editor and display tool.

EFONT, *Init_Font* [, /BLOCK] [, GROUP=*widget_id*]

EIGENQL - Computes eigenvalues and eigenvectors of a real, symmetric array.

Result = EIGENQL(*A* [, /ABSOLUTE] [, /ASCENDING]
[, /DOUBLE] [, EIGENVECTORS=*variable*]
[, /OVERWRITE | , RESIDUAL=*variable*])

EIGENVEC - Computes eigenvectors of a real, non-symmetric array.
Result = EIGENVEC(*A*, *Eval* [, /DOUBLE]
[, ITMAX=*value*] [, RESIDUAL=*variable*])

ELMHES - Reduces nonsymmetric array to upper Hessenberg form.
Result = ELMHES(*A* [, /COLUMN] [, /DOUBLE]
[, /NO_BALANCE])

EMPTY - Empties the graphics output buffer.
EMPTY

ENABLE_SYSRTN - Enables/disables IDL system routines.
ENABLE_SYSRTN [, *Routines*] [, /DISABLE]
[, /EXCLUSIVE] [, /FUNCTIONS]

EOF - Tests the specified file for the end-of-file condition.
Result = EOF(*Unit*)

EOS_* Routines - See "EOS Routines" on page 54.

ERASE - Erases the screen of the current graphics device, or starts a new page if the device is a printer.
ERASE [, *Background_Color*] [, CHANNEL=*value*]
[, COLOR=*value*]

ERODE - Implements the erosion operator on binary and grayscale images and vectors.
Result = ERODE(*Image*, *Structure* [, X_0 [, Y_0 [, Z_0]]]
[, /GRAY [, /PRESERVE_TYPE | , /UINT | , /ULONG]]
[, VALUES=*array*])

ERRORF - Returns the value of an error function.
Result = ERRORF(*X*)

ERRPLOT - Plots error bars over a previously drawn plot.
ERRPLOT, [*X*,] *Low*, *High* [, WIDTH=*value*]

EXECUTE - Compiles and executes IDL statements contained in a string.
Result = EXECUTE(*String* [, *QuietCompile*])

EXIT - Quits IDL and exits back to the operating system.
EXIT [, /NO_CONFIRM] [, STATUS=*code*]

EXP - Returns the natural exponential function of *Expression*.
Result = EXP(*Expression*)

EXPAND - Shrinks/expands image using bilinear interpolation.
EXPAND, *A*, *Nx*, *Ny*, *Result* [, FILLVAL=*value*]
[, MAXVAL=*value*]

EXPAND_PATH - Expands path-definition string into full path name for use with the !PATH system variable.
Result = EXPAND_PATH(*String* [, /ALL_DIRS]
[, /ARRAY] [, COUNT=*variable*] [, /DLM] [, /HELP])

EXPINT - Returns the value of the exponential integral.
Result = EXPINT(*N*, *X* [, /DOUBLE] [, EPS=*value*]
[, ITMAX=*value*])

EXTRAC - Returns sub-matrix of input array. Array operators (e.g., * and :) should usually be used instead.
Result = EXTRAC(*Array*, C_1, C_2, ..., C_n, S_1, S_2, ..., S_n)

EXTRACT_SLICE - Returns 2D planar slice extracted from volume.
Result = EXTRACT_SLICE(*Vol*, *Xsize*, *Ysize*, *Xcenter*,
Ycenter, *Zcenter*, *Xrot*, *Yrot*, *Zrot*
[, ANISOTROPY=*[xspacing*, *yspacing*, *zspacing]*]
[, /CUBIC] [, OUT_VAL=*value*] [, /RADIANS]
[, /SAMPLE] [, VERTICES=*variable*])
or
Result = EXTRACT_SLICE(*Vol*, *Xsize*, *Ysize*, *Xcenter*,
Ycenter, *Zcenter*, *PlaneNormal*, *Xvec*
[, ANISOTROPY=*[xspacing*, *yspacing*, *zspacing]*]
[, /CUBIC] [, OUT_VAL=*value*] [, /RADIANS]
[, /SAMPLE] [, VERTICES=*variable*])

F

F_CVF - Computes the cutoff value in an F distribution.
Result = F_CVF(*P*, *Dfn*, *Dfd*)

F_PDF - Computes the F distribution function.
Result = F_PDF(*V*, *Dfn*, *Dfd*)

FACTORIAL - Computes the factorial *N*!.
Result = FACTORIAL(*N* [, /STIRLING] [, /UL64])

FFT - Returns the Fast Fourier Transform of *Array*.
Result = FFT(*Array* [, *Direction*] [, /DOUBLE]
[, /INVERSE] [, /OVERWRITE])

FILE_CHMOD - Changes the current access permissions (or modes) associated with a file or directory.
FILE_CHMOD, *File* [, *Mode*]
[, /A_EXECUTE | /A_READ | , /A_WRITE]
[, /G_EXECTUE | /G_READ | , /G_WRITE]
[, /O_EXECTUE | /O_READ | , /O_WRITE]
[, /U_EXECTUE | /U_READ | , /U_WRITE]
UNIX-Only Keywords: [, /SETGID] [, /SETUID]
[, /STICKY_BIT]

FILE_DELETE - Deletes a file or empty directory, if the process has the necessary permissions to remove the file as defined by the current operating system.
FILE_DELETE, *File1* [,... *FileN*] [, /QUIET]

FILE_EXPAND_PATH - Expands a given file or partial directory name to its fully qualified name regardless of the current working directory.
Return = FILE_EXPAND_PATH (*Path*)

FILE_MKDIR - Creates a new directory, or directories, with default access permissions for the current process.
FILE_MKDIR, *File1* [,... *FileN*]

FILE_TEST - Checks files for existence and other file attributes without first having to open the file.
Result = FILE_TEST(*File* [, /DIRECTORY | ,
/EXECUTABLE | , /READ | , /REGULAR | , /WRITE |
, /ZERO_LENGTH] [, GET_MODE=*variable*])
UNIX-Only Keywords: [, /BLOCK_SPECIAL |
, /CHARACTER_SPECIAL | , /DANGLING_SYMLINK |

, /NAMED_PIPE | , /SETGID | , /SETUID | , /SOCKET |
, /STICKY_BIT | , /SYMLINK]
UNIX and VMS-Only Keywords: [, /GROUP | , /USER]

FILE_WHICH - Separates a specified file path into its component
directories, and searches each directory in turn for a specific file.
Result = FILE_WHICH([*Path*,] *File*
[, /INCLUDE_CURRENT_DIR])

FILEPATH - Returns full path to a file in the IDL distribution.
Result = FILEPATH(*Filename* [, ROOT_DIR=*string*]
[, SUBDIRECTORY=*string/string_array*]
[, /TERMINAL] [, /TMP])

FINDFILE - Finds all files matching *File_Specification*.
Result = FINDFILE(*File_Specification*
[, COUNT=*variable*])

FINDGEN - Returns a floating-point array with each element set to its
subscript.
Result = FINDGEN(D_1, ..., D_8)

FINITE - Returns True if its argument is finite.
Result = FINITE(*X* [, /INFINITY] [, /NAN])

FIX - Converts argument to integer type, or type specified by TYPE key-
word.
Result = FIX(*Expression* [, *Offset* [, Dim_1, ..., Dim_8]]
[, /PRINT] [, TYPE=*type code*{0 to 15}])

FLICK - Causes the display to flicker between two images.
FLICK, *A*, *B* [, *Rate*]

FLOAT - Converts argument to single-precision floating-point.
Result = FLOAT(*Expression* [, *Offset* [, Dim_1, ..., Dim_8]])

FLOOR - Returns closest integer less than or equal to argument.
Result = FLOOR(*X* [, /L64])

FLOW3 - Draws lines representing a 3D flow/velocity field.
FLOW3, *Vx*, *Vy*, *Vz* [, ARROWSIZE=*value*] [, /BLOB]
[, LEN=*value*] [, NSTEPS=*value*] [, NVECS=*value*]
[, SX=*vector*, SY=*vector*, SZ=*vector*]

FLTARR - Returns a single-precision, floating-point vector or array.
Result = FLTARR(D_1, ..., D_8 [, /NOZERO])

FLUSH - Flushes file unit buffers.
FLUSH, $Unit_1$, ..., $Unit_n$

FOR - Executes statements repeatedly, incrementing or decrementing a
variable with each repetition, until a condition is met.
FOR *variable* = *init*, *limit* [, *Increment*] DO *statement*
or
FOR *variable* = *init*, *limit* [, *Increment*] DO BEGIN
    statements
ENDFOR

FORMAT_AXIS_VALUES - Formats numbers as strings for use as
axis values.
Result = FORMAT_AXIS_VALUES(*Values*)

FORWARD_FUNCTION - Causes argument(s) to be interpreted as
functions rather than variables (versions of IDL prior to 5.0 used
parentheses to declare arrays).
FORWARD_FUNCTION $Name_1$, $Name_2$, ..., $Name_n$

FREE_LUN - Frees previously-reserved file units.
FREE_LUN [, $Unit_1$, ..., $Unit_n$]
[, EXIT_STATUS=*variable*] [, /FORCE]

FSTAT - Returns information about a specified file unit.
Result = FSTAT(*Unit*)

FULSTR - Restores a sparse matrix to full storage mode.
Result = FULSTR(*A*)

FUNCT - Evaluates sum of a Gaussian and a 2nd-order polynomial and
returns value of its partial derivatives.
FUNCT, *X*, *A*, *F* [, *Pder*]

FUNCTION - Defines a function.
FUNCTION *Function_Name*, $parameter_1$, ..., $parameter_n$

FV_TEST - Performs the F-variance test.
Result = FV_TEST(*X*, *Y*)

FX_ROOT - Computes real and complex roots of a univariate nonlin-
ear function using an optimal Müller's method.
Result = FX_ROOT(*X*, *Func* [, /DOUBLE]
[, ITMAX=*value*] [, /STOP] [, TOL=*value*])

FZ_ROOTS - Finds the roots of a complex polynomial using
Laguerre's method.
Result = FZ_ROOTS(*C* [, /DOUBLE] [, EPS=*value*]
[, /NO_POLISH])

G

GAMMA - Returns the gamma function of *X*.
Result = GAMMA(*X*)

GAMMA_CT - Applies gamma correction to a color table.
GAMMA_CT, *Gamma* [, /CURRENT] [, /INTENSITY]

GAUSS_CVF - Computes cutoff value in Gaussian distribution.
Result = GAUSS_CVF(*P*)

GAUSS_PDF - Computes Gaussian distribution function.
Result = GAUSS_PDF(*V*)

GAUSS2DFIT - Fits a 2D elliptical Gaussian equation to rectilinearly
gridded data.
Result = GAUSS2DFIT(*Z*, *A* [, *X*, *Y*] [, /NEGATIVE]
[, /TILT])

GAUSSFIT - Fits the sum of a Gaussian and a quadratic.
Result = GAUSSFIT(*X*, *Y* [, *A*] [, ESTIMATES=*array*]
[, NTERMS=*integer*{3 to 6}])

GAUSSINT - Returns integral of Gaussian probability function.
Result = GAUSSINT(*X*)

GET_DRIVE_LIST - Returns string array of the names of valid drives/volumes for the file system. (Windows/Macintosh only)
Result = GET_DRIVE_LIST( )

GET_KBRD - Gets one input IDL character.
Result = GET_KBRD(*Wait*)

GET_LUN - Reserves a logical unit number (file unit).
GET_LUN, *Unit*

GET_SCREEN_SIZE - Returns dimensions of the screen.
Result = GET_SCREEN_SIZE([*Display_name*]
[, RESOLUTION=*variable*])
X Windows Keywords: [, DISPLAY_NAME=*string*]

GET_SYMBOL (VMS Only) - Returns value of a VMS DCL interpreter symbol.
Result = GET_SYMBOL(*Name* [, TYPE={1 | 2}])

GETENV - Returns the value of an environment variable.
Result = GETENV(*Name*)
UNIX-Only Keywords: [, /ENVIRONMENT]

GOTO - Transfers program control to point specified by *label*.
GOTO, *label*

GRID_TPS - Uses thin plate splines to interpolate a set of values over a regular 2D grid, from irregularly sampled data values.
Interp = GRID_TPS (*Xp*, *Yp*, *Values*
[, COEFFICIENTS=*variable*] [, NGRID=*[nx, ny]*]
[, START=*[x0, y0]*] [, DELTA=*[dx, dy]*])

GRID3 - Creates a regularly-gridded 3D dataset from a set of scattered 3D nodes.
Result = GRID3(*X*, *Y*, *Z*, *F*, *Gx*, *Gy*, *Gz*
[, DELTA=*scalar/vector*] [, DTOL=*value*] [, GRID=*value*]
[, NGRID=*value*] [, START=*[x, y, z]*])

GS_ITER - Solves linear system using Gauss-Seidel iteration.
Result = GS_ITER(*A*, *B* [, /CHECK] [, /DOUBLE]
[, LAMBDA=*value*{0.0 to 2.0}] [, MAX_ITER=*value*]
[, TOL=*value*] [, X_0=*vector*])

H

H_EQ_CT - Histogram-equalizes the color tables for an image or a region of the display.
H_EQ_CT [, *Image*]

H_EQ_INT - Interactively histogram-equalizes the color tables of an image or a region of the display.
H_EQ_INT [, *Image*]

HANNING - Creates Hanning and Hamming windows.
Result = HANNING(N_1 [, N_2] [, ALPHA=*value*{0.5 to 1.0}] [, /DOUBLE])

HDF_* Routines - See "HDF Routines" on page 59.

HDF_BROWSER - Opens GUI to view contents of HDF, HDF-EOS, or NetCDF file.
Template = HDF_BROWSER([*Filename*]
[, CANCEL=*variable*] [, GROUP=*widget_id*]
[, PREFIX=*string*])

HDF_READ - Extracts HDF, HDF-EOS, and NetCDF data and metadata into an output structure.
Result = HDF_READ([*Filename*] [, DFR8=*variable*]
[, DF24=*variable*] [, PREFIX=*string*]
[, TEMPLATE=*value*])

HEAP_GC - Performs garbage collection on heap variables.
HEAP_GC [, /OBJ | , /PTR] [, /VERBOSE]

HELP - Provides information about the current IDL session.
HELP, *Expression₁*, ..., *Expressionₙ* [, /ALL_KEYS]
[, /BREAKPOINTS] [, /BRIEF] [, CALLS=*variable*]
[, /DEVICE] [, /DLM] [, /FILES] [, /FULL]
[, /FUNCTIONS] [, /HEAP_VARIABLES] [, /KEYS]
[, /LAST_MESSAGE] [, /MEMORY] [, /MESSAGES]
[, NAMES=*string_of_variable_names*] [, /OBJECTS]
[, OUTPUT=*variable*] [, /PROCEDURES]
[, /RECALL_COMMANDS] [, /ROUTINES]
[, /SOURCE_FILES] [, /STRUCTURES]
[, /SYSTEM_VARIABLES] [, /TRACEBACK]

HILBERT - Constructs a Hilbert transform.
Result = HILBERT(*X* [, *D*])

HIST_2D - Returns histogram of two variables.
Result = HIST_2D(V_1, V_2 [, BIN1=*width*] [, BIN2=*height*]
[, MAX1=*value*] [, MAX2=*value*] [, MIN1=*value*]
[, MIN2=*value*])

HIST_EQUAL - Histogram-equalizes an image.
Result = HIST_EQUAL(*A* [, BINSIZE=*value*]
[, /HISTOGRAM_ONLY] [, MAXV=*value*]
[, MINV=*value*] [, OMAX=*variable*] [, OMIN=*variable*]
[, PERCENT=*value*] [, TOP=*value*])

HISTOGRAM - Computes the density function of an array.
Result = HISTOGRAM(*Array* [, BINSIZE=*value*]
[, INPUT=*variable*] [, MAX=*value*] [, MIN=*value*]
[, /NAN] [, NBINS=*value*] [, OMAX=*variable*]
[, OMIN=*variable*]
[, /L64 | REVERSE_INDICES=*variable*])

HLS - Creates color table in Hue, Lightness, Saturation color system.
HLS, *Litlo*, *Lithi*, *Satlo*, *Sathi*, *Hue*, *Loops* [, *Colr*]

HOUGH - Returns the Hough transform of a two-dimensional image.
Hough Transform: *Result* = HOUGH(*Array*
[, /DOUBLE] [, DRHO=*scalar*] [, DX=*scalar*]
[, DY=*scalar*] [, /GRAY] [, NRHO=*scalar*]
[, NTHETA=*scalar*] [, RHO=*variable*] [, RMIN=*scalar*]
[, THETA=*variable*] [, XMIN=*scalar*] [, YMIN=*scalar*])

Hough Backprojection: *Result* = HOUGH(*Array*, /BACKPROJECT, RHO=*variable*, THETA=*variable* [, /DOUBLE] [, DX=*scalar*] [, DY=*scalar*] [, NX=*scalar*] [, NY=*scalar*] [, XMIN=*scalar*] [, YMIN=*scalar*])

HQR - Returns all eigenvalues of an upper Hessenberg array.
Result = HQR(*A* [, /COLUMN] [, /DOUBLE])

HSV - Creates color table based on Hue/Saturation Value color system.
HSV, *Vlo*, *Vhi*, *Satlo*, *Sathi*, *Hue*, *Loops* [, *Colr*]

I

IBETA - Computes the incomplete beta function.
Result = IBETA(*A*, *B*, *X* [, /DOUBLE] [, EPS=*value*] [, ITER=*variable*] [, ITMAX=*value*])

IDENTITY - Returns an identity array.
Result = IDENTITY(*N* [, /DOUBLE])

IDL_Container Object - See "IDL_Container" on page 65.

IDLanROI Object - See "IDLanROI" on page 65.

IDLanROIGroup Object - See "IDLanROIGroup" on page 66.

IDLffDICOM Object - See "IDLffDICOM" on page 66.

IDLffDXF Object - See "IDLffDXF" on page 67.

IDLffLanguageCat Object - See "IDLffLanguageCat" on page 67.

IDLffShape Object - See "IDLffShape" on page 67.

IDLgr* Objects - IDLgr* objects and their methods are described starting with "IDLgrAxis" on page 68.

IF...THEN...ELSE - Conditionally executes a statement or block of statements.
IF *expression* THEN *statement* [ELSE *statement*]
or
IF *expression* THEN BEGIN
  statements
ENDIF [ELSE BEGIN
  statements
ENDELSE]

IGAMMA - Computes the incomplete gamma function.
Result = IGAMMA(*A*, *X* [, /DOUBLE] [, EPS=*value*] [, ITER=*variable*] [, ITMAX=*value*] [, METHOD=*variable*])

IMAGE_CONT - Overlays an image with a contour plot.
IMAGE_CONT, *A* [, /ASPECT] [, /INTERP] [, /WINDOW_SCALE]

IMAGE_STATISTICS - Computes sample statistics for a given array of values.
IMAGE_STATISTICS, *Data* [, /LABELED | [, /WEIGHTED] [, WEIGHT_SUM=*variable*]] [, /VECTOR] [, LUT=*array*] [, MASK=*array*] [, COUNT=*variable*] [, MEAN=*variable*] [, STDDEV=*variable*] [, DATA_SUM=*variable*] [, SUM_OF_SQUARES=*variable*]

[, MINIMUM=*variable*] [, MAXIMUM=*variable*] [, VARIANCE=*variable*]

IMAGINARY - Returns the imaginary part of a complex value.
Result = IMAGINARY(*Complex_Expression*)

INDGEN - Return an integer array with each element set to its subscript.
Result = INDGEN(D_1, ..., D_8) [, /BYTE | , /COMPLEX | , /DCOMPLEX | , /DOUBLE | , /FLOAT | , /L64 | , /LONG | , /STRING | , /UINT | , /UL64 | , /ULONG] [, TYPE=*value*]

INT_2D - Computes the double integral of a bivariate function.
Result = INT_2D(*Fxy*, *AB_Limits*, *PQ_Limits*, *Pts* [, /DOUBLE] [, /ORDER])

INT_3D - Computes the triple integral of a trivariate function.
Result = INT_3D(*Fxyz*, *AB_Limits*, *PQ_Limits*, *UV_Limits*, *Pts* [, /DOUBLE])

INT_TABULATED - Integrates a tabulated set of data.
Result = INT_TABULATED(*X*, *F* [, /DOUBLE] [, /SORT])

INTARR - Creates an integer vector or array.
Result = INTARR(D_1, ..., D_8 [, /NOZERO])

INTERPOL - Performs linear interpolation on vectors.
For regular grids: *Result* = INTERPOL(V, N [, /LSQUADRATIC] [, /QUADRATIC] [, /SPLINE])
For irregular grids: *Result* = INTERPOL(V, X, U [, /LSQUADRATIC] [, /QUADRATIC] [, /SPLINE])

INTERPOLATE - Returns an array of interpolates.
Result = INTERPOLATE(*P*, *X* [, *Y* [, *Z*]] [, CUBIC=*value*{-1 to 0}] [, /GRID] [, MISSING=*value*])

INVERT - Computes the inverse of a square array.
Result = INVERT(*Array* [, *Status*] [, /DOUBLE])

IOCTL - Performs special functions on UNIX files.
Result = IOCTL(*File_Unit* [, *Request*, *Arg*] [, /BY_VALUE] [, /MT_OFFLINE] [, /MT_REWIND] [, MT_SKIP_FILE=[-]*number_of_files*] [, MT_SKIP_RECORD=[-]*number_of_records*] [, /MT_WEOF] [, /SUPRESS_ERROR])

ISHFT - Performs integer bit shift.
Result = ISHFT(P_1, P_2)

ISOCONTOUR - Interprets the contouring algorithm found in the IDLgrContour object.
ISOCONTOUR, *Values*, *Outverts*, *Outconn* [, AUXDATA_IN=*array*, AUXDATA_OUT=*variable*] [, C_VALUE=*scalar or vector*] [, /DOUBLE] [, GEOMX=*vector*] [, GEOMY=*vector*] [, GEOMZ=*vector*] [, /FILL] [, LEVEL_VALUES=*variable*] [, N_LEVELS=*levels*] [, OUTCONN_INDICES=*variable*] [, POLYGONS=*array of polygon descriptions*]

ISOSURFACE - Returns topologically consistent triangles by using oriented tetrahedral decomposition.

ISOSURFACE, *Data*, *Value*, *Outverts*, *Outconn*
[, GEOM_XYZ=*array*, TETRAHEDRA=*array*]
[, AUXDATA_IN=*array*, AUXDATA_OUT=*variable*]

J

JOURNAL - Logs IDL commands to a file.IDL.

JOURNAL [, *Arg*]

JULDAY - Returns Julian Day Number for given month, day, and year.

Result = JULDAY(*Month*,*Day*,*Year*,*Hour*,*Minute*,*Second*)

K

KEYWORD_SET - Returns True if *Expression* is defined and non-zero or an array.

Result = KEYWORD_SET(*Expression*)

KRIG2D - Interpolates set of points using kriging.

Result = KRIG2D(*Z* [, *X*, *Y*] [, EXPONENTIAL=*vector*]
[, SPHERICAL=*vector*] [, /REGULAR]
[, XGRID=*[xstart*, *xspacing]*] [, XVALUES=*array*]
[, YGRID=*[ystart*, *yspacing]*] [, YVALUES=*array*]
[, GS=*[xspacing*, *yspacing]*] [, BOUNDS=*[xmin*, *ymin*,
xmax, *ymax]*] [, NX=*value*] [, NY=*value*])

KURTOSIS - Computes statistical kurtosis of *n*-element vector.

Result = KURTOSIS(*X* [, /DOUBLE] [, /NAN])

KW_TEST - Performs Kruskal-Wallis H-test.

Result = KW_TEST(*X* [, DF=*variable*]
[, MISSING=*nonzero_value*])

L

L64INDGEN - Returns a 64-bit integer array with each element set to its subscript.

Result = L64INDGEN(D_1, ..., D_8)

LABEL_DATE - Labels axes with dates. Use with [XYZ]TICKFOR-MAT keyword.

Result = LABEL_DATE(
DATE_FORMAT=*string/string array* [, AM_PM=2-
element vector of strings] [, DAYS_OF_WEEK=7-
element vector of strings] [, MONTHS=12-
element vector of strings] [, OFFSET=*value*]
[, /ROUND_UP])
and then,
PLOT, *x*, *y*, XTICKFORMAT = 'LABEL_DATE'

LABEL_REGION - Labels regions (blobs) of a bi-level image.

Result = LABEL_REGION(*Data* [, /ALL_NEIGHBORS]
[, /ULONG])

LADFIT - Fits paired data using least absolute deviation method.

Result = LADFIT(*X*, *Y* [, ABSDEV=*variable*]
[, /DOUBLE])

LAGUERRE - Returns value of the associated Laguerre polynomial.

Result = LAGUERRE(*X*, *N* [, *K*]
[, COEFFICIENTS=*variable*] [, /DOUBLE])

LEEFILT - Performs the Lee filter algorithm on an image array.

Result = LEEFILT(*A* [, *N* [, *Sig*]] [, /DOUBLE]
[, /EXACT])

LEGENDRE - Returns value of the associated Legendre polynomial.

Result = LEGENDRE(*X*, *L* [, *M*] [, /DOUBLE])

LINBCG - Solves a set of sparse linear equations using the iterative biconjugate gradient method.

Result = LINBCG(*A*, *B*, *X* [, /DOUBLE] [, ITOL={4 | 5 | 6
| 7}] [, TOL=*value*] [, ITER=*variable*] [, ITMAX=*value*])

LINDGEN - Returns a longword integer array with each element set to its subscript.

Result = LINDGEN(D_1, ..., D_8)

LINFIT - Fits by minimizing the Chi-square error statistic.

Result = LINFIT(*X*, *Y* [, CHISQ=*variable*]
[, COVAR=*variable*] [, /DOUBLE]
[, MEASURE_ERRORS=*vector*] [, PROB=*variable*]
[, SIGMA=*variable*] [, YFIT=*variable*])

LINKIMAGE - Merges routines written in other languages with IDL at run-time.

LINKIMAGE, *Name*, *Image* [, *Type* [, *Entry*]]
[, /DEVICE] [, /FUNCT] [, /KEYWORDS]
[, MAX_ARGS=*value*] [, MIN_ARGS=*value*]
VMS Keywords: [, DEFAULT=*string*]

LIVE_CONTOUR - Displays contour plots using a GUI.

LIVE_CONTOUR [, Z_1,..., Z_{25}] [, /BUFFER]
[, /DOUBLE] [, DIMENSIONS=*[width*, *height]*{normal
units}] [, DRAW_DIMENSIONS=*[width*, *height]*{devive
units}] [, ERROR=*variable*] [, /INDEXED_COLOR]
[, INSTANCING={-1 | 0 | 1}]
[, LOCATION=*[x*, *y]*{normal units}]
[, /MANAGE_STYLE] [, NAME=*structure*]
[, /NO_DRAW] [, /NO_SELECTION] [, /NO_STATUS]
[, /NO_TOOLBAR] [, PARENT_BASE=*widget_id* | ,
TLB_LOCATION=*[Xoffset*, *Yoffset]*{device units}]
[, PREFERENCE_FILE=*filename*{full path}]
[, REFERENCE_OUT=*variable*] [, RENDERER={0 | 1}]
[, REPLACE={*structure* / {0 | 1 | 2 | 3 | 4}}]
[, STYLE=*name_or_reference*]
[, TEMPLATE_FILE=*filename*] [, TITLE=*string*]
[, WINDOW_IN=*string*]
[, {X | Y}INDEPENDENT=*value*] [, {/X | /Y}LOG]
[, {X | Y}RANGE=*[min, max]*{data units}]
[, {X | Y}_TICKNAME=*array*]

LIVE_CONTROL - Sets the properties of a visualization in a LIVE tool from the IDL command line.

LIVE_CONTROL, [*Name*] [, /DIALOG]
[, ERROR=*variable*] [, /NO_DRAW]
[, PROPERTIES=*structure*] [, /SELECT]
[, /UPDATE_DATA] [, WINDOW_IN=*string*]

LIVE_DESTROY - Destroys a window visualization or an element in a visualization.

LIVE_DESTROY, [*Name₁*,..., *Name₂₅*]
[, /ENVIRONMENT] [, ERROR=*variable*]
[, /NO_DRAW] [, /PURGE] [, WINDOW_IN=*string*]

LIVE_EXPORT - Exports visualization or window to a file.

LIVE_EXPORT [, /APPEND]
[, COMPRESSION={0 | 1 | 2}{TIFF only}] [, /DIALOG]
[, DIMENSIONS=*[width, height]*] [, ERROR=*variable*]
[, FILENAME=*string*] [, ORDER={0 | 1}{JPEG or TIFF}] [, /PROGRESSIVE{JPEG only}]
[, QUALITY={0 | 1 | 2}{for VRML} | {0 to 100}{for JPEG}] [, RESOLUTION=*value*] [, TYPE={'BMP' | 'JPG' | 'PIC' | 'SRF' | 'TIF' | 'XWD' | 'VRML'}]
[, UNITS={0 | 1 | 2}] [, VISUALIZATION_IN=*string*]
[, WINDOW_IN=*string*]

LIVE_IMAGE - Displays visualizations using a GUI.

LIVE_IMAGE, *Image* [, RED=*byte_vector*]
[, GREEN=*byte_vector*] [, BLUE=*byte_vector*]
[, /BUFFER] [, DIMENSIONS=*[width, height]*{normal units}] [, DRAW_DIMENSIONS=*[width, height]*{devive units}] [, ERROR=*variable*] [, /INDEXED_COLOR]
[, INSTANCING={-1 | 0 | 1}]
[, LOCATION=*[x, y]*{normal units}]
[, , /MANAGE_STYLE] [, NAME=*structure*]
[, /NO_DRAW] [, /NO_SELECTION] [, /NO_STATUS]
[, /NO_TOOLBAR] [, PARENT_BASE=*widget_id* | ,
TLB_LOCATION=*[Xoffset, Yoffset]*{device units}]
[, PREFERENCE_FILE=*filename*{full path}]
[, REFERENCE_OUT=*variable*] [, RENDERER={0 | 1}]
[, REPLACE={*structure* / {0 | 1 | 2 | 3 | 4}}]
[, STYLE=*name_or_reference*]
[, TEMPLATE_FILE=*filename*] [, TITLE=*string*]
[, WINDOW_IN=*string*]

LIVE_INFO - Gets the properties of a LIVE tool.

LIVE_INFO, [*Name*] [, ERROR=*variable*]
[, PROPERTIES=*variable*] [, WINDOW_IN=*string*]

LIVE_LINE - Provides an interface for line annotation.

LIVE_LINE [, ARROW_ANGLE=*value*{1.0 to 179.0}]
[, /ARROW_END] [, ARROW_SIZE=*value*{0.0 to 0.3}]
[, /ARROW_START] [, COLOR='*color name*']
[, /DIALOG] [, DIMENSIONS=*[width, height]*]
[, ERROR=*variable*] [, /HIDE] [, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, LOCATION=*[x, y]*] [, NAME=*string*]
[, /NO_DRAW] [, /NO_SELECTION]
[, REFERENCE_OUT=*variable*]

[, THICK=pixels{1 to 10}]
[, VISUALIZATION_IN=*string*] [, WINDOW_IN=*string*]

LIVE_LOAD - Loads into memory the complete set of routines necessary to run all LIVE tools.

LIVE_LOAD

LIVE_OPLOT - Inserts data into pre-existing plots.

LIVE_OPLOT, *Yvector1* [,... , *Yvector25*]
[, ERROR=*variable*] [, INDEPENDENT=*vector*]
[, NAME=*structure*] [, /NEW_AXES] [, /NO_DRAW]
[, /NO_SELECTION] [, REFERENCE_OUT=*variable*]
[, REPLACE={*structure* / {0 | 1 | 2 | 3 | 4}}]
[, SUBTYPE={'LinePlot' | 'ScatterPlot' | 'Histogram' | 'PolarPlot'}] [, VISUALIZATION_IN=*string*]
[, WINDOW_IN=*string*] [, {X | Y}_TICKNAME=*array*]
[, {X | Y}AXIS_IN=*string*]

LIVE_PLOT - Displays a plot using a GUI.

LIVE_PLOT, *Yvector1* [, *Yvector2*,..., *Yvector25*]
[, /BUFFER] [, DIMENSIONS=*[width, height]*{normal units}] [, /DOUBLE]
[, DRAW_DIMENSIONS=*[width, height]*{devive units}]
[, ERROR=*variable*] [, /HISTOGRAM | , /LINE | , /POLAR | , /SCATTER] [, /INDEXED_COLOR]
[, INSTANCING={-1 | 0 | 1}] [, LOCATION=*[x, y]*{normal units}] [, INDEPENDENT=*vector*]
[, /MANAGE_STYLE] [, NAME=*structure*]
[, /NO_DRAW] [, /NO_SELECTION] [, /NO_STATUS]
[, /NO_TOOLBAR] [, PARENT_BASE=*widget_id* | ,
TLB_LOCATION=*[Xoffset, Yoffset]*{device units}]
[, PREFERENCE_FILE=*filename*{full path}]
[, REFERENCE_OUT=*variable*] [, RENDERER={0 | 1}]
[, REPLACE={*structure* / {0 | 1 | 2 | 3 | 4}}]
[, STYLE=*name_or_reference*]
[, TEMPLATE_FILE=*filename*] [, TITLE=*string*]
[, WINDOW_IN=*string*] [, {/X | /Y}LOG] [, {X | Y}RANGE=*[min, max]*{data units}] [, {X | Y}_TICKNAME=*array*]

LIVE_PRINT - Prints a given window to the printer.

LIVE_PRINT [, /DIALOG] [, ERROR=*variable*]
[, WINDOW_IN=*string*]
Macintosh Keywords: [, /SETUP]

LIVE_RECT - Provides an interface for insertion of rectangles.

LIVE_RECT [, COLOR='*color name*'] [, /DIALOG]
[, DIMENSIONS=*[width, height]*] [, ERROR=*variable*]
[, /HIDE] [, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}]
[, LOCATION=*[x, y]*] [, NAME=*string*] [, /NO_DRAW]
[, /NO_SELECTION] [, REFERENCE_OUT=*variable*]
[, THICK=*pixels*{1 to 10}]
[, VISUALIZATION_IN=*string*] [, WINDOW_IN=*string*]

LIVE_STYLE - Controls style settings for a LIVE_ tool.

Style = LIVE_STYLE ({ 'contour' | 'image' | 'plot' | 'surface'} [, BASE_STYLE=*style_name*]
[, COLORBAR_PROPERTIES=*structure*]

[, ERROR=*variable*]
[, GRAPHIC_PROPERTIES=*structure*]
[, GROUP=*widget_id*]
[, LEGEND_PROPERTIES=*structure*] [, NAME=*string*]
[, /SAVE] [, TEMPLATE_FILE=*filename*]
[, VISUALIZATION_PROPERTIES=*structure*]
[, {X | Y | Z}AXIS_PROPERTIES=*structure*])

LIVE_SURFACE - Displays a surface using a GUI.
LIVE_SURFACE, *Data*, *Data2*,... [, /BUFFER]
[, DIMENSIONS=*[width, height]*{normal units}]
[, /DOUBLE] [, DRAW_DIMENSIONS=*[width,
height]*{devive units}] [, ERROR=*variable*]
[, /INDEXED_COLOR] [, INSTANCING={-1 | 0 | 1}]
[, LOCATION=*[x, y]*{normal units}]
[, /MANAGE_STYLE] [, NAME=*structure*]
[, /NO_DRAW] [, /NO_SELECTION] [, /NO_STATUS]
[, /NO_TOOLBAR] [, PARENT_BASE=*widget_id* | ,
TLB_LOCATION=*[Xoffset, Yoffset]*{device units}]
[, PREFERENCE_FILE=*filename*{full path}]
[, REFERENCE_OUT=*variable*] [, RENDERER={0 | 1}]
[, REPLACE={*structure* / {0 | 1 | 2 | 3 | 4}}]
[, STYLE=*name_or_reference*]
[, TEMPLATE_FILE=*filename*] [, TITLE=*string*]
[, WINDOW_IN=*string*]
[, {X | Y}INDEPENDENT=*vector*] [, {/X | /Y}LOG]
[, {X | Y}RANGE=*[min, max]*{data units}]
[, {X | Y}_TICKNAME=*array*]

LIVE_TEXT - Provides an interface for text annotation.
LIVE_TEXT[, *Text*] [, ALIGNMENT=*value*{0.0 to 1.0}]
[, COLOR=*'color name'*] [, /DIALOG]
[, /ENABLE_FORMATTING] [, ERROR=*variable*]
[, FONTNAME=*string*] [, FONTSIZE=*points*{9 to 72}]
[, /HIDE] [, LOCATION=*[x, y]*] [, NAME=*string*]
[, /NO_DRAW] [, /NO_SELECTION]
[, REFERENCE_OUT=*variable*]
[, TEXTANGLE=*value*{0.0 to 360.0}]
[, VERTICAL_ALIGNMENT=*value*{0.0 to 1.0}]
[, VISUALIZATION_IN=*string*] [, WINDOW_IN=*string*]

LJLCT - Loads standard color tables for LJ-250/252 printer.
LJLCT

LL_ARC_DISTANCE - Returns the longitude and latitude of a point given arc distance and azimuth.
Result = LL_ARC_DISTANCE(*Lon_lat0*, *Arc_Dist*, *Az*
[, /DEGREES])

LMFIT - Does a non-linear least squares fit.
Result = LMFIT(*X*, *Y*, *A* [, ALPHA=*variable*]
[, CHISQ=*variable*] [, CONVERGENCE=*variable*]
[, COVAR=*variable*] [, /DOUBLE] [, FITA=*vector*]
[, FUNCTION_NAME=*string*] [, ITER=*variable*]
[, ITMAX=*value*] [, ITMIN=*value*]

[, MEASURE_ERRORS=*vector*] [, SIGMA=*variable*]
[, TOL=*value*])

LMGR - Determines the type of license used by the current IDL session.
Result = LMGR([, /CLIENTSERVER | , /DEMO | ,
/EMBEDDED | , /RUNTIME | , /STUDENT | , /TRIAL]
[, EXPIRE_DATE=*variable*] [, /FORCE_DEMO]
[, INSTALL_NUM=*variable*] [, LMHOSTID=*variable*]
[, SITE_NOTICE=*variable*])

LNGAMMA - Returns logarithm of the gamma function of *X*.
Result = LNGAMMA(*X*)

LNP_TEST - Computes the Lomb Normalized Periodogram.
Result = LNP_TEST(*X*, *Y* [, /DOUBLE]
[, HIFAC=*scale_factor*] [, JMAX=*variable*]
[, OFAC=*value*] [, WK1=*variable*] [, WK2=*variable*])

LOADCT - Loads one of the predefined IDL color tables.
LOADCT [, *Table*] [, BOTTOM=*value*] [, FILE=*string*]
[, GET_NAMES=*variable*] [, NCOLORS=*value*]
[, /SILENT]

LOCALE_GET - Returns the current locale of the operating platform.
Result = LOCALE_GET( )

LON64ARR - Returns a 64-bit integer vector or array.
Result = LON64ARR(*D₁*, ..., *D₈* [, /NOZERO])

LONARR - Returns a longword integer vector or array.
Result = LONARR(*D₁*, ..., *D₈* [, /NOZERO])

LONG - Converts argument to longword integer type.
Result = LONG(*Expression*[, *Offset* [, *Dim₁*, ..., *Dim₈*]])

LONG64 - Converts argument to 64-bit integer type.
Result = LONG64(*Expression* [, *Offset* [, *D₁*, ..., *D₈*]])

LSODE - Advances a solution to a system of ordinary differential equations one time-step H.
Result = LSODE(Y, X, H, Derivs[, Status]
[, ATOL=*value*] [, RTOL=*value*])

LU_COMPLEX - Solves complex linear system using LU decomposition.
Result = LU_COMPLEX(*A*, *B* [, /DOUBLE]
[, /INVERSE] [, /SPARSE])

LUDC - Replaces array with the LU decomposition.
LUDC, *A*, *Index* [, /COLUMN] [, /DOUBLE]
[, INTERCHANGES=*variable*]

LUMPROVE - Uses LU decomposition to iteratively improve an approximate solution.
Result = LUMPROVE(*A*, *Alud*, *Index*, *B*, *X* [, /COLUMN]
[, /DOUBLE])

LUSOL - Solves a set of linear equations. Use with LUDC.
Result = LUSOL(*A*, *Index*, *B* [, /COLUMN] [, /DOUBLE])

M

M_CORRELATE - Computes multiple correlation coefficient.

Result = M_CORRELATE(*X*, *Y* [, /DOUBLE])

MACHAR - Determines and returns machine-specific parameters affecting floating-point arithmetic.

Result = MACHAR([, /DOUBLE])

MAKE_ARRAY - Returns an array of the specified type, dimensions, and initialization.

Result = MAKE_ARRAY ([*D₁*, ..., *D₈*] [, /BYTE | , /COMPLEX | , /DCOMPLEX | , /DOUBLE | , /FLOAT | , /INT | , /L64 | , /LONG | , /OBJ, | , /PTR | , /STRING | , /UINT | , /UL64 | , /ULONG | , DIMENSION=*vector*] [, /INDEX] [, /NOZERO] [, SIZE=*vector*] [, TYPE=*type_code*] [, VALUE=*value*])

MAKE_DLL - Builds a shareable library suitable for use with IDL's dynamic linking.

MAKE_DLL, *InputFiles* [, *OutputFile*], *ExportedRoutineNames* [, CC=*string*] [, COMPILE_DIRECTORY=*path*] [, DLL_PATH=*variable*] [, EXPORTED_DATA=*string*] [, EXTRA_CFLAGS=*string*] [, EXTRA_LFLAGS=*string*] [, INPUT_DIRECTORY=*path*] [, LD=*string*] [, /NOCLEANUP] [, OUTPUT_DIRECTORY=*path*] [, /SHOW_ALL_OUTPUT] [, /VERBOSE] **VMS-Only Keywords:** [/VAX_FLOAT]

MAP_2POINTS - Returns distance, azimuth, and path relating to the great circle or rhumb line connecting two points on a sphere.

Result = MAP_2POINTS(*lon0*, *lat0*, *lon1*, *lat1* [, DPATH=*value* / , /METERS | , /MILES | , NPATH=*integer*{2 or greater} | , /PARAMETERS | , RADIUS=*value*] [, /RADIANS] [, /RHUMB])

MAP_CONTINENTS - Draws continental boundaries, filled continents, political boundaries, coastlines, and/or rivers, over an existing map projection established by MAP_SET.

MAP_CONTINENTS [, /COASTS] [, COLOR=*index*] [, /CONTINENTS] [, /COUNTRIES] [,FILL_CONTINENTS={1 | 2}[, ORIENTATION=*value*]] [, /HIRES] [, LIMIT=*vector*] [, MLINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, MLINETHICK=*value*] [, /RIVERS] [, SPACING=*centimeters*] [, /USA] **Graphics Keywords:** [, /T3D] [, ZVALUE=*value*{0 to 1}]

MAP_GRID - Draws parallels and meridians over a map projection.

MAP_GRID [, /BOX_AXES | [, CLIP_TEXT=0] [, LATALIGN=*value*{0.0 to 1.0}] [, LONALIGN=*value*{0.0 to 1.0}] [, LATLAB=*longitude*] [, LONLAB=*latitude*] [, ORIENTATION=*clockwise_degrees_from_horiz*]] [, CHARSIZE=*value*] [, COLOR=*index*] [, /FILL_HORIZON] [, GLINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, GLINETHICK=*value*] [, /HORIZON] [, INCREMENT=*value*] [, LABEL=*n*{label_every_*n*th_gridline}] [, LATDEL=*degrees*] [, LATNAMES=*array*, LATS=*vector*] [, LONDEL=*degrees*] [, LONNAMES=*array*, LONS=*vector*] [, /NO_GRID] **Graphics Keywords:** [, /T3D] [, ZVALUE=*value*{0 to 1}]

MAP_IMAGE - Returns an image warped to fit the current map projection. (Use when map data is larger than the display).

Result = MAP_IMAGE(*Image* [, *Startx*, *Starty* [, *Xsize*, *Ysize*]] [, LATMIN=*degrees*{-90 to 90}] [, LATMAX=*degrees*{-90 to 90}] [, LONMIN=*degrees*{-180 to 180}] [, LONMAX=*degrees*{-180 to 180}] [, /BILINEAR] [, COMPRESS=*value*] [, SCALE=*value*] [, MAX_VALUE=*value*] [, MIN_VALUE=*value*] [, MISSING=*value*])

MAP_PATCH - Returns an image warped to fit the current map projection. (Use when map data is smaller than the display).

Result = MAP_PATCH(*Image_Orig* [, *Lons*, *Lats*] [, LAT0=*value*] [, LAT1=*value*] [, LON0=*value*] [, LON1=*value*] [, MAX_VALUE=*value*] [, MISSING=*value*] [, /TRIANGULATE] [, XSIZE=*variable*] [, XSTART=*variable*] [, YSIZE=*variable*] [, YSTART=*variable*])

MAP_PROJ_INFO - Returns information about current map and/or the available projections.

MAP_PROJ_INFO [, *iproj*] [, AZIMUTHAL=*variable*] [, CIRCLE=*variable*] [, CYLINDRICAL=*variable*] [, /CURRENT] [, LL_LIMITS=*variable*] [, NAME=*variable*] [, PROJ_NAMES=*variable*] [, UV_LIMITS=*variable*] [, UV_RANGE=*variable*]

MAP_SET - Establishes map projection type and limits.

MAP_SET [, *P0lat*, *P0lon*, *Rot*] **Keywords—Projection Types:** [[, /AITOFF | , /ALBERS | , /AZIMUTHAL | , /CONIC | , /CYLINDRICAL | , /GNOMIC | , /GOODESHOMOLOSINE | , /HAMMER | , /LAMBERT | , /MERCATOR | , /MILLER_CYLINDRICAL | , /MOLLEWIDE | , /ORTHOGRAPHIC | , /ROBINSON | , /SATELLITE | , /SINUSOIDAL | , /STEREOGRAPHIC | , /TRANSVERSE_MERCATOR] | NAME=*string*]] **Keywords—Map Characteristics:** [, /ADVANCE] [, CHARSIZE=*value*] [, /CLIP] [, COLOR=*index*] [, /CONTINENTS [, CON_COLOR=*index*] [, /HIRES]] [, E_CONTINENTS=*structure*, E_GRID=*structure*] [, E_HORIZON=*structure*] [, GLINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, GLINETHICK=*value*] [, /GRID] [, /HORIZON] [, LABEL=*n*{label every *n*th gridline}] [, LATALIGN=*value*{0.0 to 1.0}] [, LATDEL=*degrees*] [, LATLAB=*longitude*] [, LONDEL=*degrees*]

[, LONLAB=*latitude*] [, MLINESTYLE={0 | 1 | 2 | 3 | 4 |
5}] [, MLINETHICK=*value*] [, /NOBORDER]
[, /NOERASE] [, REVERSE={0 | 1 | 2 | 3}]
[, TITLE=*string*] [, /USA] [, XMARGIN=*value*]
[, YMARGIN=*value*]
Keywords—Projection Parameters:
[, CENTRAL_AZIMUTH=*degrees_east_of_north*]
[, ELLIPSOID=*array*] [, /ISOTROPIC] [, LIMIT=*vector*]
[, SAT_P=*vector*] [, SCALE=*value*]
[, STANDARD_PARALLELS=*array*]
Graphics Keywords: [, POSITION=*[X$_0$, Y$_0$, X$_1$, Y$_1$]*]
[, /T3D] [, ZVALUE=*value*{0 to 1}]

MATRIX_MULTIPLY - Calculates the IDL matrix-multiply operator
(#) of two (possibly transposed) arrays.

Result = MATRIX_MULTIPLY(A, B [, /ATRANSPOSE]
[, /BTRANSPOSE])

MAX - Returns the value of the largest element of *Array*.

Result = MAX(*Array* [, *Max_Subscript*] [, MIN=*variable*]
[, /NAN])

MD_TEST - Performs the Median Delta test.

Result = MD_TEST(*X* [, ABOVE=*variable*]
[, BELOW=*variable*] [, MDC=*variable*])

MEAN - Computes the mean of a numeric vector.

Result = MEAN(*X* [, /DOUBLE] [, /NAN])

MEANABSDEV - Computes the mean absolute deviation of a vector.

Result = MEANABSDEV(*X* [, /DOUBLE] [, /MEDIAN]
[, /NAN])

MEDIAN - Returns the median value of *Array* or applies a median fil-
ter.

Result = MEDIAN(*Array* [, *Width*] [, /EVEN])

MEMORY - Returns a vector containing information on the amount of
dynamic memory currently in use by the IDL session.

Result = MEMORY([, /CURRENT | , /HIGHWATER |
, /NUM_ALLOC | , /NUM_FREE |
, /STRUCTURE] [/L64])

MESH_CLIP - Clips a polygonal mesh to an arbitrary plane in space
and returns a polygonal mesh of the remaining portion.

Result = MESH_CLIP (*Plane*, *Vertsin*, *Connin*, *Vertsout*,
Connout [, AUXDATA_IN=*array*,
AUXDATA_OUT=*variable*] [, CUT_VERTS=*variable*])

MESH_DECIMATE - Reduces the density of geometry while pre-
serving as much of the original data as possible.

Result = MESH_DECIMATE (*Verts*, *Conn*, *Connout*
[, VERTICES=*variable*]
[, PERCENT_VERTICES=*percent* |
, PERCENT_POLYGONS=*percent*])

MESH_ISSOLID - Computes various mesh properties and enables
IDL to determine if a mesh encloses space (is a solid).

Result = MESH_ISSOLID (*Conn*)

MESH_MERGE - Merges two polygonal meshes.

Result = MESH_MERGE (*Verts*, *Conn*, *Verts1*, *Conn1*
[, /COMBINE_VERTICES] [, TOLERANCE=*value*])

MESH_NUMTRIANGLES - Computes the number of triangles in a
polygonal mesh..

Result = MESH_NUMTRIANGLES (*Conn*)

MESH_OBJ - Generates a polygon mesh for various simple objects.

MESH_OBJ, *Type*, *Vertex_List*, *Polygon_List*, *Array1*
[, *Array2*] [, /DEGREES] [, P1=*value*] [, P2=*value*]
[, P3=*value*] [, P4=*value*] [, P5=*value*]

MESH_SMOOTH - Performs spatial smoothing on a polygon mesh.

Result = MESH_SMOOTH (*Verts*, *Conn*
[, ITERATIONS=*value*] [, FIXED_VERTICES=*array*]
[, /FIXED_EDGE_VERTICES] [, LAMBDA=*value*])

MESH_SURFACEAREA - Computes various mesh properties to
determine the mesh surface area, including integration of other
properties interpolated on the surface of the mesh.

Result = MESH_SURFACEAREA (*Verts*, *Conn*
[, AUXDATA=*array*] [, MOMENT=*variable*])

MESH_VALIDATE - Checks for NaN values in vertices, removes
unused vertices, and combines close vertices.

Result = MESH_VALIDATE (*Verts*, *Conn*
[, /REMOVE_NAN] [, /PACK_VERTICES]
[, /COMBINE_VERTICES] [, TOLERANCE=*value*])

MESH_VOLUME - Computes the volume that the mesh encloses.

Result = MESH_VOLUME (*Verts, Conn* [, /SIGNED])

MESSAGE - Issues error and informational messages.

MESSAGE, [*Text*] [, /CONTINUE]
[, /INFORMATIONAL] [, /IOERROR] [, /NONAME]
[, /NOPREFIX] [, /NOPRINT] [, /RESET]

MIN - Returns the value of the smallest element of an array.

Result = MIN(*Array* [, *Min_Subscript*] [, MAX=*variable*]
[, /NAN])

MIN_CURVE_SURF - Interpolates over either a plane or a sphere
with a minimum curvature surface or a thin-plate-spline surface.

Result = MIN_CURVE_SURF(*Z* [, *X*, *Y*] [, /DOUBLE]
[, /TPS] [, /REGULAR] [, /SPHERE [, /CONST]]
[, XGRID=*[xstart, xspacing]* | , XVALUES=*array*]
[, YGRID=*[ystart, yspacing]* | , YVALUES=*array*]
[, GS=*[xspace,yspace]*] [, BOUNDS=*[xmin, ymin, xmax,
ymax]*] [, NX=*value*] [, NY=*value*] [, XOUT=*vector*]
[, YOUT=*vector*] [, XPOUT=*array*, YPOUT=*array*])

MK_HTML_HELP - Converts text documentation headers to HTML
files.

MK_HTML_HELP, *Sources*, *Filename* [, /STRICT]
[, TITLE=*string*] [, /VERBOSE]

MODIFYCT - Saves modified color tables in the IDL color table file.

MODIFYCT, *Itab*, *Name*, *R*, *G*, *B* [, FILE=*filename*]

MOMENT - Computes mean, variance, skewness, and kurtosis.

Result = MOMENT(*X* [, /DOUBLE] [, MDEV=*variable*]
[, /NAN] [, SDEV=*variable*])

MORPH_CLOSE - Applies closing operator to binary or grayscale image.

Result = MORPH_CLOSE (*Image*, *Structure* [, /GRAY]
[, PRESERVE_TYPE=*bytearray* | /UINT | /ULONG]
[, VALUES=*array*])

MORPH_DISTANCE - Estimates *N*-dimensional distance maps, which contain for each foreground pixel the distance to the nearest background pixel, using a given norm.

Result = MORPH_DISTANCE (*Data*
[, /BACKGROUND]
[, NEIGHBOR_SAMPLING={1 | 2 | 3 }] [, /NO_COPY])

MORPH_GRADIENT - Applies the morphological gradient operator to a grayscale image.

Result = MORPH_GRADIENT (*Image*, *Structure*
[, PRESERVE_TYPE=*bytearray* | /UINT | /ULONG]
[, VALUES=*array*])

MORPH_HITORMISS - Applies the hit-or-miss operator to a binary image.

Result = MORPH_HITORMISS (*Image, HitStructure,
MissStructure*)

MORPH_OPEN - Applies the opening operator to a binary or grayscale image.

Result = MORPH_OPEN (*Image, Structure* [, /GRAY]
[, PRESERVE_TYPE=*bytearray* | /UINT | /ULONG]
[, VALUES=*array*])

MORPH_THIN - Performs a thinning operation on binary images.

Result = MORPH_THIN (*Image, HitStructure,
MissStructure*)

MORPH_TOPHAT - Applies top-hat operator to a grayscale image.

Result = MORPH_TOPHAT (*Image, Structure*
[, PRESERVE_TYPE=*bytearray* | /UINT | /ULONG]
[, VALUES=*array*])

MPEG_CLOSE - Closes an MPEG sequence.

MPEG_CLOSE, *mpegID*

MPEG_OPEN - Opens an MPEG sequence.

mpegID = MPEG_OPEN(*Dimensions*
[, BITRATE=*value*] [, FILENAME=*string*]
[, IFRAME_GAP=*integer value*]
[, MOTION_VEC_LENGTH={1 | 2 | 3}]
[QUALITY=*value*{0 to 100}])

MPEG_PUT - Inserts an image array into an MPEG sequence

MPEG_PUT, *mpegID* [, /COLOR]
[, FRAME=*frame_number*] [, IMAGE=*array* | ,
WINDOW=*index*] [, /ORDER]

MPEG_SAVE - Encodes and saves an open MPEG sequence.

MPEG_SAVE, *mpegID* [, FILENAME=*string*]

MSG_CAT_CLOSE - Closes a catalog file from the stored cache.

MSG_CAT_CLOSE, *object*

MSG_CAT_COMPILE - Creates an IDL language catalog file.

MSG_CAT_COMPILE, *input*[, *output*]
[, LOCALE_ALIAS=*string*] [, /MBCS]

MSG_CAT_OPEN - Returns a catalog object for the given parameters if found.

Result = MSG_CAT_OPEN(*application*
[, DEFAULT_FILENAME=*filename*]
[, FILENAME=*string*] [, FOUND=*variable*]
[, LOCALE=*string*] [, PATH=*string*]
[, SUB_QUERY=*value*])

MULTI - Replicates current color table to enhance contrast.

MULTI, *N*

N

N_ELEMENTS - Returns the number of elements contained in an expression or variable.

Result = N_ELEMENTS(*Expression*)

N_PARAMS - Returns the number of non-keyword parameters used in calling an IDL procedure or function.

Result = N_PARAMS( )

N_TAGS - Returns the number of tags in a structure.

Result = N_TAGS(*Expression* [, /LENGTH])

NCDF_* Routines - See "NetCDF Routines" on page 64.

NEWTON - Solves nonlinear equations using Newton's method.

Result = NEWTON(*X*, *Vecfunc* [, CHECK=*variable*]
[, /DOUBLE] [, ITMAX=*value*] [, STEPMAX=*value*]
[, TOLF=*value*] [, TOLMIN=*value*] [, TOLX=*value*])

NORM - Computes Euclidean norm of vector or Infinity norm of array.

Result = NORM(*A* [, /DOUBLE])

O

OBJ_CLASS - Determines the class name of an object.

Result = OBJ_CLASS([*Arg*] [, COUNT=*variable*]
[, /SUPERCLASS{must specify Arg}])

OBJ_DESTROY - Destroys an object reference.

OBJ_DESTROY, *ObjRef* [, *Arg₁*, …, *Argₙ*]

OBJ_ISA - Determines inheritance relationship of an object.

Result = OBJ_ISA(*ObjectInstance*, *ClassName*)

OBJ_NEW - Creates an object reference.

Result = OBJ_NEW([*ObjectClassName* [, *Arg₁*......*Argₙ*]])

OBJ_VALID - Verifies validity of object references.

Result = OBJ_VALID([*Arg*] [, CAST=*integer*]
[, COUNT=*variable*])

OBJARR - Creates an array of object references.

Result = OBJARR(*D₁*, …, *D₈* [, /NOZERO])

ON_ERROR - Designates the error recovery method.
ON_ERROR, *N*

ON_IOERROR - Declares I/O error exception handler.
ON_IOERROR, *Label*
· · ·
Label: *Statement to perform upon I/O error*

ONLINE_HELP - Invokes hypertext help viewer from programs.
ONLINE_HELP [, *Value*] [, BOOK='*filename*']
[, /CONTEXT] [, /FULL_PATH] [, /HTML_HELP]
[, /QUIT] [, /TOPICS]

OPEN - Opens files for reading, updating, or writing.
OPENR, *Unit*, *File* [, *Record_Length*]
OPENW, *Unit*, *File* [, *Record_Length*]
OPENU, *Unit*, *File* [, *Record_Length*]
Keywords (all platforms): [, /APPEND | , /COMPRESS]
[, BUFSIZE={0 | 1 | *value*>512}] [, /DELETE]
[, ERROR=*variable*] [, /F77_UNFORMATTED]
[, /GET_LUN] [, /MORE] [, /STDIO]
[, /SWAP_ENDIAN] [, SWAP_IF_BIG_ENDIAN]
[, /SWAP_IF_LITTLE_ENDIAN] [, /VAX_FLOAT]
[, WIDTH=*value*] [, /XDR]
Macintosh-Only Keywords: [, MACCREATOR=*string*]
[, MACTYPE= *string*]
UNIX-Only Keywords: [, /RAWIO]
VMS-Only Keywords: [, /BLOCK | , /SHARED | ,
/UDF_BLOCK] [, DEFAULT='.*extension*']
[, /EXTENDSIZE] [, /FIXED] [, /FORTRAN]
[, INITIALSIZE=*blocks*] [, /KEYED] [, /LIST] [, /NONE]
[, /PRINT] [, /SEGMENTED] [, /STREAM] [, /SUBMIT]
[, /SUPERSEDE] [, /TRUNCATE_ON_CLOSE]
[, /VARIABLE]

OPLOT - Plots vector data over a previously-drawn plot.
OPLOT, [*X*,] *Y* [, MAX_VALUE=*value*]
[, MIN_VALUE=*value*] [, NSUM=*value*] [, /POLAR]
[, THICK=*value*]
Graphics Keywords: [, CLIP=*[X₀, Y₀, X₁, Y₁]*]
[, COLOR=*value*] [, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}]
[, /NOCLIP] [, PSYM=*integer*{0 to 10}]
[, SYMSIZE=*value*] [, /T3D] [, ZVALUE=*value*{0 to 1}]

OPLOTERR - Draws error bars over a previously drawn plot.
OPLOTERR, [*X* ,] *Y* , *Err* [, *Psym*]

P

P_CORRELATE - Computes partial correlation coefficient.
Result = P_CORRELATE(*X*, *Y*, *C* [, /DOUBLE])

PARTICLE_TRACE - Traces the path of a massless particle through a vector field.
PARTICLE_TRACE, *Data*, *Seeds*, *Verts*, *Conn*
[, *Normals*] [, MAX_ITERATIONS=*value*]

[, ANISOTROPY=*array*] [, INTEGRATION={0 | 1}]
[, SEED_NORMAL=*vector*] [, TOLERANCE=*value*]
[, MAX_STEPSIZE=*value*] [, /UNIFORM]

PCOMP - Computes principal components/derived variables.
Result = PCOMP(*A* [, COEFFICIENTS=*variable*]
[, /COVARIANCE] [, /DOUBLE]
[, EIGENVALUES=*variable*] [, NVARIABLES=*value*]
[, /STANDARDIZE] [, VARIANCES=*variable*])

PLOT - Plots vector arguments as X versus Y graphs.
PLOT, [*X*,] *Y* [, MAX_VALUE=*value*]
[, MIN_VALUE=*value*] [, NSUM=*value*] [, /POLAR]
[, THICK=*value*] [, /XLOG] [, /YLOG] [, /YNOZERO]
Graphics Keywords: [, BACKGROUND=*color_index*]
[, CHARSIZE=*value*] [, CHARTHICK=*integer*]
[, CLIP=*[X₀, Y₀, X₁, Y₁]*] [, COLOR=*value*] [, /DATA | ,
/DEVICE | , /NORMAL] [, FONT=*integer*]
[, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, /NOCLIP]
[, /NODATA] [, /NOERASE] [, POSITION=*[X₀, Y₀, X₁,
Y₁]*] [, PSYM=*integer*{0 to 10}] [, SUBTITLE=*string*]
[, SYMSIZE=*value*] [, /T3D] [, THICK=*value*]
[, TICKLEN=*value*] [, TITLE=*string*]
[, {X | Y | Z}CHARSIZE=*value*]
[, {X | Y | Z}GRIDSTYLE=*integer*{0 to 5}]
[, {X | Y | Z}MARGIN=*[left, right]*]
[, {X | Y | Z}MINOR=*integer*]
[, {X | Y | Z}RANGE=*[min, max]*]
[, {X | Y | Z}STYLE=*value*]
[, {X | Y | Z}THICK=*value*]
[, {X | Y | Z}TICK_GET=*variable*]
[, {X | Y | Z}TICKFORMAT=*string*]
[, {X | Y | Z}TICKINTERVAL=*value*]
[, {X | Y | Z}TICKLAYOUT=*scalar*]
[, {X | Y | Z}TICKLEN=*value*]
[, {X | Y | Z}TICKNAME=*string_array*]
[, {X | Y | Z}TICKS=*integer*]
[, {X | Y | Z}TICKUNITS=*string*]
[, {X | Y | Z}TICKV=*array*]
[, {X | Y | Z}TITLE=*string*]
[, ZVALUE=*value*{0 to 1}]

PLOT_3DBOX - Plots function of two variables inside 3D box.
PLOT_3DBOX, *X*, *Y*, *Z* [, GRIDSTYLE={0 | 1 | 2 | 3 | 4 |
5}] [, PSYM=*integer*{1 to 10}] [, /SOLID_WALLS]
[, /XY_PLANE] [, XYSTYLE={0 | 1 | 2 | 3 | 4 | 5}]
[, /XZ_PLANE] [, XZSTYLE={0 | 1 | 2 | 3 | 4 | 5}]
[, /YZ_PLANE] [, YZSTYLE={0 | 1 | 2 | 3 | 4 | 5}]
[, AX=*degrees*] [, AZ=*degrees*] [, ZAXIS={1 | 2 | 3 | 4}]
Graphics Keywords: Accepts all graphics keywords
accepted by PLOT except for: FONT, PSYM, SYMSIZE,
{XYZ}TICK_GET, and ZVALUE.

PLOT_FIELD - Plots a 2D field using arrows.
PLOT_FIELD, *U*, *V* [, ASPECT=*ratio*]
[, LENGTH=*value*] [, N=*num_arrows*] [, TITLE=*string*]

PLOTERR - Plots individual data points with error bars.

PLOTERR, [*X* ,] *Y* [, *Err* [, TYPE={1 | 2 | 3 | 4}]
[, PSYM=*integer*{1 to 10}]

PLOTS - Plots vectors and points.

PLOTS, *X* [, *Y* [, *Z*]] [, /CONTINUE]
Graphics Keywords: [, CLIP=*[X_0, Y_0, X_1, Y_1]*]
[, COLOR=*value*] [, /DATA | , /DEVICE | , /NORMAL]
[, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, /NOCLIP]
[, PSYM=*integer*{0 to 10}] [, SYMSIZE=*value*] [, /T3D]
[, THICK=*value*] [, Z=*value*]

PNT_LINE - Returns the perpendicular distance between a point and a line.

Result = PNT_LINE(*P0*, *L0*, *L1* [, *Pl*] [, /INTERVAL])

POINT_LUN - Sets or gets current position of the file pointer.

POINT_LUN, *Unit*, *Position*

POLAR_CONTOUR - Draws a contour plot from data in polar coordinates.

POLAR_CONTOUR, *Z*, *Theta*, *R*
[, C_ANNOTATION=*vector_of_strings*]
[, C_CHARSIZE=*value*] [, C_CHARTHICK=*integer*]
[, C_COLORS=*vector*] [, C_LINESTYLE=*vector*]
[, /FILL | , CELL_FILL] [, C_ORIENTATION=*degrees*]
[, C_SPACING=*value*]] [, C_THICK=*vector*]
[, /CLOSED] [, /IRREGULAR] [, LEVELS=*vector* /
NLEVELS=*integer*{1 to 29}] [, MAX_VALUE=*value*]
[, MIN_VALUE=*value*] [, /OVERPLOT]
[, /PATH_DATA_COORDS |
,TRIANGULATION=*variable*] [, /XLOG] [, /YLOG]
[, /ZAXIS] [, SHOW_TRIANGULATION=*color_index*]

POLAR_SURFACE - Interpolates a surface from polar coordinates to rectangular coordinates.

Result = POLAR_SURFACE(*Z*, *R*, *Theta* [, /GRID]
[, SPACING=*[xspacing, yspacing]*]
[, BOUNDS=*[x_0, y_0, x_1, y_1]*] [, /QUINTIC]
[, MISSING=*value*])

POLY - Evaluates polynomial function of a variable.

Result = POLY(*X*, *C*)

POLY_2D - Performs polynomial warping of images.

Result = POLY_2D(*Array*, *P*, *Q* [, *Interp* [, *Dim_x*, *Dim_y*]]
[, CUBIC={-1 to 0}] [, MISSING=*value*])

POLY_AREA - Returns the area of a polygon given the coordinates of its vertices.

Result = POLY_AREA(*X*, *Y* [, /SIGNED])

POLY_FIT - Performs a least-square polynomial fit.

Result = POLY_FIT(*X*, *Y*, *Degree* [, CHISQ=*variable*]
[, COVAR=*variable*] [, /DOUBLE]
[, MEASURE_ERRORS=*vector*] [, SIGMA=*variable*]
[, STATUS=*variable*] [, YBAND=*variable*]
[, YERROR=*variable*] [, YFIT=*variable*])

POLYFILL - Fills the interior of a polygon.

POLYFILL, *X* [, *Y* [, *Z*]] [, IMAGE_COORD=*array*]
[, /IMAGE_INTERP] [, /LINE_FILL]
[, PATTERN=*array*] [, SPACING=*centimeters*]
[, TRANSPARENT=*value*]
Graphics Keywords: [, CLIP=*[X_0, Y_0, X_1, Y_1]*]
[, COLOR=*value*] [, /DATA | , /DEVICE | , /NORMAL]
[, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5}] [, /NOCLIP]
[, ORIENTATION=*ccw_degrees_from_horiz*] [, /T3D]
[, THICK=*value*] [, Z=*value*]

POLYFILLV - Returns subscripts of pixels inside a polygon.

Result = POLYFILLV(*X*, *Y*, *S_x*, *S_y* [, *Run_Length*])

POLYSHADE - Creates a shaded surface representation from a set of polygons.

Result = POLYSHADE(*Vertices*, *Polygons*)
or
Result = POLYSHADE(*X*, *Y*, *Z*, *Polygons*)
Keywords: [, /DATA | , /NORMAL]
[, POLY_SHADES=*array*] [, SHADES=*array*] [, /T3D]
[, TOP=*value*] [, XSIZE=*columns*] [, YSIZE=*rows*]

POLYWARP - Performs polynomial spatial warping.

POLYWARP, *Xi*, *Yi*, *Xo*, *Yo*, *Degree*, *Kx*, *Ky*

POPD - Removes the top directory on the working directory stack maintained by PUSHD/POPD.

POPD

POWELL - Minimizes a function using the Powell method.

POWELL, *P*, *Xi*, *Ftol*, *Fmin*, *Func* [, /DOUBLE]
[, ITER=*variable*] [, ITMAX=*value*]

PRIMES - Computes the first *K* prime numbers.

Result = PRIMES(*K*)

PRINT/PRINTF - Writes formatted output to screen or file.

PRINT [, *Expr_1*, ..., *Expr_n*]
PRINTF [, *Unit*, *Expr_1*, ..., *Expr_n*]
Keywords: [, AM_PM=*[string, string]*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, FORMAT=*value*] [, MONTHS=*string_array*{12
names}] [, /STDIO_NON_FINITE]
VMS Keywords: [, /REWRITE]

PRINTD - Prints contents of the directory stack maintained by PUSHD/POPD.

PRINTD

PRO - Defines a procedure.

PRO *Procedure_Name*, *argument_1*, ..., *argument_n*
. . .
END

PROFILE - Extracts a profile from an image.

Result = PROFILE(*Image* [, *XX*, *YY*] [, /NOMARK]
[, XSTART=*value*] [, YSTART=*value*])

PROFILER - Accesses the IDL Code Profiler used to analyze performance of applications.
PROFILER [, *Module*] [, /CLEAR] [, DATA=*variable*]
[, OUTPUT=*variable*] [, /REPORT] [, /RESET]
[, /SYSTEM]

PROFILES - Interactively examines image profiles.
PROFILES, *Image* [, /ORDER] [, SX=*value*] [, SY=*value*]
[, WSIZE=*value*]

PROJECT_VOL - Returns a translucent rendering of a volume projected onto a plane.
Return = PROJECT_VOL(*Vol*, *X_Sample*, *Y_Sample*,
Z_Sample [, DEPTH_Q=*value*] [, OPAQUE=*3D_array*]
[, TRANS=*array*])

PS_SHOW_FONTS - Displays all the PostScript fonts that IDL knows about.
PS_SHOW_FONTS [, /NOLATIN]

PSAFM - Converts Adobe Font Metrics file to IDL format.
PSAFM, *Input_Filename*, *Output_Filename*

PSEUDO - Creates pseudo-color table based on Lightness, Hue, and Brightness system.
PSEUDO, *Litlo*, *Lithi*, *Satlo*, *Sathi*, *Hue*, *Loops* [, *Colr*]

PTR_FREE - Destroys a pointer.
PTR_FREE, P_1, ... …, P_n

PTR_NEW - Creates a pointer.
Result = PTR_NEW([*InitExpr*] [, /ALLOCATE_HEAP]
[, /NO_COPY])

PTR_VALID - Verifies the validity of pointers.
Result = PTR_VALID([*Arg*] [, /CAST]
[, COUNT=*variable*])

PTRARR - Creates an array of pointers.
Result = PTRARR(D_1, ... …, D_8 [, /ALLOCATE_HEAP |
, /NOZERO])

PUSHD - Pushes a directory to top of directory stack maintained by PUSHD/POPD.
PUSHD, *Dir*

Q

QROMB - Evaluates integral over a closed interval.
Result = QROMB(*Func*, *A*, *B* [, /DOUBLE] [, EPS=*value*]
[, JMAX=*value*] [, K=*value*])

QROMO - Evaluates integral over an open interval.
Result = QROMO(*Func*, *A* [, *B*] [, /DOUBLE]
[, EPS=*value*] [, JMAX=*value*] [, K=*value*] [, /MIDEXP | ,
/MIDINF | , /MIDPNT | , /MIDSQL | , /MIDSQU])

QSIMP - Evaluates integral using Simpson's rule.
Result = QSIMP(*Func*, *A*, *B* [, /DOUBLE] [, EPS=*value*]
[, JMAX=*value*])

QUERY_BMP - Obtains information about a BMP image file.
Result = QUERY_BMP (*Filename* [, *Info*])

QUERY_DICOM - Tests file for compatibility with READ_DICOM.
Result = QUERY_DICOM(*Filename*[, *Info*]
[, IMAGE_INDEX=*index*])

QUERY_IMAGE - Determines if a file is recognized as an image file.
Result = QUERY_IMAGE (*Filename*[, *Info*]
[, CHANNELS=*variable*] [, DIMENSIONS=*variable*]
[, HAS_PALETTE=*variable*] [, IMAGE_INDEX=*index*]
[, NUM_IMAGES=*variable*] [, PIXEL_TYPE=*variable*]
[, SUPPORTED_READ=*variable*]
[, SUPPORTED_WRITE=*variable*] [, TYPE=*variable*])

QUERY_JPEG - Obtains information about a JPEG image file.
Result = QUERY_JPEG (*Filename* [, *Info*])

QUERY_PICT - Obtains information about a PICT image file.
Result = QUERY_PICT (*Filename*, *Info*)

QUERY_PNG - Obtains information about a PNG image file.
Result = QUERY_PNG (*Filename* [, *Info*])

QUERY_PPM - Obtains information about a PPM image file.
Result = QUERY_PPM (*Filename* [, *Info*]
[, MAXVAL=*variable*])

QUERY_SRF - Obtains information about an SRF image file.
Result = QUERY_SRF (*Filename* [, *Info*])

QUERY_TIFF - Obtains information about a TIFF image file.
Result = QUERY_TIFF (*Filename* [, *Info*]
[, IMAGE_INDEX=*index*])

QUERY_WAV - Checks that the file is actually a .WAV file and that the READ_WAV function can read the data in the file.
Result = QUERY_WAV (*Filename*[, *Info*])

R

R_CORRELATE - Computes rank correlation.
Result = R_CORRELATE(*X*, *Y* [, D=*variable*]
[, /KENDALL] [, PROBD=*variable*] [, ZD=*variable*])

R_TEST - Runs test for randomness.
Result = R_TEST(*X* [, N0=*variable*] [, N1=*variable*]
[, R=*variable*])

RADON - Returns the Radon transform of a two-dimensional image.
Radon Transform: *Result* = RADON(*Array*
[, /DOUBLE] [, DRHO=*scalar*] [, DX=*scalar*]
[, DY=*scalar*] [, /GRAY] [, /LINEAR] [, NRHO=*scalar*]
[, NTHETA=*scalar*] [, RHO=*variable*] [, RMIN=*scalar*]
[, THETA=*variable*] [, XMIN=*scalar*] [, YMIN=*scalar*])
Radon Backprojection: *Result* = RADON(*Array,*
/BACKPROJECT, RHO=*variable*, THETA=*variable*
[, /DOUBLE] [, DX=*scalar*] [, DY=*scalar*] [, /LINEAR]
[, NX=*scalar*] [, NY=*scalar*] [, XMIN=*scalar*]
[, YMIN=*scalar*])

RANDOMN - Returns normally-distributed pseudo-random numbers.

Result = RANDOMN(*Seed* [, D_1, ..., D_8]
[[, BINOMIAL=*[trials, probability]*] [, /DOUBLE]
[, GAMMA=*integer{>0}*] [, /NORMAL]
[, POISSON=*value*] [, /UNIFORM] | [, /LONG]])

RANDOMU - Returns uniformly-distributed pseudo-random numbers.

Result = RANDOMU(*Seed* [, D_1, ..., D_8]
[[, BINOMIAL=*[trials, probability]*] [, /DOUBLE]
[, GAMMA=*integer{>0}*] [, /NORMAL]
[, POISSON=*value*] [, /UNIFORM] | [, /LONG]])

RANKS - Computes magnitude-based ranks.

Result = RANKS(*X*)

RDPIX - Interactively displays image pixel values.

RDPIX, *Image* [, *X0, Y0*]

READ/READF - Reads formatted input from keyboard or file.

READ, [*Prompt,*] *Var_1*, ..., *Var_n*
READF, [*Prompt,*] *Unit, Var_1*, ..., *Var_n*
Keywords: [, AM_PM=*[string, string]*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, FORMAT=*value*] [, MONTHS=*string_array*{12
names}] [, PROMPT=*string*]
VMS Keywords: [, KEY_ID=*value*]
[, KEY_MATCH=*relation*] [, KEY_VALUE=*value*]

READ_ASCII - Reads data from an ASCII file.

Result = READ_ASCII([*Filename*]
[, COMMENT_SYMBOL=*string*] [, COUNT=*variable*]
[, DATA_START=*lines_to_skip*] [, DELIMITER=*string*]
[, HEADER=*variable*] [, MISSING_VALUE=*value*]
[, NUM_RECORDS=*value*] [, RECORD_START=*index*]
[, TEMPLATE=*value*] [, /VERBOSE])

READ_BINARY - Reads the contents of a binary file using a passed template or basic command line keywords.

Result = READ_BINARY ([*Filename | FileUnit*]
[, TEMPLATE=*template*] | [[, DATA_START=*value*]
[, DATA_TYPE=*typecodes*] [, DATA_DIMS=*array*]
[, ENDIAN=*string*]])

READ_BMP - Reads Microsoft Windows bitmap file (.BMP).

Result = READ_BMP(*Filename,* [, *R, G, B*] [, *Ihdr*]
[, /RGB])

READ_DICOM - Reads an image from a DICOM file.

Result = READ_DICOM (*Filename* [, *Red, Green, Blue*]
[, IMAGE_INDEX=*index*])

READ_IMAGE - Reads the image contents of a file and returns the image in an IDL variable.

Result = READ_IMAGE (*Filename* [, *Red, Green, Blue*]
[, IMAGE_INDEX=*index*])

READ_INTERFILE - Reads Interfile (v3.3) file.

READ_INTERFILE, *File, Data*

READ_JPEG - Reads JPEG file.

READ_JPEG [, *Filename* | , UNIT=*lun*] , *Image*
[, *Colortable*] [, BUFFER=*variable*]
[, COLORS=*value{8 to 256}*] [, DITHER={0 | 1 | 2}]
[, /GRAYSCALE] [, /ORDER] [, TRUE={1 | 2 | 3}]
[, /TWO_PASS_QUANTIZE]

READ_PICT - Reads Macintosh PICT (version 2) bitmap file.

READ_PICT, *Filename, Image* [, *R, G, B*]

READ_PNG - Reads Portable Network Graphics (PNG) file.

Result = READ_PNG (*Filename* [, *R, G, B*] [,/ORDER]
[, /VERBOSE] [, /TRANSPARENT])
or
READ_PNG, *Filename, Image* [, *R, G, B*] [,/ORDER]
[, /VERBOSE] [, /TRANSPARENT]

READ_PPM - Reads PGM (gray scale) or PPM (portable pixmap for color) file.

READ_PPM, *Filename, Image* [, MAXVAL=*variable*]

READ_SPR - Reads a row-indexed sparse matrix from a file.

Result = READ_SPR(*Filename*)

READ_SRF - Reads Sun Raster Format file.

READ_SRF, *Filename, Image* [, *R, G, B*]

READ_SYLK - Reads Symbolic Link format spreadsheet file.

Result = READ_SYLK(*File* [, /ARRAY]
[, /COLMAJOR] [, NCOLS=*columns*] [, NROWS=*rows*]
[, STARTCOL=*column*] [, STARTROW=*row*]
[, /USEDOUBLES] [, /USELONGS])

READ_TIFF - Reads TIFF format file.

Result = READ_TIFF(*Filename* [, *R, G, B*]
[, CHANNELS=*scalar or vector*] [, GEOTIFF=*variable*]
[, IMAGE_INDEX=*value*] [, INTERLEAVE={0 | 1 |2}]
[, ORDER=*variable*] [, PLANARCONFIG=*variable*]
[, SUB_RECT=*[x, y, width, height]*] [, /UNSIGNED]
[, /VERBOSE])

READ_WAV - Reads the audio stream from the named .WAV file.

Result = READ_WAV (*Filename* [, *Rate*])

READ_WAVE - Reads Wavefront Advanced Visualizer file.

READ_WAVE, *File, Variables, Names, Dimensions*
[, MESHNAMES=*variable*]

READ_X11_BITMAP - Reads X11 bitmap file.

READ_X11_BITMAP, *File, Bitmap* [, *X, Y*]
[, /EXPAND_TO_BYTES]

READ_XWD - Reads X Windows Dump file.

Result = READ_XWD(*Filename*[, *R, G, B*])

READS - Reads formatted input from a string variable.

READS, *Input, Var_1*, ..., *Var_n* [, AM_PM=*[string, string]*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, FORMAT=*value*] [, MONTHS=*string_array*{12
names}]

READU - Reads unformatted binary data from a file.

READU, *Unit*, *Var₁*, ..., *Var_n*
[, TRANSFER_COUNT=*variable*]
VMS-Only Keywords: [, KEY_ID=*index*]
[, KEY_MATCH=*relation*] [, KEY_VALUE=*value*]

REBIN - Resizes a vector or array by integer multiples.

Result = REBIN(*Array*, *D₁* [, ..., *D₈*] [, /SAMPLE])

RECALL_COMMANDS - Returns entries in IDL's command recall buffer.

Result = RECALL_COMMANDS( )

RECON3 - Reconstructs a 3D representation of an object from 2D images.

Result = RECON3(*Images*, *Obj_Rot*, *Obj_Pos*, *Focal*, *Dist*,*Vol_Pos*, *Img_Ref*, *Img_Mag*, *Vol_Size* [, /CUBIC]
[, MISSING=*value*] [, MODE=*value*])

REDUCE_COLORS - Reduces the number of colors used in an image by eliminating unused pixel values.

REDUCE_COLORS, *Image*, *Values*

REFORM - Changes array dimensions without changing the total number of elements.

Result = REFORM(*Array*, *D₁*, ..., *D₈* [, /OVERWRITE])

REGRESS - Computes fit using multiple linear regression.

Result = REGRESS(*X*, *Y*, [, CHISQ=*variable*]
[, CONST=*variable*] [, CORRELATION=*variable*]
[, /DOUBLE] [, FTEST=*variable*]
[, MCORRELATION=*variable*]
[, MEASURE_ERRORS=*vector*] [, SIGMA=*variable*]
[, STATUS=*variable*] [, YFIT=*variable*])

REPEAT...UNTIL - Repeats statement(s) until expression evaluates to true. Subject is always executed at least once.

REPEAT *statement* UNTIL *expression*

or

REPEAT BEGIN
   statements
ENDREP UNTIL *expression*

REPLICATE - Creates an array of given dimensions, filled with specified value.

Result = REPLICATE(*Value*, *D₁* [, ..., *D₈*])

REPLICATE_INPLACE - Updates an array by replacing all or selected parts of it with a specified value.

REPLICATE_INPLACE, *X*, *Value* [, *D1*, *Loc1* [, *D2*, *Range*]]

RESOLVE_ALL - Compiles any uncompiled routines.

RESOLVE_ALL [, /CONTINUE_ON_ERROR]
[, /QUIET]

RESOLVE_ROUTINE - Compiles a routine.

RESOLVE_ROUTINE, *Name*
[, /COMPILE_FULL_FILE]
[, /EITHER | , /IS_FUNCTION] [, /NO_RECOMPLIE]

RESTORE - Restores IDL variables and routines saved in an IDL SAVE file.

RESTORE [, *Filename*] [, FILENAME=*name*]
[, /RELAXED_STRUCTURE_ASSIGNMENT]
[, RESTORED_OBJECTS=*variable*] [, /VERBOSE]

RETALL - Returns control to the main program level.

RETALL

RETURN - Returns control to the next-higher program level.

RETURN [, *Return_value*]

REVERSE - Reverses the order of one dimension of an array.

Result = REVERSE(*Array* [, *Subscript_Index*]
[, /OVERWRITE])

REWIND (VMS only) - Rewinds tape on designated IDL tape unit.

REWIND, *Unit*

RK4 - Solves differential equations using fourth-order Runge-Kutta method.

Result = RK4(*Y*, *Dydx*, *X*, *H*, *Derivs* [, /DOUBLE])

ROBERTS - Returns an approximation of Roberts edge enhancement.

Result = ROBERTS(*Image*)

ROT - Rotates an image by any amount.

Result = ROT(*A*, *Angle*, [*Mag*, X_0, Y_0] [, /INTERP]
[, CUBIC=*value*{-1 to 0}] [, MISSING=*value*]
[, /PIVOT])

ROTATE - Rotates/transposes an array in multiples of 90 degrees.

Result = ROTATE(*Array*, *Direction*)

ROUND - Rounds the argument to its closest integer.

Result = ROUND(*X* [, /L64])

ROUTINE_INFO - Provides information about compiled procedures and functions.

Result = ROUTINE_INFO([*Routine*
[[, /PARAMETERS{must specify *Routine*}] [, /SOURCE]
[, /UNRESOLVED] [, /VARIABLES] | , /SYSTEM]]
[, /DISABLED] [, /ENABLED] [, /FUNCTIONS])

RS_TEST - Performs the Wilcoxon Rank-Sum test.

Result = RS_TEST(*X*, *Y* [, UX=*variable*] [, UY=*variable*])

S

S_TEST - Performs the Sign test.

Result = S_TEST(*X*, *Y* [, ZDIFF=*variable*])

SAVGOL - Returns coefficients of Savitzky-Golay smoothing filter.

Result = SAVGOL(*Nleft*, *Nright*, *Order*, *Degree*
[, /DOUBLE])

SAVE - Saves variables, system variables, and IDL routines in a file for later use.

SAVE [, *Var₁*, ..., *Varₙ*] [, /ALL] [, /COMM,
/VARIABLES] [, /COMPRESS] [, FILENAME=*string*]
[, ROUTINES] [, /SYSTEM_VARIABLES]
[, /VERBOSE]

SCALE3 - Sets up axis ranges and viewing angles for 3D plots.

SCALE3 [, XRANGE=*vector*] [, YRANGE=*vector*]
[, ZRANGE=*vector*] [, AX=*degrees*] [, AZ=*degrees*]

SCALE3D - Scales 3D unit cube into the viewing area.

SCALE3D

SEARCH2D - Finds "objects" or regions of similar data within a 2D array.

Result = SEARCH2D(*Array*, *Xpos*, *Ypos*, *Min_Val*,
Max_Val [, /DECREASE, /INCREASE
[, LPF_BAND=*integer*{≥3}]] [, /DIAGONAL])

SEARCH3D - Finds "objects" or regions of similar data values within a volume.

Result = SEARCH3D(*Array*, *Xpos*, *Ypos*, *Zpos*, *Min_Val*,
Max_Val [, /DECREASE, /INCREASE
[, LPF_BAND=*integer*{≥3}]] [, /DIAGONAL])

SET_PLOT - Sets the output device used by the IDL direct graphics procedures.

SET_PLOT, *Device* [, /COPY] [, /INTERPOLATE]

SET_SHADING - Sets the light source shading parameters.

SET_SHADING [, /GOURAUD] [, LIGHT=*[x, y, z]*]
[, /REJECT] [, VALUES=*[darkest, brightest]*]

SET_SYMBOL (VMS Only) - Defines a VMS DCL interpreter symbol.

SET_SYMBOL, *Name*, *Value* [, TYPE={1 | 2}]

SETENV (UNIX/Windows Only) - Adds or changes an environment variable.

SETENV, *Environment_Expression*

SETLOG (VMS Only) - Defines a VMS logical name.

SETLOG, *Lognam*, *Value* [, /CONCEALED]
[, /CONFINE] [, /NO_ALIAS] [, TABLE=*string*]
[, /TERMINAL]

SETUP_KEYS - Sets function keys for use with UNIX versions of IDL.

SETUP_KEYS [, /EIGHTBIT] [, /SUN | , /VT200 | ,
/HP9000 | , /MIPS | , /PSTERM | , /SGI]
[, /APP_KEYPAD] [, /NUM_KEYPAD]

SFIT - Performs polynomial fit to a surface.

Result = SFIT(*Data*, *Degree* [, KX=*variable*])

SHADE_SURF - Creates a shaded-surface representation of gridded data.

SHADE_SURF, *Z* [, *X*, *Y*] [, AX=*degrees*] [, AZ=*degrees*]
[, IMAGE=*variable*] [, MAX_VALUE=*value*]
[, MIN_VALUE=*value*] [, PIXELS=*pixels*] [, /SAVE]
[, SHADES=*array*] [, /XLOG] [, /YLOG]
Graphics Keywords: [, CHARSIZE=*value*]
[, CHARTHICK=*integer*] [, COLOR=*value*] [, /DATA | ,
/DEVICE | , /NORMAL] [, FONT=*integer*] [, /NODATA]
[, POSITION=*[X₀, Y₀, X₁, Y₁]*] [, SUBTITLE=*string*]
[, /T3D] [, THICK=*value*] [, TICKLEN=*value*]
[, TITLE=*string*]
[, {X | Y | Z}CHARSIZE=*value*]
[, {X | Y | Z}GRIDSTYLE=*integer*{0 to 5}]
[, {X | Y | Z}MARGIN=*[left, right]*]
[, {X | Y | Z}MINOR=*integer*]
[, {X | Y | Z}RANGE=*[min, max]*]
[, {X | Y | Z}STYLE=*value*] [, {X | Y | Z}THICK=*value*]
[, {X | Y | Z}TICKFORMAT=*string*]
[, {X | Y | Z}TICKINTERVAL=*value*]
[, {X | Y | Z}TICKLAYOUT=*scalar*]
[, {X | Y | Z}TICKLEN=*value*]
[, {X | Y | Z}TICKNAME=*string_array*]
[, {X | Y | Z}TICKS=*integer*]
[, {X | Y | Z}TICKUNITS=*string*]
[, {X | Y | Z}TICKV=*array*]
[, {X | Y | Z}TICK_GET=*variable*]
[, {X | Y | Z}TITLE=*string*]
[, ZVALUE=*value*{0 to 1}]

SHADE_SURF_IRR - Creates a shaded-surface representation of an irregularly gridded dataset.

SHADE_SURF_IRR, *Z*, *X*, *Y* [, AX=*degrees*]
[, AZ=*degrees*] [, IMAGE=*variable*] [, PLIST=*variable*]
[, /T3D]

SHADE_VOLUME - Contours a volume to create a list of vertices and polygons that can be displayed using POLYSHADE.

SHADE_VOLUME, *Volume*, *Value*, *Vertex*, *Poly*
[, /LOW] [, SHADES=*array*] [, /VERBOSE]
[, XRANGE=*vector*] [, YRANGE=*vector*]
[, ZRANGE=*vector*]

SHIFT - Shifts elements of vectors or arrays by a specified number of elements.

Result = SHIFT(*Array*, *S₁*, ..., *Sₙ*)

SHOW3 - Displays array as image, surface plot, and contour plot simultaneously.

SHOW3, *Image* [, *X*, *Y*] [, /INTERP]
[, E_CONTOUR=*structure*] [, E_SURFACE=*structure*]
[, SSCALE=*scale*]

SHOWFONT - Displays a TrueType or vector font

SHOWFONT, *Font*, *Name* [, /ENCAPSULATED]
[, /TT_FONT]

SIN - Returns the trigonometric sine of *X*.

$Result = SIN(X)$

SINDGEN - Returns a string array with each element set to its subscript.

$Result = SINDGEN(D_1, ..., D_8)$

SINH - Returns the hyperbolic sine of X.

$Result = SINH(X)$

SIZE - Returns array size and type information.

$Result = SIZE(Expression$ [, /L64] [, /DIMENSIONS | , /FILE_LUN | , /N_DIMENSIONS | , /N_ELEMENTS | , /STRUCTURE | , /TNAME | , /TYPE])

SKEWNESS - Computes statistical skewness of an *n*-element vector.

$Result = SKEWNESS(X$ [, /DOUBLE] [, /NAN])

SKIPF - Skips records or files on the designated magnetic tape unit.

SKIPF, *Unit*, *Files* or SKIPF, *Unit*, *Records*, *R*

SLICER3 - Interactive volume visualization tool.

SLICER3 [, *hData3D*]
[, DATA_NAMES=*string/string_array*] [, /DETACH]
[, GROUP=*widget_id*] [, /MODAL]

SLIDE_IMAGE - Creates a scrolling graphics window for examining large images.

SLIDE_IMAGE [, *Image*] [, /BLOCK] [, CONGRID=0]
[, FULL_WINDOW=*variable*] [, GROUP=*widget_id*]
[, /ORDER] [, /REGISTER] [, RETAIN={0 | 1 | 2}]
[, SLIDE_WINDOW=*variable*] [, SHOW_FULL=0]
[, TITLE=*string*] [, TOP_ID=*variable*] [, XSIZE=*width*]
[, XVISIBLE=*width*] [, YSIZE=*height*]
[, YVISIBLE=*height*]

SMOOTH - Smooths with a boxcar average.

$Result = SMOOTH(Array$, *Width*
[, /EDGE_TRUNCATE] [, /NAN])

SOBEL - Returns an approximation of Sobel edge enhancement.

$Result = SOBEL(Image)$

SOCKET - Opens client-side TCP/IP Internet socket as IDL file unit.

SOCKET, *Unit*, *Host*, *Port*
[, CONNECT_TIMEOUT=*value*] [, ERROR=*variable*]
[, /GET_LUN] [, /RAWIO] [, READ_TIMEOUT=*value*]
[, /SWAP_ENDIAN] [, /SWAP_IF_BIG_ENDIAN]
[, /SWAP_IF_LITTLE_ENDIAN] [, WIDTH=*value*]
[, WRITE_TIMEOUT=*value*]
UNIX-Only Keywords: [, /STDIO]

SORT - Returns indices of an array sorted in ascending order.

$Result = SORT(Array$ [, /L64])

SPAWN - Spawns child process for access to operating system.

SPAWN [, *Command* [, *Result*] [, *ErrResult*]]
Keywords (all platforms): [, COUNT=*variable*]
[, EXIT_STATUS=*variable*] [, /FORCE] [, PID=*variable*]
Macintosh-Only Keywords: [, MACCREATOR=*string*]
[, NO_WAIT]

UNIX-Only Keywords: [, /NOSHELL]
[, /NOTTYRESET] [, /NULL_STDIN] [, /SH]
[, /STDERR] [, /UNIT{*Command* required, *Result* not allowed}]
VMS-Only Keywords: [, /NOCLISYM]
[, /NOLOGNAM] [[, /NOTIFY] , /NOWAIT]
Windows-Only Keywords: [, /HIDE] [, /LOG_OUTPUT]
[, /NOSHELL] [, /NOWAIT] [, /NULL_STDIN]
[, /STDERR]

SPH_4PNT - Returns center and radius of a sphere given 4 points.

SPH_4PNT, *X*, *Y*, *Z*, *Xc*, *Yc*, *Zc*, *R* [, /DOUBLE]

SPH_SCAT - Performs spherical gridding.

$Result = SPH\_SCAT(Lon$, *Lat*, *F* [, BOUNDS=*[lonmin, latmin, lonmax, latmax]*] [, BOUT=*variable*]
[, GOUT=*variable*] [, GS=*[lonspacing, latspacing]*]
[, NLON=*value*] [, NLAT=*value*])

SPHER_HARM - Returns value of the spherical harmonic function.

$Result=SPHER\_HARM(Theta$, *Phi*, *L*, *M*, [, /DOUBLE])

SPL_INIT - Establishes the type of interpolating spline.

$Result = SPL\_INIT(X$, *Y* [, /DOUBLE] [, YP0=*value*]
[, YPN_1=*value*])

SPL_INTERP - Performs cubic spline interpolation.

$Result = SPL\_INTERP(X$, *Y*, *Y2*, *X2* [, /DOUBLE])

SPLINE - Performs cubic spline interpolation.

$Result = SPLINE(X$, *Y*, *T* [, *Sigma*])

SPLINE_P - Performs parametric cubic spline interpolation.

SPLINE_P, *X*, *Y*, *Xr*, *Yr* [, INTERVAL=*value*]
[, TAN0=*[X_0, Y_0]*] [, TAN1=*[X_{n-1}, Y_{n-1}]*]

SPRSAB - Performs matrix multiplication on sparse matrices.

$Result = SPRSAB(A$, *B* [, /DOUBLE]
[, THRESHOLD=*value*])

SPRSAX - Multiplies sparse matrix by a vector.

$Result = SPRSAX(A$, *X* [, /DOUBLE])

SPRSIN - Converts matrix to row-index sparse matrix.

$Result = SPRSIN(A$ [, /COLUMN] [, /DOUBLE]
[, THRESHOLD=*value*]) or
$Result = SPRSIN(Columns$, *Rows, Values, N*
[, /DOUBLE] [, THRESHOLD=*value*])

SPRSTP - Constructs the transpose of a sparse matrix.

$Result = SPRSTP(A)$

SQRT - Returns the square root of *X*.

$Result = SQRT(X)$

STANDARDIZE - Computes standardized variables.

$Result = STANDARDIZE(A$ [, /DOUBLE])

STDDEV - Computes the standard deviation of an *n*-element vector.

$Result = STDDEV(X$ [, /DOUBLE] [, /NAN])

STOP - Stops the execution of a running program or batch file.

STOP [, *Expr_1*, ..., *Expr_n*]

STRARR - Returns string array containing zero-length strings.

Result = STRARR(D_1, ..., D_8)

STRCMP - Compares two strings.

Result = STRCMP(*String1*, *String2* [, *N*]
[, /FOLD_CASE])

STRCOMPRESS - Removes whitespace from a string.

Result = STRCOMPRESS(*String* [, /REMOVE_ALL])

STREAMLINE - Generates the visualization graphics from a path.

STREAMLINE, *Verts*, *Conn*, *Normals*, *Outverts*, *Outconn*
[, ANISOTROPY=*array*] [, SIZE=*vector*]
[, PROFILE=*array*]

STREGEX - Performs regular expression matching.

Result = STREGEX(*StringExpression*, *RegularExpression*
[, /BOOLEAN | , /EXTRACT | , LENGTH=*variable*
[, /SUBEXPR]] [, /FOLD_CASE])

STRETCH - Stretches color table for contrast enhancement.

STRETCH [, *Low*, *High* [, *Gamma*]] [, /CHOP]

STRING - Converts its arguments to string type.

Result = STRING(*Expression₁*, ..., *Expressionₙ*
[, AM_PM=*[string, string]*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, FORMAT=*value*] [, MONTHS=*string_array*{12
names}] [, /PRINT])

STRJOIN - Collapses a string scalar or array into merged strings.

Result = STRJOIN(*String* [, *Delimiter*] [, /SINGLE])

STRLEN - Returns the length of a string.

Result = STRLEN(*Expression*)

STRLOWCASE - Converts a string to lower case.

Result = STRLOWCASE(*String*)

STRMATCH - Compares search string against input string expression.

Result = STRMATCH(*String*, *SearchString*
[, /FOLD_CASE])

STRMESSAGE - Returns the text of an error number.

Result = STRMESSAGE(*Err* [, /BLOCK | , /CODE | ,
/NAME])

STRMID - Extracts a substring from a string.

Result = STRMID(*Expression*, *First_Character* [, *Length*]
[, /REVERSE_OFFSET])

STRPOS - Finds first occurrence of a substring within a string.

Result = STRPOS(*Expression*, *Search String* [, *Pos*]
[, /REVERSE_OFFSET] [, /REVERSE_SEARCH])

STRPUT - Inserts the contents of one string into another.

STRPUT, *Destination*, *Source* [, *Position*]

STRSPLIT - Splits its input string argument into separate substrings, according to the specified pattern.

Result = STRSPLIT(*String* [, *Pattern*] [, ESCAPE=*string* |
, /REGEX [, /FOLD_CASE]] [, /EXTRACT |
, LENGTH=*variable*] [, /PRESERVE_NULL])

STRTRIM - Removes leading and/or trailing blanks from string.

Result = STRTRIM(*String* [, *Flag*])

STRUCT_ASSIGN - Performs "relaxed structure assignment" to copy a structure.

STRUCT_ASSIGN, *Source*, *Destination* [, /NOZERO]
[, /VERBOSE]

STRUCT_HIDE - Prevents the IDL HELP procedure from displaying information about structures or objects.

STRUCT_HIDE, *Arg₁* [, *Arg₂*, ..., *Argₙ*]

STRUPCASE - Converts a string to upper case.

Result = STRUPCASE(*String*)

SURFACE - Plots an array as a wireframe mesh surface.

SURFACE, *Z* [, *X*, *Y*] [, AX=*degrees*] [, AZ=*degrees*]
[, BOTTOM=*index*] [, /HORIZONTAL] [, /LEGO]
[, /LOWER_ONLY | , /UPPER_ONLY]
[, MAX_VALUE=*value*] [, MIN_VALUE=*value*]
[, /SAVE] [, SHADES=*array*] [, SKIRT=*value*] [, /XLOG]
[, /YLOG] [, ZAXIS={1 | 2 | 3 | 4}] [, /ZLOG]
Graphics Keywords: Accepts all graphics keywords
accepted by PLOT except for: PSYM, SYMSIZE.

SURFR - Sets up 3D transformations by duplicating rotation, translation, and scaling of SURFACE.

SURFR [, AX=*degrees*] [, AZ=*degrees*]

SVDC - Computes Singular Value Decomposition of an array.

SVDC, *A*, *W*, *U*, *V* [, /COLUMN] [, /DOUBLE]
[, ITMAX=*value*]

SVDFIT - Multivariate least squares fit using SVD method.

Result = SVDFIT(*X*, *Y* [, *M*] [, A=*vector*]
[, CHISQ=*variable*] [, COVAR=*variable*] [, /DOUBLE]
[, FUNCTION_NAME=*string*] [, /LEGENDRE]
[, MEASURE_ERRORS=*vector*] [, SIGMA=*variable*]
[, SINGULAR=*variable*] [, VARIANCE=*variable*]
[, YFIT=*variable*])

SVSOL - Solves set of linear equations using back-substitution.

Result = SVSOL(*U*, *W*, *V*, *B* [, /COLUMN] [, /DOUBLE])

SWAP_ENDIAN - Reverses the byte ordering of scalars, arrays or structures.

Result = SWAP_ENDIAN(*Variable*)

SWITCH - Selects one statement for execution from multiple choices, depending upon the value of an expression.

SWITCH expression OF
    expression: statement
    ...
    expression: statement
ELSE: statement
ENDSWITCH

SYSTIME - Returns the current time as either a date/time string, as the number of seconds elapsed since 1 January 1970, or as a Julian date/time value.

String = SYSTIME([0 [, *ElaspedSeconds*]] [, /UTC])

or

Seconds = SYSTIME(1 | /SECONDS)

or

Julian = SYSTIME(/JULIAN [, /UTC])

T

T_CVF - Computes the cutoff value in a Student's t distribution.

Result = T_CVF(*P*, *Df*)

T_PDF - Computes Student's t distribution.

Result = T_PDF(*V*, *Df*)

T3D - Performs various 3D transformations.

T3D [, *Array* | , /RESET] [, MATRIX=*variable*] [, OBLIQUE=*vector*] [, PERSPECTIVE=*p*{eye at (0,0,*p*)}] [, ROTATE=*[x, y, z]*] [, SCALE=*[x, y, z]*] [, TRANSLATE=*[x, y, z]*] [, /XYEXCH | , /XZEXCH | , /YZEXCH]

TAG_NAMES - Returns the names of tags in a structure.

Result = TAG_NAMES(*Expression* [, /STRUCTURE_NAME])

TAN - Returns the tangent of *X*.

Result = TAN(*X*)

TANH - Returns the hyperbolic tangent of X.

Result = TANH(*X*)

TAPRD - Reads the next record on a tape.

TAPRD, *Array*, *Unit* [, *Byte_Reverse*]

TAPWRT - Writes data to a tape.

TAPWRT, *Array*, *Unit* [, *Byte_Reverse*]

TEK_COLOR - Loads color table based on Tektronix printer.

TEK_COLOR [, *Start_Index*, *Colors*]

TEMPORARY - Returns a temporary copy of a variable, and sets the original variable to "undefined".

Result = TEMPORARY(*Variable*)

TETRA_CLIP - Clips a tetrahedral mesh to an arbitrary plane in space and returns a tetrahedral mesh of the remaining portion.

Result = TETRA_CLIP (*Plane*, *Vertsin*, *Connin*, *Vertsout*, *Connout* [, AUXDATA_IN=*array*, AUXDATA_OUT=*variable*] [, CUT_VERTS=*variable*])

TETRA_SURFACE - Extracts a polygonal mesh as the exterior surface of a tetrahedral mesh.

Result = TETRA_SURFACE (*Verts*, *Connin*)

TETRA_VOLUME - Computes properties of tetrahedral mesh array.

Result = TETRA_VOLUME (*Verts*, *Conn* [, AUXDATA=*array*] [, MOMENT=*variable*])

THIN - Returns the "skeleton" of a bi-level image.

Result = THIN(*Image*[, /NEIGHBOR_COUNT] [, /PRUNE])

THREED - Plots a 2D array as a pseudo 3D plot.

THREED, *A* [, *Sp*] [, TITLE=*string*] [, XTITLE=*string*] [, YTITLE=*string*]

TIME_TEST2 - Performs speed benchmarks for IDL.

TIME_TEST2 [, *Filename*]

TIMEGEN - Returns an array of double-precision floating-point values that represent times in Julian values.

Result = TIMEGEN([D1,...,D8 | , FINAL=*value*] [, DAYS=*vector*] [, HOURS=*vector*] [, MINUTES=*vector*] [, MONTHS=*vector*] [, SECONDS=*vector*] [, START=*value*] [, STEP_SIZE=*value*] [, UNITS=*string*] [, YEAR=*value*])

TM_TEST - Performs t-means test.

Result = TM_TEST(*X*, *Y* [, /PAIRED] [, /UNEQUAL])

TOTAL - Sums of the elements of an array.

Result = TOTAL(*Array* [, *Dimension*] [, /CUMULATIVE] [, /DOUBLE] [, /NAN])

TrackBall Object - See

TRACE - Computes the trace of an array.

Result = TRACE(*A* [, /DOUBLE])

TRANSPOSE - Transposes an array.

Result = TRANSPOSE(*Array* [, *P*])

TRI_SURF - Interpolates gridded set of points with a smooth quintic surface.

Result = TRI_SURF(*Z* [, *X*, *Y*] [, /EXTRAPOLATE] [, MISSING=*value*] [, /REGULAR] [, XGRID=*[xstart, xspacing]* | [, XVALUES=*array*]] [, YGRID=*[yxstart, yspacing]* | [, YVALUES=*array*]] [, GS=*[xspacing, yspacing]*] [, BOUNDS=*[xmin, ymin, xmax, ymax]*] [, NX=*value*] [, NY=*value*])

TRIANGULATE - Constructs Delaunay triangulation of a planar set of points.

TRIANGULATE, *X*, *Y*, *Triangles* [, *B*] [, CONNECTIVITY=*variable*] [, /DEGREES] [, FVALUE=*variable*] [, REPEATS=*variable*] [, SPHERE=*variable*]

TRIGRID - Interpolates irregularly-gridded data to a regular grid.

Result = TRIGRID(*X*, *Y*, *Z*, *Triangles* [, *GS*, *Limits*])

For spherical gridding: *Result* = TRIGRID(*F* , *GS*, *Limits*, SPHERE=*S*)

Keywords: [, /DEGREES] [, EXTRAPOLATE=*array* | , /QUINTIC] [, INPUT=*variable*] [, MAX_VALUE=*value*] [, MIN_VALUE=*value*] [, MISSING=*value*] [, NX=*value*] [, NY=*value*] [, SPHERE=*variable*] [, XGRID=*variable*] [, YGRID=*variable*] [, XOUT=*vector*, YOUT=*vector*]

TRIQL - Determines eigenvalues and eigenvectors of tridiagonal array.

TRIQL, *D*, *E*, *A* [, /DOUBLE]

TRIRED - Reduces a real, symmetric array to tridiagonal form.

TRIRED, *A*, *D*, *E* [, /DOUBLE]

TRISOL - Solves tridiagonal systems of linear equations.

Result = TRISOL(*A*, *B*, *C*, *R* [, /DOUBLE])

TRNLOG (VMS Only) - Searches the VMS logical name tables for a specified logical name.

Result = TRNLOG(*Lognam*, *Value* [, ACMODE={0 | 1 | 2 | 3}] [, /FULL_TRANSLATION] [, /ISSUE_ERROR] [, RESULT_ACMODE=*variable*] [, RESULT_TABLE=*variable*] [, TABLE=*string*])

TS_COEF - Computes the coefficients for autoregressive time-series.

Result = TS_COEF(*X*, *P* [, /DOUBLE] [, MSE=*variable*])

TS_DIFF - Computes the forward differences of a time-series.

Result = TS_DIFF(*X*, *K* [, /DOUBLE])

TS_FCAST - Computes future or past values of a stationary time-series.

Result = TS_FCAST(*X*, *P*, *Nvalues* [, /BACKCAST] [, /DOUBLE])

TS_SMOOTH - Computes moving averages of a time-series.

Result = TS_SMOOTH(*X*, *Nvalues* [, /BACKWARD] [, /DOUBLE] [, /FORWARD] [, ORDER=*value*])

TV - Displays an image.

TV, *Image* [, *Position*]

or

TV, *Image* [, *X*, *Y* [, *Channel*]]

Keywords: [, /CENTIMETERS | , /INCHES] [, CHANNEL=*value*] [, /ORDER] [, TRUE={1 | 2 | 3}] [, /WORDS] [, XSIZE=*value*] [, YSIZE=*value*] [, /DATA | , /DEVICE | , /NORMAL] [, /T3D | Z=*value*]

TVCRS - Manipulates the image display cursor.

TVCRS [, *ON_OFF*]

or

TVCRS [, *X*, *Y*]

Keywords: [, /CENTIMETERS | , /INCHES] [, /HIDE_CURSOR] [, /DATA | , /DEVICE | , /NORMAL] [, /T3D | Z=*value*]

TVLCT - Loads display color tables.

TVLCT, V_1, V_2, V_3 [, *Start*] [, /GET] [, /HLS | , /HSV]

or

TVLCT, *V* [, *Start*] [, /GET] [, /HLS | , /HSV]

TVRD - Reads an image from a window into a variable.

Result = TVRD([X_0 [, Y_0 [, N_x [, N_y [, *Channel*]]]]] [, CHANNEL=*value*] [, /ORDER] [, TRUE={1 | 2 | 3}] [, /WORDS])

TVSCL - Scales and displays an image.

TVSCL, *Image* [, *Position*]

or

TVSCL, *Image* [, *X*, *Y* [, *Channel*]]

Keywords: [, /CENTIMETERS | , /INCHES] [, CHANNEL=*value*] [, /NAN] [, /ORDER] [, TOP=*value*] [, TRUE={1 | 2 | 3}] [, /WORDS] [, XSIZE=*value*] [, YSIZE=*value*] [, /DATA | , /DEVICE | , /NORMAL] [, /T3D | Z=*value*]

U

UINDGEN - Returns unsigned integer array with each element set to its subscript.

Result = UINDGEN(D_1, ..., D_8)

UINT - Converts argument to unsigned integer type.

Result = UINT(*Expression*[, *Offset* [, Dim_1, ..., Dim_8]])

UINTARR - Returns an unsigned integer vector or array.

Result = UINTARR(D_1, ..., D_8 [, /NOZERO])

UL64INDGEN - Returns an unsigned 64-bit integer array with each element set to its subscript.

Result = UL64INDGEN(D_1, ..., D_8)

ULINDGEN - Returns an unsigned longword array with each element set to its subscript.

Result = ULINDGEN(D_1, ..., D_8)

ULON64ARR - Returns an unsigned 64-bit integer vector or array.

Result = ULON64ARR(D_1, ..., D_8 [, /NOZERO])

ULONARR - Returns an unsigned longword integer vector or array.

Result = ULONARR(D_1, ..., D_8 [, /NOZERO])

ULONG - Converts argument to unsigned longword integer type.

Result = ULONG(*Expression*[, *Offset* [, Dim_1, ..., Dim_8]])

ULONG64 - Converts argument to unsigned 64-bit integer type.

Result = ULONG64(*Expression*[, *Offset* [, Dim_1, ..., Dim_8]])

UNIQ - Returns subscripts of the unique elements in an array.

Result = UNIQ(*Array* [, *Index*])

USERSYM - Defines a new plotting symbol.

USERSYM, *X* [, *Y*] [, COLOR=*value*] [, /FILL] [, THICK=*value*]

V

VALUE_LOCATE - Finds the intervals within a given monotonic vector that brackets a given set of one or more search values.
Result = VALUE_LOCATE (*Vector*, *Value* [, /L64])

VARIANCE - Computes the statistical variance of an *n*-element vector.
Result = VARIANCE(*X* [, /DOUBLE] [, /NAN])

VAX_FLOAT - Determines the default value for the VAX_FLOAT keyword or if an open file unit has the VAX_FLOAT attribute set.
Result = VAX_FLOAT([*Default*] [, FILE_UNIT=*lun*])

VECTOR_FIELD - Places colored, oriented vectors of specified length at each vertex in an input vertex array.
VECTOR_FIELD, *Field*, *Outverts*, *Outconn*
[, ANISOTROPY=*array*] [, SCALE=*value*]
[, VERTICES=*array*]

VEL - Draws a velocity (flow) field with streamlines.
VEL, *U*, *V* [, NVECS=*value*] [, XMAX=
value{*xsize/ysize*}] [, LENGTH=*value*{*longest/steps*}]
[, NSTEPS=*value*] [, TITLE=*string*]

VELOVECT - Draws a 2D velocity field plot.
VELOVECT, *U*, *V* [, *X*, *Y*] [, COLOR=*index*]
[, MISSING=*value* [, /DOTS]] [, LENGTH=*value*]
[, /OVERPLOT] [Also accepts all PLOT keywords]

VERT_T3D - Transforms a 3D array by a 4x4 transformation matrix.
Result = VERT_T3D(*Vertex_List* [, /DOUBLE]
[, MATRIX=*4x4_array*] [, /NO_COPY] [, /NO_DIVIDE
[, SAVE_DIVIDE=*variable*]])

VOIGT - Calculates intensity of atomic absorption line (Voight) profile.
Result = VOIGT(*A*, *U*)

VORONOI - Computes Voronoi polygon given Delaunay triangulation.
VORONOI, *X*, *Y*, *I0*, *C*, *Xp*, *Yp*, *Rect*

VOXEL_PROJ - Generates volume visualizations using voxel technique.
Result = VOXEL_PROJ(*V* [, *RGBO*]
[, BACKGROUND=*array*] [, CUTTING_PLANE=*array*]
[, /INTERPOLATE] [, /MAXIMUM_INTENSITY]
[, STEP=*[Sx, Sy, Sz]*] [, XSIZE=*pixels*] [, YSIZE=*pixels*]
[, ZBUFFER=*int_array*] [, ZPIXELS=*byte_array*])

W

WAIT - Suspends execution of an IDL program for a specified period.
WAIT, *Seconds*

WARP_TRI - Warps an image using control points.
Result = WARP_TRI(*Xo*, *Yo*, *Xi*, *Yi*, *Image*
[, OUTPUT_SIZE=*vector*] [, /QUINTIC]
[, /EXTRAPOLATE])

WATERSHED - Applies the morphological watershed operator to a grayscale image.
Result = WATERSHED (*Image*
[, CONNECTIVITY={4 | 8}])

WDELETE - Deletes IDL graphics windows.
WDELETE [, *Window_Index* [, ...]]

WEOF - Writes an end-of-file mark on the designated tape unit.
WEOF, *Unit*

WF_DRAW - Draws weather fronts with smoothing.
WF_DRAW, *X*, *Y* [[, /COLD | , FRONT_TYPE=1] |
[, /WARM | , FRONT_TYPE=2] | [, /OCCLUDED | ,
FRONT_TYPE=3] | [, /STATIONARY | ,
FRONT_TYPE=4] | [, /CONVERGENCE | ,
FRONT_TYPE=5]] [, COLOR=*value*] [, /DATA | ,
/DEVICE | , /NORMAL] [, INTERVAL=*value*]
[, PSYM=*value*] [, SYM_HT=*value*]
[, SYM_LEN=*value*] [, THICK=*value*]

WHERE - Returns subscripts of nonzero array elements.
Result = WHERE(*Array_Expression* [, *Count*]
[, COMPLEMENT=*variable*] [, /L64]
[, NCOMPLEMENT=*variable*])

WHILE...DO - Performs statement(s) as long as expression evaluates to true. Subject is never executed if condition is initially false.
WHILE *expression* DO *statement*
or
WHILE *expression* DO BEGIN
  statements
ENDWHILE

WIDGET_BASE - Creates base widget (containers for other widgets).
Result = WIDGET_BASE([*Parent*] [, /ALIGN_BOTTOM
| , /ALIGN_CENTER | , /ALIGN_LEFT | ,
/ALIGN_RIGHT | , /ALIGN_TOP]
[, APP_MBAR=*variable*{same as mbar on Windows and
Motif} | , /MBAR | , /MODAL]
[, /BASE_ALIGN_BOTTOM | ,
/BASE_ALIGN_CENTER | , /BASE_ALIGN_LEFT | ,
/BASE_ALIGN_RIGHT | , /BASE_ALIGN_TOP]
[, /COLUMN | , /ROW] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, /EXCLUSIVE | ,
/NONEXCLUSIVE] [, /FLOATING] [, FRAME=*width*]
[, FUNC_GET_VALUE=*string*] [, /GRID_LAYOUT]
[, GROUP_LEADER=*widget_id*{must specify for modal
dialogs}] [, /KBRD_FOCUS_EVENTS]
[, KILL_NOTIFY=*string*] [, /MAP{not for modal bases}]
[, /NO_COPY] [, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SCROLL{not for modal
bases}] [, /SENSITIVE] [, SPACE=*value*{ignored if
exclusive or nonexclusive}] [, TITLE=*string*]
[, TLB_FRAME_ATTR=*value*{top-level bases only}]
[, /TLB_KILL_REQUEST_EVENTS{top-level bases

only}] [, /TLB_SIZE_EVENTS{top-level bases only}]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, XOFFSET=*value*] [, XPAD=*value*{ignored if exclusive
or nonexclusive}] [, XSIZE=*value*]
[, X_SCROLL_SIZE=*value*] [, YOFFSET=*value*]
[, YPAD=*value*{ignored if exclusive or nonexclusive}]
[, YSIZE=*value*] [, Y_SCROLL_SIZE=*value*])
X Windows Keywords: [, DISPLAY_NAME=*string*]
[, RESOURCE_NAME=*string*]
[, RNAME_MBAR=*string*]

WIDGET_BUTTON - Creates button widgets.
Result = WIDGET_BUTTON(*Parent*
[, /ALIGN_CENTER | , /ALIGN_LEFT | ,
/ALIGN_RIGHT] [, /BITMAP] [, /DYNAMIC_RESIZE]
[, EVENT_FUNC=*string*] [, EVENT_PRO=*string*]
[, FONT=*string*] [, FRAME=*width*]
[, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*] [, /HELP]
[, KILL_NOTIFY=*string*] [, /MENU] [, /NO_COPY]
[, /NO_RELEASE] [, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SENSITIVE]
[, /SEPARATOR] [, /TRACKING_EVENTS]
[, UNAME=*string*] [, UNITS={0 | 1 | 2}]
[, UVALUE=*value*] [, VALUE=*value*]
[, X_BITMAP_EXTRA=*bits*] [, XOFFSET=*value*]
[, XSIZE=*value*] [, YOFFSET=*value*] [, YSIZE=*value*])
X Windows Keywords: [, RESOURCE_NAME=*string*]

WIDGET_CONTROL - Realizes, manages, and destroys widgets.
WIDGET_CONTROL [, *Widget_ID*]
All widgets: [, BAD_ID=*variable*] [, /CLEAR_EVENTS]
[, DEFAULT_FONT=*string*{do not specify *Widget_ID*}]
[, /DELAY_DESTROY{do not specify *Widget_ID*}]
[, /DESTROY] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, FUNC_GET_VALUE=*string*]
[, GET_UVALUE=*variable*]
[, GROUP_LEADER=*widget_id*] [, /HOURGLASS{do
not specify *Widget_ID*}] [, KILL_NOTIFY=*string*]
[, /MAP] [, /NO_COPY] [, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*] [, /REALIZE]
[, /RESET{do not specify *Widget_ID*}]
[, SCR_XSIZE=*width*] [, SCR_YSIZE=*height*]
[, SEND_EVENT=*structure*] [, /SENSITIVE]
[, SET_UNAME=*string*] [, SET_UVALUE=*value*]
[, /SHOW] [, TIMER=*value*]
[, TLB_GET_OFFSET=*variable*]
[, TLB_GET_SIZE=*variable*]
[, /TLB_KILL_REQUEST_EVENTS]
[, TLB_SET_TITLE=*string*]
[, TLB_SET_XOFFSET=*value*]
[, TLB_SET_YOFFSET=*value*]
[, /TRACKING_EVENTS] [, UNITS={0 | 1 | 2}]
[, /UPDATE] [, XOFFSET=*value*] [, XSIZE=*value*]

[, YOFFSET=*value*] [, YSIZE=*value*]
widget_base: [, CANCEL_BUTTON=*widget_id*{for
modal bases}] [, DEFAULT_BUTTON=*widget_id*{for
modal bases}] [, /ICONIFY]
[, /KBRD_FOCUS_EVENTS]
[, /TLB_KILL_REQUEST_EVENTS]
widget_button: [, /BITMAP] [, /DYNAMIC_RESIZE]
[, GET_VALUE=*value*] [, /INPUT_FOCUS]
[, /SET_BUTTON] [, SET_VALUE=*value*]
[, X_BITMAP_EXTRA=*bits*]
widget_draw: [, /DRAW_BUTTON_EVENTS]
[, /DRAW_EXPOSE_EVENTS]
[, /DRAW_MOTION_EVENTS]
[, /DRAW_VIEWPORT_EVENTS]
[, DRAW_XSIZE=*integer*] [, DRAW_YSIZE=*integer*]
[, GET_DRAW_VIEW=*variable*]
[, GET_UVALUE=*variable*] [, GET_VALUE=*variable*]
[, /INPUT_FOCUS] [, SET_DRAW_VIEW=*[x, y]*]
widget_droplist: [, /DYNAMIC_RESIZE]
[, SET_DROPLIST_SELECT=*integer*]
[, SET_VALUE=*value*]
widget_label: [, /DYNAMIC_RESIZE]
[, GET_VALUE=*value*] [, SET_VALUE=*value*]
widget_list: [, SET_LIST_SELECT=*value*]
[, SET_LIST_TOP=*integer*] [, SET_VALUE=*value*]
widget_slider: [, GET_VALUE=*value*]
[, SET_SLIDER_MAX=*value*]
[, SET_SLIDER_MIN=*value*] [, SET_VALUE=*value*]
widget_table: [, ALIGNMENT={0 | 1 | 2}]
[, /ALL_TABLE_EVENTS] [, AM_PM=*[string, string]*]
[, COLUMN_LABELS=*string_array*]
[, COLUMN_WIDTHS=*array*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, /DELETE_COLUMNS{not for row_major mode}]
[, /DELETE_ROWS{not for column_major mode}]
[, /EDITABLE] [, EDIT_CELL=*[integer, integer]*]
[, FORMAT=*value*] [, GET_VALUE=*variable*]
[, INSERT_COLUMNS=*value*]
[, INSERT_ROWS=*value*] [, /KBRD_FOCUS_EVENTS]
[, MONTHS=*string_array*{12 names}]
[, ROW_LABELS=*string_array*]
[, ROW_HEIGHTS=*array*]
[, SET_TABLE_SELECT=*[left, top, right, bottom]*]
[, SET_TABLE_VIEW=*[integer, integer]*]
[, SET_TEXT_SELECT=*[integer, integer]*]
[, SET_VALUE=*value*] [, TABLE_XSIZE=*columns*]
[, TABLE_YSIZE=*rows*] [, /USE_TABLE_SELECT | ,
USE_TABLE_SELECT=*[left, top, right, bottom]*]
[, /USE_TEXT_SELECT]
widget_text: [, /ALL_TEXT_EVENTS] [, /APPEND]
[, /EDITABLE] [, GET_VALUE=*variable*]
[, /INPUT_FOCUS] [, /KBRD_FOCUS_EVENTS]
[, /NO_NEWLINE] [, SET_TEXT_SELECT=*[integer,
integer]*] [, SET_TEXT_TOP_LINE=*line_number*]
[, SET_VALUE=*value*] [, /USE_TEXT_SELECT]

WIDGET_DRAW - Creates drawable widgets.

Result = WIDGET_DRAW(*Parent* [, /APP_SCROLL]
[, /BUTTON_EVENTS] [, /COLOR_MODEL]
[, COLORS=*integer*] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, /EXPOSE_EVENTS]
[, FRAME=*width*] [, FUNC_GET_VALUE=*string*]
[, GRAPHICS_LEVEL=2]
[, GROUP_LEADER=*widget_id*]
[, KILL_NOTIFY=*string*] [, /MOTION_EVENTS]
[, /NO_COPY] [, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*] [, RENDERER={0 | 1}]
[, RESOURCE_NAME=*string*] [, RETAIN={0 | 1 | 2}]
[, SCR_XSIZE=*width*] [, SCR_YSIZE=*height*]
[, /SCROLL] [, /SENSITIVE] [, /TRACKING_EVENTS]
[, UNAME=*string*] [, UNITS={0 | 1 | 2}]
[, UVALUE=*value*] [, VALUE=*value*]
[, /VIEWPORT_EVENTS] [, XOFFSET=*value*]
[, XSIZE=*value*] [, X_SCROLL_SIZE=*width*]
[, YOFFSET=*value*] [, YSIZE=*value*]
[, Y_SCROLL_SIZE=*height*])

WIDGET_DROPLIST - Creates droplist widgets.

Result = WIDGET_DROPLIST(*Parent*
[, /DYNAMIC_RESIZE] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, FONT=*string*]
[, FRAME=*value*] [, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, KILL_NOTIFY=*string*] [, /NO_COPY]
[, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*]
[, RESOURCE_NAME=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SENSITIVE] [, TITLE=*string*]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, VALUE=*value*] [, XOFFSET=*value*] [, XSIZE=*value*]
[, YOFFSET=*value*] [, YSIZE=*value*])

WIDGET_EVENT - Returns events for the widget hierarchy.

Result = WIDGET_EVENT([*Widget_ID*])
[, BAD_ID=*variable*] [, /NOWAIT]
[, /SAVE_HOURGLASS]
UNIX Keywords: [, /YIELD_TO_TTY]

WIDGET_INFO - Obtains information about widgets.

Result = WIDGET_INFO([*Widget_ID*])
All widgets: [, /ACTIVE] [, /CHILD] [, /EVENT_FUNC]
[, /EVENT_PRO] [, FIND_BY_UNAME=*string*]
[, /GEOMETRY] [, /KBRD_FOCUS_EVENTS]
[, /MANAGED] [, /NAME] [, /PARENT] [, /REALIZED]
[, /SIBLING] [, /TRACKING_EVENTS] [, /TYPE]
[, UNITS={0 | 1 | 2}] [, /UNAME] [, /UPDATE]
[, /VALID_ID] [, /VERSION]
widget_base: [, /MODAL]
[, /TLB_KILL_REQUEST_EVENTS]
widget_button: [, /DYNAMIC_RESIZE]

widget_draw: [, /DRAW_BUTTON_EVENTS]
[, /DRAW_EXPOSE_EVENTS]
[, /DRAW_MOTION_EVENTS]
[, /DRAW_VIEWPORT_EVENTS]
widget_droplist: [, /DROPLIST_NUMBER]
[, /DROPLIST_SELECT] [, /DYNAMIC_RESIZE]
widget_label: [, /DYNAMIC_RESIZE]
widget_list: [, /LIST_MULTIPLE] [, /LIST_NUMBER]
[, /LIST_NUM_VISIBLE] [, /LIST_SELECT]
[, /LIST_TOP]
widget_slider: [, /SLIDER_MIN_MAX]
widget_table: [, /COLUMN_WIDTHS]
[, /ROW_HEIGHTS{not supported in Windows}]
[, /TABLE_ALL_EVENTS] [, /TABLE_EDITABLE]
[, /TABLE_EDIT_CELL] [, /TABLE_SELECT]
[, /TABLE_VIEW] [, /USE_TABLE_SELECT]
widget_text: [, /TEXT_ALL_EVENTS]
[, /TEXT_EDITABLE] [, /TEXT_NUMBER]
[, TEXT_OFFSET_TO_XY=*integer*] [, /TEXT_SELECT]
[, /TEXT_TOP_LINE]
[, TEXT_XY_TO_OFFSET=*[column*, *line]*]

WIDGET_LABEL - Creates label widgets.

Result = WIDGET_LABEL(*Parent* [, /ALIGN_CENTER
| , /ALIGN_LEFT | , /ALIGN_RIGHT]
[, /DYNAMIC_RESIZE] [, FONT=*string*]
[, FRAME=*width*] [, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, KILL_NOTIFY=*string*] [, /NO_COPY]
[, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*]
[, RESOURCE_NAME=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SENSITIVE]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, VALUE=*value*] [, XOFFSET=*value*] [, XSIZE=*value*]
[, YOFFSET=*value*] [, YSIZE=*value*])

WIDGET_LIST - Creates list widgets.

Result = WIDGET_LIST(*Parent*
[, EVENT_FUNC=*string*] [, EVENT_PRO=*string*]
[, FONT=*string*] [, FRAME=*width*]
[, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, KILL_NOTIFY=*string*] [, /MULTIPLE] [, /NO_COPY]
[, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*]
[, RESOURCE_NAME=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SENSITIVE]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, VALUE=*value*] [, XOFFSET=*value*] [, XSIZE=*value*]
[, YOFFSET=*value*] [, YSIZE=*value*])

WIDGET_SLIDER - Creates slider widgets.

Result = WIDGET_SLIDER(*Parent* [, /DRAG]
[, EVENT_FUNC=*string*] [, EVENT_PRO=*string*]
[, FONT=*string*] [, FRAME=*width*]
[, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, KILL_NOTIFY=*string*] [, MAXIMUM=*value*]
[, MINIMUM=*value*] [, /NO_COPY]
[, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*]
[, RESOURCE_NAME=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, SCROLL=*units*]
[, /SENSITIVE] [, /SUPPRESS_VALUE]
[, /TRACKING_EVENTS] [, TITLE=*string*]
[, UNAME=*string*] [, UNITS={0 | 1 | 2}]
[, UVALUE=*value*] [, VALUE=*value*] [, /VERTICAL]
[, XOFFSET=*value*] [, XSIZE=*value*]
[, YOFFSET=*value*] [, YSIZE=*value*])

WIDGET_TABLE - Creates table widgets.

Result = WIDGET_TABLE(*Parent* [, ALIGNMENT={0 |
1 | 2}] [, /ALL_EVENTS] [, AM_PM=*[string, string]*]
[, COLUMN_LABELS=*string_array*]
[, /COLUMN_MAJOR | , /ROW_MAJOR]
[, COLUMN_WIDTHS=*array*]
[, DAYS_OF_WEEK=*string_array*{7 names}]
[, /EDITABLE] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, FONT=*string*]
[, FORMAT=*value*] [, FRAME=*width*]
[, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, /KBRD_FOCUS_EVENTS] [, KILL_NOTIFY=*string*]
[, MONTHS=*string_array*{12 names}] [, /NO_COPY]
[, /NO_HEADERS] [, NOTIFY_REALIZE=*string*]
[, PRO_SET_VALUE=*string*]
[, /RESIZEABLE_COLUMNS]
[, /RESIZEABLE_ROWS{not supported in Windows}]
[, RESOURCE_NAME=*string*]
[, ROW_HEIGHTS=*array*{not supported in Windows}]
[, ROW_LABELS=*string_array*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SCROLL] [, /SENSITIVE]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, VALUE=*value*] [, XOFFSET=*value*] [, XSIZE=*value*]
[, X_SCROLL_SIZE=*width*] [, YOFFSET=*value*]
[, YSIZE=*value*] [, Y_SCROLL_SIZE=*height*])

WIDGET_TEXT - Creates text widgets.

Result = WIDGET_TEXT(*Parent* [, /ALL_EVENTS]
[, /EDITABLE] [, EVENT_FUNC=*string*]
[, EVENT_PRO=*string*] [, FONT=*string*]
[, FRAME=*width*] [, FUNC_GET_VALUE=*string*]
[, GROUP_LEADER=*widget_id*]
[, /KBRD_FOCUS_EVENTS] [, KILL_NOTIFY=*string*]
[, /NO_COPY] [, /NO_NEWLINE]
[, NOTIFY_REALIZE=*string*]

[, PRO_SET_VALUE=*string*]
[, RESOURCE_NAME=*string*] [, SCR_XSIZE=*width*]
[, SCR_YSIZE=*height*] [, /SCROLL] [, /SENSITIVE]
[, /TRACKING_EVENTS] [, UNAME=*string*]
[, UNITS={0 | 1 | 2}] [, UVALUE=*value*]
[, VALUE=*value*] [, /WRAP] [, XOFFSET=*value*]
[, XSIZE=*value*] [, YOFFSET=*value*] [, YSIZE=*value*])

WINDOW - Creates window for the display of graphics or text.

WINDOW [, *Window_Index*] [, COLORS=*value*]
[, /FREE] [, /PIXMAP] [, RETAIN={0 | 1 | 2}]
[, TITLE=*string*] [, XPOS=*value*] [, YPOS=*value*]
[, XSIZE=*pixels*] [, YSIZE=*pixels*]

WRITE_BMP - Writes Microsoft Windows Version 3 device independent bitmap file (.BMP).

WRITE_BMP, *Filename*, *Image*[, *R*, *G*, *B*] [, /FOUR_BIT]
[, IHDR=*structure*] [, HEADER_DEFINE=*h*{define *h*
before call}] [, /RGB]

WRITE_IMAGE - Writes an image and its color table vectors, if any, to a file of a specified type.

WRITE_IMAGE, *Filename*, *Format*, *Data* [, *Red*, *Green*,
Blue] [, /APPEND]

WRITE_JPEG - Writes JPEG file.

WRITE_JPEG [, *Filename* | , UNIT=*lun*] , *Image*
[, /ORDER] [, /PROGRESSIVE]
[, QUALITY=*value*{0 to 100}] [, TRUE={1 | 2 | 3}]

WRITE_NRIF - Writes NCAR Raster Interchange Format rasterfile.

WRITE_NRIF, *File*, *Image* [, *R*, *G*, *B*]

WRITE_PICT - Writes Macintosh PICT (version 2) bitmap file.

WRITE_PICT, *Filename* [, *Image*, *R*, *G*, *B*]

WRITE_PNG - Writes Portable Network Graphics (PNG) file.

WRITE_PNG, *Filename*, *Image*[, *R*, *G*, *B*] [, /VERBOSE]
[, TRANSPARENT=*array*] [, /ORDER]

WRITE_PPM - Writes PPM (true-color) or PGM (gray scale) file.

WRITE_PPM, *Filename*, *Image* [, /ASCII]

WRITE_SPR - Writes row-indexed sparse array structure to a file.

WRITE_SPR, *AS*, *Filename*

WRITE_SRF - Writes Sun Raster File (SRF).

WRITE_SRF, *Filename* [, *Image*, *R*, *G*, *B*] [, /ORDER]
[, /WRITE_32]

WRITE_SYLK - Writes SYLK (Symbolic Link) spreadsheet file.

Result = WRITE_SYLK(*File*, *Data*
[, STARTCOL=*column*] [, STARTROW=*row*])

WRITE_TIFF - Writes TIFF file with 1 to 3 channels.

WRITE_TIFF, *Filename* [, *Image*, *Order*] [, /APPEND]
[, RED=*value*] [, GREEN=*value*] [, BLUE=*value*]
[, COMPRESSION={0 | 1 | 2}] [, GEOTIFF=*structure*]
[, /LONG | , /SHORT | ,/FLOAT] [, PLANARCONFIG={1
| 2}] [, /VERBOSE] [, XRESOL=*pixels/inch*]
[, YRESOL=*pixels/inch*]

WRITE_WAV - Writes the audio stream to the named .WAV file.
WRITE_WAV, *Filename* , *Data* [, *Rate*]

WRITE_WAVE - Writes Wavefront Advanced Visualizer (.WAV) file.
WRITE_WAVE, *File*, *Array* [, /BIN]
[, DATANAME=*string*] [, MESHNAME=*string*]
[, /NOMESHDEF] [, /VECTOR]

WRITEU - Writes unformatted binary data to a file.
WRITEU, *Unit*, *Expr₁* ..., *Exprₙ*
[, TRANSFER_COUNT=*variable*]
VMS-Only Keywords: [, /REWRITE]

WSET - Selects the current window.
WSET [, *Window_Index*]

WSHOW - Exposes or hides the designated window.
WSHOW [, *Window_Index* [, *Show*]] [, /ICONIC]

WTN - Returns wavelet transform of the input array.
Result = WTN(*A*, *Coef* [, /COLUMN] [, /DOUBLE]
[, /INVERSE] [, /OVERWRITE])

X

XBM_EDIT - Creates, edits bitmap icons for IDL widget button labels.
XBM_EDIT [, /BLOCK] [, FILENAME=*string*]
[, GROUP=*widget_id*] [, XSIZE=*pixels*] [, YSIZE=*pixels*]

XDISPLAYFILE - Displays ASCII text file in scrolling text widget.
XDISPLAYFILE, *Filename* [, /BLOCK]
[, DONE_BUTTON=*string*] [, /EDITABLE]
[, FONT=*string*] [, GROUP=*widget_id*] [, HEIGHT=*lines*]
[, /MODAL] [, TEXT=*string or string array*]
[, TITLE=*string*] [, WIDTH=*characters*]
[, WTEXT=*variable*]

XDXF - Utility for displaying and interactively manipulating DXF objects
XDXF [, *Filename*] [, /BLOCK] [, GROUP=*widget_id*]
[, /MODAL] [, SCALE=*value*] [, /TEST]
[*keywords to XOBJVIEW*]

XFONT - Creates modal widget to select and view an X Windows font.
Result = XFONT([, GROUP=*widget_id*]
[, /PRESERVE_FONT_INFO])

XINTERANIMATE - Displays animated sequence of images.
XINTERANIMATE [, *Rate*]
Keywords for initialization: [, SET=*[sizex*, *sizey*, *nframes]*] [, /BLOCK] [, /CYCLE] [, GROUP=*widget_id*]
[, /MODAL] [, MPEG_BITRATE=*value*]
[, MPEG_IFRAME_GAP=*integer value*]
[, MPEG_MOTION_VEC_LENGTH={1 | 2 | 3}]
[, /MPEG_OPEN, MPEG_FILENAME=*string*]

[MPEG_QUALITY=*value*{0 to 100}] [, /SHOWLOAD]
[, /TRACK] [, TITLE=*string*]
Keywords for loading images: [, FRAME=*value*{0 to
(*nframes*-1)}][, IMAGE=*value*]] [, /ORDER]
[, WINDOW=*[window_num* [, *x0*, *y0*, *sx*, *sy*]*]*]
Keywords for running animations: [, /CLOSE]
[, /KEEP_PIXMAPS] [, /MPEG_CLOSE]
[, XOFFSET=*pixels*] [, YOFFSET=*pixels*]

XLOADCT - Provides GUI to interactively select and load color tables.
XLOADCT [, /BLOCK] [, BOTTOM=*value*]
[, FILE=*string*] [, GROUP=*widget_id*] [, /MODAL]
[, NCOLORS=*value*] [, /SILENT]
[, UPDATECALLBACK='*procedure_name*'
[, UPDATECBDATA=*value*]] [, /USE_CURENT]

XMANAGER - Provides event loop manager for IDL widgets.
XMANAGER [, *Name*, *ID*] [, /CATCH]
[, CLEANUP=*string*] [, EVENT_HANDLER=*procedure*]
[, GROUP_LEADER=*widget_id*] [, /JUST_REG]
[, /NO_BLOCK]

XMNG_TMPL - Template for creating widgets.
XMNG_TMPL [, /BLOCK] [, GROUP=*widget_id*]

XMTOOL - Displays tool for viewing XMANAGER widgets.
XMTOOL [, /BLOCK] [, GROUP=*widget_id*]

XOBJVIEW - Displays object viewer widget.
XOBJVIEW, *Obj* [, BACKGROUND=*[r, g, b]*]
[, /BLOCK] [, /DOUBLE_VIEW] [, GROUP=*widget_id*]
[, /MODAL] [, REFRESH=*widget_id*] [, SCALE=*value*]
[, STATIONARY=*objref(s)*] [, /TEST] [, TITLE=*string*]
[, TLB=*variable*] [, XSIZE=*pixels*] [, YSIZE=*pixels*]

XPALETTE - Displays widget used to create and modify color tables.
XPALETTE [, /BLOCK] [, GROUP=*widget_id*]
[, UPDATECALLBACK='*procedure_name*'
[, UPDATECBDATA=*value*]]

XPCOLOR - Adjusts the value of the current foreground plotting color, !P.COLOR.
XPCOLOR [, GROUP=*widget_id*]

XPLOT3D - Utility for creating and interactively manipulating 3D plots.
XPLOT3D, *X*, *Y*, *Z* [, /BLOCK] [, COLOR=*[r,g,b]*]
[, /DOUBLE_VIEW] [, GROUP=*widget_id*]
[, LINESTYLE={0 | 1 | 2 | 3 | 4 | 5 | 6}]] [, /MODAL]
[, NAME=*string*] [, /OVERPLOT] [, SYMBOL=*objref(s)*]
[, /TEST] [, THICK=*points*{1.0 to 10.0}] [, TITLE=*string*]
[, XRANGE=*[min*, *max]*] [, YRANGE=*[min*, *max]*]
[, ZRANGE=*[min*, *max]*] [, XTITLE=*string*]
[, YTITLE=*string*] [, ZTITLE=*string*]

XREGISTERED - Returns registration status of a given widget.
Result = XREGISTERED(*Name* [, /NO_SHOW])

XROI - Utility for interactively creating and obtaining information about ROIs.

XROI [, *ImageData*] [, *R*] [, *G*] [, *B*] [, /BLOCK]
[[, /FLOATING] , GROUP=*widget_ID*] [, /MODAL]
[, REGIONS_IN=*value*] [, REGIONS_OUT=*value*]
[, REJECTED=*variable*] [, RENDERER={0 | 1}]
[, ROI_COLOR=*[r, g, b] or variable*]
[, ROI_GEOMETRY=*variable*]
[, ROI_SELECT_COLOR=*[r, g, b] or variable*]
[, STATISTICS=*variable*] [, TITLE=*string*]
[, TOOLS=*string or string array*{valid values are
'Freehand Draw', 'Polygon Draw', and 'Selection'}]

XSQ_TEST - Computes Chi-square goodness-of-fit test.

Result = XSQ_TEST(*Obfreq*, *Exfreq*
[, EXCELL=*variable*] [, OBCELL=*variable*]
[, RESIDUAL=*variable*])

XSURFACE - Provides GUI to SURFACE and SHADE_SURF.

XSURFACE, *Data* [, /BLOCK] [, GROUP=*widget_id*]

XVAREDIT - Provides widget-based editor for IDL variables.

XVAREDIT, *Var* [, NAME='*variable_name*'{ignored if
variable is a structure}] [, GROUP=*widget_id*]
[, X_SCROLL_SIZE=*columns*]
[, Y_SCROLL_SIZE=*rows*]

XVOLUME - Utility for viewing and interactively manipulating volumes and isosurfaces.

XVOLUME, *Vol*, [, /BLOCK] [, GROUP=*widget_id*]
[, /INTERPOLATE] [, /MODAL] [, RENDERER={0 | 1}]
[, /REPLACE] [, SCALE=*value*] [, /TEST]
[, XSIZE=*pixels*] [, YSIZE=*pixels*]

XYOUTS - Draws text on currently-selected graphics device.

XYOUTS, [*X*, *Y*,] *String* [, ALIGNMENT=*value*{0.0 to
1.0}] [, CHARSIZE=*value*] [, CHARTHICK=*value*]
[, TEXT_AXES={0 | 1 | 2 | 3 | 4 | 5}] [, WIDTH=*variable*]
Graphics Keywords: [, CLIP=*[X$_0$, Y$_0$, X$_1$, Y$_1$]*]
[, COLOR=*value*] [, /DATA | , /DEVICE | , /NORMAL]
[, FONT=*integer*]
[, ORIENTATION=*ccw_degrees_from_horiz*]
[, /NOCLIP] [, /T3D] [, Z=*value*]

Z

ZOOM - Zooms portions of the display.

ZOOM [, /CONTINUOUS] [, FACT=*integer*] [, /INTERP]
[, /KEEP] [, /NEW_WINDOW] [, XSIZE=*value*]
[, YSIZE=*value*] [, ZOOM_WINDOW=*variable*]

ZOOM_24 - Zooms portions of true-color (24-bit) display.

ZOOM_24 [, FACT=*integer*] [, /RIGHT] [, XSIZE=*value*]
[, YSIZE=*value*]

Scientific Data Formats

CDF Routines

CDF_ATTCREATE - Creates a new attribute.
Result = CDF_ATTCREATE(*Id*, *Attribute_Name*
[, /GLOBAL_SCOPE] [, /VARIABLE_SCOPE])

CDF_ATTDELETE - Deletes attribute from specified CDF file.
CDF_ATTDELETE, *Id*, *Attribute* [, *EntryNum*]
[, /ZVARIABLE]

CDF_ATTEXISTS - Determines whether specified attribute exists.
Result = CDF_ATTEXISTS(*Id*, *Attribute* [, *EntryNum*]
[, /ZVARIABLE])

CDF_ATTGET - Reads an attribute entry from a CDF file.
CDF_ATTGET, *Id*, *Attribute*, *EntryNum*, *Value*
[, CDF_TYPE= *variable*] [, /ZVARIABLE]

CDF_ATTINQ - Obtains information about specified attribute.
CDF_ATTINQ, *Id*, *Attribute*, *Name*, *Scope*, *MaxEntry*
[, *MaxZEntry*]

CDF_ATTNUM - Returns an attribute number.
Result = CDF_ATTNUM(*Id*, *Attribute_Name*)

CDF_ATTPUT - Writes an attribute entry to a CDF file.
CDF_ATTPUT, *Id*, *Attribute*, *EntryNum*, *Value*
[, /ZVARIABLE]

CDF_ATTRENAME - Renames an existing attribute.
CDF_ATTRENAME, *Id*, *OldAttr*, *NewName*

CDF_CLOSE - Closes specified Common Data Format file.
CDF_CLOSE, *Id*

CDF_COMPRESSION - Sets or returns the compression mode for a CDF file and/or variables.
CDF_COMPRESSION, *Id*
[, GET_COMPRESSION=*variable*]
[, GET_GZIP_LEVEL=*variable*]
[, GET_VAR_COMPRESSION=*variable*]
[, GET_VAR_GZIP_LEVEL=*variable*]
[, SET_COMPRESSION={0 | 1 | 2 | 3 | 5}]
[, SET_GZIP_LEVEL=*integer*{1 to 9}]
[, SET_VAR_COMPRESSION={0 | 1 | 2 | 3 | 5}]
[, SET_VAR_GZIP_LEVEL=*integer*{1 to 9}]
[, VARIABLE=*variable name or index*] [, /ZVARIABLE]

CDF_CONTROL - Obtains or sets information for a CDF file.
CDF_CONTROL, *Id* [, ATTRIBUTE=*name or number*]
[, GET_ATTR_INFO=*variable*]
[, GET_CACHESIZE=*variable*]
[, GET_COPYRIGHT=*variable*]
[, GET_FILENAME=*variable*]
[, GET_FORMAT=*variable*]
[, GET_NEGTOPOSFP0_MODE=*variable*]

[, GET_NUMATTRS=*variable*]
[, GET_READONLY_MODE=*variable*]
[, GET_RVAR_CACHESIZE=*variable*]
[, GET_VAR_INFO=*variable*]
[, GET_ZMODE=*variable*]
[, GET_ZVAR_CACHESIZE=*variable*]
[, SET_CACHESIZE=*value*]
[, SET_EXTENDRECS=*records*]
[, SET_INITIALRECS=*records*]
[, /SET_NEGTOPOSFP0_MODE]
[, SET_PADVALUE=*value*]
[, /SET_READONLY_MODE]
[, SET_RVAR_CACHESIZE=*value*{See Note}]
[, SET_RVARS_CACHESIZE=*value*{See Note}]
[, SET_ZMODE={0 | 1 | 2}]
[, SET_ZVAR_CACHESIZE=*value*{See Note}]
[, SET_ZVARS_CACHESIZE=*value*{See Note}]
[, VARIABLE=*name or index*] [, /ZVARIABLE]
Note: Use only with MULTI_FILE CDF files

CDF_CREATE - Creates a new Common Data Format file.
Result = CDF_CREATE(*Filename*, [*Dimensions*]
[, /CLOBBER] [, /MULTI_FILE | , /SINGLE_FILE]
[, /COL_MAJOR | , /ROW_MAJOR])
Encoding Keywords (pick one):
[, /ALPHAOSF1_ENCODING]
[, /ALPHAVMSD_ENCODING]
[, /ALPHAVMSG_ENCODING]
[, /DECSTATION_ENCODING]
[, /HOST_ENCODING]
[, /HP_ENCODING]
[, /IBMRS_ENCODING]
[, /IBMPC_ENCODING]
[, /MAC_ENCODING]
[, /NETWORK_ENCODING]
[, /NEXT_ENCODING]
[, /SGI_ENCODING]
[, /SUN_ENCODING]
Decoding Keywords (pick one):
[, /ALPHAOSF1_DECODING]
[, /ALPHAVMSD_DECODING]
[, /ALPHAVMSG_DECODING]
[, /DECSTATION_DECODING]
[, /HOST_DECODING]
[, /HP_DECODING]
[, /IBMRS_DECODING]
[, /IBMPC_DECODING]
[, /MAC_DECODING]
[, /NETWORK_DECODING]
[, /NEXT_DECODING]
[, /SGI_DECODING]
[, /SUN_DECODING]

CDF_DELETE - Deletes specified Common Data Format file.
CDF_DELETE, *Id*

CDF_DOC - Gets documentation information about a CDF file.
CDF_DOC, *Id*, *Version*, *Release*, *Copyright*
[, INCREMENT=*variable*]

CDF_ENCODE_EPOCH - Encodes CDF_EPOCH variable into a string.
Result = CDF_ENCODE_EPOCH(*Epoch* [, EPOCH={0 | 1 | 2 | 3}])

CDF_EPOCH - Computes/breaks down CDF_EPOCH values.
CDF_EPOCH, *Epoch*, *Year* [, *Month*, *Day*, *Hour*, *Minute*, *Second*, *Milli*] [, /BREAKDOWN_EPOCH]
[, /COMPUTE_EPOCH]

CDF_ERROR - Returns explanation of a given status code.
Result = CDF_ERROR(*Status*)

CDF_EXISTS - Returns True if CDF data format library is supported on the current IDL platform.
Result = CDF_EXISTS( )

CDF_INQUIRE - Returns global information about CDF file.
Result = CDF_INQUIRE(*Id*)

CDF_LIB_INFO - Returns information about the CDF Library being used.
CDF_LIB_INFO [, COPYRIGHT=*variable*]
[, INCREMENT=*variable*] [, RELEASE=*variable*]
[, SUBINCREMENT=*variable*] [, VERSION=*variable*]

CDF_OPEN - Opens an existing Common Data Format file.
Result = CDF_OPEN(*Filename*)

CDF_PARSE_EPOCH - Parses input string into a double precision value properly formatted for use as CDF_EPOCH variable.
Result = CDF_PARSE_EPOCH(*Epoch_string*)

CDF_VARCREATE - Creates new variable in CDF file.
Result = CDF_VARCREATE(*Id*, *Name* [, *DimVary*]
[, /CDF_BYTE | , /CDF_CHAR | , /CDF_DOUBLE | , /CDF_EPOCH | , /CDF_FLOAT | , /CDF_INT1 | , /CDF_INT2 | , /CDF_INT4 | , /CDF_REAL4 | , /CDF_REAL8 | , /CDF_UCHAR | , /CDF_UINT1 | , /CDF_UINT2 | , /CDF_UINT4]
[, ALLOCATERECS=*records*] [, DIMENSIONS=*array*]
[, NUMELEM=*characters*] [, /REC_NOVARY | , /REC_VARY] [, /ZVARIABLE])

CDF_VARDELETE - Deletes variable from a SINGLE_FILE CDF file.
CDF_VARDELETE, *Id*, *Variable* [, /ZVARIABLE]

CDF_VARGET - Reads multiple values from CDF file variable.
CDF_VARGET, *Id*, *Variable*, *Value* [, COUNT=*vector*]
[, INTERVAL=*vector*] [, OFFSET=*vector*]
[, REC_COUNT=*records*] [, REC_INTERVAL=*value*]
[, REC_START=*record*] [, /STRING{data in CDF file must be type CDF_CHAR or CDF_UCHAR}]
[, /ZVARIABLE]

CDF_VARGET1 - Reads one value from a CDF file variable.
CDF_VARGET1, *Id*, *Variable*, *Value* [, OFFSET=*vector*]
[, REC_START=*record*] [, /STRING{data in CDF file must be type CDF_CHAR or CDF_UCHAR}]
[, /ZVARIABLE]

CDF_VARINQ - Returns structure containing information about specified variable.
Result = CDF_VARINQ(*Id*, *Variable* [, /ZVARIABLE])

CDF_VARNUM - Returns variable number associated with given variable name.
Result = CDF_VARNUM(*Id*, *VarName* [, *IsZVar*])

CDF_VARPUT - Writes value to a variable.
CDF_VARPUT, *Id*, *Variable*, *Value* [, COUNT=*vector*]
[, INTERVAL=*vector*] [, OFFSET=*vector*]
[, REC_INTERVAL=*value*] [, REC_START=*record*]
[, /ZVARIABLE]

CDF_VARRENAME - Renames existing variable.
CDF_VARRENAME, *Id*, *OldVariable*, *NewName*
[, /ZVARIABLE]

EOS Routines

EOS_EH_CONVANG - Converts angles between decimal degrees, radians, and packed degrees-minutes-seconds.
Result = EOS_EH_CONVANG(*inAngle*, *code*)

EOS_EH_GETVERSION - Retrieves the HDF-EOS version string of an HDF-EOS file.
Result = EOS_EH_GETVERSION(*fid*, *version*)

EOS_EH_IDINFO - Returns the HDF file IDs corresponding to the HDF-EOS file ID returned by EOS_SW_OPEN, EOS_GD_OPEN, or EOS_PT_OPEN.
Result = EOS_EH_IDINFO(*fid*, *HDFfid*, *sdInterfaceID*)

EOS_EXISTS - Returns True if HDF EOS format library is supported on the current IDL platform.
Result = EOS_EXISTS( )

EOS_GD_ATTACH - Attaches to the grid using the gridname parameter as the identifier.
Result = EOS_GD_ATTACH(*fid*, *gridname*)

EOS_GD_ATTRINFO - Returns number type and number of elements (count) of a grid attribute.
Result = EOS_GD_ATTRINFO(*gridID*, *attrname*, *numbertype*, *count*)

EOS_GD_CLOSE - Closes the HDF grid file.
Result = EOS_GD_CLOSE(*fid*)

EOS_GD_COMPINFO - Returns the compression code and compression parameters for a given field.
Result = EOS_GD_COMPINFO(*gridID*, *fieldname*, *compcode*, *compparm*)

EOS_GD_CREATE - Creates a grid within the file.
Result = EOS_GD_CREATE(*fid*, *gridname*, *xdimsize*, *ydimsize*, *upleftpt*, *lowrightpt*)

EOS_GD_DEFBOXREGION - Defines a longitude-latitude box region for a grid.

Result = EOS_GD_DEFBOXREGION(*gridID*, *cornerlon*, *cornerlat*)

EOS_GD_DEFCOMP - Sets the HDF field compression for subsequent grid field definitions.

Result = EOS_GD_DEFCOMP(*gridID*, *compcode* [, *compparm*])

EOS_GD_DEFDIM - Defines dimensions used by field definition routines to establish size of the field.

Result = EOS_GD_DEFDIM(*gridID*, *dimname*, *dim*)

EOS_GD_DEFFIELD - Defines data fields to be stored in the grid.

Result = EOS_GD_DEFFIELD(*gridID*, *fieldname*, *dimlist*, *numbertype* [, /MERGE])

EOS_GD_DEFORIGIN - Defines the origin of the grid data.

Result = EOS_GD_DEFORIGIN(*gridID*, *origincode*)

EOS_GD_DEFPIXREG - Defines whether the pixel center or pixel corner is used when requesting the location of a given pixel.

Result = EOS_GD_DEFPIXREG(*gridID*, *pixreg*)

EOS_GD_DEFPROJ - Defines the GCTP projection and projection parameters of the grid.

Result = EOS_GD_DEFPROJ(*gridID*, *projcode*, *zonecode*, *spherecode*, *projparm*)

EOS_GD_DEFTILE - Defines the tiling dimensions for fields defined following this function call.

Result = EOS_GD_DEFTILE(*gridID*, *tilecode* [, *tilerank*, *tiledims*])

EOS_GD_DEFTIMEPERIOD - Defines a time period for a grid.

Result = EOS_GD_DEFTIMEPERIOD(*gridID*, *periodID*, *starttime*, *stoptime*)

EOS_GD_DEFVRTREGION - Subsets on a monotonic field or contiguous elements of a dimension.

Result = EOS_GD_DEFVRTREGION(*gridID*, *regionID*, *vertObj*, *range*)

EOS_GD_DETACH - Detaches from grid interface.

Result = EOS_GD_DETACH(*gridID*)

EOS_GD_DIMINFO - Retrieves the size of the specified dimension.

Result = EOS_GD_DIMINFO(*gridID*, *dimname*)

EOS_GD_DUPREGION - Copies information stored in current region or period to a new region or period.

Result = EOS_GD_DUPREGION(*regionID*)

EOS_GD_EXTRACTREGION - Reads data into the data buffer from a subsetted region as defined by EOS_GD_DEFBOXREGION.

Result = EOS_GD_EXTRACTREGION(*gridID*, *regionID*, *fieldname*, *buffer*)

EOS_GD_FIELDINFO - Retrieves information on a specific data field.

Result = EOS_GD_FIELDINFO(*gridID*, *fieldname*, *rank*, *dims*, *numbertype*, *dimlist*)

EOS_GD_GETFILLVALUE - Retrieves fill value for specified field.

Result = EOS_GD_GETFILLVALUE(*gridID*, *fieldname*, *fillvalue*)

EOS_GD_GETPIXELS - Returns the pixel rows and columns for specified longitude/latitude pairs.

Result = EOS_GD_GETPIXELS(*gridID*, *nLonLat*, *lonVal*, *latVal*, *pixRow*, *pixCol*)

EOS_GD_GETPIXVALUES - Reads data from a data field for the specified pixels.

Result = EOS_GD_GETPIXVALUES(*gridID*, *nPixels*, *pixRow*, *pixCol*, *fieldname*, *buffer*)

EOS_GD_GRIDINFO - Returns number of rows, columns, and the location of the upper left and lower right corners of the grid image.

Result = EOS_GD_GRIDINFO(*gridID*, *xdimsize*, *ydimsize*, *upleft*, *lowright*)

EOS_GD_INQATTRS - Retrieves information about attributes defined in grid.

Result = EOS_GD_INQATTRS(*gridID*, *attrlist* [, LENGTH (OUT)=*value*])

EOS_GD_INQDIMS - Retrieves information about dimensions defined in grid.

Result = EOS_GD_INQDIMS(*gridID*, *dimname*, *dims*)

EOS_GD_INQFIELDS - Retrieves information about the data fields defined in grid.

Result = EOS_GD_INQFIELDS(*gridID*, *fieldlist*, *rank*, *numbertype*)

EOS_GD_INQGRID - Retrieves number and names of grids defined in HDF-EOS file.

Result = EOS_GD_INQGRID(*filename*, *gridlist* [, LENGTH (OUT)=*value*])

EOS_GD_INTERPOLATE - Performs bilinear interpolation on a grid field.

Result = EOS_GD_INTERPOLATE(*gridID*, *Interp*, *lonVal*, *latVal*, *fieldname*, *interpVal*)

EOS_GD_NENTRIES - Returns number of entries and descriptive string buffer size for a specified entity.

Result = EOS_GD_NENTRIES(*gridID*, *entrycode* [, LENGTH (OUT)=*value*])

EOS_GD_OPEN - Opens an existing file or creates a new file.

Result = EOS_GD_OPEN(*filename*, *access* [, /CREATE] [, /RDWR | , /READ])

EOS_GD_ORIGININFO - Retrieves origin code.

Result = EOS_GD_ORIGININFO(*gridID*, *origincode*)

EOS_GD_PIXREGINFO - Retrieves the pixel registration code.

Result = EOS_GD_PIXREGINFO(*gridID*, *pixregcode*)

EOS_GD_PROJINFO - Retrieves GCTP projection code, zone code, spheroid code, and projection parameters of the grid.

Result = EOS_GD_PROJINFO(*gridID*, *projcode*, *zonecode*, *spherecode*, *projparm*)

EOS_GD_QUERY - Returns information about a specified grid.
Result = EOS_GD_QUERY(*Filename*, *GridName*, [*Info*])

EOS_GD_READATTR - Reads attribute from a grid.
Result = EOS_GD_READATTR(*gridID*, *attrname*, *datbuf*)

EOS_GD_READFIELD - Reads data from a grid field.
Result = EOS_GD_READFIELD(*gridID*, *fieldname*, *buffer* [, EDGE=*array*] [, START=*array*] [, STRIDE=*array*])

EOS_GD_READTILE - Reads from tile within field.
Result = EOS_GD_READTILE(*gridID*, *fieldname*, *tilecoords*, *buffer*)

EOS_GD_REGIONINFO - Returns information about a subsetted region for a particular field.
Result = EOS_GD_REGIONINFO(*gridID*, *regionID*, *fieldname*, *ntype*, *rank*, *dims*, *size*, *upleftpt*, *lowrightpt*)

EOS_GD_SETFILLVALUE - Sets fill value for the specified field.
Result = EOS_GD_SETFILLVALUE(*gridID*, *fieldname*, *fillvalue*)

EOS_GD_SETTILECACHE - Sets tile cache parameters.
Result = EOS_GD_SETTILECACHE(*gridID*, *fieldname*, *maxcache*, *cachecode*)

EOS_GD_TILEINFO - Returns tiling code, tiling rank, and tiling dimensions for a given field.
Result = EOS_GD_TILEINFO(*gridID*, *fieldname*, *tilecode*, *tilerank*, *tiledims*)

EOS_GD_WRITEATTR - Writes/updates attribute in a grid.
Result = EOS_GD_WRITEATTR(*gridID*, *attrname*, *datbuf* [, COUNT=*value*] [, HDF_TYPE=*value*])

EOS_GD_WRITEFIELD - Writes data to a grid field.
Result = EOS_GD_WRITEFIELD(*gridID*, *fieldname*, *data* [, EDGE=*array*] [, START=*array*] [, STRIDE=*array*])

EOS_GD_WRITEFIELDMETA - Writes field metadata for a grid field not defined by the Grid API.
Result = EOS_GD_WRITEFIELDMETA(*gridID*, *fieldname*, *dimlist*, *numbertype*)

EOS_GD_WRITETILE - Writes a single tile of data to a field.
Result = EOS_GD_WRITETILE(*gridID*, *fieldname*, *tilecoords*, *data*)

EOS_PT_ATTACH - Attaches to point using the pointname parameter as the identifier.
Result = EOS_PT_ATTACH(*fid*, *pointname*)

EOS_PT_ATTRINFO - Returns number type and number of elements of a point attribute.
Result = EOS_PT_ATTRINFO(*pointID*, *attrname*, *numbertype*, *count*)

EOS_PT_BCKLINKINFO - Returns linkfield to the previous level.
Result = EOS_PT_BCKLINKINFO(*pointID*, *level*, *linkfield*)

EOS_PT_CLOSE - Closes the HDF point file.
Result = EOS_PT_CLOSE(*fid*)

EOS_PT_CREATE - Creates point as a Vgroup within the HDF file.
Result = EOS_PT_CREATE(*fid*, *pointname*)

EOS_PT_DEFBOXREGION - Defines area of interest for a point.
Result = EOS_PT_DEFBOXREGION(*pointID*, *cornerlon*, *cornerlat*)

EOS_PT_DEFLEVEL - Defines a level within a point.
Result = EOS_PT_DEFLEVEL(*pointID*, *levelname*, *fieldlist*, *fieldtype*, *fieldorder*)

EOS_PT_DEFLINKAGE - Defines linkfield between two levels.
Result = EOS_PT_DEFLINKAGE(*pointID*, *parent*, *child*, *linkfield*)

EOS_PT_DEFTIMEPERIOD - Defines a time period for a point.
Result = EOS_PT_DEFTIMEPERIOD(*pointID*, *starttime*, *stoptime*)

EOS_PT_DEFVRTREGION - Selects records within a point whose field values are within a given range.
Result = EOS_PT_DEFVRTREGION(*pointID*, *regionID*, *vertObj*, *range*)

EOS_PT_DETACH - Detaches from a point data set.
Result = EOS_PT_DETACH(*pointID*)

EOS_PT_EXTRACTPERIOD - Reads data from the designated level fields into the data buffer from the subsetted time period.
Result = EOS_PT_EXTRACTPERIOD(*pointID*, *periodID*, *level*, *fieldlist*, *buffer*)

EOS_PT_EXTRACTREGION - Reads data from the designated level fields into the data buffer from the subsetted area of interest.
Result = EOS_PT_EXTRACTREGION(*pointID*, *regionID*, *level*, *fieldlist*, *buffer*)

EOS_PT_FWDLINKINFO - Returns linkfield to the given level.
Result = EOS_PT_FWDLINKINFO(*pointID*, *level*, *linkfield*)

EOS_PT_GETLEVELNAME - Returns the name of a level given the level number (0-based).
Result = EOS_PT_GETLEVELNAME(*pointID*, *level*, *levelname* [, LENGTH (OUT)=*variable*])

EOS_PT_GETRECNUMS - Returns record numbers in one level that are connected to a given set of records in a different level.
Result = EOS_PT_GETRECNUMS(*pointID*, *inlevel*, *outlevel*, *inNrec*, *inRecs*, *outNrec*, *outRecs*)

EOS_PT_INQATTRS - Returns attribute list as a comma-separated string.
Result = EOS_PT_INQATTRS(*pointID*, *attrlist* [, LENGTH=*value*])

EOS_PT_INQPOINT - Retrieves number and names of points defined in HDF-EOS file.

Result = EOS_PT_INQPOINT*(filename, pointlist* [, LENGTH (OUT)=*value*])

EOS_PT_LEVELINDX - Returns the level index for a given level.

Result = EOS_PT_LEVELINDX(*pointID*, *levelname*)

EOS_PT_LEVELINFO - Returns information about the fields in a given level.

Result = EOS_PT_LEVELINFO(*pointID*, *level*, *fieldlist*, *fldtype*, *fldorder*)

EOS_PT_NFIELDS - Returns the number of fields in a level.

Result = EOS_PT_NFIELDS(*pointID*, *level* [, LENGTH=*bytes*])

EOS_PT_NLEVELS - Returns the number of levels in a point.

Result = EOS_PT_NLEVELS(*pointID*)

EOS_PT_NRECS - Returns the number of records in a given level.

Result = EOS_PT_NRECS(*pointID*, *level*)

EOS_PT_OPEN - Creates a new file or opens an existing one.

Result = EOS_PT_OPEN(*fieldname* [, /CREATE] [, /RDWR | , /READ])

EOS_PT_PERIODINFO - Returns information about a subsetted time period for a given fieldlist.

Result = EOS_PT_PERIODINFO(*pointID*, *periodID*, *level*, *fieldlist*, *size*)

EOS_PT_PERIODRECS - Returns record numbers within a subsetted time period for a given level.

Result = EOS_PT_PERIODRECS(*pointID*, *periodID*, *level*, *nrec*, *recs*)

EOS_PT_QUERY - Returns information about a specified point.

Result = EOS_PT_QUERY(*Filename*, *PointName*, [*Info*])

EOS_PT_READATTR - Reads attributes.

Result = EOS_PT_READATTR(*pointID*, *attrname*, *datbuf*)

EOS_PT_READLEVEL - Reads data from the specified fields and records of a single level in a point.

Result = EOS_PT_READLEVEL(*pointID*, *level*, *fieldlist*, *nrec*, *recs*, *buffer*)

EOS_PT_REGIONINFO - Returns information about a subsetted area of interest for a given fieldlist.

Result = EOS_PT_REGIONINFO(*pointID*, *regionID*, *level*, *fieldlist*, *size*)

EOS_PT_REGIONRECS - Returns the record numbers within a subsetted geographic region for a given level.

Result = EOS_PT_REGIONRECS(*pointID*, *regionID*, *level*, *nrec*, *recs*)

EOS_PT_SIZEOF - Returns information about specified fields in a point regardless of level.

Result = EOS_PT_SIZEOF(*pointID*, *fieldlist*, *fldlevel*)

EOS_PT_UPDATELEVEL - Updates the specified fields and records of a single level.

Result = EOS_PT_UPDATELEVEL(*pointID*, *level*, *field*, *list*, *nrec*, *recs*, *data*)

EOS_PT_WRITEATTR - Writes/updates an attribute in a point.

Result = EOS_PT_WRITEATTR(*pointID*, *attrname*, *datbuf* [, COUNT=*value*] [, HDF_TYPE=*value*])

EOS_PT_WRITELEVEL - Writes (appends) full records to a level.

Result = EOS_PT_WRITELEVEL(*pointID*, *level*, *nrec*, *data*)

EOS_QUERY - Returns information about the makeup of an HDF-EOS file.

Result = EOS_QUERY(*Filename*, [*Info*])

EOS_SW_ATTACH - Attaches to the swath using the swathname parameter as the identifier.

Result = EOS_SW_ATTACH(*fid*, *swathname*)

EOS_SW_ATTRINFO - Returns number type and number of elements of a swath attribute.

Result = EOS_SW_ATTRINFO(*swathID*, *attrname*, *numbertype*, *count*)

EOS_SW_CLOSE - Closes the HDF swath file.

Result = EOS_SW_CLOSE(*fid*)

EOS_SW_COMPINFO - Returns compression code and compression parameters for a given field.

Result = EOS_SW_COMPINFO(*swathID*, *fieldname*, *compcode*, *compparm*)

EOS_SW_CREATE - Creates a swath within the file.

Result = EOS_SW_CREATE(*fid*, *swathname*)

EOS_SW_DEFBOXREGION - Defines a longitude-latitude box region for a swath.

Result = EOS_SW_DEFBOXREGION(*swathID*, *cornerlon*, *cornerlat*, *mode*)

EOS_SW_DEFCOMP - Sets HDF field compression for subsequent swath field definitions.

Result = EOS_SW_DEFCOMP(*swathID*, *compcode*, [, *compparm*])

EOS_SW_DEFDATAFIELD - Defines geolocation fields to be stored in the swath.

Result = EOS_SW_DEFDATAFIELD(*swathID*, *fieldname*, *dimlist*, *numbertype* [, /MERGE])

EOS_SW_DEFDIM - Defines dimensions that are used by the field definition routines to establish the size of the field.

Result = EOS_SW_DEFDIM(*swathID*, *fieldname*, *dim*)

EOS_SW_DEFDIMMAP - Defines monotonic mapping between the geolocation and data dimensions.

Result = EOS_SW_DEFDIMMAP(*swathID*, *geodim*, *datadim*, *offset*, *increment*)

EOS_SW_DEFGEOFIELD - Defines geolocation fields to be stored in the swath.

Result = EOS_SW_DEFGEOFIELD(*swathID*, *fieldname*, *dimlist*, *numbertype* [, /MERGE])

EOS_SW_DEFIDXMAP - Defines mapping between a geolocation and data dimension.

Result = EOS_SW_DEFIDXMAP(*swathID*, *geodim*, *datadim*, *index*)

EOS_SW_DEFTIMEPERIOD - Defines a time period for a swath.

Result = EOS_SW_DEFTIMEPERIOD(*swathID*, *starttime* , *stoptime*, *mode*)

EOS_SW_DEFVRTREGION - Subsets along any dimension.

Result = EOS_SW_DEFVRTREGION(*swathID*, *regionID*, *vertObj*, *range*)

EOS_SW_DETACH - Detaches from the swath interface.

Result = EOS_SW_DETACH(*swathID*)

EOS_SW_DIMINFO - Retrieves the size of the specified dimension.

Result = EOS_SW_DIMINFO(*swathID*, *dimname*)

EOS_SW_DUPREGION - Copies information stored in a current region or period to a new region or period.

Result = EOS_SW_DUPREGION(*regionID*)

EOS_SW_EXTRACTPERIOD - Reads data into the data buffer from the subsetted time period.

Result = EOS_SW_EXTRACTPERIOD(*swathID*, *periodID*, *fieldname*, *external_mode*, *buffer*)

EOS_SW_EXTRACTREGION - Reads data into the data buffer from the subsetted region.

Result = EOS_SW_EXTRACTREGION(*swathID*, *regionID*, *fieldname*, *external_mode*, *buffer*)

EOS_SW_FIELDINFO - Retrieves information on a specific data field.

Result = EOS_SW_FIELDINFO(*swathID*, *fieldname*, *rank*, *dims*, *numbertype*, *dimlist*)

EOS_SW_GETFILLVALUE - Retrieves fill value for given field.

Result = EOS_SW_GETFILLVALUE(*swathID*, *fieldname*, *fillvalue*)

EOS_SW_IDXMAPINFO - Retrieves size of the indexed array and the array of indexed elements of the specified geolocation mapping.

Result = EOS_SW_IDXMAPINFO(*swathID*, *geodim*, *datadim*, *index*)

EOS_SW_INQATTRS - Retrieves information about attributes defined in swath.

Result = EOS_SW_INQATTRS(*swathID*, *attrlist* [, LENGTH (OUT)=*value*])

EOS_SW_INQDATAFIELDS - Retrieves information about all of the data fields defined in swath.

Result = EOS_SW_INQDATAFIELDS(*swathID*, *fieldlist*, *rank*, *numbertype*)

EOS_SW_INQDIMS - Retrieves information about all of the dimensions defined in swath.

Result = EOS_SW_INQDIMS(*swathID*, *dimname*, *dim*)

EOS_SW_INQGEOFIELDS - Retrieves information about all of the geolocation fields defined in swath.

Result = EOS_SW_INQGEOFIELDS(*swathID*, *fieldlist*, *rank*, *numbertype*)

EOS_SW_INQIDXMAPS - Retrieves information about all indexed geolocation/data mappings in swath.

Result = EOS_SW_INQIDXMAPS(*swathID*, *idxmap*, *idxsizes*)

EOS_SW_INQMAPS - Retrieves information about all non-indexed geolocation relations in swath.

Result = EOS_SW_INQMAPS(*swathID*, *dimmap*, *offset*, *increment*)

EOS_SW_INQSWATH - Retrieves number and names of swaths defined in HDF-EOS file.

Result = EOS_SW_INQSWATH(*filename*, *swathlist* [, LENGTH=*value*])

EOS_SW_MAPINFO - Retrieves offset and increment of the specified geolocation mapping.

Result = EOS_SW_MAPINFO(*swathID*, *geodim*, *datadim*, *offset*, *increment*)

EOS_SW_NENTRIES - Returns number of entries and descriptive string buffer size for specified entity.

Result = EOS_SW_NENTRIES(*swathID*, *entrycode* [, LENGTH (OUT)=*value*])

EOS_SW_OPEN - Opens an existing file, or creates a new file.

Result = EOS_SW_OPEN(*filename* [, /CREATE] [, /RDWR | , /READ])

EOS_SW_PERIODINFO - Returns information about a subsetted time period for a given field.

Result = EOS_SW_PERIODINFO(*swathID*, *periodID*, *fieldname*, *ntype*, *rank*, *dims*, *size*)

EOS_SW_QUERY - Returns information about a specified swath.

Result=EOS_SW_QUERY(*Filename*, *SwathName*, [*Info*])

EOS_SW_READATTR - Reads attribute from a swath field.

Result = EOS_SW_READATTR(*swathID*, *attrname*, *datbuf*)

EOS_SW_READFIELD - Reads data from a swath field.

Result = EOS_SW_READFIELD(*swathID*, *fieldname*, *buffer* [, EDGE=*array*] [, START=*array*] [, STRIDE=*array*])

EOS_SW_REGIONINFO - Returns information about a subsetted region for a given field.

Result = EOS_SW_REGIONINFO(*swathID*, *regionID*, *fieldname*, *ntype*, *rank*, *dims*, *size*)

EOS_SW_SETFILLVALUE - Sets fill value for the specified field.

Result = EOS_SW_SETFILLVALUE(*swathID*, *fieldname*, *fillvalue*)

EOS_SW_WRITEATTR - Writes/updates attribute in a swath.
Result = EOS_SW_WRITEATTR(*swathID*, *attrname*, *datbuf* [, COUNT=*value*] [, HDF_TYPE=*value*])

EOS_SW_WRITEDATAMETA - Writes field metadata for an existing data field.
Result = EOS_SW_WRITEDATAMETA(*swathID*, *fieldname*, *dimlist*, *numbertype*)

EOS_SW_WRITEFIELD - Writes data to a swath field.
Result = EOS_SW_WRITEFIELD(*swathID*, *fieldname*, *cut*, *data* [, EDGE=*array*] [, START=*array*] [, STRIDE=*array*])

EOS_SW_WRITEGEOMETA - Writes field metadata for an existing geolocation field.
Result = EOS_SW_WRITEGEOMETA(*swathID*, *fieldname*, *dimlist*, *numbertype*)

HDF Routines

HDF_AN_ANNLEN - Returns number of characters in annotation.
Result = HDF_AN_ANNLEN(*ann_id*)

HDF_AN_ANNLIST - Obtains a list of annotation identifiers.
Result = HDF_AN_ANNLIST(*an_id*, *annot_type*, *obj_tag*, *obj_ref*, *ann_list*)

HDF_AN_ATYPE2TAG - Returns HDF tag corresponding to given annotation type.
Result = HDF_AN_ATYPE2TAG(*annot_type*)

HDF_AN_CREATE - Creates HDF AN annotation.
Result = HDF_AN_CREATE(*an_id*, *obj_tag*, *obj_ref*, *annot_type*)

HDF_AN_CREATEF - Creates file annotation.
Result = HDF_AN_CREATEF(*an_id*, *annot_type*)

HDF_AN_END - Terminates access to the HDF AN interface.
HDF_AN_END, *an_id*

HDF_AN_ENDACCESS - Terminates access to an annotation.
HDF_AN_ENDACCESS, *ann_id*

HDF_AN_FILEINFO - Retrieves total number of annotations and stores them in the appropriate parameters.
Result = HDF_AN_FILEINFO(*an_id*, *n_file_labels*, *n_file_descs*, *n_data_labels*, *n_data_descs*)

HDF_AN_GET_TAGREF - Retrieves HDF tag and reference number of annotation.
Result = HDF_AN_GET_TAGREF(*an_id*, *index*, *annot_type*, *ann_tag*, *ann_ref*)

HDF_AN_ID2TAGREF - Retrieves HDF tag/reference number pair of annotation.
Result = HDF_AN_ID2TAGREF(*ann_id*, *ann_tag*, *ann_ref*)

HDF_AN_NUMANN - Returns total number of annotations of a given type.
Result = HDF_AN_NUMANN(*an_id*, *annot_type*, *obj_tag*, *obj_ref*)

HDF_AN_READANN - Reads specified annotation.
Result = HDF_AN_READANN(*ann_id*, *annotation* [, LENGTH=*characters*])

HDF_AN_SELECT - Obtains identifier of specified annotation.
Result = HDF_AN_SELECT(*an_id*, *index*, *annot_type*)

HDF_AN_START - Initializes interface for specified file.
Result = HDF_AN_START(*file_id*)

HDF_AN_TAG2ATYPE - Returns annotation type of corresponding HDF tag.
Result = HDF_AN_TAG2ATYPE(*ann_tag*)

HDF_AN_TAGREF2ID - Returns ID of annotation with given tag.
Result = HDF_AN_TAGREF2ID(*an_id*, *ann_tag*, *ann_ref*)

HDF_AN_WRITEANN - Writes annotation text.
Result = HDF_AN_WRITEANN(*ann_id*, *annotation* [, LENGTH=*characters*])

HDF_BROWSER - See "HDF_BROWSER" on page 29.

HDF_CLOSE - Closes HDF file associated with the given file handle.
HDF_CLOSE, *FileHandle*

HDF_DELDD - Deletes tag or reference from list of data descriptors.
HDF_DELDD, *FileHandle*, *Tag*, *Ref*

HDF_DF24_ADDIMAGE - Writes 24-bit raster image to HDF file.
HDF_DF24_ADDIMAGE, *Filename*, *Image* [, /FORCE_BASELINE{useful only if QUALITY<25}] [, /JPEG | , /RLE] [, QUALITY=*value*{0 to 100}]

HDF_DF24_GETIMAGE - Reads 24-bit raster image from HDF file.
HDF_DF24_GETIMAGE, *Filename*, *Image* [, /LINE | , /PIXEL | , /PLANE]

HDF_DF24_GETINFO - Retrieves information about the current 24-bit HDF image.
HDF_DF24_GETINFO, *Filename*, *Width*, *Height*, *Interlace*

HDF_DF24_LASTREF - Returns reference number of most recently read or written 24-bit image in an HDF file.
Result = HDF_DF24_LASTREF( )

HDF_DF24_NIMAGES - Returns the number of 24-bit images in an HDF file.
Result = HDF_DF24_NIMAGES(*Filename*)

HDF_DF24_READREF - Sets reference number of image in an HDF file.
HDF_DF24_READREF, *Filename*, *Refno*

HDF_DF24_RESTART - Causes next call to
HDF_DF24_GETIMAGE to read first 24-bit image in the HDF
file.
HDF_DF24_RESTART

HDF_DFAN_ADDFDS - Adds file description to HDF file.
HDF_DFAN_ADDFDS, *Filename*, *Description*

HDF_DFAN_ADDFID - Adds file annotation to HDF file.
HDF_DFAN_ADDFID, *Filename*, *Label*

HDF_DFAN_GETDESC - Reads description for given tag and ref-
erence number in HDF file.
HDF_DFAN_GETDESC, *Filename*, *Tag*, *Ref*, *Description*
[, /STRING]

HDF_DFAN_GETFDS - Reads next available file description.
HDF_DFAN_GETFDS, *Filename*, *Description* [, /FIRST]
[, /STRING]

HDF_DFAN_GETFID - Reads next available file annotation.
HDF_DFAN_GETFID, *Filename*, *Label* [, /FIRST]

HDF_DFAN_GETLABEL - Reads label for given tag-reference
pair.
HDF_DFAN_GETLABEL, *Filename*, *Tag*, *Ref*, *Label*

HDF_DFAN_LABLIST - Retrieves list of reference numbers and
labels for given tag.
Result = HDF_DFAN_LABLIST(*Filename*, *Tag*, *Reflist*,
Labellist [, LISTSIZE=*value*] [, MAXLABEL=*value*]
[, STARTPOS=*value*] [, /STRING])

HDF_DFAN_LASTREF - Returns reference number of most
recently read or written annotation.
Result = HDF_DFAN_LASTREF( )

HDF_DFAN_PUTDESC - Writes description for given tag and ref-
erence number.
HDF_DFAN_PUTDESC, *Filename*, *Tag*, *Ref*, *Description*

HDF_DFAN_PUTLABEL - Writes label for given tag and refer-
ence number.
HDF_DFAN_PUTLABEL, *Filename*, *Tag*, *Ref*, *Label*

HDF_DFP_ADDPAL - Appends palette to a HDF file.
HDF_DFP_ADDPAL, *Filename*, *Palette*

HDF_DFP_GETPAL - Reads next available palette from HDF file.
HDF_DFP_GETPAL, *Filename*, *Palette*

HDF_DFP_LASTREF - Returns reference number of most recently
read or written palette in HDF file.
Result = HDF_DFP_LASTREF( )

HDF_DFP_NPALS - Returns number of palettes present in HDF
file.
Result = HDF_DFP_NPALS(*Filename*)

HDF_DFP_PUTPAL - Appends palette to a HDF file.
HDF_DFP_PUTPAL, *Filename*, *Palette* [, /DELETE]
[, /OVERWRITE]

HDF_DFP_READREF - Sets reference number of the palette.
HDF_DFP_READREF, *Filename*, *Refno*

HDF_DFP_RESTART - Causes next call to HDF_DFR8_GETPAL
to read from the first palette in HDF file.
HDF_DFP_RESTART

HDF_DFP_WRITEREF - Sets reference number for next palette to
be written to a HDF file.
HDF_DFP_WRITEREF, *Filename*, *Refno*

HDF_DFR8_ADDIMAGE - Appends 8-bit raster image to the spec-
ified HDF file.
HDF_DFR8_ADDIMAGE, *Filename*, *Image*
[, /FORCE_BASELINE{useful only if QUALITY<25}]
[, /JPEG | , /RLE] [[, /IMCOMP] , PALETTE=*vector or
array*] [, QUALITY=*value*]

HDF_DFR8_GETIMAGE - Retrieves image, palette from HDF file.
HDF_DFR8_GETIMAGE, *Filename*, *Image* [, *Palette*]

HDF_DFR8_GETINFO - Retrieves information about the current 8-
bit HDF image.
HDF_DFR8_GETINFO, *Filename*, *Width*, *Height*,
Has_Palette

HDF_DFR8_LASTREF - Returns reference number of the most
recently read or written 8-bit image in HDF file.
Result = HDF_DFR8_LASTREF( )

HDF_DFR8_NIMAGES - Returns number of 8-bit images in speci-
fied HDF file.
Result = HDF_DFR8_NIMAGES(*Filename*)

HDF_DFR8_PUTIMAGE - Writes 8-bit raster image as first image
in HDF file.
HDF_DFR8_PUTIMAGE, *Filename*, *Image*
[, /FORCE_BASELINE{useful only if QUALITY<25}]
[[, /IMCOMP] , PALETTE=*vector or array*] [, /JPEG | ,
/RLE] [, QUALITY=*value*]

HDF_DFR8_READREF - Sets reference number of image to be
read from a HDF file by the next call to HDF_DFR8_GETIMAGE.
HDF_DFR8_READREF, *Filename*, *Refno*

HDF_DFR8_RESTART - Causes next call to
HDF_DFR8_GETIMAGE to read from first image in HDF file.
HDF_DFR8_RESTART

HDF_DFR8_SETPALETTE - Sets current palette to be used for
subsequent images in a HDF file.
HDF_DFR8_SETPALETTE, *Palette*

HDF_DUPDD - Generates new references to existing data in HDF file.
HDF_DUPDD, *FileHandle*, *NewTag*, *NewRef*, *OldTag*,
OldRef

HDF_EXISTS - Returns True if HDF format library is supported on
the current IDL platform.
Result = HDF_EXISTS( )

HDF_GR_ATTRINFO - Retrieves information about specified HDF
data object.
Result = HDF_GR_ATTRINFO(*obj_id*, *attr_index*, *name*,
data_type, *count*)

HDF_GR_CREATE - Creates HDF GR raster image.
Result = HDF_GR_CREATE(*gr_id*, *name*, *ncomp*, *data_type*, *interlace_mode*, *dim_sizes*)

HDF_GR_END - Terminates specified HDF GR interface session.
HDF_GR_END, *gr_id*

HDF_GR_ENDACCESS - Terminates access to specified raster image.
HDF_GR_ENDACCESS, *ri_id*

HDF_GR_FILEINFO - Retrieves number of raster images and global attributes for the specified HDF GR interface.
Result = HDF_GR_FILEINFO(*gr_id*, *n_images*, *n_file_attrs*)

HDF_GR_FINDATTR - Finds index of HDF data object's attribute given its attribute name.
Result = HDF_GR_FINDATTR(*obj_id*, *attr_name*)

HDF_GR_GETATTR - Obtains all values of HDF GR attribute.
Result = HDF_GR_GETATTR(*obj_id*, *attr_index*, *values*)

HDF_GR_GETCHUNKINFO - Retrieves chunking information about HDF GR raster image.
Result = HDF_GR_GETCHUNKINFO(*ri_id*, *dim_length*, *flag*)

HDF_GR_GETIMINFO - Retrieves general information about HDF GR raster image.
Result = HDF_GR_GETIMINFO(*ri_id*, *gr_name*, *ncomp*, *data_type*, *interlace_mode*, *dim_sizes*, *num_attrs*)

HDF_GR_GETLUTID - Gets identifier of HDF GR palette.
Result = HDF_GR_GETLUTID(*ri_id*, *pal_index*)

HDF_GR_GETLUTINFO - Retrieves information about a palette.
Result = HDF_GR_GETLUTINFO(*pal_id*, *ncomp*, *data_type*, *interlace_mode*, *num_entries*)

HDF_GR_IDTOREF - Returns HDF reference number of specified raster image.
Result = HDF_GR_IDTOREF(*ri_id*)

HDF_GR_LUTTOREF - Returns HDF reference number of the specified palette.
Result = HDF_GR_LUTTOREF(*pal_id*)

HDF_GR_NAMETOINDEX - Returns index of raster image given its name
Result = HDF_GR_NAMETOINDEX(*gr_id*, *gr_name*)

HDF_GR_READIMAGE - Reads subsample of raster image.
Result = HDF_GR_READIMAGE(*ri_id*, *data* [, EDGE=*array*] [, /INTERLACE] [, START=*array*] [, STRIDE=*array*])

HDF_GR_READLUT - Reads specified palette.
Result = HDF_GR_READLUT(*pal_id*, *pal_data* [, /INTERLACE])

HDF_GR_REFTOINDEX - Returns index of specified raster image.
Result = HDF_GR_REFTOINDEX(*gr_id*, *gr_ref*)

HDF_GR_SELECT - Obtains identifier of specified raster image.
Result = HDF_GR_SELECT(*gr_id*, *index*)

HDF_GR_SETATTR - Attaches attribute to specified object.
Result = HDF_GR_SETATTR(*obj_id*, *attr_name*, *data_type*, *count*, *values*)

HDF_GR_SETCHUNK - Makes specified raster image a chunked raster image.
Result = HDF_GR_SETCHUNK(*ri_id*, *dim_length*, *comp_type*, *comp_prm*)

HDF_GR_SETCHUNKCACHE - Sets maximum number of chunks to be cached.
Result = HDF_GR_SETCHUNKCACHE(*ri_id*, *maxcache*, *flags*)

HDF_GR_SETCOMPRESS - Specifies whether specified raster image will be stored in compressed format.
Result = HDF_GR_SETCOMPRESS(*ri_id*, *comp_type*, *comp_prm*)

HDF_GR_SETEXTERNALFILE - Specifies that raster image will be written to external file.
Result = HDF_GR_SETEXTERNALFILE(*ri_id*, *filename*, *offset*)

HDF_GR_START - Initializes interface for the specified file.
Result = HDF_GR_START(*file_id*)

HDF_GR_WRITEIMAGE - Writes subsample of raster image data.
Result = HDF_GR_WRITEIMAGE(*ri_id*, *data* [, EDGE=*array*] [, INTERLACE={0 | 1 | 2}] [, START=*array*] [, STRIDE=*array*])

HDF_GR_WRITELUT - Writes a palette.
Result = HDF_GR_WRITELUT(*pal_id*, *pal_data* [, DATA_TYPE=*value*] [, INTERLACE_MODE={0 | 1 | 2}] [, NENTRIES=*value*])

HDF_HDF2IDLTYPE - Converts HDF data type code into IDL variable type code.
Result = HDF_HDF2IDLTYPE(*hdftypecode*)

HDF_IDL2HDFTYPE - Converts IDL variable type code into HDF data type code.
Result = HDF_IDL2HDFTYPE(*idltypecode*)

HDF_ISHDF - Determines whether specified file is HDF file.
Result = HDF_ISHDF(*Filename*)

HDF_LIB_INFO - Returns information about the HDF Library being used.
HDF_LIB_INFO, [*FileHandle*] [, MAJOR=*variable*] [, MINOR=*variable*] [, RELEASE=*variable*] [, VERSION=*variable*]

HDF_NEWREF - Returns next available reference number for HDF file.
Result = HDF_NEWREF(*FileHandle*)

HDF_NUMBER - Returns number of tags in HDF file or the number of references associated with a given tag.
Result = HDF_NUMBER(*FileHandle* [, TAG=*integer*])

HDF_OPEN - Opens or creates HDF file for reading and/or writing.

Result = HDF_OPEN(*Filename* [, /ALL] [, /CREATE]
[, NUM_DD=*value*] [, /RDWR] [, /READ] [, /WRITE])

HDF_PACKDATA - Packs a set IDL variable into an array of raw byte data.

Result = HDF_PACKDATA(*data1* [, *data2* [, *data3*
[, *data4* [, *data5* [, *data6* [, *data7* [, *data8*]]]]]]]
[, HDF_ORDER=*array*] [, HDF_TYPE=*array*]
[, NREC=*records*])

HDF_READ - See "HDF_READ" on page 29.

HDF_SD_ADDDATA - Writes hyperslab of values to an SD dataset.

HDF_SD_ADDDATA, *SDS_ID*, *Data* [, COUNT=*vector*]
[, /NOREVERSE] [, START=*vector*] [, STRIDE=*vector*]

HDF_SD_ATTRFIND - Locates index of HDF attribute given its name.

Result = HDF_SD_ATTRFIND(*S_ID*, *Name*)

HDF_SD_ATTRINFO - Reads or retrieves information about SD attribute.

HDF_SD_ATTRINFO, *S_ID*, *Attr_Index*
[, COUNT=*variable*] [, DATA=*variable*]
[, HDF_TYPE=*variable*] [, NAME=*variable*]
[, TYPE=*variable*]

HDF_SD_ATTRSET - Writes attributes to an open HDF SD dataset.

HDF_SD_ATTRSET, *S_ID*, *Attr_Name*, *Values* [, *Count*]
[, /BYTE] [, /DFNT_CHAR] [, /DFNT_FLOAT32]
[, /DFNT_FLOAT64] [, /DFNT_INT8] [, /DFNT_INT16]
[, /DFNT_INT32] [, /DFNT_UINT8] [, /DFNT_UINT16]
[, /DFNT_UINT32] [, /DOUBLE] [, /FLOAT] [, /INT]
[, /LONG] [, /SHORT] [, /STRING]

HDF_SD_CREATE - Creates and defines a Scientific Dataset for an HDF file.

Result = HDF_SD_CREATE(*SD_ID*, *Name*, *Dims*
[, /BYTE] [, /DFNT_CHAR] [, /DFNT_FLOAT32]
[, /DFNT_FLOAT64] [, /DFNT_INT8] [, /DFNT_INT16]
[, /DFNT_INT32] [, /DFNT_UINT8] [, /DFNT_UINT16]
[, /DFNT_UINT32] [, /DOUBLE] [, /FLOAT]
[, HDF_TYPE=*type*] [, /INT] [, /LONG] [, /SHORT]
[, /STRING])

HDF_SD_DIMGET - Retrieves info. about SD dataset dimension.

HDF_SD_DIMGET, *Dim_ID* [, /COUNT]
[, COMPATIBILITY=*variable*] [, /FORMAT] [, /LABEL]
[, /NAME] [, /NATTR] [, /SCALE] [, /TYPE] [, /UNIT]

HDF_SD_DIMGETID - Returns dimension ID given a dataset "SDS_ID" and dimension number.

Result = HDF_SD_DIMGETID(*SDS_ID*,
Dimension_Number)

HDF_SD_DIMSET - Sets scale and data strings for SD dimension.

HDF_SD_DIMSET, *Dim_ID* [, /BW_INCOMP]
[, FORMAT=*string*] [, LABEL=*string*] [, NAME=*string*]
[, SCALE=*vector*] [, UNIT=*string*]

HDF_SD_END - Closes SD interface to an HDF file.

HDF_SD_END, *SD_ID*

HDF_SD_ENDACCESS - Closes SD dataset interface.

HDF_SD_ENDACCESS, *SD_ID*

HDF_SD_FILEINFO - Retrieves the number of datasets and global attributes in HDF file.

HDF_SD_FILEINFO, *SD_ID*, *Datasets*, *Attributes*

HDF_SD_GETDATA - Retrieves a hyperslab of values from SD dataset.

HDF_SD_GETDATA, *SDS_ID*, *Data* [, COUNT=*vector*]
[, /NOREVERSE] [, START=*vector*] [, STRIDE=*vector*]

HDF_SD_GETINFO - Retrieves information about SD dataset.

HDF_SD_GETINFO, *SDS_ID* [, CALDATA=*variable*]
[, COORDSYS=*variable*] [, DIMS=*variable*]
[, FILL=*variable*] [, FORMAT=*variable*]
[, HDF_TYPE=*variable*] [, LABEL=*variable*]
[, NAME=*variable]* [, NATTS=*variable*]
[, NDIMS=*variable*] [, /NOREVERSE]
[, RANGE=*variable*] [, TYPE=*variable*]
[, UNIT=*variable*]

HDF_SD_IDTOREF - Converts SD data set ID into SD data set reference number.

Result = HDF_SD_IDTOREF(*SDS_ID*)

HDF_SD_ISCOORDVAR - Determines whether supplied dataset ID represents NetCDF "coordinate" variable.

Result = HDF_SD_ISCOORDVAR(*SDS_ID*)

HDF_SD_NAMETOINDEX - Returns SD dataset index given its name and SD interface ID.

Result = HDF_SD_NAMETOINDEX(*SD_ID*,
SDS_Name)

HDF_SD_REFTOINDEX - Returns SD dataset index given its reference number and SD interface ID.

Result = HDF_SD_REFTOINDEX(*SD_ID*, *Refno*)

HDF_SD_SELECT - Returns SD dataset ID.

Result = HDF_SD_SELECT(*SD_ID*, *Number*)

HDF_SD_SETCOMPRESS - Compresses an existing HDF SD dataset or sets the compression method of a new HDF SD dataset.

HDF_SD_SETCOMPRESS, *SDS_ID*, *comptype*
[, EFFORT=*integer*{1 to 9}]

HDF_SD_SETEXTFILE - Moves data values from a dataset into an external file.

HDF_SD_SETEXTFILE, *SDS_ID*, *Filename*
[, OFFSET=*bytes*]

HDF_SD_SETINFO - Sets information about SD dataset.

HDF_SD_SETINFO, *SDS_ID* [, FILL=*value*]
[, FORMAT=*string*] [, LABEL=*string*]
[, RANGE=*[max*, *min]*] [, UNIT=*string*]
[, COORDSYS=*string*] [, CALDATA=*structure*]

HDF_SD_START - Opens or creates HDF file and initializes SD interface.

Result = HDF_SD_START(*Filename* [, /READ | , /RDWR] [, /CREATE])

HDF_UNPACKDATA - Unpacks array of byte data into IDL variables.

HDF_UNPACKDATA, *packeddata*, *data1* [, *data2* [, *data3* [, *data4* [, *data5* [, *data6* [, *data7* [, *data8*]]]]]]] [, HDF_ORDER=*array*] [, HDF_TYPE=*array*] [, NREC=*records*]

HDF_VD_ATTACH - Accesses a VData with the given ID.

Result = HDF_VD_ATTACH(*FileHandle*, *VDataId* [, /READ] [, /WRITE])

HDF_VD_DETACH - Called when done accessing a VData.

HDF_VD_DETACH, *VData*

HDF_VD_FDEFINE - Adds new field specification for VData.

HDF_VD_FDEFINE, *VData*, *Fieldname* [, /BYTE | , /DLONG, | , /DOUBLE | , /DULONG | , /FLOAT | , /INT | , /LONG | , /UINT, | , /ULONG] [, ORDER=*value*]

HDF_VD_FEXIST - Returns true if specified fields exist in HDF file.

Result = HDF_VD_FEXIST(*VData*, *Fieldnames*)

HDF_VD_FIND - Returns reference number of specified VData.

Result = HDF_VD_FIND(*FileHandle*, *Name*)

HDF_VD_GET - Returns information about a VData.

HDF_VD_GET, *VData* [, CLASS=*variable*] [, COUNT=*variable*] [, FIELDS=*variable*] [, INTERLACE=*variable*] [, NAME=*variable*] [, NFIELDS=*variable*] [, REF=*variable*] [, SIZE=*variable*] [, TAG=*variable*]

HDF_VD_GETID - Returns VData reference number for next VData.

Result = HDF_VD_GETID(*FileHandle*, *VDataId*)

HDF_VD_GETINFO - Returns information about each Vdata field.

HDF_VD_GETINFO, *VData*, *Index* [, NAME=*variable*] [, ORDER=*variable*] [, SIZE=*variable*] [, TYPE=*variable*]

HDF_VD_GETNEXT - Returns reference number of the next object inside a VData.

Result = HDF_VD_GETNEXT(*VData*, *Id*)

HDF_VD_INSERT - Adds VData or VGroup to contents of VGroup.

HDF_VD_INSERT, *VGroup*, *VData(or Vgroup)*[, POSITION=*variable*]

HDF_VD_ISVD - Returns True (1) if an object is a VData.

Result = HDF_VD_ISVD(*VGroup*, *Id*)

HDF_VD_ISVG - Returns True (1) if object is a VGroup.

Result = HDF_VG_ISVG(*VGroup*, *Id*)

HDF_VD_LONE - Returns array containing all VDatas that are not contained in another VData.

Result = HDF_VD_LONE(*FileHandle* [, MAXSIZE=*value*])

HDF_VD_READ - Reads data from a VData.

Result = HDF_VD_READ(*VData*, *Data* [, FIELDS=*string*] [, /FULL_INTERLACE | , /NO_INTERLACE] [, NRECORDS=*records*])

HDF_VD_SEEK - Moves read pointer in specified VData to specific record number.

HDF_VD_SEEK, *VData*, *Record*

HDF_VD_SETINFO - Specifies general information about a VData.

HDF_VD_SETINFO, *VData* [, CLASS=*string*] [, /FULL_INTERLACE | , /NO_INTERLACE] [, NAME=*string*]

HDF_VD_WRITE - Stores data in a VData

HDF_VD_WRITE, *VData*, *Fields*, *Data* [, /FULL_INTERLACE | , /NO_INTERLACE] [, NRECORDS=*records*]

HDF_VG_ADDTR - Adds tag and reference to specified VGroup.

HDF_VG_ADDTR, *VGroup*, *Tag*, *Ref*

HDF_VG_ATTACH - Attaches (opens) a VGroup.

Result = HDF_VG_ATTACH(*FileHandle*, *VGroupId* [, /READ] [, /WRITE])

HDF_VG_DETACH - Called when finished accessing a VGroup.

HDF_VG_DETACH, *VGroup*

HDF_VG_GETID - Returns VGroup ID for specified VGroup.

Result = HDF_VG_GETID(*FileHandle*, *VGroupId*)

HDF_VG_GETINFO - Returns information about a VGroup.

HDF_VG_GETINFO, *VGroup* [, CLASS=*variable*] [, NAME=*variable*] [, NENTRIES=*variable*] [, REF=*variable*] [, TAG=*variable*]

HDF_VG_GETNEXT - Returns reference number of the next object in a VGroup.

Result = HDF_VG_GETNEXT(*VGroup*, *Id*)

HDF_VG_GETTR - Returns tag/reference pair at specified position within a VGroup.

HDF_VG_GETTR, *VGroup*, *Index*, *Tags*, *Refs*

HDF_VG_GETTRS - Returns tag/reference pairs of HDF file objects belonging to the specified VGroup.

HDF_VG_GETTRS, *VGroup*, *Tags*, *Refs* [, MAXSIZE=*value*]

HDF_VG_INQTR - Returns true if specified tag/reference pair is linked to the specified Vgroup.

Result = HDF_VG_INQTR(*VGroup*, *Tag*, *Ref*)

HDF_VG_INSERT - Adds VData or VGroup to contents of VGroup.

HDF_VG_INSERT, *VGroup*, *VData(or Vgroup)*[, POSITION=*variable*]

HDF_VG_ISVD - Returns true if object is a VData.

Result = HDF_VG_ISVD(*VGroup*, *Id*)

HDF_VG_ISVG - Returns true if object is a VGroup.

Result = HDF_VG_ISVG(*VGroup*, *Id*)

HDF_VG_LONE - Returns array containing IDs of all VGroups that are not contained in another VGroup.

Result = HDF_VG_LONE(*FileHandle* [, MAXSIZE=*value*])

HDF_VG_NUMBER - Returns number of HDF file objects in specified VGroup.

Result = HDF_VG_NUMBER(*VGroup*)

HDF_VG_SETINFO - Sets the name and class of a VGroup.

HDF_VG_SETINFO, *VGroup* [, CLASS=*string*] [, NAME=*string*]

NetCDF Routines

NCDF_ATTCOPY - Copies attribute from one netCDF file to another.

Result = NCDF_ATTCOPY(*Incdf* [, *Invar* | , /IN_GLOBAL] , *Name*, *Outcdf* [, *Outvar*] [, /OUT_GLOBAL])

NCDF_ATTDEL - Deletes an attribute from a netCDF file.

NCDF_ATTDEL, *Cdfid* [, *Varid* / , /GLOBAL] , *Name*

NCDF_ATTGET - Retrieves value of an attribute from a netCDF file.

NCDF_ATTGET, *Cdfid* [, *Varid* | , /GLOBAL] , *Name*, *Value*

NCDF_ATTINQ - Returns information about a netCDF attribute.

Result = NCDF_ATTINQ(*Cdfid* [, *Varid* | , /GLOBAL] , *Name*)

NCDF_ATTNAME - Returns the name of an attribute given its ID.

Result = NCDF_ATTNAME(*Cdfid* [, *Varid* | , /GLOBAL] , *Attnum*)

NCDF_ATTPUT - Creates an attribute in a netCDF file.

NCDF_ATTPUT, *Cdfid* [, *Varid* | , /GLOBAL] , *Name* , *Value* [, LENGTH=*value*] [, /BYTE | , /CHAR | , /DOUBLE | , /FLOAT | , /LONG | , /SHORT]

NCDF_ATTRENAME - Renames an attribute in a netCDF file.

NCDF_ATTRENAME, *Cdfid* [, *Varid* | , /GLOBAL] *Oldname*, *Newname*

NCDF_CLOSE - Closes an open netCDF file.

NCDF_CLOSE, *Cdfid*

NCDF_CONTROL - Performs miscellaneous netCDF operations.

NCDF_CONTROL, *Cdfid* [, /ABORT] [, /ENDEF] [, /FILL | , /NOFILL] [, /NOVERBOSE | , /VERBOSE] [, OLDFILL=*variable*] [, /REDEF] [, /SYNC]

NCDF_CREATE - Creates a new netCDF file.

Result = NCDF_CREATE(*Filename* [, /CLOBBER | , /NOCLOBBER])

NCDF_DIMDEF - Defines a dimension given its name and size.

Result = NCDF_DIMDEF(*Cdfid*, *DimName*, *Size* [, /UNLIMITED])

NCDF_DIMID - Returns the ID of a netCDF dimension, given the name of the dimension.

Result = NCDF_DIMID(*Cdfid*, *DimName*)

NCDF_DIMINQ - Retrieves the name and size of a dimension in a netCDF file, given its ID.

NCDF_DIMINQ, *Cdfid*, *Dimid*, *Name*, *Size*

NCDF_DIMRENAME - Renames an existing dimension in a netCDF file that has been opened for writing.

NCDF_DIMRENAME, *Cdfid*, *Dimid*, *NewName*

NCDF_EXISTS - Returns True if the netCDF format library is supported on the current IDL platform.

Result = NCDF_EXISTS( )

NCDF_INQUIRE - Returns information about an open netCDF file.

Result = NCDF_INQUIRE(*Cdfid*)

NCDF_OPEN - Opens an existing netCDF file.

Result = NCDF_OPEN(*Filename* [, /NOWRITE | , /WRITE])

NCDF_VARDEF - Adds a new variable to an open netCDF file in define mode.

Result = NCDF_VARDEF(*Cdfid*, *Name* [, *Dim*] [, /BYTE | , /CHAR | , /DOUBLE | , /FLOAT | , /LONG | , /SHORT])

NCDF_VARGET - Retrieves a hyperslab of values from a netCDF variable.

NCDF_VARGET, *Cdfid*, *Varid*, *Value* [, COUNT=*vector*] [, OFFSET=*vector*] [, STRIDE=*vector*]

NCDF_VARGET1 - Retrieves one element from a netCDF variable.

NCDF_VARGET1, *Cdfid*, *Varid*, *Value* [, OFFSET=*vector*]

NCDF_VARID - Returns the ID of a netCDF variable.

Result = NCDF_VARID(*Cdfid*, *Name*)

NCDF_VARINQ - Returns information about a netCDF variable, given its ID.

Result = NCDF_VARINQ(*Cdfid*, *Varid*)

NCDF_VARPUT - Writes a hyperslab of values to a netCDF variable.

NCDF_VARPUT, *Cdfid*, *Varid*, *Value* [, COUNT=*vector*] [, OFFSET=*vector*] [, STRIDE=*vector*]

NCDF_VARRENAME - Renames a netCDF variable.

NCDF_VARRENAME, *Cdfid*, *Varid*, *Name*

Objects

This section lists all IDL objects and their methods. In addition to the syntax conventions discussed in "IDL Syntax Conventions" on page 16, note the following:

- The *Object_Name*::Init method for each object has keywords that are followed by either {Get}, {Set}, or {Get, Set}. Properties retrievable via *Object_Name*::GetProperty are indicated by {Get}; properties settable via *Object_Name*::SetProperty are indicated by {Set}. Properties that are both retrievable and settable are indicated by {Get, Set}. Do not include the braces, Get, or Set in your call.

- Each object's Cleanup method lists two possible syntaxes. The second syntax (*Obj->Object_Name*::Cleanup) can be used only in a subclass' Cleanup method.

- Some objects have Init methods that list two possible syntaxes. The second syntax (*Obj->Object_Name*::Init) can be used only in a subclass' Init method.

IDL_Container - Object used to hold other objects. No superclasses. Subclasses: IDLgrModel IDLgrScene IDLgrView IDLgrViewgroup.

IDL_Container::Add - Adds a child object to the container.
Obj -> [IDL_Container::]Add,*Object* [POSITION=*index*]

IDL_Container::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj->*
[IDL_Container::]Cleanup

IDL_Container::Count - Returns the number of objects contained by the container object.
Result = Obj -> [IDL_Container::]Count( )

IDL_Container::Get - Returns an array of object references to objects in a container.
Result = Obj -> [IDL_Container::]Get(
[, /ALL [, ISA=*class_name(s)*] | , POSITION=*index*]
[COUNT=*variable*])

IDL_Container::Init - Initializes the container object.
Obj = OBJ_NEW('IDL_Container')
Result = Obj -> [IDL_Container::]Init( )

IDL_Container::IsContained - Returns true (1) if the specified object is in the container, or false (0) otherwise.
Result = Obj -> [IDL_Container::]IsContained(*Object*
[, POSITION=*variable*])

IDL_Container::Move - Moves an object from one position in a container to a new position.
Obj -> [IDL_Container::]Move, *Source*, *Destination*

IDL_Container::Remove - Removes an object from the container.
Obj -> [IDL_Container::]Remove [, *Child_object* | ,
POSITION=*index* | , /ALL]

IDLanROI - Represents a region of interest. Superclass of IDLgrROI.

IDLanROI::AppendData - Appends vertices to the region.
Obj->[IDLanROI::]AppendData, *X* [, *Y*] [, *Z*]
[, XRANGE=*variable*] [, YRANGE=*variable*]
[, ZRANGE=*variable*]

IDLanROI::Cleanup - Performs all cleanup for the object.
Obj->[IDLanROI::]Cleanup or OBJ_DESTROY, *Obj*

IDLanROI::ComputeGeometry - Computes the geometrical values for area, perimeter, and/or centroid of the region.
Result = Obj->[IDLanROI::]ComputeGeometry(
[, AREA=*variable*] [, CENTROID=*variable*]
[, PERIMETER=*variable*] [, SPATIAL_OFFSET=*vector*]
[, SPATIAL_SCALE=*vector*])

IDLanROI::ComputeMask - Prepares a two-dimensional mask for the region.
Result = Obj->[IDLanROI::]ComputeMask(
[, INITIALIZE={ –1 | 0 | 1 }]
[, DIMENSIONS=*[xdim, ydim]*] | [, MASK_IN=*array*]
[, LOCATION=*[x, y [, z]]*] [, MASK_RULE={ 0 | 1 | 2 }]
[, PLANE_NORMAL=*[x, y, z]*]
[, PLANE_XAXIS=*[x,y,z]*])

IDLanROI::ContainsPoints - Determines whether the given data coordinates are contained within the closed polygon region.
Result = Obj->[IDLanROI::]ContainsPoints(*X* [, *Y* [, *Z*]])

IDLanROI::GetProperty - Retrieves the value of a property or group of properties for the region.
Obj->[IDLanROI::]GetProperty [, ALL=*variable*]
[, N_VERTS=*variable*] [, ROI_XRANGE=*variable*]
[, ROI_YRANGE=*variable*] [, ROI_ZRANGE=*variable*]

IDLanROI::Init - Initializes a region of interest object.
Obj = OBJ_NEW('IDLanROI' [, *X* [, *Y* [, *Z*]]]
[, BLOCKSIZE{Get, Set}=*vertices*] [, DATA{Get,
Set}=*array*] [, DOUBLE{Get, Set}=*value*]
[, /INTERIOR{Get, Set}] [, TYPE{Get}={ 0 | 1 | 2 }])
or
Result = Obj -> [IDLanROI::]Init([*X* [, *Y* [, *Z*]]])

IDLanROI::RemoveData - Removes vertices from the region.

Obj–>[IDLanROI::]RemoveData[, COUNT=*vertices*]
[, START=*index*] [, XRANGE=*variable*]
[, YRANGE=*variable*] [, ZRANGE=*variable*]

IDLanROI::ReplaceData - Replaces vertices in the region with alternate values.

Obj–>[IDLanROI::]ReplaceData, *X*[, *Y*[, *Z*]]
[, START=*index*] [, FINISH=*index*]
[, XRANGE=*variable*] [, YRANGE=*variable*]
[, ZRANGE=*variable*]

IDLanROI::Rotate - Modifies the vertices for the region by applying a rotation.

Obj–>[IDLanROI::]Rotate, *Axis*, *Angle*
[, CENTER=*[x, y[, z]]*]

IDLanROI::Scale - Modifies the vertices for the region by applying a scale.

Obj–>[IDLanROI::]Scale, *Sx*[, *Sy*[, *Sz*]]

IDLanROI::SetProperty - Sets the value of a property or group of properties for the region.

Obj–>[IDLanROI::]SetProperty

IDLanROI::Translate - Modifies the vertices for the region by applying a translation.

Obj–>[IDLanROI::]Translate, *Tx*[, *Ty*[, *Tz*]]

IDLanROIGroup - This object is an analytical representation of a group of regions of interest. Subclass of IDL_Container. Superclass of IDLgrROIGroup.

IDLanROIGroup::Add - Adds a region to the region group.

Obj–>[IDLanROIGroup::]Add, *ROI*

IDLanROIGroup::Cleanup - Performs all cleanup for the object.

OBJ_DESTROY, *Obj*

or *Obj*–>[IDLanROIGroup::]Cleanup

IDLanROIGroup::ContainsPoints - Determines whether the given points (in data coordinates) are contained within the closed polygon regions within this group.

Result = *Obj*–>[IDLanROIGroup::]ContainsPoints(
X[, *Y*[, *Z*]])

IDLanROIGroup::ComputeMask - Prepares a 2-D mask for this group of regions.

Result = *Obj*–>[IDLanROIGroup::]ComputeMask(
[, INITIALIZE={ –1 | 0 | 1 }]
[, DIMENSIONS=*[xdim, ydim]*] | [, MASK_IN=*array*]
[, LOCATION=*[x, y [, z]]*] [, MASK_RULE={ 0 | 1 | 2 }])

IDLanROIGroup::ComputeMesh - Triangulates a surface mesh with optional capping from the stack of regions contained within this group.

Result = *Obj*->[IDLanROIGroup::]ComputeMesh(
Vertices, *Conn* [, CAPPED={ 0 | 1 | 2}]
[, SURFACE_AREA=*variable*])

IDLanROIGroup::GetProperty - Retrieves the value of a property or group of properties for the region group.

Obj–>[IDLanROIGroup::]GetProperty[, ALL=*variable*]
[, ROIGROUP_XRANGE=*variable*]

[, ROIGROUP_YRANGE=*variable*]
[, ROIGROUP_ZRANGE=*variable*]

IDLanROIGroup::Init - Initializes a region of interest group object.

Obj = OBJ_NEW('IDLanROIGroup') or
Result = *Obj*–>[IDLanROIGroup::]Init( )

IDLanROIGroup::Rotate - Modifies the vertices for all regions within the group by applying a rotation.

Obj–>[IDLanROIGroup::]Rotate, *Axis*,
Angle[, CENTER=*[x, y[, z]]*]

IDLanROIGroup::Scale - Modifies the vertices for the region by applying a scale.

Obj–>[IDLanROIGroup::]Scale, *Sx*[, *Sy*[, *Sz*]]

IDLanROIGroup::Translate - Modifies the vertices of all regions within the group by applying a translation.

Obj–>[IDLanROIGroup::]Translate, *Tx*[, *Ty*[, *Tz*]]

IDLffDICOM - Contains the data for one or more images embedded in a DICOM part 10 file. No superclasses. No subclasses.

IDLffDICOM::Cleanup - Destroys the IDLffDICOM object.

OBJ_DESTROY, *Obj*

or

OBJ –> [IDLffDICOM::]Cleanup

IDLffDICOM::DumpElements - Dumps a description of the DICOM data elements of IDLffDICOM object to the screen or to a file.

Obj –> [IDLffDICOM::]DumpElements [, *Filename*]

IDLffDICOM::GetChildren - Finds the member element references of a DICOM sequence.

array = *Obj* –> [IDLffDICOM::]GetChildren(*Reference*)

IDLffDICOM::GetDescription - Takes optional DICOM group and element arguments and returns array of STRING descriptions.

array = *Obj* –> [IDLffDICOM::]GetDescription([*Group*
[, *Element*]] [, REFERENCE=*list of element references*])

IDLffDICOM::GetElement - Takes optional DICOM group and/or element arguments and returns an array of DICOM Element numbers for those parameters.

array = *Obj* –> [IDLffDICOM::]GetElement([*Group*
[, *Element*]] [, REFERENCE=*list of element references*])

IDLffDICOM::GetGroup - Takes optional DICOM group and/or element arguments and returns an array of DICOM Group numbers for those parameters.

array = *Obj* –> [IDLffDICOM::]GetGroup([*Group*
[, *Element*]] [, REFERENCE=*list of element references*])

IDLffDICOM::GetLength - Takes optional DICOM group and/or element arguments and returns an array of LONGs.

array = *Obj* –> [IDLffDICOM::]GetLength([*Group*
[, *Element*]] [, REFERENCE=*list of element references*])

IDLffDICOM::GetParent - Finds the parent references of a set of elements in a DICOM sequence.

array = *Obj* ->[IDLffDICOM::]GetParent(*ReferenceList*)

IDLffDICOM::GetPreamble - Returns the preamble of a DICOM v3.0 Part 10 file.

array = *Obj* –> [IDLffDICOM::]GetPreamble( )

IDLffDICOM::GetReference - Takes optional DICOM group and/or element arguments and returns an array of references to matching elements in the object.

array = Obj −> [IDLffDICOM::]GetReference([*Group* [, *Element*]] [, DESCRIPTION=*string*] [, VR=*DICOM VR string*])

IDLffDICOM::GetValue - Takes optional DICOM group and/or element arguments and returns an array of POINTERs to the values of the elements matching those parameters.

ptrArray = Obj −> [IDLffDICOM::]GetValue([*Group* [, *Element*]] [, REFERENCE=*list of element references*] [, /NO_COPY])

IDLffDICOM::GetVR - Takes optional DICOM group and/or element arguments and returns an array of VR (Value Representation) STRINGs for those parameters.

array = Obj −> [IDLffDICOM::]GetVR([*Group* [, *Element*]] [, REFERENCE=*list of references*])

IDLffDICOM::Init - Creates a new IDLffDICOM object and optionally reads the specified file as defined in the IDLffDICOM::Read method.

Result = OBJ_NEW('IDLffDICOM' [, *Filename*] [, /VERBOSE]) or

Result = Obj −> [IDLffDICOM::]Init([, *Filename*] [, /VERBOSE])

IDLffDICOM::Read - Opens and reads from the specified disk file, places the information into the DICOM object, then closes the file.

result = Obj −> [IDLffDICOM::]Read(*Filename* [, ENDIAN={1 | 2 | 3 | 4}])

IDLffDICOM::Reset - Removes all of the elements from the IDLffDICOM object, leaving the object otherwise intact.

Obj −> [IDLffDICOM::]Reset

IDLffDXF - Object that contains geometry, connectivity, and attributes for graphics primitives. No superclasses. No subclasses.

IDLffDXF::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* −> [IDLffDXF::]Cleanup

IDLffDXF::GetContents - Returns the DXF entity types contained in the object.

Result = Obj−> [IDLffDXF::]GetContents([*Filter*] [BLOCK=*string*] [, COUNT=*variable*] [LAYER=*string*])

IDLffDXF::GetEntity - Returns an array of vertex data for the requested entity type.

Result = Obj−> [IDLffDXF::]GetEntity(*Type* [, BLOCK=*string*] [, INDEX=*value*] [, LAYER=*string*])

IDLffDXF::GetPalette - Returns current color table in the object.

Obj−> [IDLffDXF::]GetPalette, *Red*, *Green*, *Blue*

IDLffDXF::Init - Initializes the DXF object.

Result = OBJ_NEW('IDLffDXF' [, *Filename*]) or

Result = Obj −> [IDLffDXF::]Init([*Filename*])

IDLffDXF::PutEntity - Inserts an entity into the DXF object.

Obj −> [IDLffDXF::]PutEntity, *Data*

IDLffDXF::Read - Reads a file, parsing the DXF object information contained in the file, and inserts it into itself.

Result = Obj−> [IDLffDXF::]Read(*Filename*)

IDLffDXF::RemoveEntity - Removes the specified entity or entities from the DXF object.

Obj −> [IDLffDXF::]RemoveEntity[, *Type*] [, INDEX=*value*]

IDLffDXF::Reset - Removes all the entities from the DXF object.

Obj−> [IDLffDXF::]Reset

IDLffDXF::SetPalette - Sets the current color table in the object.

Obj−> [IDLffDXF::]SetPalette, *Red*, *Green*, *Blue*

IDLffDXF::Write - Writes a file for the DXF entity information this object contains.

Result = Obj−> [IDLffDXF::]Write(*Filename*)

IDLffLanguageCat - Provides an interface to IDL language catalog files.

IDLffLanguageCat::IsValid - Determines whether the object has a valid catalog.

Result = Obj −>[IDLffLanguageCat::]IsValid( )

IDLffLanguageCat::Query - Returns the language string associated with the given key.

Result = Obj −>[IDLffLanguageCat::]Query(*key* [, DEFAULT_STRING=*string*])

IDLffLanguageCat::SetCatalog - Sets appropriate catalog file.

Result = Obj −>[IDLffLanguageCat::]SetCatalog(*application* [, FILENAME=*string*] [, LOCALE=*string*] [, PATH=*string*])

IDLffShape - Contains geometry, connectivity and attributes for graphics primitives accessed from ESRI Shapefiles. No superclass. No subclasses.

IDLffShape::AddAttribute - Adds an attribute to a shapefile.

Obj->[IDLffShape::]AddAttribute, *Name*, *Type*, *Width* [, PRECISION=*integer*]

IDLffShape::Cleanup - Performs all cleanup on a Shapefile object.

OBJ_DESTROY, *Obj* or *Obj* -> [IDLffShape::]Cleanup

IDLffShape::Close - Closes a Shapefile.

Obj->[IDLffShape::]Close

IDLffShape::DestroyEntity - Frees memory associated with the entity structure.

Obj->[IDLffShape::]DestroyEntity, *Entity*

IDLffShape::GetAttributes - Retrieves the attributes for the entities you specify from a Shapefile.

Result = Obj->[IDLffShape::]GetAttributes([*Index*] [, /ALL] [, /ATTRIBUTE_STRUCTURE])

IDLffShape::GetEntity - Returns an array of entity structures from a Shapefile.

Result = Obj->[IDLffShape::]GetEntity([*Index*] [, /ALL] [, /ATTRIBUTES])

IDLffShape::GetProperty - Returns the values of properties associated with a Shapefile object.

Obj->[IDLffShape::]GetProperty

[, N_ENTITIES=*variable*] [, ENTITY_TYPE=*variable*]

[, N_ATTRIBUTES=*variable*]

[, ATTRIBUTE_NAMES=*variable*]

[, ATTRIBUTE_INFO=*variable*] [, IS_OPEN=*variable*]

[, FILENAME=*variable*]

IDLffShape::Init - Initializes or constructs a Shapefile object.

Result = OBJ_NEW('IDLffShape' [, *Filename*]

[, /UPDATE] [, ENTITY_TYPE='*Value*')

IDLffShape::Open - Opens a specified Shapefile.

Result = *Obj*->[IDLffShape::]Open(*'Filename'*

[, /UPDATE] [, ENTITY_TYPE='*value*'])

IDLffShape::PutEntity - Inserts an entity into the Shapefile object.

Obj->[IDLffShape::]PutEntity, *Data*

IDLffShape::SetAttributes - Modifies the attributes for a specified entity in a Shapefile object.

Obj->[IDLffShape::]SetAttributes, *Index*, *Attribute_Num*, *Value*

or

Obj->[IDLffShape::]SetAttributes, *Index*, *Attributes*

IDLgrAxis - Represents a single vector that may include a set of tick marks, tick labels, and a title. No superclasses. No subclasses.

IDLgrAxis::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrAxis::]Cleanup

IDLgrAxis::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.

Result = *Obj* –> [IDLgrAxis::]GetCTM(

[, DESTINATION=*objref*] [, PATH=*objref(s)*]

[, TOP=*objref*])

IDLgrAxis::GetProperty - Retrieves the value of a property or group of properties for the axis.

Obj –> [IDLgrAxis::]GetProperty [, ALL=*variable*]

[, CRANGE=*variable*] [, PARENT=*variable*]

[, XRANGE=*variable*] [, YRANGE=*variable*]

[, ZRANGE=*variable*]

Note: See also the {Get} properties in IDLgrAxis::Init

IDLgrAxis::Init - Initializes an axis object.

Obj = OBJ_NEW('IDLgrAxis' [, *Direction*]

[, AM_PM{Get, Set}=*array*] [, COLOR{Get, Set}=*index or RGB_vector*] [, DAYS_OF_WEEK{Get, Set}=*array*]

[, DIRECTION{Get, Set}=*integer*] [, /EXACT{Get, Set}]

[, /EXTEND{Get, Set}] [, GRIDSTYLE{Get, Set}=*integer*{0 to 6}or *[repeat*{1 to 255}, *bitmask]*]

[, /HIDE{Get, Set}] [, LOCATION{Get, Set}=*[x, y]* or *[x, y, z]*] [, /LOG{Get, Set}] [, MAJOR{Get, Set}=*integer*]

[, MINOR{Get, Set}=*integer*] [, MONTHS{Get, Set}=*array*] [, NAME{Get, Set}=*string*]

[, /NOTEXT{Get, Set}] [, PALETTE{Get, Set}=*objref*]

[, RANGE{Get, Set}=*[min, max]*] [, SUBTICKLEN{Get, Set}=*value*] [, TEXTALIGNMENTS{Get, Set}=*[horiz*{0.0 to 1.0}, *vert*{0.0 to 1.0}*]*]

[, TEXTBASELINE{Get, Set}=*vector*] [, TEXTPOS{Get, Set}={0 | 1}] [, TEXTUPDIR{Get, Set}=*vector*]

[, THICK{Get, Set}=*points*{1.0 to 10.0}]

[, TICKDIR{Get, Set}={0 | 1}] [, TICKFORMAT{Get, Set}=*string or array of strings*]

[, TICKFRMTDATA{Get, Set}=*value*]

[, TICKINTERVAL{Get, Set}=*value*]

[, TICKLAYOUT{Get, Set}=*scalar*] [, TICKLEN{Get, Set}=*value*] [, TICKTEXT{Get, Set}=*objref or vector*]

[, TICKUNITS{Get, Set}=*string or a vector of strings*]

[, TICKVALUES{Get, Set}=*vector*] [, TITLE{Get, Set}=*objref*] [, /USE_TEXT_COLOR{Get, Set}]

[, UVALUE{Get, Set}=*value*] [, XCOORD_CONV{Get, Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]

[, ZCOORD_CONV{Get, Set}=*vector*])

or

Result = *Obj* –> [IDLgrAxis::]Init([*Direction*])

IDLgrAxis::SetProperty - Sets the value of a property or group of properties for the axis.

Obj –> [IDLgrAxis::]SetProperty

Note: See also the {Set} properties in IDLgrAxis::Init

IDLgrBuffer - An in-memory, off-screen destination object. No superclasses. No subclasses.

IDLgrBuffer::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrBuffer::]Cleanup

IDLgrBuffer::Draw - Draws picture to this graphics destination.

Obj –> [IDLgrBuffer::]Draw [, *Picture*]

[, CREATE_INSTANCE={1 | 2}]

[, /DRAW_INSTANCE]

IDLgrBuffer::Erase - Erases this graphics destination.

Obj –> [IDLgrBuffer::]Erase [, COLOR=*index or RGB vector*]

IDLgrBuffer::GetContiguousPixels - Returns an array of long integers whose length is equal to the number of colors available in the index color mode (value of the N_COLORS property).

Return = *Obj* –> [IDLgrBuffer::]GetContiguousPixels( )

IDLgrBuffer::GetDeviceInfo - Returns information that allows IDL applications to make decisions for optimal performance.

Obj–>[IDLgrBuffer::]GetDeviceInfo [, ALL=*variable*]

[, MAX_TEXTURE_DIMENSIONS=*variable*]

[, MAX_VIEWPORT_DIMENSIONS=*variable*]

[, NAME=*variable*] [, NUM_CPUS=*variable*]

[, VENDOR=*variable*] [, VERSION=*variable*]

IDLgrBuffer::GetFontnames - Returns the list of available fonts that can be used in IDLgrFont objects.

Return = *Obj* –> [IDLgrBuffer::]GetFontnames(

FamilyName[, IDL_FONTS={0 | 1 | 2 }]

[, STYLES=*string*])

IDLgrBuffer::GetProperty - Retrieves the value of a property or group of properties for the buffer.

Obj –> [IDLgrBuffer::]GetProperty [, ALL=*variable*]

[, IMAGE_DATA=*variable*]

[, SCREEN_DIMENSIONS=*variable*]
[, ZBUFFER_DATA=*variable*]
Note: See also the {Get} properties in IDLgrBuffer::Init

IDLgrBuffer::GetTextDimensions - Retrieves the dimensions of a text object that will be rendered in the buffer.
Result = Obj –>[IDLgrBuffer::]GetTextDimensions(
TextObj [, DESCENT=*variable*] [, PATH=*objref(s)*])

IDLgrBuffer::Init - Initializes the buffer object.
Obj = OBJ_NEW('IDLgrBuffer'
[, COLOR_MODEL{Get}={0|1}] [, DIMENSIONS{Get,
Set}=*[width*, *height]*] [, GRAPHICS_TREE{Get,
Set}=*objref*] [, N_COLORS{Get}=*integer*{2 to 256}]
[, PALETTE{Get, Set}=*objref*] [, QUALITY{Get,
Set}={0|1|2}] [, RESOLUTION{Get, Set}=*[xres*, *yres]*]
[, UNITS{Get, Set}={0|1|2|3}] [, UVALUE{Get,
Set}=*value*])
or
Result = Obj –> [IDLgrBuffer::]Init( )

IDLgrBuffer::PickData - Maps a point in the 2D device space of the buffer to a point in the 3D data space of an object tree.
Result = Obj –> [IDLgrBuffer::]PickData(*View*, *Object*,
Location, *XYZLocation* [, PATH=*objref(s)*])

IDLgrBuffer::Read - Reads an image from a buffer.
Result = Obj –> [IDLgrBuffer::]Read( )

IDLgrBuffer::Select - Returns a list of objects selected at a specified location.
Result = Obj –> [IDLgrBuffer::]Select(*Picture, XY*
[, DIMENSIONS=*[width*, *height]*]
[, UNITS={0|1|2|3}])

IDLgrBuffer::SetProperty - Sets the value of a property or group of properties for the buffer.
Obj –> [IDLgrBuffer::]SetProperty
Note: See also the {Set} properties in IDLgrBuffer::Init

IDLgrClipboard - A destination object representing the native clipboard. No superclasses. No Subclasses.

IDLgrClipboard::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY,*Obj* or *Obj*–
>[IDLgrClipboard::]Cleanup

IDLgrClipboard::Draw - Draws a picture to a graphics destination.
Obj –> [IDLgrClipboard::]Draw [, *Picture*]
[, FILENAME=*string*] [, POSTSCRIPT=*value*]
[, VECTOR={ 0|1 }]

IDLgrClipboard::GetContiguousPixels - Returns array of long integers whose length is equal to the number of colors available in the index color mode (value of the N_COLORS property).
Return = Obj –>[IDLgrClipboard::]GetContiguousPixels()

IDLgrClipboard::GetDeviceInfo - Returns information that allows IDL applications to make decisions for optimal performance.
Obj–>[IDLgrClipboard::]GetDeviceInfo [, ALL=*variable*]
[, MAX_TEXTURE_DIMENSIONS=*variable*]

[, MAX_VIEWPORT_DIMENSIONS=*variable*]
[, NAME=*variable*] [, NUM_CPUS=*variable*]
[, VENDOR=*variable*] [, VERSION=*variable*]

IDLgrClipboard::GetFontnames - Returns the list of available fonts that can be used in IDLgrFont objects.
Return = Obj –> [IDLgrClipboard::]GetFontnames(
FamilyName [, IDL_FONTS={0|1|2}]
[, STYLES=*string*])

IDLgrClipboard::GetProperty - Retrieves the value of a property or group of properties for the clipboard buffer.
Obj –> [IDLgrClipboard::]GetProperty [, ALL=*variable*]
[, SCREEN_DIMENSIONS=*variable*]
Note: See also the {Get} properties in
IDLgrClipboard::Init

IDLgrClipboard::GetTextDimensions - Retrieves the dimensions of a text object that will be rendered in the clipboard buffer.
Result = Obj –>[IDLgrClipboard::]GetTextDimensions(
TextObj [, DESCENT=*variable*] [, PATH=*objref(s)*])

IDLgrClipboard::Init - Initializes the clipboard object.
Obj = OBJ_NEW('IDLgrClipboard'
[, COLOR_MODEL{Get}={0|1}] [, DIMENSIONS{Get,
Set}=*[width*, *height]*] [, GRAPHICS_TREE{Get,
Set}=*objref*] [, N_COLORS{Get}=*integer*{2 to 256}]
[, PALETTE{Get, Set}=*objref*] [, QUALITY{Get,
Set}={0|1|2}] [, RESOLUTION{Get, Set}=*[xres*, *yres]*]
[, UNITS{Get, Set}={0|1|2|3}] [, UVALUE{Get,
Set}=*value*])
or
Result = Obj –> [IDLgrClipboard::]Init( )

IDLgrClipboard::SetProperty - Sets the value of a property or group of properties for the clipboard buffer.
Obj –> [IDLgrClipboard::]SetProperty
Note: See also the {Set} properties in
IDLgrClipboard::Init

IDLgrColorbar - Consists of a color-ramp with an optional framing box and annotation axis. Superclasses: IDLgrModel. No subclasses.

IDLgrColorbar::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY,*Obj* or *Obj* –>
[IDLgrColorbar::]Cleanup

IDLgrColorbar::ComputeDimensions - Retrieves the dimensions of a colorbar object for the given destination object.
Result = Obj –>[IDLgrColorbar::]ComputeDimensions(
DestinationObj [, PATH=*objref(s)*])

IDLgrColorbar::GetProperty - Retrieves the value of a property or group of properties for the colorbar.
Obj –> [IDLgrColorbar::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*] [, XRANGE=*variable*]
[, YRANGE=*variable*] [, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrColorbar::Init

IDLgrColorbar::Init - Initializes the colorbar object.

> *Obj* = OBJ_NEW('IDLgrColorbar'
> [, *aRed, aGreen, aBlue*] [, BLUE_VALUES{Get,
> Set}=*vector*] [, COLOR{Get, Set}=*index or RGB vector*]
> [, DIMENSIONS{Get, Set}=*[dx, dy]*]
> [, GREEN_VALUES{Get, Set}=*vector*] [, /HIDE{Get,
> Set}] [, MAJOR{Get, Set}=*integer*] [, MINOR{Get,
> Set}=*integer*] [NAME{Get, Set}=*string*]
> [, PALETTE{Get, Set}=*objref*] [, RED_VALUES{Get,
> Set}=*vector*] [, SHOW_AXIS{Get, Set}={0 | 1 | 2}]
> [, /SHOW_OUTLINE{Get, Set}] [, SUBTICKLEN{Get,
> Set}=*minor_tick_length/major_tick_length*]
> [, THICK{Get, Set}=*points*{1.0 to 10.0}]
> [, /THREED{Get}] [, TICKFORMAT{Get, Set}=*string*]
> [, TICKFRMTDATA{Get, Set}=*value*] [, TICKLEN{Get,
> Set}=*value*] [, TICKTEXT{Get, Set}=*objref(s)*]
> [, TICKVALUES{Get, Set}=*vector*] [, TITLE{Get,
> Set}=*objref*] [, UVALUE{Get, Set}=*value*]
> [, XCOORD_CONV{Get, Set}=*vector*]
> [, YCOORD_CONV{Get, Set}=*vector*]
> [, ZCOORD_CONV{Get, Set}=*vector*])
> or
> *Result = Obj* -> [IDLgrColorbar::]Init([*aRed, aGreen, aBlue*])

IDLgrColorbar::SetProperty - Sets the value of a property or group of properties for the colorbar.

> *Obj* -> [IDLgrColorbar::]SetProperty
> **Note:** See also the {Set} properties in IDLgrColorbar::Init

IDLgrContour - Draws a contour plot from data stored in a rectangular array or from a set of unstructured points. No superclasses. No subclasses.

IDLgrContour::Cleanup - Performs all cleanup on the object.
> OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrContour::]Cleanup

IDLgrContour::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object

> *Result = Obj* -> [IDLgrContour::]GetCTM(
> [, DESTINATION=*objref*] [, PATH=*objref(s)*]
> [, TOP=*objref*])

IDLgrContour::GetProperty - Retrieves the value of a property or group of properties for the contour.

> *Obj* -> [IDLgrContour::]GetProperty [, ALL=*variable*]
> [, GEOM=*variable*] [, PARENT=*variable*]
> [, XRANGE=*variable*] [, YRANGE=*variable*]
> [, ZRANGE=*variable*]
> **Note:** See also the {Get} properties in IDLgrContour::Init

IDLgrContour::Init - Initializes the contour object.

> *Obj* = OBJ_NEW('IDLgrContour' [, *Values*]
> [, ANISOTROPY{Get, Set}=*[x, y, z]*] [, C_COLOR{Get,
> Set}=*vector*] [, C_FILL_PATTERN{Get, Set}=*array of
> IDLgrPattern objects*] [, C_LINESTYLE{Get, Set}=*array
> of linestyles*] [, C_THICK{Get, Set}=*float array*{each
> element 1.0 to 10.0}] [, C_VALUE{Get, Set}=*scalar or
> vector*] [, COLOR{Get, Set}=*index or RGB vector*]
> [, DATA_VALUES{Get, Set}=*vector or 2D array*]

> [, /DOUBLE_DATA] [, /DOUBLE_GEOM]
> [, /DOWNHILL{Get, Set}] [, /FILL{Get, Set}]
> [, GEOMX{Set}=*vector or 2D array*]
> [, GEOMY{Set}=*vector or 2D array*]
> [, GEOMZ{Set}=*scalar, vector, or 2D array*]
> [, /HIDE{Get, Set}] [, MAX_VALUE{Get, Set}=*value*]
> [, MIN_VALUE{Get, Set}=*value*] [, NAME{Get,
> Set}=*string*] [, N_LEVELS{Get, Set}=*value*]
> [, PALETTE{Get, Set}=*objref*] [, /PLANAR{Get, Set}]
> [, POLYGONS{Get, Set}=*array of polygon descriptions*]
> [, SHADE_RANGE{Get, Set}=*[min, max]*]
> [, SHADING{Get, Set}={0 |1}] [, TICKINTERVAL{Get,
> Set}=*value*] [, TICKLEN{Get, Set}=*value*]
> [, UVALUE{Get, Set}=*value*] [, XCOORD_CONV{Get,
> Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]
> [, ZCOORD_CONV{Get, Set}=*vector*])
> or
> *Result = Obj* -> [IDLgrContour::]Init([*Values*])

IDLgrContour::SetProperty - Sets the value of a property or group of properties for the contour.

> *Obj* -> [IDLgrContour::]SetProperty
> **Note:** See also the {Set} properties in IDLgrContour::Init

IDLgrFont - Represents a typeface, style, weight, and point size that may be associated with text objects. No superclasses. No subclasses.

IDLgrFont::Cleanup - Performs all cleanup on the object.
> OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrFont::]Cleanup

IDLgrFont::GetProperty - Retrieves the value of a property or group of properties for the font.

> *Obj* -> [IDLgrFont:]GetProperty [, ALL=*variable*]
> **Note:** See also the {Get} properties in IDLgrFont::Init

IDLgrFont::Init - Initializes the font object.

> *Obj* = OBJ_NEW('IDLgrFont' [, *Fontname*]
> [, NAME{Get, Set}=*string*] [, SIZE{Get, Set}=*points*]
> [, SUBSTITUTE{Get, Set}={ 'Helvetica' | 'Courier' |
> 'Times' | 'Symbol' | 'Hershey'}] [, THICK{Get,
> Set}=*points*{1.0 to 10.0}] [, UVALUE{Get, Set}=*value*])
> or
> *Result = Obj* -> [IDLgrFont::]Init([*Fontname*])

IDLgrFont::SetProperty - Sets the value of a property or group of properties for the font.

> *Obj* -> [IDLgrFont:]SetProperty
> **Note:** See also the {Set} properties in IDLgrFont::Init

IDLgrImage - Represents a mapping from a 2D array of data values to a 2D array of pixel colors, resulting in a flat 2D-scaled version of the image, drawn at Z = 0. No superclasses. No subclasses.

IDLgrImage::Cleanup - Performs all cleanup on the object.
> OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrImage::]Cleanup

IDLgrImage::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object.

> *Result = Obj* -> [IDLgrImage::]GetCTM(
> [, DESTINATION=*objref*] [, PATH=*objref(s)*]
> [, TOP=*objref to IDLgrModel object*])

IDLgrImage::GetProperty - Retrieves the value of the property or group of properties for the image.
> *Obj –>* [IDLgrImage::]GetProperty [, ALL=*variable*]
> [, PARENT=*variable*] [, XRANGE=*variable*]
> [, YRANGE=*variable*] [, ZRANGE=*variable*]
> **Note:** See also the {Get} properties in IDLgrImage::Init

IDLgrImage::Init - Initializes the image object.
> *Obj* = OBJ_NEW('IDLgrImage' [, *ImageData*]
> [, BLEND_FUNCTION{Get, Set}=*vector*]
> [, CHANNEL{Get, Set}=*hexadecimal bitmask*]
> [, DATA{Get, Set}=*nxm, 2xnxm, 3xnxm*, or *4xnxm array of image data*] [, DIMENSIONS{Get, Set}=*[width, height]*] [, /GREYSCALE{Get, Set}] [, /HIDE{Get, Set}]
> [, INTERLEAVE{Get, Set}={0 | 1 | 2}]
> [, /INTERPOLATE{Get, Set}] [LOCATION{Get, Set}=*[x, y] or [x, y, z]*] [, NAME{Get, Set}=*string*]
> [, /NO_COPY{Get, Set}] [, /ORDER{Get, Set}]
> [, PALETTE{Get, Set}=*objref*] [, /RESET_DATA{Set}]
> [, SHARE_DATA{Set}=*objref*] [, SUB_RECT{Get, Set}=*[x, y, xdim, ydim]*] [, UVALUE{Get, Set}=*value*]
> [, XCOORD_CONV{Get, Set}=*vector*]
> [YCOORD_CONV{Get, Set}=*vector*]
> [, ZCOORD_CONV{Get, Set}=*vector*])
> or
> *Result = Obj –>* [IDLgrImage::]Init([*ImageData*])

IDLgrImage::SetProperty - Sets the value of the property or group of properties for the image.
> *Obj –>* [IDLgrImage::]SetProperty
> **Note:** See also the {Set} properties in IDLgrImage::Init

IDLgrLegend - Provides a simple interface for displaying a legend. Superclass: IDLgrModel. No subclasses.

IDLgrLegend::Cleanup - Performs all cleanup on the object.
> OBJ_DESTROY, *Obj* or *Obj –>* [IDLgrLegend::]Cleanup

IDLgrLegend::ComputeDimensions - Retrieves the dimensions of a legend object for the given destination object.
> *Result = Obj –>*[IDLgrLegend::]ComputeDimensions(*DestinationObj* [, PATH=*objref(s)*])

IDLgrLegend::GetProperty - Retrieves the value of a property or group of properties for the legend.
> *Obj –>* [IDLgrLegend::]GetProperty [, ALL=*variable*]
> [, PARENT=*variable*] [, XRANGE=*variable*]
> [, YRANGE=*variable*] [, ZRANGE=*variable*]
> **Note:** See also the {Get} properties in IDLgrLegend::Init

IDLgrLegend::Init - Initializes the legend object.
> *Obj* = OBJ_NEW('IDLgrLegend' [, *aItemNames*]
> [, BORDER_GAP{Get, Set}=*value*] [, COLUMNS{Get, Set}=*integer*] [, FILL_COLOR{Get, Set}=*index or RGB vector*] [, FONT{Get, Set}=*objref*] [, GAP{Get, Set}=*value*] [, GLYPH_WIDTH{Get, Set}=*value*]
> [, /HIDE{Get, Set}] [, ITEM_COLOR{Get, Set}=*array of colors*] [, ITEM_LINESTYLE{Get, Set}=*int array*]
> [, ITEM_NAME{Get, Set}=*string array*]

[, ITEM_OBJECT{Get, Set}=*array of objrefs of type IDLgrSymbol or IDLgrPattern*] [, ITEM_THICK{Get, Set}=*float array*{each element 1.0 to 10.0}]
[, ITEM_TYPE{Get, Set}=*int array*{each element 0 or 1}]
[, NAME{Get, Set}=*string*] [, OUTLINE_COLOR{Get, Set}=*index or RGB vector*] [, OUTLINE_THICK{Get, Set}=*points*{1.0 to 10.0}] [, /SHOW_FILL{Get, Set}]
[, /SHOW_OUTLINE{Get, Set}] [, TEXT_COLOR{Get, Set}=*index or RGB vector*] [, TITLE{Get, Set}=*objref*]
[, UVALUE{Get, Set}=*value*] [, XCOORD_CONV{Get, Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]
[, ZCOORD_CONV{Get, Set}=*vector*])
or
Result = Obj –> [IDLgrLegend::]Init([*aItemNames*])

IDLgrLegend::SetProperty - Sets the value of a property or group of properties for the legend.
> *Obj–>* [IDLgrLegend::]SetProperty [, RECOMPUTE={0 | 1}{0 prevents recompute, 1 is the default}]
> **Note:** See also the {Set} properties in IDLgrLegend::Init

IDLgrLight - Represents a source of illumination for 3D graphic objects. No superclasses. No subclasses.

IDLgrLight::Cleanup - Performs all cleanup on the object.
> OBJ_DESTROY, *Obj* or *Obj –>* [IDLgrLight::]Cleanup

IDLgrLight::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object.
> *Result = Obj –>* [IDLgrLight::]GetCTM([, DESTINATION=*objref*] [, PATH=*objref(s)*]
> [, TOP=*objref to IDLgrModel object*])

IDLgrLight::GetProperty - Retrieves the value of a property or group of properties for the light.
> *Obj –>* [IDLgrLight::]GetProperty [, ALL=*variable*]
> [, PARENT=*variable*]
> **Note:** See also the {Get} properties in IDLgrLight::Init

IDLgrLight::Init - Initializes the light object.
> *Obj* = OBJ_NEW('IDLgrLight' [, ATTENUATION{Get, Set}=*[constant, linear, quadratic]*] [, COLOR{Get, Set}=*[R, G, B]*] [, CONEANGLE{Get, Set}=*degrees*]
> [, DIRECTION{Get, Set}=*3-element vector*]
> [, FOCUS{Get, Set}=*value*] [, /HIDE{Get, Set}]
> [, INTENSITY{Get, Set}=*value*{0.0 to 1.0}]
> [, LOCATION{Get, Set}=*[x, y, z]*] [, NAME{Get, Set}=*string*] [, TYPE{Get, Set}={0 | 1 | 2 | 3}]
> [, UVALUE{Get, Set}=*value*] [, XCOORD_CONV{Get, Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]
> [, ZCOORD_CONV{Get, Set}=*vector*])
> or
> *Result = Obj –>* [IDLgrLight::]Init( )

IDLgrLight::SetProperty - Sets the value of a property or group of properties for the light.
> *Obj –>* [IDLgrLight::]SetProperty
> **Note:** See also the {Set} properties in IDLgrLight::Init

IDLgrModel - Represents a graphical item or group of items that can be transformed (rotated, scaled, and/or translated). Superclass: IDL_Container. The following classes are subclassed from this class: IDLgrColorbar, IDLgrLegend.

IDLgrModel::Add - Adds a child to this Model.

Obj –> [IDLgrModel::]Add, *Object* [, /ALIAS]
[, POSITION=*index*]

IDLgrModel::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrModel::]Cleanup

IDLgrModel:Draw - Draws the specified picture to the specified graphics destination. *This method is provided for purposes of sub-classing only, and is intended to be called only from the Draw method of a subclass of IDLgrModel.*

Obj –> [IDLgrModel::]Draw, *Destination, Picture*

IDLgrModel::GetByName - Finds contained objects by name and returns the object reference to the named object.

Result = Obj –> [IDLgrModel::]GetByName(*Name*)

IDLgrModel::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object

Result = Obj –> [IDLgrModel::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrModel::GetProperty - Retrieves the value of a property or group of properties for the model.

Obj –> [IDLgrModel::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*]
Note: See also the {Get} properties in IDLgrModel::Init

IDLgrModel::Init - Initializes the model object.

Obj = OBJ_NEW('IDLgrModel' [, /HIDE{Get, Set}]
[, LIGHTING{Get, Set}={0 | 1 | 2}] [, NAME{Get, Set}=*string*] [, /SELECT_TARGET{Get, Set}]
[, TRANSFORM{Get, Set}=*4x4 transformation matrix*]
[, UVALUE{Get, Set}=*value*])
or
Result = Obj –> [IDLgrModel::]Init( )

IDLgrModel::Reset - Sets the current transform matrix for the model object to the identity matrix.

Obj –> [IDLgrModel::]Reset

IDLgrModel::Rotate - Rotates the model about the specified axis by the specified angle.

Obj –> [IDLgrModel::]Rotate, *Axis, Angle*
[, /PREMULTIPLY]

IDLgrModel::Scale - Scales model by the specified scaling factors.

Obj –> [IDLgrModel::]Scale, *Sx, Sy, Sz*
[, /PREMULTIPLY]

IDLgrModel::SetProperty - Sets the value of a property or group of properties for the model.

Obj –> [IDLgrModel::]SetProperty
Note: See also the {Set} properties in IDLgrModel::Init

IDLgrModel::Translate - Translates the model by the specified translation offsets.

Obj –> [IDLgrModel::]Translate, *Tx, Ty, Tz*
[, /PREMULTIPLY]

IDLgrMPEG - Creates an MPEG movie file from an array of image frames. No superclasses. No subclasses.

IDLgrMPEG::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrMPEG::]Cleanup

IDLgrMPEG::GetProperty - Retrieves the value of a property or group of properties for the MPEG object.

Obj –> [IDLgrMPEG::]GetProperty [, ALL=*variable*]
Note: See also the {Get} properties in IDLgrMPEG::Init

IDLgrMPEG::Init - Initializes the MPEG object.

Obj = OBJ_NEW('IDLgrMPEG' [, BITRATE{Get, Set}=*value*] [, DIMENSIONS{Get, Set}=*2-element array*]
[, FILENAME{Get, Set}=*string*] [, FORMAT{Get, Set}={0 | 1}] [, FRAME_RATE{Get, Set} ={1 | 2 | 3 | 4 | 5 | 6 | 7 | 8}] [, IFRAME_GAP{Get, Set}=*integer value*]
[, /INTERLACED{Get, Set}]
[, MOTION_VEC_LENGTH{Get, Set}={1 | 2 | 3}]
[, QUALITY{Get, Set}=*value*{0 to100}] [, SCALE{Get, Set}=*[xscale, yscale]*] [, /STATISTICS{Get, Set}]
[, TEMP_DIRECTORY=*string*])
or
Result = Obj –> [IDLgrMPEG::]Init( )

IDLgrMPEG::Put - Puts a given image into the MPEG sequence at the specified frame.

Obj –> [IDLgrMPEG::]Put, *Image*[, *Frame*]

IDLgrMPEG::Save - Encodes and saves an MPEG sequence to a file.

Obj –> [IDLgrMPEG::]Save [, FILENAME=*string*]
Macintosh Keywords: [, CREATOR_TYPE=*string*]

IDLgrMPEG::SetProperty - Sets the value of a property or group of properties for the MPEG object.

Obj –> [IDLgrMPEG::]SetProperty
Note: See also the {Set} properties in IDLgrMPEG::Init

IDLgrPalette - Represents a color lookup table that maps indices to red, green, and blue values. No superclasses. No subclasses.

IDLgrPalette::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrPalette::]Cleanup

IDLgrPalette::GetRGB - Returns the RGB values contained in the palette at the given index.

Result = Obj –> [IDLgrPalette::]GetRGB(*Index*)

IDLgrPalette::GetProperty - Retrieves the value of a property or group of properties for the palette.

Obj –> [IDLgrPalette::]GetProperty [, ALL=*variable*]
[, N_COLORS=*variable*]
Note: See also the {Get} properties in IDLgrPalette::Init

IDLgrPalette::Init - Initializes a palette object.

Obj=OBJ_NEW('IDLgrPalette', *aRed*, *aGreen*, *aBlue*
[, BLUE_VALUES{Get, Set}=*vector*]
[, BOTTOM_STRETCH{Get, Set}=*value*{0 to 100}]
[, GAMMA{Get, Set}=*value*{0.1 to 10.0}]
[, GREEN_VALUES{Get, Set}=*vector*] [, NAME{Get, Set}=*string*] [, RED_VALUES{Get, Set}=*vector*]

[, TOP_STRETCH{Get, Set}=*value*{0 to 100}]
[, UVALUE{Get, Set}=*value*])
or
Result=Obj–>[IDLgrPalette::Init([*aRed*, *aGreen*, *aBlue*])

IDLgrPalette::LoadCT - Loads one of the IDL predefined color tables into an IDLgrPalette object.
Obj –> [IDLgrPalette::]LoadCT, *TableNum*
[, FILENAME=*colortable filename*]

IDLgrPalette::NearestColor - Returns the index of the color in the palette that best matches the given RGB values.
Result = Obj–> [IDLgrPalette::]NearestColor(*Red*, *Green*, *Blue*)

IDLgrPalette::SetRGB - Sets the color values at a specified index in the palette to the specified Red, Green and Blue values.
Obj –> [IDLgrPalette::]SetRGB, *Index*, *Red*, *Green*, *Blue*

IDLgrPalette::SetProperty - Sets the value of a property or group of properties for the palette.
Obj –> [IDLgrPalette::]SetProperty
Note: See also the {Set} properties in IDLgrPalette::Init

IDLgrPattern - Describes which pixels are filled and which are left blank when an area is filled. No superclasses. No subclasses.

IDLgrPattern::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj –>* [IDLgrPattern::]Cleanup

IDLgrPattern::GetProperty - Retrieves the value of a property or group of properties for the pattern.
Obj –> [IDLgrPattern::]GetProperty [, ALL=*variable*]
Note: See also the {Get} properties in IDLgrPattern::Init

IDLgrPattern::Init - Initializes the pattern object.
Obj = OBJ_NEW('IDLgrPattern' [, *Style*]
[, ORIENTATION{Get, Set}=*ccw degrees from horiz*]
[, NAME{Get, Set}=*string*] [, PATTERN{Get, Set}=*32 x 32 bit array*] [, SPACING{Get, Set}=*points*]
[, STYLE*{Get, Set}*={0 | 1 | 2}]
[, THICK=*points*{1.0 to 10.0}] [, UVALUE{Get, Set}=*value*])
or
Result = Obj –> [IDLgrPattern::]Init([*Style*])

IDLgrPattern:SetProperty - Sets the value of a property or group of properties for the pattern.
Obj –> [IDLgrPattern::]SetProperty
Note: See also the {Set} properties in IDLgrPattern::Init

IDLgrPlot - Creates set of polylines connecting data points in 2D space. No superclasses. No subclasses.

IDLgrPlot::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj –>* [IDLgrPlot::]Cleanup

IDLgrPlot::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.
Result = Obj –> [IDLgrPlot::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrPlot::GetProperty - Retrieves the value of the property or group of properties for the plot.
Obj –> [IDLgrPlot::]GetProperty [, ALL=*variable*]
[, DATA=*variable*] [, PARENT=*variable*]
[, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrPlot::Init

IDLgrPlot::Init - Initializes the plot object.
Obj = OBJ_NEW('IDLgrPlot' [, [*X*,] *Y*] [, COLOR{Get, Set}=*index or RGB vector* | , VERT_COLORS{Get, Set}=*vector*] [, DATAX {Set}=*vector*]
[, DATAY{Set}=*vector*] [, DOUBLE{Get, Set}=*value*]
[, /HIDE{Get, Set}] [, /HISTOGRAM{Get, Set}]
[, LINESTYLE{Get, Set}=*integer or two-element vector*]
[, MAX_VALUE{Get, Set}=*value*] [, MIN_VALUE{Get, Set}=*value*] [, NAME{Get, Set}=*string*] [, NSUM{Get, Set}=*value*] [, PALETTE{Get, Set}=*objref*]
[, /POLAR{Get, Set}] [, /RESET_DATA{Set}]
[, SHARE_DATA{Set}=*objref*] [, SYMBOL{Get, Set}=*objref(s)*] [, THICK{Get, Set}=*points*{1.0 to 10.0}]
[, /USE_ZVALUE] [, UVALUE{Get, Set}=*value*]
[, XCOORD_CONV{Get, Set}=*vector*] [, XRANGE{Get, Set}=*[xmin, xmax]*] [, YCOORD_CONV{Get, Set}=*vector*] [, YRANGE{Get, Set}=*[ymin, ymax]*]
[, ZCOORD_CONV{Get, Set}=*vector*] [, ZVALUE{Get, Set}=*value*])
or
Result = Obj –> [IDLgrPlot::]Init([[*X*,] *Y*])

IDLgrPlot::SetProperty - Sets the value of the property or group of properties for the plot.
Obj –> [IDLgrPlot::]SetProperty
Note: See also the {Set} properties in IDLgrPlot::Init

IDLgrPolygon - Represents one or more polygons that share a set of vertices and rendering attributes. No superclasses. No subclasses.

IDLgrPolygon::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj –>* [IDLgrPolygon::]Cleanup

IDLgrPolygon::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.
Result = Obj –> [IDLgrPolygon::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrPolygon::GetProperty - Retrieves the value of the property or group of properties for the polygons.
Obj –> [IDLgrPolygon::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*] [, XRANGE=*variable*]
[, YRANGE=*variable*] [, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrPolygon::Init

IDLgrPolygon::Init - Initializes the polygons object.
Obj = OBJ_NEW('IDLgrPolygon' [, *X* [, *Y*[, *Z*]]]
[, BOTTOM{Get, Set}=*index or RGB vector*]
[, COLOR{Get, Set}=*index or RGB vector* |
, VERT_COLORS{Get, Set}=*vector*] [, DATA{Get,

Set}=*array*] [, DOUBLE{Get, Set}=*value*]
[, FILL_PATTERN{Get, Set}=*objref to IDLgrPattern object*] [, /HIDDEN_LINES] [, /HIDE{Get, Set}]
[, LINESTYLE{Get, Set}=*value*] [, NAME{Get, Set}=*string*] [, NORMALS{Get, Set}=*array*]
[, PALETTE=*objref*] [, POLYGONS{Get, Set}=*array of polygon descriptions*] [, REJECT{Get, Set}={0 | 1 | 2}]
[, /RESET_DATA{Set}] [, SHADE_RANGE{Get, Set}=*array*] [, SHADING{Get, Set}={0 | 1}]
[, SHARE_DATA{Set}=*objref*] [, STYLE{Get, Set}={0 | 1 | 2}] [, TEXTURE_COORD{Get, Set}=*array*]
[, /TEXTURE_INTERP{Get, Set}]
[, TEXTURE_MAP*{Get, Set}=objref to IDLgrImage object*] [, THICK{Get, Set}=*points*{1.0 to 10.0}]
[, XCOORD_CONV{Get, Set}=*vector*]
[, YCOORD_CONV{Get, Set}=*vector*]
[, ZCOORD_CONV{Get, Set}=*vector*]
[, ZERO_OPACITY_SKIP{Get, Set}={0 | 1}])
or
Result = Obj -> [IDLgrPolygon::]Init([*X*, [*Y*, [*Z*]]])

IDLgrPolygon::SetProperty - Sets the value of the property or group of properties for the polygons.
 Obj -> [IDLgrPolygon::]SetProperty
 Note: See also the {Set} properties in IDLgrPolygon::Init

IDLgrPolyline - Represents one or more polylines that share a set of vertices and rendering attributes. No superclasses. No subclasses.

IDLgrPolyline::Cleanup - Performs all cleanup on the object.
 OBJ_DESTROY, *Obj* or *Obj* ->
 [IDLgrPolyline::]Cleanup

IDLgrPolyline::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.
 Result = Obj -> [IDLgrPolyline::]GetCTM(
 [, DESTINATION=*objref*] [, PATH=*objref(s)*]
 [, TOP=*objref to IDLgrModel object*])

IDLgrPolyline::GetProperty - Retrieves the value of a property or group of properties for the polylines.
 Obj -> [IDLgrPolyline::]GetProperty [, ALL=*variable*]
 [, PARENT=*variable*] [, XRANGE=*variable*]
 [, YRANGE=*variable*] [, ZRANGE=*variable*]
 Note: See also the {Get} properties in IDLgrPolyline::Init

IDLgrPolyline::Init - Initializes the polylines object.
 Obj = OBJ_NEW('IDLgrPolyline' [, *X* [, *Y*[, *Z*]]]
 [, COLOR{Get, Set}=*index or RGB vector |*
 , VERT_COLORS{Get, Set}=*vector*] [, DATA{Get, Set}=*array*] [, DOUBLE{Get, Set}=*value*] [, /HIDE{Get, Set}] [, LINESTYLE{Get, Set}=*value*] [, NAME{Get, Set}=*string*] [, PALETTE{Get, Set}=*objref*]
 [, POLYLINES{Get, Set}=*array of polyline descriptions*]
 [, /RESET_DATA{Set}] [, SHADING{Get, Set}={0 | 1}]
 [, SHARE_DATA{Set}=*objref*] [, SYMBOL{Get, Set}=*objref(s)*] [, THICK{Get, Set}=*points*{1.0 to 10.0}]
 [, UVALUE{Get, Set}=*value*] [, XCOORD_CONV{Get,

Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]
[, ZCOORD_CONV{Get, Set}=*vector*])
or
Result = Obj -> [IDLgrPolyline::]Init([*X*, [*Y*, [*Z*]]])

IDLgrPolyline::SetProperty - Sets the value of a property or group of properties for the polylines.
 Obj -> [IDLgrPolyline::]SetProperty
 Note: See also the {Set} properties in IDLgrPolyline::Init

IDLgrPrinter - Represents a hardcopy graphics destination. No super-classes. No subclasses.

IDLgrPrinter::Cleanup - Performs all cleanup on the object.
 OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrPrinter::]Cleanup

IDLgrPrinter::Draw - Draws a picture to this graphics destination.
 Obj -> [IDLgrPrinter::]Draw [, *Picture*]
 [, VECTOR={ 0 | 1 }]

IDLgrPrinter::GetContiguousPixels - Returns an array of long integers whose length is equal to the number of colors avail-able in the index color mode (value of N_COLORS property).
 Return = Obj -> [IDLgrPrinter::]GetContiguousPixels( )

IDLgrPrinter::GetFontnames - Returns the list of available fonts that can be used in IDLgrFont objects.
 Return = Obj -> [IDLgrPrinter::]GetFontnames(
 FamilyName [, IDL_FONTS={0 | 1 | 2}]
 [, STYLES=*string*])

IDLgrPrinter::GetProperty - Retrieves the value of a property or group of properties for the printer.
 Obj -> [IDLgrPrinter::]GetProperty [, ALL=*variable*]
 [, DIMENSIONS=*variable*] [, NAME=*string*]
 [, RESOLUTION=*variable*]
 Note: See also the {Get} properties in IDLgrPrinter::Init

IDLgrPrinter::GetTextDimensions - Retrieves the dimensions of a text object that will be rendered on the printer.
 Result = Obj ->[IDLgrPrinter::]GetTextDimensions(
 TextObj [, DESCENT=*variable*] [, PATH=*objref(s)*])

IDLgrPrinter::Init - Initializes the printer object.
 Obj = OBJ_NEW('IDLgrPrinter'
 [, COLOR_MODEL{Get}={0 | 1}]
 [, GRAPHICS_TREE{Get, Set}=*objref of type IDLgrScene, IDLgrViewgroup, or IDLgrView*]
 [, /LANDSCAPE{Get, Set}]
 [, N_COLORS{Get}=*integer*{2 to 256}]
 [, N_COPIES{Get, Set}=*integer*] [, PALETTE{Get, Set}=*objref*] [, PRINT_QUALITY{Get, Set}={0 | 1 | 2}]
 [, QUALITY{Get, Set}={0 | 1 | 2}] [, UNITS{Get, Set}={0 | 1 | 2 | 3}] [, UVALUE{Get, Set}=*value*])
 or
 Result = Obj -> [IDLgrPrinter::]Init( )

IDLgrPrinter::NewDocument - Closes current document (page or group of pages), which causes pending output to be sent to the printer, finishing the printer job.
 Obj -> [IDLgrPrinter::]NewDocument

IDLgrPrinter::NewPage - Issues new page command to printer.

   Obj –> [IDLgrPrinter::]NewPage

IDLgrPrinter::SetProperty - Sets the value of a property or group of properties for the printer.

   Obj –> [IDLgrPrinter::]SetProperty

   Note: See also the {Set} properties in IDLgrPrinter::Init

IDLgrROI - Object graphics representation of a region of interest. Subclass of IDLanROI.

IDLgrROI::Cleanup - Performs all cleanup for the object.

   OBJ_DESTROY, *Obj* or *Obj*–>[IDLgrROI::]Cleanup

IDLgrROI::GetProperty - Retrieves the value of a property or group of properties for the Object Graphics region.

   Obj–>[IDLgrROI::]GetProperty [, ALL=*variable*]
   [, XRANGE=*variable*] [, YRANGE=*variable*]
   [, ZRANGE=*variable*]

IDLgrROI::Init - Initializes an Object Graphics region of interest.

   Obj = OBJ_NEW('IDLgrROI' [, *X*[, *Y*[, *Z*]]]
   [, COLOR{Get, Set}=*vector*] [, DOUBLE{Get,
   Set}=*value*] [, /HIDE{Get, Set}]
   [, LINESTYLE{Get, Set}=*value*]
   [, NAME{Get, Set}=*string*]
   [, PALETTE{Get, Set}=*objref*]
   [, STYLE{Get, Set}={ 0 | 1 | 2 }]
   [, SYMBOL{Get, Set}=*objref*]
   [, THICK{Get, Set}=*points*{1.0 to 10.0}]
   [, UVALUE{Get, Set}=*uvalue*]
   [, XCOORD_CONV{Get, Set}=*[s_0, s_1]*]
   [, YCOORD_CONV{Get, Set}=*[s_0, s_1]*]
   [, ZCOORD_CONV{Get, Set}=*[s_0, s_1]*])
   or
   Result = *Obj*–>[IDLgrROI::]Init([*X*[, *Y*[, *Z*]]])

IDLgrROI::PickVertex - Picks a vertex of the region that, when projected onto the given destination device, is nearest to the given 2D device coordinate.

   Result = *Obj*–>[IDLgrROI::]PickVertex(*Dest*, *View*, *Point*
   [, PATH=*objref*])

IDLgrROI::SetProperty - Sets the value of a property or group of properties for the Object Graphics region.

   Obj–>[IDLgrROI::]SetProperty

IDLgrROIGroup - Object Graphics representation of a group of regions of interest. Subclass of IDLanROIGroup.

IDLgrROIGroup::Add - Adds a region to the region group.

   Obj–>[IDLgrROIGroup::]Add, *ROI*

IDLgrROIGroup::Cleanup - Performs all cleanup for the object.

   OBJ_DESTROY, *Obj* or
   Obj–>[IDLgrROIGroup::]Cleanup

IDLgrROIGroup::GetProperty - Retrieves the value of a property or group of properties for the region group.

   Obj–>[IDLgrROIGroup::]GetProperty [, ALL=*variable*]
   [, PARENT=*variable*] [, XRANGE=*variable*]
   [, YRANGE=*variable*] [, ZRANGE=*variable*]

IDLgrROIGroup::Init - Initializes an Object Graphics region of interest group object.

   Obj = OBJ_NEW('IDLgrROIGroup'
   [, COLOR{Get, Set}=*vector*] [, /HIDE{Get, Set}]
   [, NAME{Get, Set}=*string*]
   [, XCOORD_CONV{Get, Set}=*[s_0, s_1]*]
   [, YCOORD_CONV{Get, Set}=*[s_0, s_1]*]
   [, ZCOORD_CONV{Get, Set}=*[s_0, s_1]*])
   or
   Result = *Obj*–>[IDLgrROIGroup::]Init( )

IDLgrROIGroup::PickRegion - Picks a region within the group that, when projected onto the given destination device, is nearest to the given 2D device coordinate.

   Result = *Obj*–>[IDLgrROIGroup::]PickRegion(*Dest*,
   View, *Point* [, PATH=*objref*])

IDLgrROIGroup::SetProperty - Sets the value of a property or group of properties for the region group.

   Obj–>[IDLgrROIGroup::]SetProperty

IDLgrScene - Represents the entire scene to be drawn and serves as a container of IDLgrView or IDLgrViewgroup objects. Superclass: IDL_Container. No subclasses.

IDLgrScene::Add - Verifies that the added item is an instance of an IDLgrView or IDLgrViewgroup object.

   Obj –> [IDLgrScene::]Add, *View* [, POSITION=*index*]

IDLgrScene::Cleanup - Performs all cleanup on the object.

   OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrScene::]Cleanup

IDLgrScene::GetByName - Finds contained objects by name and returns the object reference to the named object.

   Result = *Obj* –> [IDLgrScene::]GetByName(*Name*)

IDLgrScene::GetProperty - Retrieves the value of a property or group of properties for the contour.

   Obj –> [IDLgrScene::]GetProperty [, ALL=*variable*]

   Note: See also the {Get} properties in IDLgrScene::Init

IDLgrScene::Init - Initializes the scene object.

   Obj = OBJ_NEW('IDLgrScene' [, COLOR{Get,
   Set}=*index or RGB vector*] [, /HIDE{Get, Set}]
   [, NAME{Get, Set}=*string*] [, /TRANSPARENT{Get,
   Set}] [, UVALUE{Get, Set}=*value*])
   or
   Result = *Obj* –> [IDLgrScene::]Init( )

IDLgrScene::SetProperty - Sets the value of one or more properties for the scene.

   Obj –> [IDLgrScene::]SetProperty

   Note: See also the {Set} properties in IDLgrScene::Init

IDLgrSurface - A shaded or vector representation of a mesh grid. No superclasses. No subclasses.

IDLgrSurface::Cleanup - Performs all cleanup on the object.

   OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrSurface::]Cleanup

IDLgrSurface::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.

Result = Obj –> [IDLgrSurface::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrSurface::GetProperty - Retrieves the value of a property or group of properties for the surface.

Obj –> [IDLgrSurface::]GetProperty [, ALL=*variable*]
[, DATA=*variable*] [, PARENT=*variable*]
[, XRANGE=*variable*] [, YRANGE=*variable*]
[, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrSurface::Init

IDLgrSurface::Init - Initializes the surface object.

Obj = OBJ_NEW('IDLgrSurface' [, *Z* [, *X*, *Y*]]
[, BOTTOM{Get, Set}=*index or RGB vector*]
[, COLOR{Get, Set}=*index or RGB vector*]
[, DATAX{Set}=*vector or 2D array*]
[, DATAY{Set}=*vector or 2D array*] [, DATAZ{Set}=*2D array*] [, DOUBLE{Get, Set}=*value*]
[, , /EXTENDED_LEGO{Get, Set}]
[, , /HIDDEN_LINES{Get, Set}] [, /HIDE{Get, Set}]
[, LINESTYLE{Get, Set}=*value*] [, MAX_VALUE{Get, Set}=*value*] [, MIN_VALUE{Get, Set}=*value*]
[, NAME{Get, Set}=*string*] [, PALETTE{Get, Set}=*objref*] [, /RESET_DATA{Set}]
[, SHADE_RANGE{Get, Set}=*[index of darkest pixel, index of brightest pixel]*] [, SHADING{Get, Set}={0 | 1}]
[, SHARE_DATA{Set}=*objref*] [, /SHOW_SKIRT{Get, Set}] [, SKIRT{Get, Set}=*Z value*] [, STYLE{Get, Set}={0 | 1 | 2 | 3 | 4 | 5 | 6}] [, TEXTURE_COORD{Get, Set}=*array*] [, /TEXTURE_INTERP{Get, Set}]
[, TEXTURE_MAP{Get, Set}=*objref to IDLgrImage*]
[, THICK{Get, Set}=*points{1.0 to 10.0}*]
[, UVALUE{Get, Set}=*value*] [, /USE_TRIANGLES{Get, Set}] [, VERT_COLORS{Get, Set}=*vector*]
[, XCOORD_CONV{Get, Set}=*vector*]
[, YCOORD_CONV{Get, Set}=*vector*]
[, ZCOORD_CONV{Get, Set}=*vector*]
[, ZERO_OPACITY_SKIP{Get, Set}={0 | 1}])
or
Result = Obj –> [IDLgrSurface::]Init([*Z* [, *X*, *Y*]])

IDLgrSurface::SetProperty - Sets the value of a property or group of properties for the surface.

Obj –> [IDLgrSurface::]SetProperty
Note: See also the {Set} properties in IDLgrSurface::Init

IDLgrSymbol - Represents a graphical element that is plotted relative to a particular position. No superclasses. No subclasses.

IDLgrSymbol::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrSymbol::]Cleanup

IDLgrSymbol::GetProperty - Retrieves the value of a property or group of properties for the symbol.

Obj –> [IDLgrSymbol::]GetProperty [, ALL=*variable*]
Note: See also the {Get} properties in IDLgrSymbol::Init

IDLgrSymbol::Init - Initializes the plot symbol.

Obj = OBJ_NEW('IDLgrSymbol' [, *Data*] [, COLOR{Get, Set}=*index or RGB vector*] [, DATA{Get, Set}=*integer or objref*] [, NAME{Get, Set}=*string*] [, SIZE{Get, Set}=*vector*] [, THICK{Get, Set}=*points{1.0 to 10.0}*]
[, UVALUE{Get, Set}=*value*])
or
Result = Obj –> [IDLgrSymbol::]Init([*Data*])

IDLgrSymbol::SetProperty - Sets the value of a property or group of properties for the symbol.

Obj –> [IDLgrSymbol::]SetProperty
Note: See also the {Set} properties in IDLgrSymbol::Init

IDLgrTessellator - Converts a simple concave polygon (or a simple polygon with "holes") into a number of simple convex polygons (general triangles). No superclasses. No subclasses.

IDLgrTessellator::AddPolygon - Adds a polygon to the tessellator object.

Obj –> [IDLgrTessellator::]AddPolygon, *X* [, *Y*[, *Z*]]
[, POLYGON{Get, Set}=*array of polygon descriptions*]
[, /INTERIOR]

IDLgrTessellator::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY,*Obj* or
Obj –> [IDLgrTessellator::]Cleanup

IDLgrTessellator::Init - Initializes the tessellator object.

Obj = OBJ_NEW('IDLgrTesselator') or
Result = Obj –> [IDLgrTessellator::]Init( )

IDLgrTessellator::Reset - Resets the object's internal state.

Obj –> [IDLgrTessellator::]Reset

IDLgrTessellator::Tessellate - Performs the actual tessellation.

Result = Obj –> [IDLgrTessellator::]Tessellate(*Vertices, Poly* [, /QUIET])

IDLgrText - Represents one or more text strings that share common rendering attributes. No superclasses. No subclasses.

IDLgrText::Cleanup - Performs all cleanup on the object.

OBJ_DESTROY, *Obj* or *Obj* –> [IDLgrText::]Cleanup

IDLgrText::GetCTM - Returns the 4 x 4 graphics transform matrix from the current object upward through the graphics tree.

Result = Obj –> [IDLgrText::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrText::GetProperty - Retrieves the value of a property or group of properties for the text.

Obj –> [IDLgrText::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*] [, XRANGE=*variable*]
[, YRANGE=*variable*] [, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrText::Init

IDLgrText::Init - Initializes the text object.

Obj = OBJ_NEW('IDLgrText' [, *String/string array*]
[, ALIGNMENT{Get, Set}=*value{0.0 to 1.0}*]
[, BASELINE{Get, Set}=*vector*]
[, CHAR_DIMENSIONS{Get, Set}=*[width, height]*]

[, COLOR{Get, Set}=*index or RGB vector*]
[, /ENABLE_FORMATTING{Get, Set}] [, FONT{Get,
Set}=*objref*] [, /HIDE{Get, Set}] [, LOCATIONS{Get,
Set}=*array*] [, NAME{Get, Set}=*string*]
[, /ONGLASS{Get, Set}] [, PALETTE{Get, Set}=*objref*]
[, RECOMPUTE_DIMENSIONS{Get, Set}={0 | 1 | 2}]
[, STRINGS{Get, Set}=*string or vector of strings*]
[, UPDIR{Get, Set}=*vector*] [, UVALUE{Get,
Set}=*value*] [, VERTICAL_ALIGNMENT{Get,
Set}=*value*{0.0 to 1.0}] [, XCOORD_CONV{Get,
Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*]
[, ZCOORD_CONV{Get, Set}=*vector*]) or
Result = Obj −> [IDLgrText::]Init([*String/sting array*])

IDLgrText::SetProperty - Sets the value of a property or group of
properties for the text.
Obj −> [IDLgrText::]SetProperty
Note: See also the {Set} properties in IDLgrText::Init

IDLgrView - Represents a rectangular area in which graphics objects
are drawn. It is a container for objects of the IDLgrModel class.
Superclass: IDL_Container. No subclasses.

IDLgrView::Add - Adds a child to this view.
Obj −> [IDLgrView::]Add, *Model* [, POSITION=*index*]

IDLgrView::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj −>* [IDLgrView::]Cleanup

IDLgrView::GetByName - Finds contained objects by name.
Result = Obj −> [IDLgrView::]GetByName(*Name*)

IDLgrView::GetProperty - Retrieves the value of the property or
group of properties for the view.
Obj −> [IDLgrView::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*]
Note: See also the {Get} properties in IDLgrView::Init

IDLgrView::Init - Initializes the view object.
Obj = OBJ_NEW('IDLgrView' [, COLOR{Get,
Set}=*index or RGB vector*] [, DEPTH_CUE{Get,
Set}=*[zbright, zdim]*] [, DIMENSIONS{Get, Set}=*[width,
height]*] [, DOUBLE {Get, Set}=*value*] [, EYE{Get,
Set}=*distance*] [, LOCATION{Get, Set}=*[x, y]*]
[, PROJECTION{Get, Set}={1 | 2}]
[, /TRANSPARENT{Get, Set}] [, UNITS{Get, Set}={0 | 1
| 2 | 3}] [, UVALUE{Get, Set}=*value*]
[, VIEWPLANE_RECT{Get, Set}=*[x, y, width, height]*]
[, ZCLIP{Get, Set}=*[near, far]*])
or
Result = Obj −> [IDLgrView::]Init( )

IDLgrView::SetProperty - Sets the value of the property or group
of properties for the view.
Obj −> [IDLgrView::]SetProperty
Note: See also the {Set} properties in IDLgrView::Init

IDLgrViewgroup - A simple container object that contains one or
more IDLgrView objects. An IDLgrScene can contain one or more
of these objects. Superclass: IDL_Container. No subclasses.

IDLgrViewgroup::Add - Verifies that the added item is not an
instance of the IDLgrScene or IDLgrViewgroup object.
Obj −> [IDLgrViewgroup::]Add, *Object*
[, POSITION=*index*]

IDLgrViewgroup::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY,*Obj*
or
Obj −> [IDLgrViewgroup::]Cleanup

IDLgrViewgroup::GetByName - Finds contained objects by
name.
Result = Obj −> [IDLgrViewgroup::]GetByName(*Name*)

IDLgrViewgroup::GetProperty - Retrieves the value of a prop-
erty or group of properties for the viewgroup object.
Obj −> [IDLgrViewgroup::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*]
Note: See also the {Get} properties in
IDLgrViewgroup::Init

IDLgrViewgroup::Init - Initializes the viewgroup object.
Obj = OBJ_NEW('IDLgrViewgroup' [, /HIDE{Get, Set}]
[, NAME{Get, Set}=*string*]
[, UVALUE{Get, Set}=*value*])
or
Result = Obj −> [IDLgrViewgroup::]Init( )

IDLgrViewgroup::SetProperty - Sets the value of a property or
group of properties for the viewgroup.
Obj −> [IDLgrViewgroup::]SetProperty
Note: See also the {Set} properties in
IDLgrViewgroup::Init

IDLgrVolume - Represents mapping from a 3D array of data to a 3D
array of voxel colors, which, when drawn, are projected to two
dimensions. No superclasses. No subclasses.

IDLgrVolume::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj −>* [IDLgrVolume::]Cleanup

IDLgrVolume::ComputeBounds - Computes the smallest
bounding box that contains all voxels whose opacity lookup is
greater than a given opacity value.
Obj −> [IDLgrVolume::]ComputeBounds
[, OPACITY=*value*] [, /RESET] [, VOLUMES=*int array*]

IDLgrVolume::GetCTM - Returns the 4 x 4 graphics transform
matrix from the current object upward through the graphics tree.
Result = Obj −> [IDLgrVolume::]GetCTM(
[, DESTINATION=*objref*] [, PATH=*objref(s)*]
[, TOP=*objref to IDLgrModel object*])

IDLgrVolume::GetProperty - Retrieves the value of a property or
group of properties for the volume.
Obj −> [IDLgrVolume::]GetProperty [, ALL=*variable*]
[, PARENT=*variable*] [, VALID_DATA=*variable*]
[, XRANGE=*variable*] [, YRANGE=*variable*]
[, ZRANGE=*variable*]
Note: See also the {Get} properties in IDLgrVolume::Init

IDLgrVolume::Init - Initializes the volume object.

Obj = OBJ_NEW('IDLgrVolume' [, *vol0* [, *vol1* [, *vol2* [, *vol3*]]]] [, AMBIENT{Get, Set}=*RGB vector*] [, BOUNDS{Get, Set}=*[xmin*, *ymin*, *zmin*, *xmax*, *ymax*, *zmax]*] [, COMPOSITE_FUNCTION{Get, Set}={0 | 1 | 2 | 3}] [, CUTTING_PLANES{Get, Set}=*array*] [, DATA0{Get, Set}=*[dx, dy, dz]*] [, DATA1{Get, Set}=*[dx, dy, dz]*] [, DATA2{Get, Set}=*[dx, dy, dz]*] [, DATA3{Get, Set}=*[dx, dy, dz]*] [, DEPTH_CUE{Get, Set}=*[zbright, zdim]*] [, /HIDE{Get, Set}] [, HINTS{Get, Set}={0 | 1 | 2 | 3}] [, /INTERPOLATE{Get, Set}] [, /LIGHTING_MODEL{Get, Set}] [, NAME{Get, Set}=*string*] [, /NO_COPY{Get, Set}] [, OPACITY_TABLE0{Get, Set}=*256-element byte array*] [, OPACITY_TABLE1{Get, Set}=*256-element byte array*] [, RENDER_STEP{Get, Set}=*[x, y, z]*] [, RGB_TABLE0{Get, Set}=*256 x 3-element byte array*] [, RGB_TABLE1{Get, Set}=*256 x 3-element byte array*] [, /TWO_SIDED{Get, Set}] [, UVALUE{Get, Set}=*value*] [, VOLUME_SELECT{Get, Set}={0 | 1 | 2}] [, XCOORD_CONV{Get, Set}=*vector*] [, YCOORD_CONV{Get, Set}=*vector*] [, /ZBUFFER{Get, Set}] [, ZCOORD_CONV{Get, Set}=*vector*] [, ZERO_OPACITY_SKIP{Get, Set}={0 | 1}])
or
Result = *Obj* -> [IDLgrVolume::]Init([*vol0* [, *vol1* [, *vol2* [, *vol3*]]]])

IDLgrVolume::PickVoxel - Computes the coordinates of the voxel projected to a location specified by the 2D device coordinates point, [*xi*, *yi*], and the current Z-buffer.

Result = *Obj* -> [IDLgrVolume::]PickVoxel (*Win*, *View*, *Point* [, PATH=*objref(s)*])

IDLgrVolume::SetProperty - Sets the value of a property or group of properties for the volume.

Obj -> [IDLgrVolume::]SetProperty
Note: See also the {Set} properties in IDLgrVolume::Init

IDLgrVRML - Saves the contents of an Object Graphics hierarchy into a VRML 2.0 format file. No superclasses. No subclasses.

IDLgrVRML::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrVRML::]Cleanup

IDLgrVRML::Draw - Draws a picture to this graphics destination.
Obj -> [IDLgrVRML::]Draw [, *Picture*]

IDLgrVRML::GetDeviceInfo - Returns information that allows IDL applications to make decisions for optimal performance.

Obj–>[IDLgrVRML::]GetDeviceInfo [, ALL=*variable*] [, MAX_TEXTURE_DIMENSIONS=*variable*] [, MAX_VIEWPORT_DIMENSIONS=*variable*] [, NAME=*variable*] [, NUM_CPUS=*variable*] [, VENDOR=*variable*] [, VERSION=*variable*]

IDLgrVRML::GetFontnames - Returns the list of available fonts that can be used in IDLgrFont objects.

Return = *Obj* ->[IDLgrVRML::]GetFontnames(*FamilyName* [, IDL_FONTS={0 | 1 | 2}] [, STYLES=*string*])

IDLgrVRML::GetProperty - Retrieves the value of a property or group of properties for the VRML object.

Obj -> [IDLgrVRML::]GetProperty [, ALL=*variable*] [, SCREEN_DIMENSIONS=*variable*]
Note: See also the {Get} properties in IDLgrVRML::Init

IDLgrVRML::GetTextDimensions - Retrieves the dimensions of a text object that will be rendered in the clipboard buffer.

Result = *Obj* ->[IDLgrVRML::]GetTextDimensions(*TextObj* [, DESCENT=*variable*] [, PATH=*objref(s)*])

IDLgrVRML::Init - Initializes the VRML object.

Obj = OBJ_NEW('IDLgrVRML' [, COLOR_MODEL{Get}={0 | 1}] [, DIMENSIONS{Get, Set}=*[width, height]*] [, FILENAME{Get, Set}=*string*] [, GRAPHICS_TREE{Get, Set}=*objref*] [, N_COLORS{Get}=*integer{2 to 256}*] [, PALETTE{Get, Set}=*objref*] [, QUALITY{Get, Set}={0 | 1 | 2}] [, RESOLUTION{Get, Set}=*[xres, yres]*] [, UNITS{Get, Set}={0 | 1 | 2 | 3}] [, UVALUE{Get, Set}=*value*] [, WORLDINFO=*string array*] [, WOLRDTITLE=*string*])
or
Result = *Obj* -> [IDLgrVRML::]Init( )

IDLgrVRML::SetProperty - Sets the value of a property or group of properties for the VRML world.

Obj -> [IDLgrVRML::]SetProperty
Note: See also the {Set} properties in IDLgrVRML::Init

IDLgrWindow - Represents an on-screen area on a display device that serves as a graphics destination. No superclasses. No subclasses.

IDLgrWindow::Cleanup - Performs all cleanup on the object.
OBJ_DESTROY, *Obj* or *Obj* -> [IDLgrWindow::]Cleanup

IDLgrWindow::Draw - Draws the specified scene or view object to this graphics destination.

Obj -> [IDLgrWindow::]Draw [, *Picture*] [, CREATE_INSTANCE={1 | 2}] [, /DRAW_INSTANCE]

IDLgrWindow::Erase - Erases the entire contents of the window.
Obj -> [IDLgrWindow::]Erase [, COLOR=*index or RGB vector*]

IDLgrWindow::GetContiguousPixels - Returns an array of long integers whose length is equal to the number of colors available in the index color mode (value of N_COLORS property).

Return = *Obj* -> [IDLgrWindow::]GetContiguousPixels( )

IDLgrWindow::GetDeviceInfo - Returns information that allows IDL applications to make decisions for optimal performance.

Obj–>[IDLgrWindow::]GetDeviceInfo [, ALL=*variable*] [, MAX_TEXTURE_DIMENSIONS=*variable*]

[, MAX_VIEWPORT_DIMENSIONS=*variable*]
[, NAME=*variable*] [, NUM_CPUS=*variable*]
[, VENDOR=*variable*] [, VERSION=*variable*]

IDLgrWindow::GetFontnames - Returns the list of available fonts that can be used in IDLgrFont objects.

Return = Obj –>
[IDLgrWindow::]GetFontnames(*FamilyName*
[, IDL_FONTS={0 | 1 | 2}] [, STYLES=*string*])

IDLgrWindow::GetProperty - Retrieves the value of a property or group of properties for the window.

Obj –> [IDLgrWindow::]GetProperty [, ALL=*variable*]
[, IMAGE_DATA=*variable*] [, RESOLUTION=*variable*]
[, SCREEN_DIMENSIONS=*variable*]
[, ZBUFFER_DATA=*variable*]
Note: See also the {Get} properties in IDLgrWindow::Init

IDLgrWindow::GetTextDimensions - Retrieves the dimensions of a text object that will be rendered in the window.

Result = Obj –>[IDLgrWindow::]GetTextDimensions(
TextObj [, DESCENT=*variable*] [, PATH=*objref(s)*])

IDLgrWindow::Iconify - Iconifies or de-iconifies the window.

Obj –> [IDLgrWindow::]Iconify, *IconFlag*

IDLgrWindow::Init - Initializes the window object.

Obj = OBJ_NEW('IDLgrWindow'
[, COLOR_MODEL{Get}={0 | 1}] [, DIMENSIONS{Get, Set} =*[width, height]*] [, GRAPHICS_TREE{Get, Set}=*objref of type IDLgrScene, IDLgrViewgroup, or IDLgrView*] [, LOCATION{Get, Set}=*[x, y]*]
[, N_COLORS{Get}=*integer*{2 to 256}]
[, PALETTE{Get, Set}=*objref*] [, QUALITY{Get, Set}={0 | 1 | 2}] [, RENDERER{Get}={0 | 1}]
[, RETAIN{Get}={0 | 1 | 2}] [, TITLE{Get, Set}=*string*]
[, UNITS{Get, Set}={0 | 1 | 2 | 3}] [, UVALUE{Get, Set}=*value*])
or
Result = Obj –> [IDLgrWindow::]Init( )
X Windows Keywords:
[, DISPLAY_NAME{Get}=*string*]

IDLgrWindow::Pickdata - Maps a point in the 2D device space of the window to a point in the 3D data space of an object tree.

Result = Obj –> [IDLgrWindow::]Pickdata(*View*, *Object*, *Location*, *XYZLocation* [, PATH=*objref(s)*])

IDLgrWindow::Read - Reads an image from a window.

Result = Obj –> [IDLgrWindow::]Read( )

IDLgrWindow::Select - Returns a list of objects selected at a specified location.

Result = Obj –> [IDLgrWindow::]Select(*Picture, XY*
[, DIMENSIONS=*[width, height]*] [, UNITS={0 | 1 | 2 | 3}])

IDLgrWindow::SetCurrentCursor - Sets the current cursor image to be used while positioned over a drawing area.

Obj–> [IDLgrWindow::]SetCurrentCursor
[, *CursorName*] [, IMAGE=*16 x 16 bitmap*] [, MASK=*16 x 16 bitmap*] [, HOTSPOT=*[x, y]*]
X Windows Only Keywords: [, STANDARD=*index*]

IDLgrWindow::SetProperty - Sets the value of a property or group of properties for the window.

Obj –> [IDLgrWindow::]SetProperty
Note: See also the {Set} properties in IDLgrWindow::Init

IDLgrWindow::Show - Exposes or hides a window.

Obj –> [IDLgrWindow::]Show, *Position*

TrackBall - Translates widget events from a draw widget (created with the WIDGET_DRAW function) into transformations that emulate a virtual trackball (for transforming object graphics in three dimensions). No superclasses. No subclasses.

TrackBall::Init - Initializes the TrackBall object.

Obj = OBJ_NEW('TrackBall', *Center*, *Radius* [, AXIS={0 | 1 | 2}] [, /CONSTRAIN] [, MOUSE=*bitmask*])
or
Result = Obj –> [TrackBall::]Init(*Center*, *Radius*)

Trackball::Reset - Resets the state of the TrackBall object.

Obj –> [TrackBall::]Reset, *Center*, *Radius* [, AXIS={0 | 1 | 2}] [, /CONSTRAIN] [, MOUSE=*bitmask*]

TrackBall::Update - Updates the state of the TrackBall object based on the information contained in the input widget event structure.

Result = Obj –> [TrackBall::]Update(*sEvent*
[, MOUSE=*bitmask*] [, TRANSFORM=*variable*]
[, /TRANSLATE])

Statements

Assignment

variable = expression - Assigns a value to a variable.

variable*[*subscripts*] = *expression - Assigns a value to the elements of an array specified by the array subscripts.

variable*[*subscript_range*] = *expression - Assigns a value to the elements of an array specified by the array subscript range.

Program Control

Compound Statements

BEGIN...END - Defines a block of statements.
> BEGIN
>> *statements*
>
> END | ENDIF | ENDELSE | ENDFOR | ENDREP |
> ENDWHILE

Conditional Statements

IF...THEN...ELSE - Conditionally executes a statement or block of statements.
> IF *expression* THEN *statement* [ELSE *statement*]
> or
> IF *expression* THEN BEGIN
>> *statements*
>
> ENDIF [ELSE BEGIN
>> *statements*
>
> ENDELSE]

CASE - Selects one statement for execution from multiple choices, depending on the value of an expression.
> CASE *expression* OF
>> *expression*: *statement*
>> ...
>> *expression*: *statement*
>
> [ELSE: *statement*]
> ENDCASE

SWITCH - Selects one statement for execution from multiple choices, depending upon the value of an expression.
> SWITCH *expression* OF
>> *expression*: *statement*
>> ...
>> *expression*: *statement*
>
> [ELSE: *statement*]
> ENDSWITCH

Loop Statements

FOR...DO - Executes one or more statements repeatedly, while incrementing or decrementing a variable with each repetition, until a condition is met.
> FOR *Variable* = *Init*, *Limit* [, *Increment*] DO *statement*
> or
> FOR *Variable* = *Init*, *Limit* [, *Increment*] DO BEGIN
>> *statements*
>
> ENDFOR

REPEAT...UNTIL - Repeats statement(s) until expression evaluates to true. Subject is always executed at least once.
> REPEAT *statement* UNTIL *expression*
> or
> REPEAT BEGIN
>> *statements*
>
> ENDREP UNTIL *expression*

WHILE...DO - Performs statement(s) as long as expression evaluates to true. Subject is never executed if condition is initially false.
> WHILE *expression* DO *statement*
> or
> WHILE *expression* DO BEGIN
>> *statements*
>
> ENDWHILE

Jump Statements

BREAK - Immediately exits from a loop (FOR, WHILE, REPEAT), CASE, or SWITCH statement without resorting to GOTO statements.
> BREAK

CONTINUE - Immediately starts the next iteration of the enclosing FOR, WHILE, or REPEAT loop.
> CONTINUE

GOTO - Transfers program control to point specified by *label*.
> GOTO, *label*

Functions and Procedures

COMPILE_OPT - Gives IDL compiler information that changes the default rules for compiling functions or procedures.

COMPILE_OPT opt_1 [, opt_2, ..., opt_n]

Note: opt_n can be IDL2, DEFINT32, HIDDEN, OBSOLETE, or STRICTARR

FORWARD_FUNCTION - Causes argument(s) to be interpreted as functions rather than variables (versions of IDL prior to 5.0 used parentheses to declare arrays).

FORWARD_FUNCTION $Name_1$, $Name_2$, ..., $Name_n$

FUNCTION - Defines a function.

FUNCTION *Function_Name*, $parameter_1$, ..., $parameter_n$

PRO - Defines a procedure.

PRO *Procedure_Name*, $argument_1$, ..., $argument_n$

***Procedure_Name* -** Calls a procedure.

Procedure_Name, $argument_1$, ..., $argument_n$

Result = FUNCTION(arg_1, ..., arg_n) - Calls a function.

Variable Scope

COMMON - Creates a common block.

COMMON *Block_Name*, $Variable_1$, ..., $Variable_n$

Executive Commands

Executive commands must be entered at the IDL command prompt. They cannot be used in programs.

.COMPILE - Compiles programs without running.
    .COMPILE [*File₁*,..., *Fileₙ*]
    To compile from a temporary file: .COMPILE -f *File TempFile*

.CONTINUE - Continues execution of a stopped program.
    .CONTINUE

.EDIT - Opens files in editor windows of the IDLDE (Windows and Motif only). Note that filenames are separated by spaces, not commas.
    .EDIT *File₁* [*File₂ Fileₙ*]

.FULL_RESET_SESSION - Does everything .RESET_SESSION does, plus additional reset tasks such as unloading sharable libraries.
    .FULL_RESET_SESSION

.GO - Executes previously-compiled main program.
    .GO

.OUT - Continues execution until the current routine returns.
    .OUT

.RESET_SESSION - Resets much of the state of an IDL session without requiring the user to exit and restart the IDL session.
    .RESET_SESSION

.RETURN - Continues execution until RETURN statement.
    .RETURN

.RNEW - Erases main program variables and then does .RUN.
    .RNEW [*File₁*,...,*Fileₙ*]
    To save listing in a file:.RNEW -L *ListFile.lis File₁* [, *File₂*,..., *Fileₙ*]
    To display listing on screen: .RNEW -T *File₁* [, *File₂*,..., *Fileₙ*]

.RUN - Compiles and executes IDL commands from files or keyboard.
    .RUN [*File₁*,..., *Fileₙ*]
    To save listing in a file:.RUN -L *ListFile.lis File₁* [, *File₂*,..., *Fileₙ*]
    To display listing on screen: .RUN -T *File₁* [, *File₂*,..., *Fileₙ*]

.SKIP - Skips over the next *n* statements and then single steps.
    .SKIP [*n*]

.STEP - Executes one or *n* statements from the current position.
    .STEP [*n*] or .S [*n*]

.STEPOVER - Executes a single statement if the statement doesn't call a routine.
    .STEPOVER [*n*] or .SO [*n*]

.TRACE - Similar to .CONTINUE, but displays each line of code before execution.
    .TRACE

Special Characters

Ampersand (&) - Separates multiple commands on a single line.

Apostrophe (') - Delimits strings or indicates octal or hex.

Asterisk (*) - Designates an ending subscript range equal to the size of the dimension. Also the multiplication operator and the pointer dereference operator.

At Sign (@) - Include character: Used at beginning of a line to cause the IDL compiler to substitute the contents of the file whose name appears after the @ symbol for the line. In interactive mode, the @ symbol is used to execute a batch file.

Colon (:) - Ends label identifiers. Also separates start and end subscript ranges.

Dollar Sign ($) - Continuation character (at end of line) or spawn operating system command (at start of line).

Exclamation Point (!) - First character of system variable names and font-positioning commands.

Period (.) - First character of executive commands. Also indicates floating-point numbers.

Question Mark (?) - Invokes the online help facility.

Quotation Mark (") - String delimiter or indicates octal number.

Semicolon (;) - First character of comment field. Everything after the semicolon is ignored by IDL. Semicolon can be used as the first character or after an IDL command:

; This is a comment

COUNT = 5 ; Set variable COUNT to 5

Subscripts

Subscripts are used to designate array elements to receive new values, and to retrieve the value of one or more array elements. IDL arrays are zero-based, meaning the first element is element 0.

Vector[**i**] **-** Element i + 1 of a vector. Vector[12] denotes the value of the 13th element of Vector.

Array[**i**, **j**] **-** The element stored at column i, row j of an array.

Vector[**i:j**] **-** Elements i through j of a vector.

Vector[**i:***] **-** Elements from i through the end of a vector.

Array[**i**, ***] **-** Column i of a two-dimensional array.

Array[***, **j**] **-** The jth row of a two-dimensional array.

Array[**i:j**, **m:n**] **-** Subarray of columns i though j, rows m through n.

Array[**Array2**] **-** The elements of Array whose subscripts are the values of Array2.

(Array_Expression)[**i**] **-** Element i of an array-valued expression.

Operators

Mathematical Operators

+ Addition, String Concatenation

- Subtraction and Negation

* Multiplication, Pointer dereference

/ Division

^ Exponentiation

MOD Modulo

Minimum/Maximum Operators

< The Minimum Operator

> The Maximum Operator

Matrix Operators

 # and ## Matrix Multiplication

Boolean Operators

AND - Boolean AND

NOT - Boolean complement

OR - Boolean OR

XOR - Boolean exclusive OR

Relational Operators

EQ - Equal to

GE - Greater than or equal to

GT - Greater than

LE - Less than or equal to

LT - Less than

NE - Not equal to

Other Operators

[ ] Array concatenation, enclose array subscripts

( ) Group expressions to control order of evaluation

= Assignment

?: Conditional expression

Operator Precedence

The following table lists IDL's operator precedence. Operators with the highest precedence are evaluated first. Operators with equal precedence are evaluated from left to right.

Priority	Operator
First (highest)	( ) (parentheses, to group expressions)
Second	* (pointer dereference)
	^ (exponentiation)
Third	* (multiplication)
	# and ## (matrix multiplication)
	/ (division)
	MOD (modulus)
Fourth	+ (addition)
	− (subtraction and negation)
	< (minimum)
	> (maximum)
	NOT (Boolean negation)
Fifth	EQ (equality)
	NE (not equal)
	LE (less than or equal)
	LT (less than)
	GE (greater than or equal)
	GT (greater than)
Sixth	AND (Boolean AND)
	OR (Boolean OR)
	XOR (Boolean exclusive OR)
Seventh	?: (conditional expression)

System Variables

IDL system variables contain useful constants, control plotting defaults, and store information about the current IDL session.

Constant System Variables

!DPI - Double-precision pi (p).
!DTOR - Degrees to radians, pi/180 ≈ 0.01745.
!MAP - Read-only system variable used by MAP_SET.
!PI - Single-precision pi (p).
!RADEG - Radians to degrees, 180/pi ≈ 57.2958.
!VALUES - Single- and double-precision NaN and Infinity values.

Graphics System Variables

!D - Information about current graphics device.
    Fields: FILL_DIST - line interval, in device coordinates
    FLAGS - longword of flags
    N_COLORS - number of simultaneously available colors
    NAME - string containing name of device
    ORIGIN - pan/scroll offset (*pan, scroll*)
    TABLE_SIZE - number of color table indices
    UNIT - logical number of file open for output
    WINDOW - index of currently open window
    X_CH_SIZE, Y_CHAR_SIZE - width/height of rectangle that encloses the average character in current font, in device units (usually pixels)
    X_PX_CM, Y_PX_CM - approx. number of pixels/cm
    X_SIZE, Y_SIZE - total size of the display or window, in device units
    X_VSIZE, Y_VSIZE - size of visible area of display or window
    ZOOM - X and Y zoom factors

!ORDER - Direction of image transfer: 0=bottom up, 1=top down.
!P - Information for plotting procedures.
    Fields: BACKGROUND - background color index
    CHANNEL - default source or destination channel
    CHARSIZE - character size of annotation when Hershey fonts are selected
    CHARTHICK - integer specifying thickness of vector fonts
    CLIP - device coords of clipping window ([x_0, y_0, z_0), (x_1, y_1, z_1)]
    COLOR - default color index
    FONT - integer specifying graphics text font system to use (-1 for Hershey, 0 for output device font, 1 for TrueType)

LINESTYLE - style of lines that connect points (see "Line Styles" on page 88)
MULTI - integer array: [*plots remaining on page, columns per page, rows per page, plots in Z direction, 0 for left to right or 1 for top to bottom*]
NOCLIP - if set, inhibits clipping of graphic vectors
NOERASE - set to nonzero value to prevent erasing
NSUM - number of adjacent points to average
POSITION - normalized coords of plot window (*x0, y0, x1, y1*)
PSYM - plotting symbol index (see "Plotting Symbols" on page 88)
REGION - normalized coords of plot region (*x0, y0, x1, y1*)
SUBTITLE - plot subtitle (under X axis label)
T - homogeneous 4 x 4 transformation matrix
T3D - enables 3D to 2D transformation
THICK - thickness of lines connecting points
TITLE - main plot title
TICKLEN - tick mark length (0.0 to 1.0)

!X, !Y, !Z - Axis structures for X, Y, and Z axes.
    Fields: CHARSIZE - character size of annotation when Hershey fonts are selected
    CRANGE - output axis range
    GRIDSTYLE - linestyle for tick marks/grids (see "Line Styles" on page 88)
    MARGIN - 2-element array specifying plot window margins, in units of char size ([*left or bottom, right or top*])
    MINOR - number of minor tick marks
    OMARGIN - 2-element array specifying plot window outer margins, in units of char size ([*left or bottom, right or top*])
    RANGE - 2-element vector specifying input axis range (*min, max*)
    REGION - normalized coords of region (2-element floating-point array)
    S - 2-element array specifying scaling factors for conversion between data and normalized coords
    STYLE - style of the axis encoded as bits in a longword. 1=exact, 2=extend, 4=no axis, 8=no box, 16=inhibit setting Y axis min to 0 when data are all greater than 0 (add values together for multiple effects)
    THICK - thickness of axis line
    TICKFORMAT - format string or string containing name of function that returns format string used to format axis tick mark labels
    TICKINTERVAL - indicates the interval between major tick marks for the first axis level

TICKLAYOUT - indicates the tick layout style to be used to draw each level of the axis

TICKLEN - tick mark length, in normal coords

TICKNAME - annotation for each tick (string array of up to 30 elements)

TICKS - number of major tick intervals

TICKUNITS - indicates the units to be used for axis tick labeling

TICKV - data values for each tick mark (array of up to 30 elements)

TITLE - string containing axis title

TYPE - type of axis (0 for linear, 1 for logarithmic)

WINDOW - normalized coords of axis end points (2-element floating-point array)

Error Handling/Informational System Variables

!ERROR_STATE - Structure containing all error information.

Fields: NAME - string containing error name of IDL-generated component of last error message (read-only)

BLOCK - string containing name of message block for IDL-generated component of last error message (read-only)

CODE - long-integer containing error code of IDL-generated component of last error message

SYS_CODE - long-integer containing error code of operating system component of last error message

MSG - string containing text of IDL-generated component of last error message (read-only)

MSG_PREFIX - string containing prefix string used for error messages

SYS_MSG - string containing text of operating system generated component of last error message (read-only)

!EXCEPT - Controls when IDL checks for math error conditions (0=never report exceptions, 1=report exceptions when interpreter is returning to interactive prompt, 2=report exceptions at end of each IDL statement).

!MOUSE - Status from the last cursor read operation.

Fields: X, Y - location (in device coords) of cursor when mouse button was pressed

BUTTON - specifies which mouse button was pressed (1 if left, 2 if middle, 4 if right)

TIME - number of milliseconds since a base time

!WARN - Report use of obsolete routines.

Fields: OBS_ROUTINES - if set to 1, IDL generates warnings when it encounters use of obsolete routines

OBS_SYSVARS - if set to 1, IDL generates warnings when it encounters use of obsolete system variables

PARENS - if set to 1, IDL generates warnings when it encounters use parentheses to index array

TRUNCATED_FILENAME - if set to 1, IDL generates warnings when a file can only be found by truncating its full name

IDL Environment System Variables

!DIR - Location of the main IDL directory.

!DLM_PATH - Indicates where IDL looks for Dynamically Loadable Modules when started. Read-only.

!EDIT_INPUT - Enables/disables keyboard line editing.

!HELP_PATH - Lists directories in which IDL will search for online help files

!JOURNAL - Logical unit number of journal output, or 0.

!MORE - Set to 0 to prevent paginating help text.

!MAKE_DLL - Used to configure how IDL uses the CALL_EXTERNAL, DLMs, and LINKIMAGE for the current platform.

!PATH - Search path for IDL routines.

UNIX: colon-separated list of directories.

VMS: comma-separated list of directories/text libraries.

Windows: semicolon-separated list of directories.

Macintosh: comma-separated list of folders.

!PROMPT - String to be used for IDL prompt.

!QUIET - Suppresses informational messages if set to nonzero.

!VERSION - Type, architecture, and version of IDL.

Graphics Information

Direct Graphics Devices

CGM - The CGM Device
HP - The HP-GL Device
LJ - The LJ Device
MAC - The Macintosh Display Device
NULL - The Null Display Device
PCL - The PCL Device
PRINTER - The Printer Device
PS - The PostScript Device
REGIS - The Regis Terminal Device
TEK - The Tektronix Device
WIN - The Microsoft Windows Device
X - The X Windows Device
Z - The Z-Buffer Device

Graphics Keywords

The following keywords are used with IDL plotting routines (AXIS, CONTOUR, PLOT, OPLOT, SHADE_SURF, and SURFACE) and graphics routines (CURSOR, ERASE, PLOTS, POLYFILL, TV, TVCRS, TVRD, and XYOUTS). Many have system variable equivalents. Not all keywords work with all routines. Listings such as {XYZ}KEYWORD indicate that there are 3 keywords, one for each axis (e.g., XCHARSIZE, YCHARSIZE, ZCHARSIZE).

BACKGROUND - Background color index when erasing.
CHANNEL - Channel index or mask for multi-channel displays.
CHARSIZE - Overall character size.
{XYZ}CHARSIZE - Character size for axes.
CHARTHICK - Overall thickness for vector fonts.
CLIP - Coordinates of clipping window.
COLOR - Color index for data, text, line, or polygon fill.
DATA - Set to plot in data coordinates.

DEVICE - Set to plot in device coordinates.
FONT - Text font index: -1 for vector, 0 for hardware fonts.
{XYZ}GRIDSTYLE - Linestyle index for tickmarks and grids.
LINESTYLE - LInestyle used to connect data points.
{XYZ}MARGIN - Margin of plot window in character units.
{XYZ}MINOR - number of minor tick marks.
NOCLIP - Set to disable clipping of plot.
NODATA - Set to plot only axes, titles, and annotation w/o data.
NOERASE - Set to inhibit erasing before new plot.
NORMAL - Set to plot in normal coordinates.
ORIENTATION - Angle (in degrees counter-clockwise) for text.
POSITION - Position of plot window.
PSYM - Use plotting symbols to plot data points.
{XYZ}RANGE - Axis range.
{XYZ}STYLE - Axis type.
SUBTITLE - String for subtitle.
SYMSIZE - Size of PSYM plotting symbols.
T3D - Set to use 3D transformation store in !P.T.
THICK - Overall line thickness.
{XYZ}THICK - Thickness of axis and tickmark lines.
{XYZ}TICKFORMAT - Allows advanced formatting of tick labels.
{XYZ}TICKINTERVAL - Set to indicate the interval between major tick marks for the first axis level.
{XYZ}TICKLAYOUT - Set to indicate the tick layout style to be used to draw each level of the axes.
TICKLEN - Length of tickmarks in normal coordinates. 1.0 produces a grid. Negative values extend outside window.
{XYZ}TICKLEN - Tickmark lengths for individual axes.
{XYZ}TICKNAME - String array of up to 30 labels for tickmark annotation.
{XYZ}TICKS - Number of major tick intervals for axes.
{XYZ}TICKUNITS - Set to indicate the units to be used for axis tick labeling.
{XYZ}TICKV - Array of up to 30 elements for tick mark values.
{XYZ}TICK_GET - Variable in which to return values of tick marks.
TITLE - String for plot title.
{XYZ}TITLE - String for specified axis title.
ZVALUE - The Z coordinate for a 2D plot in 3D space.
Z - Z coordinate if Z argument not specified in 3D plot call.

Line Styles

The LINESTYLE keyword to the Direct Graphics plotting routines OPLOT, PLOT, PLOTS, and SURFACE accepts the following values:

Index	Linestyle
0	Solid
1	Dotted
2	Dashed
3	Dash Dot
4	Dash Dot Dot Dot
5	Long Dashes

Plotting Symbols

The PSYM keyword to Direct Graphics plotting routines OPLOT, PLOT, and PLOTS accepts the following values:

PSYM Value	Plotting Symbol
1	Plus sign (+)
2	Asterisk (*)
3	Period (.)
4	Diamond
5	Triangle
6	Square
7	X
8	User-defined. See USERSYM procedure.
9	Undefined
10	Histogram mode.