
Packet Tracer - Configuring IPv4 Static and Default Routes Topology



Addressing Table

ing rabio				
Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
	G0/0	172.31.1.1	255.255.255.128	N/A
R1	S0/0/0	172.31.1.194	255.255.255.252	N/A
	G0/0	172.31.0.1	255.255.255.0	N/A
	S0/0/0	172.31.1.193	255.255.255.252	N/A
R2	S0/0/1	172.31.1.197	255.255.255.252	N/A
	G0/0	172.31.1.129	255.255.255.192	N/A
R3	S0/0/1	172.31.1.198	255.255.255.252	N/A
PC1	NIC	172.31.1.126	255.255.255.128	172.31.1.1
PC2	NIC	172.31.0.254	255.255.255.0	172.31.0.1

PC3	NIC	172.31.1.190	255.255.255.192	172.31.1.129

Objectives

Part 1: Examine the Network and Evaluate the Need for Static Routing

Part 2: Configure Static and Default Routes Part

3: Verify Connectivity

© 2013 Cisco and/or its affiliates. All rights reserved. This document is Cisco Public.

Background

In this activity, you will configure static and default routes. A static route is a route that is entered manually by the network administrator to create a reliable and safe route. There are four different static routes that are used in this activity: a recursive static route, a directly attached static route, a fully specified static route, and a default route.

Part 1: Examine the Network and Evaluate the Need for Static Routing

- a. Looking at the topology diagram, how many networks are there in total? 5 networks
- b. How many networks are directly connected to R1, R2, and R3? R1:2; R2:3; R3:2
- c. How many static routes are required by each router to reach networks that are not directly connected?

 Two in each case
- d. Test connectivity to the R2 and R3 LANs by pinging PC2 and PC3 from PC1.

Why were you unsuccessful? No, the networks are unreachable

Part 2: Configure Static and Default Routes

Step 1: Configure recursive static routes on R1.

- a. What is recursive static route?
 - Is a route configured with the nearest IP address to the next hop
- b. Why does a recursive static route require two routing table lookups?
 - Because one is the routing table of the next router and the other is for looking the address in the next hop
- c. Configure a recursive static route to every network not directly connected to R1, including the WAN link between R2 and R3.
- d. Test connectivity to the R2 LAN and ping the IP addresses of PC2 and PC3.
 - Why were you unsuccessful? Our configuration won't work until R2 have been configured with the addresses of the other networks.

Step 2: Configure directly attached static routes on R2.

- a. How does a directly attached static route differ from a recursive static route?
 In the directly attached static route we don't have the address of the next hop
- b. Configure a directly attached static route from R2 to every network not directly connected.
- c. Which command only displays directly connected networks? show ip route connected
- d. Which command only displays the static routes listed in the routing table? show ip route static
- e. When viewing the entire routing table, how can you distinguish between a directly attached static route and a directly connected network? The directly static route has a S in the routing table and the directly connected network has a C

Step 3: Configure a default route on R3.

- a. How does a default route differ from a regular static route?
 - This kind of route let that any packet pass through the router
- b. Configure a default route on R3 so that every network not directly connected is reachable.
- c. How is a static route displayed in the routing table? Is display with a S* 0.0.0.0/0

Step 4: Document the commands for fully specified routes.

Note: Packet Tracer does not currently support configuring fully specified static routes. Therefore, in this step, document the configuration for fully specified routes. a. Explain a fully specified route.

The fully specified route is configured with the interface address and the address of the next hop

- b. Which command provides a fully specified static route from R3 to the R2 LAN?
 - ip route 172.31.0.0 255.255.255.0 S0/0/1
- c. Write a fully specified route from R3 to the network between R2 and R1. Do not configure the route; just calculate it.
 - ip route 172.31.1.192 255.255.255.252 S0/0/1
- d. Write a fully specified static route from R3 to the R1 LAN. Do not configure the route; just calculate it.
 - ip route 172.31.1.0 255.255.255.128 S0/0/1

Step 5: Verify static route configurations.

Use the appropriate **show** commands to verify correct configurations.

Which **show** commands can you use to verify that the static routes are configured correctly? show ip route

Part 3: Verify Connectivity

Every device should now be able to ping every other device. If not, review your static and default route configurations.

Suggested Scoring Rubric

Activity Section	Question Location	Possible Points	Earned Points
Part 1: Examine the Network and Evaluate the Need for Static Routing	a - d	10	
	Part 1 Total	10	
Part 2: Configure Static and Default Routes	Step 1	7	
	Step 2	7	
	Step 3	3	
	Step 4	10	
	Step 5	3	
	30		
Р	60		
	100		