

Data movement Instructions of x86


和泳毅 李莘 董宇轩

CONTENTS



- Evolution of the Intel x86
- Instructions
- Data Movement Instructions
- Summary

Evolution of the Intel x86



$$\begin{array}{c}
\mathbf{1978} \Longrightarrow \mathbf{1980} \Longrightarrow \mathbf{1982} \Longrightarrow \mathbf{1985} \\
\downarrow \\
\mathbf{2001} \Longleftrightarrow \mathbf{1999} \Longleftrightarrow \mathbf{1997} \Longleftrightarrow \mathbf{1989} \\
\downarrow \\
\mathbf{-95} \\
\mathbf{2003} \Longrightarrow \mathbf{2004} \Longrightarrow \mathbf{2006} \Longrightarrow \mathbf{2011}$$




An instruction is a statement that becomes executable when a program is assembled. Instructions are translated by the assembler into machine language bytes, which are loaded and executed by the CPU at runtime. An instruction contains four basic parts:

- Label (optional)
- Instruction mnemonic (required)
- Operand(s) (usually required)
- Comment (optional)

This is how the different parts are arranged:

[label:] mnemonic [operands] [;comment]



Label

Data labels and Code labels.

Data labels

```
count DWORD 100
```

array DWORD 1024, 2048
DWORD 4096, 8192

> target:

```
mov ax,bx
```

...

jmp target

Code labels

```
➤ L1: movax,bx
```

> L2: ...



Instruction Mnemonic

Mnemonic	Description	
MOV	Move (assign) one value to another	
ADD	Add two values	
SUB	Subtract one value from another	
MUL	Multiply two values	
JMP	Jump to a new location	
CALL	Call a procedure	



Operands

Example	Operand Type
96	Integer literal
2 + 4	Integer expression
eax	Register
count	Memory

> stc

> inc eax

mov count,ebx

imul eax,ebx,5

; set Carry flag

; add 1 to EAX

; move EBX to count



Comments

The following information is typically included at the top of a program listing:

- Description of the program's purpose
- Names of persons who created and/or revised the program
- Program creation and revision dates
- Technical notes about the program's implementation


Comments can be specified in two ways:

- Single-line comments.
- Block comments

```
COMMENT!

This line is a comment.

This line is also a comment.
```



Operand Types

[label:] mnemonic [operands] [;comment]

Instructions can have zero, one, two, or three operands. Here, we omit the label and comment fields for clarity:

mnemonic [destination]
mnemonic [destination],[source]
mnemonic [destination],[source-1],[source-2]

Data Movement Instructions () 中国神学技术大学 University of Science and Technology of China



Operand Types

There are three basic types of operands:

- Immediate—uses a numeric literal expression
- Register—uses a named register in the CPU
- **Memory**—references a memory location

Data Movement Instructions () 中国神学技术大学 University of Science and Technology of China



Operand Types

Instruction Operand Notation, 32-Bit Mode.

Operand	Description	
reg8	8-bit general-purpose register: AH, AL, BH, BL, CH, CL, DH, DL	
reg16	16-bit general-purpose register: AX, BX, CX, DX, SI, DI, SP, BP	
reg32	32-bit general-purpose register: EAX, EBX, ECX, EDX, ESI, EDI, ESP, EBP	
reg	Any general-purpose register	
sreg	16-bit segment register: CS, DS, SS, ES, FS, GS	
imm	8-, 16-, or 32-bit immediate value	
imm8	8-bit immediate byte value	
imm16	16-bit immediate word value	
imm32	32-bit immediate doubleword value	
reg/mem8	8-bit operand, which can be an 8-bit general register or memory byte	
reg/mem16	16-bit operand, which can be a 16-bit general register or memory word	
reg/mem32	32-bit operand, which can be a 32-bit general register or memory doubleword	
mem	An 8-, 16-, or 32-bit memory operand	





Some basic concepts

General register :AX、BX、CX、DX

EAX、ECX、EDX、EBX: The extension of ax,bx,cx,dx

eax, ebx, ecx, edx, esi, edi, ebp, esp: The name of the general registers on the CPU in the X86 assembly language, which are 32-bit registers. When interpreted in C, these registers can be treated as variables.





Universal data movement instructions

MOV Transferring words or bytes.

MOVSX Expand symbols, then transfer.

MOVZX Zero expansion, then transfer.

PUSH Push words into the stack.

POP Pop words out of the stack.

PUSHA Push AX,CX, DX,BX,SP,BP,SI,DI into the stack.

POPA Pop DI,SI,BP,SP,BX,DX,CX,AX into the stack.

PUSHAD Push EAX,ECX,EDX,EBX,ESP,EBP,ESI,EDI into the stack.

POPAD Pop EDI,ESI,EBP,ESP,EBX,EDX,ECX,EAX onto the stack.

BSWAP Exchange the order of bytes in 32-bit registers.

XCHG Exchange words or bytes.

CMPXCHG Compare and exchange operands.

XADD Exchange first and then accumulate.

XLAT Byte lookup table conversion.

Data Movement Instructions () 中国神学技术大学 University of Science and Technology of China



Inputs and outputs movement instructions

IN I/O port input. OUT I/O port output.



Destination address movement instructions

LDS Send target pointer, and load contents of pointer to DS.

LES Send target pointer, and load contents of pointer to ES.

LFS Send target pointer, and load its contents into FS.

LGS Send target pointer, and load its contents into GS.

LSS Send target pointer, and load its contents into SS.



Flags movement instructions

LAHF Register transfer, loading of the flags into the AH.


SAHF Register transfer, loading the AH contents into the flag register.

PUSHF Pushing.

POPF Poping.

PUSHD 32-bit pushing.

POPD 32-bit poping.



Floating-point movement instructions

FLDZ	0.0->ST(0)	Machine code	D9 EE
FLD1	1.0->ST(0)	Machine code	D9 E8
FLDPI	π->ST(0)	Machine code	D9 EB
FLDL2T	ln10/ln2->ST(0)	Machine code	D9 E9
FLDL2E	1/ln2->ST(0)	Machine code	D9 EA
FLDLG2	ln2/ln10->ST(0)	Machine code	D9 EC
FLDLN2	In2->ST(0)	Machine code	D9 ED

FLD real4 ptr mem Single precision floating point

Machine code D9 mm000mmm

FLD real8 ptr mem Double Precision Floating Point

Machine code DD mm000mmm

FLD real10 ptr mem Crossover Floating Point

Machine code DB mm101mmm



Floating-point movement instructions

FILD word ptr mem 2-byte integers Machine code DF mm000mmm

FILD dword ptr mem 4-byte integers Machine code DB mm000mmm

FILD qword ptr mem 8-byte integers Machine code DF mm101mmm

FST real4 ptr mem Single precision floating point Machine code D9 mm010mmm

FST real8 ptr mem Double Precision Floating Point Machine code DD mm010mmm

FIST word ptr mem 2-byte integers Machine code DF mm010mmm

FIST dword ptr mem 4-byte integers Machine code DB mm010mmm

FSTP real4 ptr mem Single precision floating point Machine code D9 mm011mmm

FSTP real8 ptr mem Double Precision Floating Point Machine code DD mm011mmm

FSTP real10 ptr mem Crossover Floating Point Machine code DB mm111mmm



Floating-point movement instructions

FISTP word ptr mem FISTP dword ptr mem

FISTP qword ptr mem

2-byte integers

4-byte integers

8-byte integers

Machine code DF mm011mmm

Machine code DB mm011mmm

Machine code DF mm111mmm

FCMOVB

FCMOVBE

FCMOVE

FCMOVNB

FCMOVNBE

FCMOVNE

FCMOVNU

FCMOVU

ST(0),ST(i) <

ST(0),ST(i) <=

ST(0),ST(i) =

ST(0),ST(i) >=

ST(0),ST(i) >

ST(0),ST(i) !=

ST(0),ST(i) order

Machine code DA C0iii

Machine code DA D0iii

Machine code DA C1iii


Machine code DB C0iii

Machine code DB D0iii

Machine code DB C1iii

Machine code DB D1iii

ST(0),ST(i) disorder Machine code DA D1iii




Some basic concepts

```
.data //Data Area
sum DWORD 0
.code //Code Area
mov eax,sum
mov var2,ax
```

- BYTE 8 bits
- WORD 16 bits
- DWORD 32 bits

Data Movement Instructions (**) 中国神学技术大学 University of Science and Technology of China



The purpose of the data movement instruction is to copy a piece of data from one location to another. In that case, the data movement instruction will contain a source and a destination operand, and the instruction will copy the value of the original operand to the destination operand and overwrite it.

There are five types of data transfer instructions, namely, mov, moves, movz, push, and pop.



MOV Instruction

The MOV instruction copies data from a source operand to a destination operand. Known as a data transfer instruction, it is used in virtually every program. Its basic format shows that the first operand is the destination and the second operand is the source:

MOV destination, source

- Both operands must be the same size.
- Both operands cannot be memory operands.
- The instruction pointer register (IP, EIP, or RIP) cannot be a destination operand.



MOV Instruction

Here is a list of the standard MOV instruction formats:

(imm-Immediate reg- Register mem- Memory)

> MOV reg,reg

MOV mem,req

MOV reg,mem

MOV mem,imm

MOV reg,imm

Data Movement Instructions () 中国神学技术大学 University of Science and Technology of China



MOV Instruction

A single MOV instruction cannot be used to move data directly from one memory location to another. Instead, you must move the source operand's value to a register before assigning its value to a memory operand:

> .data var1 WORD? var2 WORD? .code mov ax,var1 mov var2,ax



MOV Instruction

The following code example shows how the same 32-bit register can be modified using differently sized data. When oneWord is moved to AX, it overwrites the existing value of AL. When oneDword is moved to EAX, it overwrites AX. Finally, when 0 is moved to AX, it overwrites the lower half of EAX.

```
.data
oneByte BYTE 78h
oneWord WORD 1234h
oneDword DWORD 12345678h
.code
mov eax,0 ; EAX = 00000000h
mov al, one Byte; EAX = 00000078h
mov ax, one Word ; EAX = 00001234h
mov eax, one Dword; EAX = 12345678h
mov ax,0
                : EAX = 12340000h
```



MOVZX Instruction

The MOVZX instruction (move with zero-extend) copies the contents of a source operand into a destination operand and zero-extends the value to 16 or 32 bits. This instruction is only used with unsigned integers. There are three variants:


> MOVZX reg32,reg/mem8 MOVZX reg32,reg/mem16 MOVZX reg16,reg/mem8

```
.data
byteVal BYTE 10001111b
.code
movzx ax,byteVal ; AX = 000000010001111b
```



MOVZX Instruction

Using MOVZX to copy a byte into a 16-bit destination.




mov bx,0A69Bh

movzx eax,bx ; EAX = 0000A69Bh

; EDX = 0000009Bhmovzx edx,bl

movzx cx,bl CX = 009Bh



MOVZX Instruction

The following examples use memory operands for the source and produce the same results:

```
.data
```

byte1 BYTE 9Bh


word1 WORD 0A69Bh

.code

movzx eax,word1 EAX = 0000A69Bh

movzx edx,byte1 ; EDX = 0000009Bh

: CX = 009Bhmovzx cx,byte1



MOVSX Instruction

The MOVSX instruction (move with sign-extend) copies the contents of a source operand into a destination operand and sign-extends the value to 16 or 32 bits. This instruction is only used with signed integers. There are three variants:


```
MOVSX reg32,reg/mem8
MOVSX reg32,reg/mem16
MOVSX reg16,reg/mem8
```

```
.data
byteVal BYTE 10001111b
.code
movsx ax,byteVal
                          AX = 1111111111100011111b
```



MOVSX Instruction

Using MOVSX to copy a byte into a 16-bit destination.



mov bx,0A69Bh

: EAX = FFFFA69Bhmovsx eax,bx

EDX = FFFFFF9Bhmovsx edx,bl

: CX = FF9Bhmovsx cx,bl



MOVSX Instruction

The following examples use memory operands for the source and produce the same results:

```
.data
```

byte1 BYTE 9Bh

word1 WORD 0A69Bh

.code

movzx eax,word1 EAX = 0000A69Bh

movzx edx,byte1 ; EDX = 0000009Bh

: CX = 009Bhmovzx cx,byte1

Summary



Intel had a 16-bit microprocessor two years before its competitors' more elegant architectures, such as the Motorola 68000, and this head start led to the selection of the 8086 as the CPU for the IBM PC. Intel engineers generally acknowledge that the x86 is more difficult to build than computers like ARMv7 and MIPS, but the large market meant in the PC era that AMD and Intel could afford more resources to help overcome the added complexity. What the x86 lacks in style, it rectifies with market size, making it beautiful from the right perspective.

Summary



Its saving grace is that the most frequently used x86 architectural components are not too difficult to implement, as AMD and Intel have demonstrated by rapidly improving performance of integer programs since 1978. To get that performance, compilers must avoid the portions of the architecture that are hard to implement fast.

In the post-PC era, however, despite considerable architectural and manufacturing expertise, x86 has not yet been competitive in the personal mobile device.



Thank you