

Architecture d'ensemble d'instructions

Solutions pour étudiants Exercices Architecture des ordinateurs

1 Instruction-Set Architecture

1.1 Code C simple vers assembleur RISC-V

1.1.1 Guide étudiants

- a) You need the instruction: add
- b) You need the instructions: add, sub
- c) You need the instruction: addi
- d) You need the instruction: addi
- e) You need the instructions: lui, addi. Beware immediates overflow.
- f) You need the instructions: lui, addi. Beware immediates overflow.

isa/c-to-riscv-01

1.2 Code C algorithmique vers assembleur RISC-V

1.2.1 Guide étudiants

- a) One variant is with: bne, add, sub
- b) One variant is with: bne, add, j, sub
- c) One variant is with: addi, bne, add, j
- d) One variant is with: addi, bge, add, slli, j
- e) One variant is with: lui, addi, lw, slli, sw
- f) One variant is with: lui, ori, addi, bge, slli, add, lw, sw, j
- g) One variant is with: addi, add, lb, beq, j

isa/c-to-riscv-02

1.3 Code machine vers assembleur RISC-V

1.3.1 Guide étudiants

a) 0x41FE 83B3 = 0100 0001 1111 1110 1000 0011 1011 0011

HEI-Vs / ZaS, AmA / 2025



$$op = 51, funct3 = 0 \Rightarrow add \text{ or sub (R-Type Command)}$$

funct7 = 01000000 ⇒ sub

funct7	rs2	rs1	funct3	rd	op
0100 000	11111	11101	000	00111	0110011
32	31	29	0	7	51

sub t2, t4, t6

b) I-Type

isa/machinecode-to-riscv-01

1.4 Opérations logiques sur registres

1.4.1 Guide étudiants

- a) s3 = 0x46A1 0000
- b) s4 = 0xFFFF 01B7
- c) s5 = 0xB95E F1B7

isa/riscv-execution-01

1.5 Opérations logiques sur valeurs

1.5.1 Guide étudiants

- a) s3 = 0x3A75 0824
- b) -
- c) -

isa/riscv-execution-02

1.6 Multiplications en RISC-V

1.6.1 Guide étudiants

s4 = 0xE000 0000

s3 = 0x0000 0000

isa/riscv-execution-03

1.7 Division et modulo

1.7.1 Guide étudiants

s3 = 0x0000 0005

s4 = 0x0000 0002

isa/riscv-execution-04



1.8 Type R vers code machine

1.8.1 Guide étudiants

R-Type Command

funct7	rs2	rs1	funct3	rd	op
0	20	19	0	18	51
0000000	10100	10011	000	10010	0110011

0x0149 8933

- b) -
- c) 0x0092 9BB3
- d) -
- e) -

isa/riscv-to-machinecode-01

1.9 Type I vers code machine

1.9.1 Guide étudiants

I-Type Command

$\mathrm{imm}_{11:0}$	rs1	funct3	rd	op
12	9	0	8	19
0000 0000 1100	01001	000	01000	001 0011

0x00C4 8413

- b) -
- c) -
- d) **0x01B0 1483**
- e) -

isa/riscv-to-machinecode-02

1.10 Type S vers code machine

1.10.1 Guide étudiants

- a) 0xFE79 AD23
- b) -
- c)



sb x30, 0x2D(x0)

S-Type Command

$\mathrm{imm}_{11:5}$	rs2	rs1	funct3	$\mathrm{imm}_{4:0}$	op
0000 001	30	0	0	01101	35
0000 001	11110	00000	000	01101	010 0011

0x03E0 06A3

isa/riscv-to-machinecode-03

1.11 Système temps réel

Quelle est la principale différence entre un système en temps réel « dur » et un système en temps réel « souple » ?

1.11.1 Guide étudiants

One of those system types is considered as failed if it misses any timing. When/Why is it necessary to be so strict?

isa/riscv-to-machinecode-04

1.12 Type U vers code machine

1.12.1 Guide étudiants

0x8CDE FAB7

isa/riscv-to-machinecode-05

1.13 Type J vers code machine

1.13.1 Guide étudiants

0x0FF8A 60EF

isa/riscv-to-machinecode-06




2 | Complément au laboratoire

Pour vous aider, n'hésitez pas à utiliser l'interpréteur RISC-V sur https://course.hevs.io/car/riscv-interpreter/ ainsi que Ripes.

Attention aux types des variables!

- Le type **int** est considéré de taille 32 bits signé.
- Le type **unsigned int** est considéré de taille 32 bits non-signé.



uint8_t est donc un byte non-signé, tandis que int8_t est un byte signé.

2.1 Calculs de base

2.1.1 Guide étudiants

a)

```
# a = b + c;
# s0 = a, s1 = b, s2 = c
\# b = 1, c = 2
addi s1, zero, 1
addi s2, zero, 2
add s0, s1, s2
                        \# a = b + c
\# s0 = 0 \times 00000003
\# s1 = 0 \times 00000001
\# s2 = 0 \times 000000002
\# b = -1, c = 2
\# s0 = 0 \times 00000001
\# s1 = 0 \times ffffffff
\# s2 = 0 \times 000000002
\# b = -12, c = 2032
\# s0 = 0 \times 000007db
```

b)

```
# a = b - c;
# d = (e + f) - (g + h);
# s0-s7 = a-h

...

# t0 = 0xffffffb1
# t1 = 0x000007db
# s0 = 0xffffffff
# s1 = 0x00000002
# s2 = 0x00000003
# s3 = 0xffffffd6
# s4 = 0xffffffff
# s5 = 0xfffffffb2
# s6 = 0x000007e7
# s7 = 0xfffffff4
```

isa/lab-basic-calc

s1 = 0xfffffff4 # s2 = 0x000007e7



2.2 Accès mémoire

2.2.1 Guide étudiants

```
# Check for sign extension comprehension


# uint16_t a = mem[3];
# mem[4] = a;
# t0 is a
thu t0, 3(zero) # if th, the last bit may be 1 -> extended -> wrong number
sw t0, 4(zero)

# int16_t a = mem[3];
# mem[4] = a;
# t0 is a
??? t0, 3(zero) # if th, the last bit may be 1 -> ???
??? t0, 4(zero)
```

isa/lab-memory

2.3 Algorithmes basiques

1. Transmettre la valeur de 8 bits de la mémoire à l'adresse 0x0000'1000 en série, bit par bit, dans le Least Significant Bit (LSB) de la mémoire à l'adresse 0x0000'1001. Les bits restants de l'adresse mémoire 0x0000'1001 doivent être < 0 >. Calculez le débit de bauds en Instructions pour l'ensemble de la transmission.



2. Multiplier deux nombres de 4 bits ensemble en utilisant en plus une des commandes **bne** ou **bge**. L'algorithme fonctionne de la manière suivante : une multiplication est la même chose que l'addition x fois du même nombre. Par exemple : 2 * 9 = 9 + 9 = 18.

2.3.1 Guide étudiants

1. UART transmission idea:

```
# Serial UART Transmisstion
# setup
lui s2, 0x00001
                 # store UART base address
addi t0, zero, 0xA # value to be send for testing
sb t0, 0(s2)
                   # save to memory
# start
lui s2, 0x00001
                 # store UART base address
addi s1, zero, 0x1 # store mask bit
lb s0, 0(s2)
                   # get value from memory
# send stopbit
sb s1, 1(s2)
                  # send stopbit to memory
addi zero, zero, 0  # nop
```



```
addi zero, zero, 0 # nop

# send startbit
...

# algorithm iteration #1 to #8
...

# send stopbit
addi zero, zero, 0 # nop
sb s1, 1(s2) # send stopbit to memory
```

2. Two numbers basic multiplication with loops idea:

```
# Input values
# a0, a1 = input, a2 = output
addi a0, zero, 9
addi a1, zero, 2

# init output to zero
addi a2, zero, 0

# check if a1 is zero
if a1 == 0 => goto end
decrement a1

accumulate:
    accumulate into a2
    decrement a1
    continue if not 0
```

isa/lab-basic-algos

2.4 Branching

2.4.1 Guide étudiants

If / else

```
addi s0, zero, 1 # int a = 1
addi s1, zero, 2 # int b = 2

# if(a == b)
test1:
   bne s0, s1, test2 # imm = 12
# a == b
equal:
   c = 0
   goto end
# else if b > a
test2: # a < b === b >= a
   if a < b => goto a_smaller
# a > b
a_bigger:
   addi s2, zero, 1
```



```
jal end # imm = 8
# a < b
a_smaller:
   addi s2, zero, 2
end:
# ...</pre>
```

2.4.2 Switch case

```
\# a = s0, mem[2] = s1
lw s1, 2(zero)
# if(b == 0)
bne s1, zero, not0 # imm = 12
# b == 0
li s0, 17
jal end # imm = 48
# b != 0
not0:
 li t1, 3
 # if(b == 3)
 bne s1, t1, not3 # imm = 12
# b == 3
li s0, 33
jal end # imm = 32
# b != 3
not3:
 # if(b == 8)
 if(b == 8) goto is8_or_12 # imm = 20
 # if(b == 12)
 if(b == 12) goto is8_or_12 # imm = 12
# b != 8 | 12 (others)
li s0, 99
jal end # imm = 8
# b == 8 | 12
is8 or 12:
 li s0, 10
end:
# ...
```

2.4.3 While / Do While

```
// A : simple do-while
addi a5, zero, 10 # int a = 10;
while_entry:
```



```
addi a5, a5, -1 # a--
bne zero, a5, while_entry # imm = -4

// B : similar
addi a5, zero, 10 # int a = 10;
while_entry:
   addi a5, a5, -1 # a--
   if a >= 0 => goto while_entry

// C : uint32_t instead of int
...
```

2.4.4 For

```
# a is s0, i is s1, mem[0] = s2
lw s2, 0(zero) # loop target

# For the for to work, blte does not exist.
# Thus, since the loop decreases, a > b
# === a-1 >= b (for signed only, else infinite loop)
# so better a >= b + 1
addi s2, s2, 1 # target + 1
li s1, 4 # i = 4
mv s0, zero # a = 0

jal for_test # imm = 8

for_do:
   add s0, s0, s1
   addi s1, s1, -1 # MUST be at the end of for

for_test:
   bge s1, s2, for_do # imm = -8
```

isa/lab-branch



2.5 Functions

2.5.1 Guide étudiants

a) A function with context saving which can be b) A function with too many arguments optimized

```
# a is s0, b is s1
li s0, 1 # a = 1
mv a0, s0 # copy into a0 as funct. arg
jal ra, doubleIt # imm = undef.
mv s1, a0 # b = result
# DO NOT FORGET THE FOLLOWING
# a0 is a scratch register, and we called
a function
# so we are not sure if a0 is still s0
mv a0, s0
jal ra, doubleItOpti # imm = undef.
mv s1, a0 # b = result
# ...
doubleIt:
  # save context
  addi sp, sp, -4
  sw s0, \theta(sp)
  \# do a = a * 2
 mv s0, a0
  sll s0, s0, 1
  mv a0, s0
  # restore context
  lw s0, 0(sp)
  addi sp, sp, 4
  jalr zero, ra, 0 # or pseudo jr ra
# If 'a' should be a register
doubleItOpti:
  mv t0, a0
 sll t0, t0, 1
  mv a0, t0
  jalr zero, ra, 0 # or pseudo jr ra
# Most opti version
doubleItOpti2:
  # nothing to save since we can do it
with a0 directly
  sll a0, a0, 1
  jalr zero, ra, 0 # or pseudo jr ra
```

```
# a to j in s0-s10
# res in s11
li s0 1
li s1 2
. . .
li s10 10
# prepare arguments
mv a0, s0
mv a1, s1
. . .
mv a7, s7
# still two args to pass -> stack
addi sp, sp, -8
# It is important that the caller
# reserves the space. Also, note
# the order in stack.
sw s8, 4(sp)
sw s9, 0(sp)
# call
jal ra, sum
# stack not needed anymore
addi sp, sp, 8
mv s1, a0 # b = result
sum:
  # do add with aX regs
  add a0, a0, a1
  add a0, a0, a2
  . . .
  add a0, a0, a7
  # load i from over sp
  lw t0, 4(sp)
  add a0, a0, t0
  # load j from over sp
  lw t0, 0(sp)
  add a0, a0, t0
  jr ra
```

isa/lab-fcts



2.5.2 Guide étudiants

2.5.2.1 Modulo

```
# RV32IM
# a is s0, b is s1, c is s2
li s0, 9
li s1, 7
remu s2, s0, s1

# RV32I
# Call a div algorithm and take remainder
# Or call a sub loop

# Modulo of power of 2
li s0, 9
li s1, 8
addi t0, s2, -1 # pow 2 - 1
and s2, t0, s0
```

2.5.2.2 °F -> °C

The main algorithm is:

```
begin:
   li s0, 550 # degrees farenheit
   li s1, 466034 # magic number
   mv s2, s0 # c = f
   # A: c = f - 32
   addi s2, s2, -32
   # B: c = c * 5
   # Variante 1 c*5 with shift
   # slli s3, s2, 2 # c * 4
   \# add s2, s3, s2 \# c + c (== * 5)
   # Variante 2 c*5 with function
   mv a0, s2
   li a1, 5
   # jal ra, mulFunct # func variant malFunct
   # jal ra, sfmulFunct # func variant sfmulFunct
   jal ra, fmulFunct # func variant fmulFunct
   mv s2, a0
   # C: c = c * 2^n / 9
   mv a0, s2
   mv a1, s1
   # jal ra, mulFunct # func variant malFunct
   # jal ra, sfmulFunct # func variant sfmulFunct
   jal ra, fmulFunct # func variant fmulFunct
   mv s2, a0
   \# D: c >>= n
   srli s2, s2, 22
# End
```



```
nop
j begin
```

The multiplication functions (from worst to best):

a) b)

```
# bad 0(n b)
mulFunct: # mulFunct(int a, int b)
   # add itself each time
   mv t0, a0
   addi a1, a1, -1
   mul_beg:
    bgeu zero, a1, mul_end # if 1 > b
    add a0, a0, t0
   addi a1, a1, -1
    j mul_beg
   mul_end:
    jr ra
# better O(n_min[a,b])
sfmulFunct: # sfmulFunct(int a, int b)
    swap a and b to loop less times
    loop to multiply
```

```
# best
fmulFunct: # fmulFunct(int a, int b)
    swap a and b to loop less times

mul_is_done:
    if b is 0 => goto fmul_end

    if b[0] is 0 => goto shift
add:
        add t0, a0, t0
shift:
    shift a0 left once
    shift a1 right once
    goto mul_is_done

fmul_end:
    mv a0, t0
    jr ra
```

The test with n = 23 should work for small numbers but overflow with bigger:

- 100F = 37C; 400F = 204C
- 1000F = 25C -> WRONG

$$\begin{aligned} \text{nbBits}_{\text{max}_{\text{fahrenheit}}} + \text{nbBits}_{\text{mult5}} + \text{nbBits}_{\text{magicNumber}} &= \\ 10(\text{max. } 1000\text{-}32) + 3 + (n - \text{nbBits}_{\text{div9}} + 1) &= \\ 10 + 3 + (16 - 4 + 1) &= \\ &= 26 \text{ bits} \end{aligned} \tag{1}$$

Because, following Équation 1, if n is $23 \rightarrow$ equation gives 33 bits, but we are on 32.

isa/lab-adv-algos